
Chapter 3: Processes





Chapter 3: Processes

- Process Concept
- Process Scheduling
- Operations on Processes
- Interprocess Communication
- Examples of IPC Systems
- Communication in Client-Server Systems






Objectives

- To introduce the notion of a process -- a program in execution, which forms the basis of all computation
- To describe the various features of processes, including scheduling, creation and termination, and communication
- To explore interprocess communication using shared memory and mes- sage passing
- To describe communication in client-server systems






Process Concept

- An operating system executes a variety of programs:
 - Batch system jobs
 - Time-shared systems user programs or tasks
- Textbook uses the terms job and process almost interchangeably
- Process a program in execution; process execution must progress in sequential fashion
- Multiple parts
 - The program code, also called **text section**
 - Current activity including program counter, processor registers
 - Stack containing temporary data
 - Function parameters, return addresses, local variables
 - Data section containing global variables
 - Heap containing memory dynamically allocated during run time







Process Concept (Contd.)

- Program is passive entity stored on disk (executable file), process is active
 - Program becomes process when executable file loaded into memory
- Execution of program started via GUI mouse clicks, command line entry of its name, etc
- One program can be several processes
 - Consider multiple users executing the same program





Process in Memory








Process State

- As a process executes, it changes state
 - **new**: The process is being created
 - running: Instructions are being executed
 - waiting: The process is waiting for some event to occur
 - ready: The process is waiting to be assigned to a processor
 - terminated: The process has finished execution






Diagram of Process State







Process Control Block (PCB)

Information associated with each process (also called task control block)

- Process state running, waiting, etc
- Program counter location of instruction to next execute
- CPU registers contents of all processcentric registers
- CPU scheduling information- priorities, scheduling queue pointers
- Memory-management information memory allocated to the process
- Accounting information CPU used, clock time elapsed since start, time limits
- I/O status information I/O devices allocated to process, list of open files

process state
process number
program counter

registers

memory limits


list of open files








CPU Switch From Process to Process







Threads

- So far, process has a single thread of execution
- Consider having multiple program counters per process
 - Multiple locations can execute at once
 - Multiple threads of control -> threads
- Must then have storage for thread details, multiple program counters in PCB

3.11


See next chapter






Process Representation in Linux

■ Represented by the C structure task_struct
pid t pid; /* process identifier */
long state; /* state of the process */
unsigned int time slice /* scheduling information */
struct task struct *parent; /* this process's parent */
struct list head children; /* this process's children */
struct files struct *files; /* list of open files */
struct mm struct *mm; /* address space of this process */








Process Scheduling


- Maximize CPU use, quickly switch processes onto CPU for time sharing
- Process scheduler selects among available processes for next execution on CPU
- Maintains scheduling queues of processes
 - Job queue set of all processes in the system
 - Ready queue set of all processes residing in main memory, ready and waiting to execute
 - Device queues set of processes waiting for an I/O device
 - Processes migrate among the various queues






Ready Queue And Various I/O Device Queues





Representation of Process Scheduling


Queuing diagram represents queues, resources, flows






Schedulers

- Long-term scheduler (or job scheduler) selects which processes should be brought into the ready queue
- Short-term scheduler (or CPU scheduler) selects which process should be executed next and allocates CPU
 - Sometimes the only scheduler in a system
- Short-term scheduler is invoked very frequently (milliseconds) ⇒ (must be fast)
- Long-term scheduler is invoked very infrequently (seconds, minutes) ⇒ (may be slow)
- The long-term scheduler controls the degree of multiprogramming
- Processes can be described as either:
 - I/O-bound process spends more time doing I/O than computations, many short CPU bursts
 - CPU-bound process spends more time doing computations; few very long CPU bursts
- Long-term scheduler strives for good process mix




Addition of Medium Term Scheduling

- Medium-term scheduler can be added if degree of multiple programming needs to decrease
 - Remove process from memory, store on disk, bring back in from disk to continue execution: swapping







Multitasking in Mobile Systems

- Some systems / early systems allow only one process to run, others suspended
- Due to screen real estate, user interface limits iOS provides for a
 - Single foreground process- controlled via user interface
 - Multiple background processes— in memory, running, but not on the display, and with limits
 - Limits include single, short task, receiving notification of events, specific long-running tasks like audio playback
- Android runs foreground and background, with fewer limits
 - Background process uses a service to perform tasks
 - Service can keep running even if background process is suspended
 - Service has no user interface, small memory use






Context Switch

- When CPU switches to another process, the system must save the state of the old process and load the saved state for the new process via a context switch
- Context of a process represented in the PCB
- Context-switch time is overhead; the system does no useful work while switching
 - The more complex the OS and the PCB -> longer the context switch
- Time dependent on hardware support
 - Some hardware provides multiple sets of registers per CPU -> multiple contexts loaded at once





Operations on Processes

 System must provide mechanisms for process creation, termination, and so on as detailed next

3.20






Process Creation


- Parent process create children processes, which, in turn create other processes, forming a tree of processes
- Generally, process identified and managed via a process identifier (pid)
- Resource sharing options
 - Parent and children share all resources
 - Children share subset of parent's resources
 - Parent and child share no resources
- Execution options
 - Parent and children execute concurrently
 - Parent waits until children terminate






A Tree of Processes in Linux





Process Creation (Cont.)

- Address space
 - Child duplicate of parent
 - Child has a program loaded into it
- UNIX examples
 - fork() system call creates new process
 - exec() system call used after a fork() to replace the process' memory space with a new program





C Program Forking Separate Process

```
#include <sys/types.h>
#include <stdio.h>
#include <unistd.h>
int main()
  pid t pid;
  /* fork a child process */
  pid = fork();
  if (pid < 0) { /* error occurred */
     fprintf(stderr, "Fork Failed");
     return 1;
```



Program Forking Separate Process (Cont'd)

```
// if (pid < 0) {
//}
else if (pid == 0) { /* child process */
  execlp("/bin/Is","Is",NULL);
else {/* parent process */
  /* parent will wait for the child to complete */
  wait(NULL);
  printf("Child Complete");
return 0;
```



Creating a Separate Process via Windows API

```
#include <stdio.h>
#include <windows.h>
int main(VOID)
  STARTUPINFO si;
  PROCESS INFORMATION pi;
  /* allocate memory */
  ZeroMemory(&si, sizeof(si));
  si.cb = sizeof(si);
  ZeroMemory(&pi, sizeof(pi));
  /* create child process */
  if (!CreateProcess(NULL, /* use command line */
    "C:\\WINDOWS\\system32\\mspaint.exe", /* command */
    NULL, /* don't inherit process handle */
    NULL, /* don't inherit thread handle */
    FALSE, /* disable handle inheritance */
    0, /* no creation flags */
    NULL, /* use parent's environment block */
    NULL, /* use parent's existing directory */
    &si,
    &pi)){
```




creating a Separate Process via Windows API(Contd)

```
// if (!CreateProcess(....){
    fprintf(stderr, "Create Process Failed");
    return -1;
}

/* parent will wait for the child to complete */
WaitForSingleObject(pi.hProcess, INFINITE);
printf("Child Complete");
/* close handles */
CloseHandle(pi.hProcess);
CloseHandle(pi.hThread);
}
```






Process Termination

- Process executes last statement and asks the operating system to delete it (exit())
 - Output data from child to parent (via wait())
 - Process' resources are deallocated by operating system
- Parent may terminate execution of children processes (abort())
 - Child has exceeded allocated resources
 - Task assigned to child is no longer required
 - If parent is exiting
 - Some operating systems do not allow child to continue if its parent terminates
 - All children terminated cascading termination





Process Termination (Cont'd)

Wait for termination, returning the pid:

```
pid t pid; int status;
pid = wait(&status);
```


- If no parent waiting, then terminated process is a zombie
- If parent terminated, processes are orphans



Multiprocess Architecture – Chrome Browser

- Many web browsers ran as single process (some still do)
 - If one web site causes trouble, entire browser can hang or crash
- Google Chrome Browser is multiprocess with 3 categories
 - Browser process manages user interface, disk and network I/O
 - Renderer process renders web pages, deals with HTML, Javascript, new one for each website opened
 - Runs in sandbox restricting disk and network I/O, minimizing effect of security exploits
 - Plug-in process for each type of plug-in







Interprocess Communication


- Processes within a system may be independent or cooperating
- Cooperating process can affect or be affected by other processes, including sharing data
- Reasons for cooperating processes:
 - Information sharing
 - Computation speedup
 - Modularity
 - Convenience
- Cooperating processes need interprocess communication (IPC)
- Two models of IPC
 - Shared memory
 - Message passing





Communications Models






Cooperating Processes

- Independent process cannot affect or be affected by the execution of another process
- Cooperating process can affect or be affected by the execution of another process
- Advantages of process cooperation
 - Information sharing
 - Computation speed-up
 - Modularity
 - Convenience






Producer-Consumer Problem

- Paradigm for cooperating processes, producer process produces information that is consumed by a consumer process
 - unbounded-buffer places no practical limit on the size of the buffer
 - bounded-buffer assumes that there is a fixed buffer size





Bounded-Buffer – Shared-Memory Solution

Shared data

```
#define BUFFER_SIZE 10

typedef struct {
    . . .
} item;


item buffer[BUFFER_SIZE];

int in = 0;

int out = 0;
```

Solution is correct, but can only use BUFFER_SIZE-1 elements






Bounded-Buffer – Producer

```
item next produced;
while (true) {
    /* produce an item in next produced */
    while (((in + 1) % BUFFER SIZE) == out)
        ; /* do nothing */
    buffer[in] = next produced;
    in = (in + 1) % BUFFER SIZE;
}
```





Bounded Buffer – Consumer

```
item next consumed;
while (true) {
    while (in == out)
        ; /* do nothing */
    next consumed = buffer[out];
    out = (out + 1) % BUFFER SIZE;

    /* consume the item in next consumed */
}
```




Interprocess Communication – Message Passing

- Mechanism for processes to communicate and to synchronize their actions
- Message system processes communicate with each other without resorting to shared variables
- IPC facility provides two operations:
 - **send**(*message*) message size fixed or variable
 - receive(message)



Interprocess Communication – Message Passing(Contd)

- If P and Q wish to communicate, they need to:
 - establish a communication link between them
 - exchange messages via send/receive
- Implementation of communication link
 - physical (e.g., shared memory, hardware bus)
 - logical (e.g., direct or indirect, synchronous or asynchronous, automatic or explicit buffering



Implementation Questions

- How are links established?
- Can a link be associated with more than two processes?
- How many links can there be between every pair of communicating processes?
- What is the capacity of a link?
- Is the size of a message that the link can accommodate fixed or variable?
- Is a link unidirectional or bi-directional?





Direct Communication

- Processes must name each other explicitly:
 - send (P, message) send a message to process P
 - receive(Q, message) receive a message from process Q
- Properties of communication link
 - Links are established automatically
 - A link is associated with exactly one pair of communicating processes
 - Between each pair there exists exactly one link
 - The link may be unidirectional, but is usually bi-directional





Indirect Communication

- Messages are directed and received from mailboxes (also referred to as ports)
 - Each mailbox has a unique id
 - Processes can communicate only if they share a mailbox
- Properties of communication link
 - Link established only if processes share a common mailbox
 - A link may be associated with many processes
 - Each pair of processes may share several communication links
 - Link may be unidirectional or bi-directional






Indirect Communication

- Operations
 - create a new mailbox
 - send and receive messages through mailbox
 - destroy a mailbox
- Primitives are defined as:

```
send(A, message) - send a message to mailbox A
receive(A, message) - receive a message from mailbox A
```






Indirect Communication

- Mailbox sharing
 - P_1 , P_2 , and P_3 share mailbox A
 - P_1 , sends; P_2 and P_3 receive
 - Who gets the message?

Solutions

- Allow a link to be associated with at most two processes
- Allow only one process at a time to execute a receive operation
- Allow the system to select arbitrarily the receiver. Sender is notified who the receiver was.






Synchronization

- n Message passing may be either blocking or non-blocking
- n **Blocking** is considered **synchronous**
 - Blocking send has the sender block until the message is received
 - Blocking receive has the receiver block until a message is available
- n Non-blocking is considered asynchronous
 - Non-blocking send has the sender send the message and continue
 - Non-blocking receive has the receiver receive a valid message or null






Synchronization (Cont.)

- n Different combinations possible
 - If both send and receive are blocking, we have a rendezvous
- n Producer-consumer becomes trivial

```
message next produced;
while (true) {
    /* produce an item in next produced */
    send(next produced);
}
message next consumed;
while (true) {
    receive(next consumed);

    /* consume the item in next consumed */
}
```





Buffering

- Queue of messages attached to the link; implemented in one of three ways
 - Zero capacity 0 messages
 Sender must wait for receiver (rendezvous)
 - 2. Bounded capacity finite length of *n* messages Sender must wait if link full
 - 3. Unbounded capacity infinite length Sender never waits






Examples of IPC Systems - POSIX

- n POSIX Shared Memory
 - Process first creates shared memory segment
 shm_fd = shm_open(name, O CREAT | O RDRW, 0666);
 - Also used to open an existing segment to share it
 - Set the size of the object ftruncate(shm fd, 4096);
 - Now the process could write to the shared memory sprintf(shared memory, "Writing to shared memory");





IPC POSIX Producer

```
#include <stdio.h>
#include <stlib.h>
#include <string.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>
int main()
  /* the size (in bytes) of shared memory object */
  const int SIZE 4096;
  /* name of the shared memory object */
  const char *name = "OS";
  /* strings written to shared memory */
  const char *message 0 = "Hello";
  const char *message 1 = "World!";
  /* shared memory file descriptor */
  int shm fd;
  /* pointer to shared memory obect */
  void *ptr;
```






IPC POSIX Producer (Cont.)

```
/* create the shared memory object */
shm fd = shm open(name, O CREAT | O RDRW, 0666);
/* configure the size of the shared memory object */
ftruncate(shm fd, SIZE);
/* memory map the shared memory object */
ptr = mmap(0, SIZE, PROT WRITE, MAP SHARED, shm fd, 0);
/* write to the shared memory object */
sprintf(ptr,"%s",message 0);
ptr += strlen(message 0);
sprintf(ptr,"%s",message 1);
ptr += strlen(message 1);
return 0;
```





IPC POSIX Consumer

```
#include <stdio.h>
#include <stlib.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>
int main()
  /* the size (in bytes) of shared memory object */
  const int SIZE = 4096;
  /* name of the shared memory object */
  const char *name = "OS";
  /* shared memory file descriptor */
  int shm fd;
  /* pointer to shared memory object */
  void *ptr;
```






IPC POSIX Consumer(Cont.)

```
/* open the shared memory object */
shm fd = shm open(name, O RDONLY, 0666);
/* memory map the shared memory object */
ptr = mmap(0, SIZE, PROT READ, MAP SHARED, shm fd, 0);
/* read from the shared memory object */
printf("%s",(char *)ptr);
/* remove the shared memory object */
shm unlink(name);
return 0;
}
```






Examples of IPC Systems - Mach

- Mach communication is message based
 - Even system calls are messages
 - Each task gets two mailboxes at creation- Kernel and Notify
 - Only three system calls needed for message transfer
 msg_send(), msg_receive(), msg_rpc()
 - Mailboxes needed for commuication, created via port allocate()
 - Send and receive are flexible, for example four options if mailbox full:
 - Wait indefinitely
 - Wait at most n milliseconds
 - Return immediately
 - Temporarily cache a message






Examples of IPC Systems – Windows

- Message-passing centric via advanced local procedure call (LPC) facility
 - Only works between processes on the same system
 - Uses ports (like mailboxes) to establish and maintain communication channels
 - Communication works as follows:
 - The client opens a handle to the subsystem's connection port object.
 - ▶ The client sends a connection request.
 - The server creates two private communication ports and returns the handle to one of them to the client.
 - The client and server use the corresponding port handle to send messages or callbacks and to listen for replies.






Local Procedure Calls in Windows XP



3.55





Communications in Client-Server Systems

- Sockets
- Remote Procedure Calls
- Pipes
- Remote Method Invocation (Java)





Sockets


- A socket is defined as an endpoint for communication
- Concatenation of IP address and port a number included at start of message packet to differentiate network services on a host
- The socket **161.25.19.8:1625** refers to port **1625** on host **161.25.19.8**
- Communication consists between a pair of sockets
- All ports below 1024 are well known, used for standard services
- Special IP address 127.0.0.1 (loopback) to refer to system on which process is running



3.57



Socket Communication





Sockets in Java

- Three types of sockets
 - **Connection-oriented** (TCP)
 - **Connectionless (UDP)**
 - MulticastSocket class data can be sent to multiple recipients
- Consider this "Date" server:

```
import java.net.*;
import java.io.*;
public class DateServer
  public static void main(String[] args) {
     try {
       ServerSocket sock = new ServerSocket(6013);
       /* now listen for connections */
       while (true) {
          Socket client = sock.accept();
          PrintWriter pout = new
           PrintWriter(client.getOutputStream(), true);
          /* write the Date to the socket */
          pout.println(new java.util.Date().toString());
          /* close the socket and resume */
          /* listening for connections */
          client.close();
     catch (IOException ioe) {
       System.err.println(ioe);
```




Remote Procedure Calls

- Remote procedure call (RPC) abstracts procedure calls between processes on networked systems
 - Again uses ports for service differentiation
- Stubs client-side proxy for the actual procedure on the server
- The client-side stub locates the server and marshalls the parameters
- The server-side stub receives this message, unpacks the marshalled parameters, and performs the procedure on the server
- On Windows, stub code compile from specification written in Microsoft Interface Definition Language (MIDL)
- Data representation handled via External Data Representation (XDL) format to account for different architectures
 - Big-endian and little-endian
- Remote communication has more failure scenarios than local
 - Messages can be delivered exactly once rather than at most once
- OS typically provides a rendezvous (or matchmaker) service to connect client and server



Execution of RPC







Pipes

Acts as a conduit allowing two processes to communicate

Issues


- Is communication unidirectional or bidirectional?
- In the case of two-way communication, is it half or full-duplex?
- Must there exist a relationship (i.e. parent-child) between the communicating processes?
- Can the pipes be used over a network?





Ordinary Pipes

- n Ordinary Pipes allow communication in standard producer-consumer style
- Producer writes to one end (the write-end of the pipe)
 Consumer reads from the other end (the read-end of the pipe)
- n Ordinary pipes are therefore unidirectional
- n Require parent-child relationship between communicating processes



- n Windows calls these anonymous pipes
- n See Unix and Windows code samples in textbook





Named Pipes

- Named Pipes are more powerful than ordinary pipes
- Communication is bidirectional
- No parent-child relationship is necessary between the communicating processes
- Several processes can use the named pipe for communication
- Provided on both UNIX and Windows systems



End of Chapter 3

