
Chapter 3 Transport Layer



Computer Networking: A Top Down Approach 5th edition. Jim Kurose, Keith Ross Addison-Wesley, April 2009.

Transport Layer 3-1

Chapter 3: Transport Layer

Our goals:

- understand principles behind transport layer services:
 - multiplexing/demultipl exing
 - o reliable data transfer
 - flow control
 - congestion control
- learn about transport layer protocols in the Internet:
 - UDP: connectionless transport
 - TCP: connection-oriented transport
 - TCP congestion control

Chapter 3 outline


- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer

2 2

Transport services and protocols

- provide logical communication between app processes running on different hosts
- transport protocols run in end systems
 - send side: breaks app messages into segments, passes to network layer
 - rcv side: reassembles segments into messages, passes to app layer
- more than one transport protocol available to apps
 - Internet: TCP and UDP



Transport vs. network layer

- network layer: logical communication between hosts
- transport layer: logical communication between processes
 - relies on, enhances, network layer services

Household analogy:


- 12 kids sending letters to 12 kids
- processes = kids
- app messages = letters in envelopes
- □ hosts = houses
- transport protocol = Ann and Bill
- network-layer protocolpostal service

Transport Layer

3-5

Internet transport-layer protocols

- reliable, in-order delivery (TCP)
 - congestion control
 - flow control
 - connection setup
- unreliable, unordered delivery: UDP
 - no-frills extension of "best-effort" IP
- services not available:
 - delay guarantees
 - bandwidth guarantees




Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control


Transport Layer

3-7



How demultiplexing works

- host receives IP datagrams
 - each datagram has source IP address, destination IP address
 - each datagram carries 1 transport-layer segment
 - each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

Transport Layer

3-9

Connectionless demultiplexing

Create sockets with port numbers:


DatagramSocket mySocket1 = new
 DatagramSocket(12534);

DatagramSocket mySocket2 = new
 DatagramSocket(12535);

UDP socket identified by two-tuple:


(dest IP address, dest port number)


- When host receives UDP segment:
 - checks destination port number in segment
 - directs UDP segment to socket with that port number
- □ IP datagrams with different source IP addresses and/or source port numbers directed to same socket



Connection-oriented demux

- TCP socket identified by 4-tuple:
 - source IP address
 - source port number
 - o dest IP address
 - o dest port number
- receiving host uses all four values to direct segment to appropriate socket
- Server host may support many simultaneous TCP sockets:
 - each socket identified by its own 4-tuple
- Web servers have different sockets for each connecting client
 - non-persistent HTTP will have different socket for each request





Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control


Transport Layer 3-15

UDP: User Datagram Protocol [RFC 768]

- "no frills," "bare bones" Internet transport protocol
- "best effort" service, UDP segments may be:
 - lost
 - delivered out of order to app
- connectionless:
 - no handshaking between UDP sender, receiver
 - each UDP segment handled independently of others

Why is there a UDP?

- no connection establishment (which can add delay)
- simple: no connection state at sender, receiver
- small segment header
- no congestion control: UDP can blast away as fast as desired



UDP checksum

<u>Goal:</u> detect "errors" (e.g., flipped bits) in transmitted segment

Sender:

- treat segment contents as sequence of 16-bit integers
- checksum: addition (1's complement sum) of segment contents
- sender puts checksum value into UDP checksum field

Receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
 - NO error detected
 - YES no error detected.
 But maybe errors nonetheless? More later

....

Internet Checksum Example

- □ Note
 - When adding numbers, a carryout from the most significant bit needs to be added to the result
- Example: add two 16-bit integers

					_	_		0	_	_			_	-			_
wraparound	1	1	0	1	1	1	0	1	1	1	0	1	1	1	0	1	1
sum checksum								1									


Transport Layer 3-19

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - o connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Principles of Reliable data transfer

- □ important in app., transport, link layers
- □ top-10 list of important networking topics!




- (a) provided service
- characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)


Transport Layer 3-21


Principles of Reliable data transfer

- important in app., transport, link layers
- top-10 list of important networking topics!




 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)







Reliable data transfer: getting started We'll: incrementally develop sender, receiver sides of reliable data transfer protocol (rdt) consider only unidirectional data transfer • but control info will flow on both directions! use finite state machines (FSM) to specify sender, receiver event causing state transition actions taken on state transition state: when in this state state "state" next state event uniquely determined 2 actions by next event Transport Layer 3-25




Rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
 - o checksum to detect bit errors
- the question: how to recover from errors:
 - acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
 - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
 - o sender retransmits pkt on receipt of NAK
- new mechanisms in rdt2.0 (beyond rdt1.0):
 - o error detection
 - o receiver feedback: control msgs (ACK,NAK) rcvr->sender







rdt2.0 has a fatal flaw!

What happens if ACK/NAK corrupted?


- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate


Handling duplicates:

- sender retransmits current pkt if ACK/NAK garbled
- sender adds sequence number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt

stop and wait

Sender sends one packet, then waits for receiver response





rdt2.1: discussion

Sender:


- seq # added to pkt
- two seq. #'s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- □ twice as many states
 - state must "remember" whether "current" pkt has 0 or 1 seq. #

Receiver:

- must check if received packet is duplicate
 - state indicates whether0 or 1 is expected pktseq #
- note: receiver can not know if its last ACK/NAK received OK at sender

rdt2.2: a NAK-free protocol

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
 - o receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt



rdt3.0: channels with errors and loss

New assumption:


underlying channel can also lose packets (data or ACKs)


 checksum, seq. #, ACKs, retransmissions will be of help, but not enough <u>Approach:</u> sender waits "reasonable" amount of time for ACK

- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
 - retransmission will be duplicate, but use of seq. #'s already handles this
 - receiver must specify seq # of pkt being ACKed
- requires countdown timer

Transport Layer 3-37

rdt3.0 sender rdt_send(data) rdt rcv(rcvpkt) && sndpkt = make_pkt(0, data, checksum) (corrupt(rcvpkt) || udt_send(sndpkt) isACK(rcvpkt,1)) start_timer rdt_rcv(rcvpkt) Wait Wait for timeout for call Ofrom udt_send(sndpkt) ACK0 above start_timer rdt_rcv(rcvpkt) && notcorrupt(rcvpkt) rdt_rcv(rcvpkt) && isACK(rcvpkt,1) && notcorrupt(rcvpkt) && isACK(rcvpkt,0) stop_timer stop_timer Wait Wait for timeout for call 1 from udt_send(sndpkt) ACK1 above rdt_rcv(rcvpkt) start_timer rdt_send(data) rdt_rcv(rcvpkt) && sndpkt = make_pkt(1, data, checksum) (corrupt(rcvpkt) || udt_send(sndpkt) isACK(rcvpkt,0)) start_timer Transport Layer 3-38





Performance of rdt3.0


- rdt3.0 works, but performance stinks
- □ ex: 1 Gbps link, 15 ms prop. delay, 8000 bit packet:

$$d_{trans} = \frac{L}{R} = \frac{8000 \text{bits}}{10^9 \text{ bps}} = 8 \text{ microseconds}$$

O U sender: utilization - fraction of time sender busy sending

$$U_{sender} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$


- o 1KB pkt every 30 msec → 33kB/sec thruput over 1 Gbps link
- o network protocol limits use of physical resources!




Pipelined protocols

Pipelining: sender allows multiple, "in-flight", yet-tobe-acknowledged pkts

- o range of sequence numbers must be increased
- o buffering at sender and/or receiver



■ Two generic forms of pipelined protocols: go-Back-N, selective repeat



Pipelining Protocols

Go-back-N: overview

- sender: up to N unACKed pkts in pipeline
- □ receiver: only sends cumulative ACKs
 - doesn't ACK pkt if there's a gap
- sender: has timer for oldest unACKed pkt
 - if timer expires: retransmit all unACKed packets

Selective Repeat: overview


- sender: up to N unACKed packets in pipeline
- receiver: ACKs individual pkts
- sender: maintains timer for each unACKed pkt
 - if timer expires: retransmit only unACKed packet

Transport Layer 3-45


Go-Back-N


Sender:


- k-bit seq # in pkt header
- "window" of up to N, consecutive unACKed pkts allowed



- $\hfill \square$ ACK(n): ACKs all pkts up to, including seq # n "cumulative ACK"
 - may receive duplicate ACKs (see receiver)
- timer for each in-flight pkt
- timeout(n): retransmit pkt n and all higher seq # pkts in window











Selective Repeat

- receiver individually acknowledges all correctly received pkts
 - buffers pkts, as needed, for eventual in-order delivery to upper layer
- sender only resends pkts for which ACK not received
 - o sender timer for each unACKed pkt
- sender window
 - N consecutive seq #'s
 - o again limits seq #s of sent, unACKed pkts









Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer
- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- □ 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer 3-55

TCP: Overview

RFCs: 793, 1122, 1323, 2018, 2581

full duplex data:

- point-to-point:
 - o one sender, one receiver
- reliable, in-order byte steam:
 - no "message boundaries"
- pipelined:
 - TCP congestion and flow control set window size
- send & receive buffers

handshaking (exchange

connection-oriented:


of control msgs) init's sender, receiver state before data exchange


bi-directional data flow in same connection


MSS: maximum segment

flow controlled:

o sender will not overwhelm receiver







TCP Round Trip Time and Timeout

- Q: how to set TCP timeout value?
- longer than RTT
 - but RTT varies
- too short: premature timeout
 - unnecessary retransmissions
- too long: slow reaction to segment loss


- Q: how to estimate RTT?
- □ SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT

Transport Layer 3-59

TCP Round Trip Time and Timeout

EstimatedRTT = $(1-\alpha)$ *EstimatedRTT + α *SampleRTT

- Exponential weighted moving average
- influence of past sample decreases exponentially fast
- \Box typical value: $\alpha = 0.125$



TCP Round Trip Time and Timeout

Setting the timeout

- EstimtedRTT plus "safety margin"
 - large variation in EstimatedRTT -> larger safety margin
- first estimate of how much SampleRTT deviates from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

Then set timeout interval:

TimeoutInterval = EstimatedRTT + 4*DevRTT

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer 3-63

TCP reliable data transfer

- TCP creates rdt service on top of IP's unreliable service
- pipelined segments
- cumulative ACKs
- TCP uses single retransmission timer
- retransmissions are triggered by:
 - timeout events
 - o duplicate ACKs
- initially consider simplified TCP sender:
 - ignore duplicate ACKs
 - ignore flow control, congestion control

TCP sender events:

data rcvd from app:

- create segment with
 seg #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running (think of timer as for oldest unACKed segment)
- expiration interval:

TimeOutInterval

timeout:

- retransmit segment that caused timeout
- restart timer

ACK rcvd:

- if acknowledges previously unACKed segments
 - update what is known to be ACKed
 - start timer if there are outstanding segments


Transport Layer 3-65


```
NextSeqNum = InitialSeqNum
SendBase = InitialSeqNum
loop (forever) {
  switch(event)
  event: data received from application above
      create TCP segment with sequence number NextSeqNum
      if (timer currently not running)
          start timer
      pass segment to IP
      NextSeqNum = NextSeqNum + length(data)
   event: timer timeout
      retransmit not-yet-acknowledged segment with
           smallest sequence number
   event: ACK received, with ACK field value of y
      if (y > SendBase) {
          SendBase = y
         if (there are currently not-yet-acknowledged segments)
 } /* end of loop forever */
```

TCP sender

Comment:

- SendBase-1: last cumulatively ACKed byte <u>Example:</u>
- SendBase-1 = 71;
 y= 73, so the rcvr
 wants 73+;
 y > SendBase, so
 that new data is
 ACKed





TCP ACK generat	ion [RFC 1122, RFC 2581]
Event at Receiver	TCP Receiver action
Arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	Delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
Arrival of in-order segment with expected seq #. One other segment has ACK pending	Immediately send single cumulative ACK, ACKing both in-order segments
Arrival of out-of-order segment higher-than-expect seq. # . Gap detected	Immediately send duplicate ACK, indicating seq. # of next expected byte

Transport Layer 3-69

Fast Retransmit

Arrival of segment that


partially or completely fills gap

- time-out period often relatively long:
 - long delay before resending lost packet
- ☐ detect lost segments via duplicate ACKs.
 - sender often sends many segments back-toback
 - if segment is lost, there will likely be many duplicate ACKs for that segment
- If sender receives 3 ACKs for same data, it assumes that segment after ACKed data was lost:

Immediate send ACK, provided that

segment starts at lower end of gap

 <u>fast retransmit:</u> resend segment before timer expires



Fast retransmit algorithm: event: ACK received, with ACK field value of y if (y > SendBase) { SendBase = y if (there are currently not-yet-acknowledged segments) start timer } else { increment count of dup ACKs received for y if (count of dup ACKs received for y = 3) { resend segment with sequence number y } a duplicate ACK for already ACKed segment

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer 3-73

TCP Flow Control

receive side of TCP connection has a receive buffer:




 app process may be slow at reading from buffer

flow control

sender won't overflow receiver's buffer by transmitting too much, too fast

 speed-matching service: matching send rate to receiving application's drain rate

TCP Flow control: how it works



(suppose TCP receiver discards out-of-order segments)

- unused buffer space:
- = rwnd
- = RcvBuffer-[LastByteRcvd LastByteRead]

- receiver: advertises unused buffer space by including rwnd value in segment header
- sender: limits # of unACKed bytes to rwnd
 - guarantees receiver's buffer doesn't overflow

Transport Layer 3-75

Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

TCP Connection Management

Recall: TCP sender, receiver establish "connection" before exchanging data segments

- initialize TCP variables:
 - o seq. #s
 - buffers, flow control info (e.g. RcvWindow)
- client: connection initiator
 Socket clientSocket = new
 Socket("hostname","port
 number");
- server: contacted by client
 Socket connectionSocket =
 welcomeSocket.accept();

Three way handshake:

- <u>Step 1:</u> client host sends TCP SYN segment to server
 - specifies initial seq #
 - o no data

<u>Step 2:</u> server host receives SYN, replies with SYNACK segment

- server allocates buffers
- specifies server initial seq. #

<u>Step 3:</u> client receives SYNACK, replies with ACK segment, which may contain data

Transport Layer 3-77


TCP Connection Management (cont.)

Closing a connection:


client closes socket:
 clientSocket.close();

Step 1: client end system sends TCP FIN control segment to server

Step 2: server receives FIN, replies with ACK. Closes connection, sends FIN.



TCP Connection Management (cont.) 🜉 client Step 3: client receives FIN, server 💹 replies with ACK. closing FIN O Enters "timed wait" will respond with ACK to received FINs ACK closing FIN Step 4: server, receives ACK. Connection closed. timed wait ACK Note: with small closed modification, can handle simultaneous FINs. closed Transport Layer 3-79



Chapter 3 outline


- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - o connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control


Transport Layer 3-81


Principles of Congestion Control


Congestion:

- □ informally: "too many sources sending too much data too fast for *network* to handle"
- □ different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- □ a top-10 problem!














another "cost" of congestion:

■ when packet dropped, any "upstream transmission capacity used for that packet was wasted!

Transport Layer 3-87

Approaches towards congestion control

two broad approaches towards congestion control:

end-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

network-assisted congestion control:

- routers provide feedback to end systems
 - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
 - explicit rate sender should send at

Case study: ATM ABR congestion control

ABR: available bit rate:


- "elastic service"
- if sender's path "underloaded":
 - sender should use available bandwidth
- if sender's path congested:
 - sender throttled to minimum guaranteed rate

RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
 - NI bit: no increase in rate (mild congestion)
 - CI bit: congestion indication
- RM cells returned to sender by receiver, with bits intact

Transport Layer 3-89

Case study: ATM ABR congestion control



- □ two-byte ER (explicit rate) field in RM cell
 - o congested switch may lower ER value in cell
 - o sender' send rate thus maximum supportable rate on path
- □ EFCI bit in data cells: set to 1 in congested switch
 - if data cell preceding RM cell has EFCI set, sender sets CI bit in returned RM cell

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control


Transport Layer 3-91

TCP congestion control:

- goal: TCP sender should transmit as fast as possible, but without congesting network
 - Q: how to find rate *just* below congestion level
- decentralized: each TCP sender sets its own rate, based on *implicit* feedback:
 - ACK: segment received (a good thing!), network not congested, so increase sending rate
 - lost segment: assume loss due to congested network, so decrease sending rate

TCP congestion control: bandwidth probing

- "probing for bandwidth": increase transmission rate on receipt of ACK, until eventually loss occurs, then decrease transmission rate
 - continue to increase on ACK, decrease on loss (since available bandwidth is changing, depending on other connections in network)



- Q: how fast to increase/decrease?
 - o details to follow

Transport Layer 3-93


TCP Congestion Control: details

sender limits rate by limiting number of unACKed bytes "in pipeline":

LastByteSent-LastByteAcked ≤ cwnd

- o cwnd: differs from rwnd (how, why?)
- o sender limited by min(cwnd,rwnd)
- roughly,

 cwnd is dynamic, function of perceived network congestion



TCP Congestion Control: more details

segment loss event: reducing cwnd

- □ timeout: no response from receiver
 - o cut cwnd to 1
- 3 duplicate ACKs: at least some segments getting through (recall fast retransmit)
 - o cut cwnd in half, less aggressively than on timeout


ACK received: increase cwnd

- slowstart phase:
 - increase exponentially fast (despite name) at connection start, or following timeout
- congestion avoidance:
 - increase linearly

Transport Layer 3-95

TCP Slow Start


- when connection begins, cwnd = 1 MSS
 - example: MSS = 500 bytes & RTT = 200 msec
 - o initial rate = 20 kbps
- available bandwidth may be >> MSS/RTT
 - o desirable to quickly ramp up to respectable rate
- increase rate exponentially until first loss event or when threshold reached
 - double cwnd every RTT
 - o done by incrementing cwnd by 1 for every ACK received



Transitioning into/out of slowstart

 ${\tt ssthresh:}$ cwnd threshold maintained by ${\tt TCP}$

- on loss event: set ssthresh to cwnd/2
 - o remember (half of) TCP rate when congestion last occurred
- when cwnd >= ssthresh: transition from slowstart to congestion avoidance phase



Transport Layer 3-97


TCP: congestion avoidance


- when cwnd > ssthresh grow cwnd linearly
 - increase cwnd by 1MSS per RTT
 - approach possible congestion slower than in slowstart
 - implementation: cwnd
 cwnd + MSS/cwnd
 for each ACK received


AIMD

- ACKs: increase awnd by 1 MSS per RTT: additive increase
- □ loss: cut cwnd in half (non-timeout-detected loss): multiplicative decrease

AIMD: Additive Increase Multiplicative Decrease







Summary: TCP Congestion Control

- when cwnd < ssthresh, sender in slow-start phase, window grows exponentially.
- when cwnd >= ssthresh, sender is in congestionavoidance phase, window grows linearly.
- when triple duplicate ACK occurs, ssthresh set to cwnd/2, cwnd set to ~ ssthresh
- when timeout occurs, ssthresh set to cwnd/2, cwnd set to 1 MSS.

TCP throughput

- what's average throughout of TCP as function of window size, RTT?
 - o ignoring slow start
- □ let W be window size when loss occurs.
 - when window is W, throughput is W/RTT
 - just after loss, window drops to W/2, throughput to W/2RTT.
 - oaverage throughout: .75 W/RTT

Transport Layer 3-103

TCP Futures: TCP over "long, fat pipes"


- example: 1500 byte segments, 100ms RTT, want 10
 Gbps throughput
- requires window size W = 83,333 in-flight segments
- throughput in terms of loss rate:

$$\frac{1.22 \cdot MSS}{RTT\sqrt{L}}$$

- □ → L = 2·10⁻¹⁰ Wow
- new versions of TCP for high-speed



fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K




Transport Layer 3-105

Why is TCP fair?

Two competing sessions:

- □ Additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



Fairness (more)

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - pump audio/video at constant rate, tolerate packet loss

<u>Fairness and parallel TCP</u> connections

- nothing prevents app from opening parallel connections between 2 hosts.
- web browsers do this
- example: link of rate R supporting 9 connections;
 - new app asks for 1 TCP, gets rate R/10
 - new app asks for 11 TCPs, gets R/2!

Transport Layer 3-107

Chapter 3: Summary

- principles behind transport layer services:
 - multiplexing, demultiplexing
 - o reliable data transfer
 - o flow control
 - congestion control
- instantiation and implementation in the Internet
 - o UDP
 - **O** TCP

Next:

- leaving the network "edge" (application, transport layers)
- □ into the network "core"