

RASTERIZER

Version 1.23

5 October 2021

About	3
Using the editor	4
Voxel Rasterizer	4
Mesh Creator	6
Texture 2D Creator	7
Texture 3D Creator	7
Particle System Creator	8
MagicaVoxel Exporter	8
Point Cloud Exporter	8
Using the programming interface	9
namespace Voxels	9
class Voxels.Rasterizer.Settings	9
class Voxels.Rasterizer	11
<pre>interface Voxels.RasterizerBase.IRasterizerSupport</pre>	14
<pre>interface Voxels.RasterizerBase.IProcessorSupport</pre>	15
abstract class Voxels.Processor	15
class Voxels.Processor.MaterialReducer	16
class Voxels.Rasterizer.Engine	17
class Voxels.Storage	19
class Voxels.Storage.Iterator	22
class Voxels.HSVColor	22

About

"Voxels: Rasterizer" is a plug-in extension for the Unity engine and development environment (www.unity.com). It utilizes the graphics hardware to rasterize renderer objects into a three-dimensional grid instead of a 2D planar surface, which is done to present them on a screen or to compute effects most of all. As opposed to other existing solutions it is able to bake a lot of shading and lighting conditions into the target color of every grid cell at the moment of the processing. Such cells are called voxels, which is a composition of **vo**lume and pi**xels**. You can use them to display grid aligned (e.g., blocky) models or particles, which are generated from existing assets. Those particles can be used to create visual effects in combination with the original objects or you transfer the data to an existing voxel engine respectively a rendering framework.

The extension is executable in the editor and at runtime and therefore provides an inspector and a programming interface, which can be accessed from other scripts. And the complete package includes two sample processing classes, which export the collect information to popular file formats, and three, which are converting the gathered data to visible game objects. One creates a hierarchy of meshes while another passes the grid elements to a particle system. The last stores color data to a 2D texture and can be used to highly optimize the meshes, which are created by the first one. You are able to adapt the existing examples or write your own processor scripts using the derivation from a base class. However, the provided processors are already capable of creating assets that are applicable in the production.

Unfortunately, not all rendering features can be baked into the final voxel colors because the culling system of Unity hides them in the scanning process. Known issues are dynamic shadow maps and particles. The first one can still be applied to converted voxel objects but cannot be included in the color of the object itself. We are still looking for workarounds or alternative rendering methods to be provide the support in future releases.


Universal and High Definition Render Pipeline are being supported by the newest version of this tool. That means that you can convert assets, which are being displayed in one of both or the standard pipeline. Collected data or generated objects can be interchanged as usual but you may have to update the assigned materials.

If you are using a proprietary scriptable render pipeline, then there is no direct support because the extension does not know how to manipulate it. But there are interfaces, which can help to implement the support by your own. Alternatively, assets can be converted using another pipeline. At least the meshes can be transferred between projects by storing the results into files and importing them afterwards. Or you store the actual cell data and load them later using scripts.

Using the editor

Voxel Rasterizer

After you have imported the package to your Unity project, you can attach the Rasterizer plug-in to any game object, even multiple times. In the hierarchy any object under the modified one or the modified one itself should contain a visual component like a mesh renderer or a terrain. Otherwise, nothing could be sampled to the volume grid.



Voxel Rasterizer shows the current progress.

You get an inspector for every converter instance. If you turn the switch off, it will not be automatically executed at the start of the scene.

Boundaries: *Minimum* and *Maximum* are the limiting 3D vectors of the volume in the scene, which is being scanned for voxels. By pressing on the *Adopt from object* button both values are measured by combining the current bounds of all attached objects.

Voxel Size: This is the extent of one grid cell in the space of the scene.

Voxel Counts: It describes the number of columns, rows and slices the volume grid contains.

Voxel Size and *Voxel Counts* are affecting one another, where the counts are the outcome of the total volume and the single cell size.

Sampling Count: Super-sampling can be used to scan the source object(s) in higher resolution and generate finer color results by combining multiple neighbor samples into one target voxel. The value here is a factor for each dimension, so 2x needs to render eight times the amount of pixels compared to factor 1 for example.


Voxel Overscan: That percentage value increases the depth of currently scanned layer, which can be helpful if the graphics hardware produces errors in rendering so that some voxels will be missing. It happens for terrains if the details become too small because the resolution is high.

Baking Mode: The shaded colors of a source object can be interpreted in various ways. By using *Original Material* the color is not baked at all. The source material, which is located at a cell, is transferred directly to its voxel. On the contrary *Averaged Color*, *Darkest Color* and *Brightest Color* burn the shaded result color to a material, which is used in association with renderer of the single voxel. *Most Frequent Color* works similar but does not simply averages all detected cell colors or builds the mini- or maximum of them but filters by the amount of their occurrences.

Opaque Template: This option only appears if you have selected a color baking mode. You can specify a default material, which is used, if the alpha value of the grid cell is 1. This means that the voxel is originally not a transparent one. Without a selection a standard legacy material is created.

Opaque Threshold: The value in the edit field defines a limit of the alpha value of cell, above which the opaque material is assigned.

Transparent Template: Comparable to *Opaque Template* it allows the choice of a material, which is used for semi-transparent cells, which means that the alpha value is between 0 and 1.



Rasterizer inspector with all properties

every processor using this handler.

Transparent Threshold: Here you can find an editable upper limit for alpha values, which will be defined as completely transparent. For the voxels between both thresholds transparent materials are being used.

Main Color / Specular Color / Emissive Color: Here you can select, which component of the applied material is modulated by the result color of the baking.

Saturation: This factor allows the manipulation of the result color by making it more or less colorful.

Brightness: A material can be made darker or lighter by modifying it.

The next six arguments are handlers, in which you can specify script methods, which are being called, when events occur.

On Object Preparing: This event is being executed right before a source object will be added to the processing queue. Here you could modify it or adjust the rasterizer instance to interoperate the way you want to.


On Rasterizer Started: It is called when this rasterizer starts the scanning step.

On Processor Started: After scanning and data processing in the rasterizer the result is transferred to attached processors. Whenever this happens a script method can be informed for

On Object Created: When a processor creates a result instance and informs the rasterizer about it, it can be forwarded here.


On Processor Finished: If a processor has ended, then it is handled here.

On Rasterizer Finished: And when the transaction of the rasterizer including all processors is completed, methods can be called from here, for example to hide the source object or start using the result(s).



Rasterizer inspector at runtime while processing

Process / **Processing...** / **Waiting...:** That button starts or stops the conversion of the selected object from the editor. It also shows the current state: *Processing...* signals that the object is currently being processed and shows the progress, whereas *Waiting...* represents that another object is currently



Rasterizer inspector at runtime while waiting for another instance to finish

in conversion and indicates the position in the queue. At runtime, the button does not appear and will be replaced by a progress bar during the conversion.

Frame Time Target: This is a global setting, which affects all converter instances and adjusts the aimed frame rate. Because the processing cannot be done in real-time it happens in cooperation with the other workload of Unity and your scene. The approximate value allows you to specify to amount of time, which should be used for total processing between two frames, but it can be more in complex scenarios.


At last, there is a box with some information about the volume size, the grid resolution and maximum

count of resulting voxels, if all grid cells would get filled. You can make use of the data to adapt setting for a target specification.

Multi Threading: Enabling that flag can shorten processing time by using more CPU cores. If you encounter issues, you may need to disable it.

Mesh Creator

One of the three sample processor scripts constructs a hierarchy of meshes from the data, which has been collected by the converter instance. That instance transfers gathered voxels to active processor



Mesh Creator inspector

components, which are attached at the same game object as the converter.

Voxel Mesh: You have to select a template, which is used to represent a voxel. Most often a cube might be the general choice. Nevertheless, you are able to

choose any imported mesh asset like a sphere. But beware of the vertex / polygon count: Thousands of voxels multiplied by thousands of triangles turn into millions of polygons that need to be processed per frame.

Size Factor: That value increases or decreases the extent of one cell mesh, which is normalized to fit the voxel size declared in the converter.

Static Containers: It is a flag, which is copied to new game object that will be created during the processing. If you want to animated single voxels, you should turn it off.

Merge Meshes: Multiple voxels that share the same material will be merged into larger meshes. So single cells cannot be moved by individual game object transform components any longer, but shaders can be used to do so.

Opaque Only: Whenever *Merge Meshes* is enabled that flag skips the combination of voxels, which have got semi-transparent alpha values. This is important if you want to retain the correct blending order from camera view with the standard Unity solution.

Texture: *Main / Emissive:* Either the script builds a Texture2D object or uses the attached component, if its *Voxel Mesh Usage* flag is active, and replaces the corresponding texture on the materials, which are being applied to the target objects. That way different colors can be used without the need for various material instances, which will result in much better performance for merged meshes.

Vertex Colors: Comparable in the effect of *Main: Texture / Emissive* the collected voxel colors are stored to the vertices of the result mesh(es). But you need to set a template material with a shader, which can handle them.

Target Name: The main container of the target object is named after the string, which is given here.

Asset Files: Here you can specify a relative path name to store a prefab file with the result. Besides this file a folder of the same name with meshes, materials and texture is being created.

Texture 2D Creator

Mentioned above this class stores all unique colors, which had been sampled before, into a twodimensional texture.

Power of Two: The resulting Unity texture will have a 2ⁿ width and height.



Target File: Select a format, if you want the store the texture content into a file. That way you are able to edit it afterwards or reuse it in a project.

2D Texture Creator inspector

File Path: Path name of the image file

Mesh Creator Usage: Link this instance to all Mesh Creator components of the same object, so that texture coordinates can be transferred to the mesh representing the voxel structure.

Texture 3D Creator

Unlike the previous component, which only stores the cell colors of, this one maintains the structure of the original object by also including empty texels.



Supersampling Count: Number of source cells in each dimension, which are merged into one target voxel by averaging the color values.

3D Texture Creator inspector

Power of Two: The resulting Unity texture will have a 2ⁿ width, height and depth.

Expand Edges: Fill empty texels with the color of the nearest neighbor cell(s). This is useful for creating mip-maps so that edges do not blend into the background color the higher the sub-level gets.

Target File: Select a format, if you want the store the texture content into a file. That way you are able to edit it afterwards or reuse it in a project. *For Unity 2020.2 and higher:* Unless "Asset" is chosen the 3D texture is converted into a two-dimensional one because the file formats are made for 2D.

File Path: Path name of the target image file

Particle System Creator

The next sample class builds a system of particles using the incoming data. You are able to combine it with other processors, so that the same data is processed into different objects.



Enabled: Equally to Voxel Mesh it activates or deactivates the processing of the component.

Particle System Creator inspector

Object Template: That needs to be game object

instance with a predefined particle system, which is instantiated as a new one for the target.

Size Factor: It is the factor, which is multiplied with the standard particle size of a voxel cell.

Target Name: The recently instantiated template gets the stated name.

MagicaVoxel Exporter

In contrast to the previous processors that one does not create data inside of Unity or the app. Instead,



MagicaVoxel Exporter inspector

a file in the format of MagicaVoxel, which is a popular voxel editor, with the specified path name is written. You can import the data, which had been generated by the Rasterizer, into the program

afterwards.

Because of the restrictions of the format only 256x256x256 maximum voxels can be stored and the color amount is limited to 254. So the exporter has to reduce the collected materials before writing the results.

Point Cloud Exporter



Point Cloud Exporter inspector

The last sample class is comparable to the previous one but without the restrictions. All voxels are stored as a point cloud to a PLY file. Although it is called Polygon File Format no indices for connecting

vertices to define polygons are stored but regardless a lot of point cloud viewers and processing applications support that file format.

Using the programming interface

namespace Voxels

All structures, enumerations and classes of the extension are collected in that main namespace.

struct int int int	Vector x y z	A vector with a coordinate (column, line, slice) in voxel space
enum	BakingOperation Undefined OriginalMaterial AveragedColor DarkestColor BrightestColor MostFrequentColor	 Method to interpret sampled colors per volume cell Use material of the source object(s) Apply average, darkest, brightest or most frequent sampled color of a cell to a derived material

class Voxels.Rasterizer.Settings

This class is used to deliver scanning and properties to the engine.

UnityEngine.Bounds	bounds	Center and size of volume to scan
UnityEngine.Vector3	voxelSize	Size of a volume cell in scene space
Voxels.Vector	volumeResolution	Number of columns, rows and slices in the scan volume
float	voxel0verscan	Factor to increase depth of a scanning step
int	samplingResolution	Multi-sampling factor to render higher resolution into a voxel for better quality
UnityEngine.Camera	scanCameraTemplate	A camera component, which is used to render the source object slices
Voxels.BakingOperation	bakingOperationMode	Type of method to use for casting scanned material or color
UnityEngine.Material	opaqueTemplate	A material, which is used to apply non-transparent cell colors to
float	opaqueThreshold	Alpha value limit for source voxels, above which it is defined as opaque
UnityEngine.Material	transparentTemplate	A material, which is used to apply semitransparent cell colors to
float	transparentThreshold	Alpha value limit for source voxels, below which it is defined as invisible

bool	mainColorModulation	Flag to modulate main color of the instantiated material by the cell content
bool	specularColorModulation	Flag to modulate specular color of the instantiated material by the cell content
bool	emissiveColorModulation	Flag to modulate emissive color of the instantiated material by the cell content
float	saturationFactor	Modifies chroma of the cell color
float	brightnessFactor	Modifies luminosity of the cell color
bool	fillInterspace	This flag is implemented for a future feature and currently not in use.
float	budgetTime	Frame time target for that specific conversion (<0 for standard value)
bool	multiThreading	Use multiple CPU threads for the processing of the scanned data

There are no other methods beside the two constructors, which are quite similar. One is for setting the size per voxel, the other to use a target resolution for the complete volume.

Settings(

```
UnityEngine.Bounds bounds,
UnityEngine.Vector3 voxelSize,
float voxelOverscan,
int samplingResolution,
Voxels.BakingOperation bakingOperationMode,
UnityEngine.Material opaqueTemplate,
UnityEngine.Material tranparentTemplate,
bool mainColorModulation,
bool specularColorModulation,
bool emissiveColorModulation,
float saturationFactor,
float brightnessFactor,
float budgetTime = -1,
bool multiThreading = true,
float opaqueThreshold = 1,
float transparentThreshold = 0,
bool fillInterspace = false,
UnityEngine.Camera scanCameraTemplate = null
```

Initialize values including voxel size and set volume resolution to zero, which leads to an automatic calculation.

```
Settings(
      UnityEngine.Bounds bounds,
      Voxels. Vector volumeResolution,
      float voxelOverscan,
      int samplingResolution,
      Voxels.BakingOperation bakingOperationMode,
      UnityEngine.Material opaqueTemplate,
      UnityEngine.Material tranparentTemplate,
      bool mainColorModulation,
      bool specularColorModulation,
      bool emissiveColorModulation,
      float saturationFactor,
      float brightnessFactor,
      float budgetTime = -1,
      bool multiThreading = true,
      float opaqueThreshold = 1,
      float transparentThreshold = 0,
      bool fillInterspace = false,
      UnityEngine.Camera scanCameraTemplate = null
```

Initialize values including volume resolution and set voxel size to zero, which leads to an automatic calculation.

Parameters:

See member variables

class Voxels.Rasterizer

That is the instance for a game object to equip it with serializable conversion settings. The class is derived from Voxels.RasterizerBase and inherits the following properties.

UnityEngine.Vector3	minimumBound	Smaller edge of the volume to scan for voxels
UnityEngine.Vector3	maximumBound	Larger edge of the volume to scan for voxels
UnityEngine.Vector3	voxelSize	Extent of a voxel cell
float	voxelOverscan	Increasing depth factor for a scan slice
int	resolutionWidth	Number of columns in the volume
int	resolutionHeight	Number of rows in the volume
int	resolutionDepth	Number of slices in the volume
int	samplingResolution	Multi-sampling factor for every voxel

UnityEngine.Camera	scanCameraTemplate	Instance of a camera component to clone an instance for scanning from
Voxels.BakingOperation	bakingOperationMode	Method to process scanned materials / colors
UnityEngine.Material	opaqueTemplate	Material to use for non-transparent cells
float	opaqueThreshold	Limit of the alpha component, above which a cell receives an opaque material
UnityEngine.Material	transparentTemplate	Material to use for cells with alpha value smaller than one
float	transparentThreshold	Limit of the alpha component, above which a cell receives a transparent material
bool	mainColorModulation	Flag to multiply main color of the template / default material with scanned cell one
bool	specularColorModulation	Flag to multiply specular color of the template / default material with scanned cell one
bool	emissiveColorModulation	Flag to multiply emissive color of the template / default material with scanned cell one
float	saturationFactor	Value makes cell colors more or less colorful
float	brightnessFactor	Value makes cell colors brighter or darker
float	budgetTime	Target time to limit total computation per frame to

The following methods are defined in the base class.

bool Process()

Transfer the game object for voxel conversion to crafting singleton using the applied settings and attached processors.

Return Value:

true, if processing initialization could be successfully completed. false, if a failure occurred.

bool Stop()

End the conversion of the game object.

```
Return Value:
```

```
true, if game object has been successfully removed from processing. false, if object is not being processed.
```

```
float GetProgress(
    )
```

Read current conversion progress.

Return Value:

- > 1, if object is waiting to be processed.
- **0** ... **1**, if object is currently being processed.
- -1, if object is not included in the processing queue.

void RecomputeBounds()

Adopt boundaries of the volume, which is scanned for voxels, from the renderers of the game object and its children.

```
bool SetVoxelSize(
    float width
    float height,
    float depth
)
```

Change the size of a voxel cell in scene space. Calling this function invalids volume resolution values.

Return Value:

true, if arguments are valid.

Parameters:

widthheightdepthWidth of a voxelHeight of a voxelDepth of a voxel

```
bool SetVolumeResolution(
    int width,
    int height,
    int depth
)
```

Change the numbers of cell columns, rows and slices of the whole volume. Calling this function invalids voxel size values.

Return Value:

true, if arguments are valid.

Parameters:

bool IsVolumeResolutionDefined()

Check if volume resolution is set. Otherwise, the voxel size is used for generating cells.

Return Value:

true, if volume resolution is used to define number of scanning cells. false, if voxel size is used to calculate number of scanning cells.

```
Voxels.Processor[] GetActiveProcessors(
    )
```

Collect all **Voxels.Processor** instances, which are attached to the same game object as the rasterizer and being currently enabled.

Return Value:

Array of processor components, which will receive the resulting data after the cell collecting and therefore the work of the rasterizer has been finished.

interface Voxels.RasterizerBase.IRasterizerSupport

The interface is necessary to support specific behavior, which is usually the result of using the scriptable render pipeline. It is definitively utilized, if the HDRP is active.

In that method the camera for scanning the slices of the original objects must be prepared to work with the current render pipeline.

Parameters:

projectionCamera Instance of the camera, which is used for collecting voxel cell data

```
void PrepareWhiteScan(
     ref UnityEngine.Color backgroundColor
)
```

A scan is being done in two iterations to detect the transparency factor. One step is to render the source items in front of a white background, which is set up here.

Parameters:

backgroundColor

This argument holds the usual white color as input and must contain the color value, which is being set for rendering, at the exit.

In the other step a black background is used. The given color has to be transferred to the camera or renderer, so the rasterizer can finally compute the alpha component of a cell.

Parameters:

backgroundColor This argument holds a black color value as input.

interface Voxels.RasterizerBase.IProcessorSupport

Like the previous interface it becomes typically necessary when a scriptable render pipeline is in use. It aids the processing of the collected voxel data and is utilized for URP and HDRP.

To create a material, which is compatible with the current render pipeline, this method is required to generate a template one if they are not stored in the corresponding rasterizer property.

Return Value:

Instance of a material, which can be used in the currently active render pipeline

Parameters:

transparent

Flag to specify, if a semi-transparent or an opaque material should be created

If you are using a scriptable render pipeline other than the Universal or the High Definition one, you might have to provide one or both interfaces from above. Therefor a class derived from Voxels.RasterizerBase overwriting the next method must be implemented and used as component in your scene. You can also enhance the existing one.

```
void Initialize(
    out Voxels.RasterizerBase.IRasterizerSupport renderSupport,
    out Voxels.RasterizerBase.IProcessorSupport processorSupport
)
```

Set up the rasterizer so it can be utilized with the current render pipeline and return interfaces to support rasterizer and processors.

Parameters:

renderSupport Optional output of the interface to help rendering in the rasterizer **processorSupport** Optional output of the interface to create materials for processors

abstract class Voxels.Processor

This class is used as a base interface to implement functions to handle the voxel data, which had been collected by the engine right before. You can derive your own classes from it like Voxels.Mesh, Voxels.Texture2D, Voxels.ParticleSystem and the exporters are. You can have a look at them if you need references.

```
delegate void Informer(
          UnityEngine.Object[] objects,
          object parameter = null
     )
```

This is the definition of a callback function to inform the script, which has started the rasterizer, about the creation of Unity objects in a processor script.

objects Array of object, which have been created by the processor

parameter Optional parameter, which is passed through from the executing script to

informer function

bool process This flag indicates if the processor is

being executed by the engine.

```
float Build(
    Voxels.Storage voxels,
    UnityEngine.Bounds bounds,
    Voxels.Processor.Informer informer = null,
    object parameter = null
)
```

The method is repeatedly called to process incoming data until it signals the completion.

Return Value:

```
0 ... <1 is the current progress. Processing has not been finished.</li>>=1 signals the end of processing.
```

Parameters:

voxels Instance containing collected voxel data

bounds Boundaries, which have been used to scan the source object(s) and therefore

define the volume of the data

informer Method, your own script should call, whenever it creates target objects, so they

can be managed by the rasterizer.

parameter Argument, the script has to forward to the informer callback.

```
int GetPriority(
     )
```

Processors for a rasterizer with a lower value are being handled before those with a higher one.

Return Value:

The processor priority to determine the processing sequence

class Voxels.Processor.MaterialReducer

That inner processor class is a helper to decrease the amount of various materials. It combines materials with neighbor colors into single ones until the specified limit is reached.

int countLimit
)

Constructor expecting a runtime instance for co-processing, a list of source materials and the maximum amount of materials to return.

```
monoBehaviour
                       Mono-behaviour of the calling instance
inputMaterials
                       List of source materials to reduce
```

countLimit Maximum number of materials to generate

```
float GetProgress(
```

Obtain current processing progress value

Return Value:

Interpolation value between 0 and 1

```
bool GetResult(
      out UnityEngine.Material[] outputMaterials,
      out System.Collections.Generic.Dictionary<int, int> assignments
```

Receive array of output materials and an assignment table between input and output indices.

Return Value:

true, if processing has been finished and results are valid.

Parameters:

outputMaterials Array of merged materials

assignments Hash table containing indices of the source materials assigned to target ones

class Voxels.Rasterizer.Engine

For scanning and transferring the result data to processor classes a singleton of this type is created. You cannot instantiate it from outside but that is not necessary because the public methods are static and therefore no object is required to call them.

bool **Processing** Read-only property returns if the engine

is currently at work

UnityEngine.Bounds **ObjectBounds** Read-only property returns center and

size of source object, which is currently

being processed

```
bool Process(
      Voxels.Rasterizer converter,
      Voxels.Rasterizer.Settings settings,
      Voxels.Processor[] processors,
      Voxels.Processor.Informer informer = null,
      object parameter = null
      )
```

Append given voxel converter component altogether with settings and processor instance to waiting queue and start conversion, if previous entries have been completed or aborted.

Return Value:

true, if converter could be successfully added to the list.

converter Component of the source object, which should be converted

settings Conversion settings

processors Array of processor class instances, which handle the result data

informer Callback to be executed after a processor has finished generating a result

parameter Free defined parameter for the callback function

```
bool Process(
     UnityEngine.GameObject source,
     Voxels.Rasterizer.Settings settings,
     Voxels.Processor[] processors,
```

Voxels.Processor.Informer informer = null, object parameter = null

Append given game object altogether with settings and processor instance to waiting queue and start conversion, if previous entries have been completed or aborted. There is no converter instance used for enhanced access.

Return Value:

true, if converter could be successfully added to the list.

Parameters:

source Source object, which should be converted

settings Conversion settings

processors Array of processor class instances, which handle the result data

informer Callback to be executed after a processor has finished generating a result

parameter Free defined parameter for the callback function

Remove given voxel converter from processing queue.

Return Value:

true, if converter could be found in the waiting list or processing has been stopped.

Parameters:

converter Component of the

Component of the source object, whose conversion has to be canceled

```
float GetProgress(
          Voxels.Rasterizer converter
)
```

Retrieve current conversion progress for given converter instance.

Return Value:

- > 1, if object is waiting to be processed.
- **0** ... **1**, if object is currently being processed.
- -1, if object is not included in the processing queue.

Parameters:

converter Component of the source object, whose state is requested

```
bool IsActive(
     )
```

Method answers if the singleton is currently alive.

Return Value:

true, if engine instance exists.

Compute the bounding box of the given object and all its children.

Return Value:

Center and half size (Unity standard)

Parameters:

gameObject Top object to be measured

class Voxels.Storage

The result data is filed and can queried using this class.

int	Width	Read-only property returns number of cell columns
int	Height	Read-only property returns number of cell rows
int	Depth	Read-only property returns number of cell slices
int	FacesCount	Read-only property returns number of faces per cell (fixed to 6)
int	Count	Read-only property returns total number of stored cells

```
bool SetIndex(
    int x,
    int y,
    int z,
    UnityEngine.CubemapFace face,
    int index,
    int sx = 0,
    int sy = 0,
    int sz = 0
)
```

Store the given (material) index for the given direction to the given coordinate.

Return Value:

true, if cell content could be written.

```
Coordinate of the cell in volume space
  x, y, z
  face
                        Direction of the cell cube plane to store index for
  index
                        Value to write
                        Sub-sampling coordinate in cell space
  sx, sy, sz
bool SetColor(
       int x,
       int y,
       int z,
       UnityEngine.CubemapFace face,
       UnityEngine.Color color,
       int sx = 0,
       int sy = 0,
       int sz = 0
```

Store the given color value for the given direction to the given coordinate.

Return Value:

true, if cell content could be written.

Parameters:

```
x, y, z
                       Coordinate of the cell in volume space
                       Direction of the cell cube plane to store index for
  face
  color
                       Value to write
  sx, sy, sz
                       Sub-sampling coordinate in cell space
bool AddColor(
      int x,
      int y,
      int z,
      UnityEngine.CubemapFace face,
      UnityEngine.Color color,
      int sx = 0,
      int sy = 0,
      int sz = 0,
      Voxels.BakingOperation operationMode = Voxels.BakingOperation.Undefined
```

Include the given color value for the given direction to the given coordinate using the given or the internally stored baking mode.

Return Value:

true, if cell content could be written.

Parameters:

x, y, z	Coordinate of the cell in volume space
face	Direction of the cell cube plane to store index for
color	Value to account
sx, sy, sz	Sub-sampling coordinate in cell space
operationMode	Baking operation to use for applying input against existing color

```
UnityEngine.Material GetMaterial(
        [out UnityEngine.Color color,]
        int x,
        int y,
        int z,
        Voxels.BakingOperation operationMode = Voxels.BakingOperation.Undefined,
        int normalized = true
    )
```

Return the source material of the cell or a newly instantiated one with the optionally modulated color of the voxel with given coordinate.

Return Value:

An existing or a new material instance

Parameters:

color Cell color, which is being applied to template material or retrieved from source

one

x, **y**, **z** Coordinate of the cell in volume space

operationMode Baking operation to use for applying input against existing color

normalized Flag to remove pre-multiplication of alpha from red, green and blue components

```
UnityEngine.Material GetMaterial(
        [out UnityEngine.Color color,]
        out int x,
        out int y,
        out int z,
        int index,
        Voxels.BakingOperation operationMode = Voxels.BakingOperation.Undefined,
        int normalized = true
```

Return the source material of the cell or a newly instantiated one with the optionally modulated color of the voxel with given index.

Return Value:

An existing or a new material instance

Parameters:

color Cell color, which is being applied to template material or retrieved from source

one

x, y, z Coordinate output of the cell in volume space

index Number of the voxel cell to retrieve

operationMode Baking operation to use for applying input against existing color

normalized Flag to remove pre-multiplication of alpha from red, green and blue components

```
Voxels.Storage.Iterator GetIterator(
```

Create and return a new iterator instance to access cells with content only.

Return Value:

New iterator instance

class Voxels.Storage.Iterator

To access collected voxels in a fast way the iterator class is perfect because it returns the material for filled cells only.

int Number Read-only index of the cell, which is being accessed next

```
UnityEngine.Material GetNextMaterial(
        [out UnityEngine.Color color,]
        out int x,
        out int y,
        out int z,
        Voxels.BakingOperation operationMode = Voxels.BakingOperation.Undefined,
        int normalized = true
    )
```

Return the source material of the next iterated cell or a newly instantiated one with the optionally modulated color of the voxel.

Return Value:

An existing or a new material instance

Parameters:

color Cell color, which is being applied to template material or retrieved from source

one

x, y, z Coordinate of the cell in volume space

operationMode Baking operation to use for applying input against existing color

normalized Flag to remove pre-multiplication of alpha from red, green and blue components

```
UnityEngine.Color GetNextColor(
    out int x,
    out int y,
    out int z,
    Voxels.BakingOperation operationMode = Voxels.BakingOperation.Undefined,
    int normalized = true
    )
```

Return the color of the next iterated cell, which has been retrieved from scan results.

Return Value:

Sampled and processed color of the cell

Parameters:

x, y, z Coordinate of the cell in volume space

operationMode Baking operation to use for applying input against existing color

normalized Flag to remove pre-multiplication of alpha from red, green and blue components

class Voxels. HSVColor

It is kind of a helper class to apply color modifications and stores color values as hue, saturation and value components.

```
float
                              h
                                                             Hue component
float
                                                             Saturation component
                              S
float
                                                             Value component
float
                                                             Alpha value (inverted transparency)
                              a
HSVColor(
       float h,
       float s,
       float v,
       [float a]
  Common constructor to initialize member variables
Parameters:
  See member variables
HSVColor(
       UnityEngine.Color col
  Initialize member variables using a RGBA color value as input.
Parameters:
  See member variables
UnityEngine.Color ToColor(
  Build a RGBA color value from instance.
Return Value:
  Converted color result
Voxels.HSVColor Lerp(
       Voxels.HSVColor a,
       Voxels.HSVColor b,
       float t
  Do a linear interpolation between two HSV color values.
Return Value:
  Blending result value
Parameters:
                         Source colors
  a, b
                         Interpolation factor; should be between 0 and 1
  t
```