SALSA USER GUIDE

Contents

- 1. Build and install
- 2. Configuration stack levels: IaaS, container and application
- 3. Wiring application components
- 4. Application specification

1. Build and install

The source code of SALSA is hosted on Github: https://github.com/tuwiendsg/SALSA. In order to build the project, user clones the repository and build the parent module by maven:

\$ mvn clean install

The artifacts will be created on particular modules and put all together in "standalone" module. For installing, please following these steps:

- 1. SALSA is packed as a web application, running on Tomcat server or standalone version with embedded Tomcat. There are two components:
- The salsa engine: salsa-engine.war (with Tomcat) or salsa-engine.jar (standalone)
- The salsa pioneer: salsa-pioneer.jar
- 2. Configure the salsa-engine's parameters in file **salsa-engine.properties** and put in the same folder with the **salsa-engine.jar** or in /etc/. (without the file, SALSA use default parameters)

Note: The most important setting is the access IP (SALSA_CENTER_IP) that the salsa-pioneer can query the salsa-engine. For example: when SALSA is deployed on cloud, user should set the floating IP, otherwise the machine outside the cloud cannot query..

- 3. The salsa-pioneer.jar need to be put in the same folder with salsa-engine.[war/jar], or upload to a public repository and configured in step 2.
- 4. Deploy salsa-engine.war to the Tomcat or run the standalone version with port:

\$ java -jar --httpPort <portNumber> salsa-engine.jar

We also provide a service pattern to run the salsa-engine. Copy the salsa-engine-service script to /etc/init.d and run by:

\$ sudo service salsa-engine-service start/stop/restart/status

5. Access to SALSA web interface with the IP and port setting above, for example:

http://10.0.0.1:8080/salsa-engine

Using RESTful API at:

http://10.0.0.1:8080/salsa-engine/rest

6. If user access to cloud, a configuration have to be in the salsa-engine folder or in /etc. Please check Section 2.1.

2. Configuration stack levels: laaS, container and application

SALSA support three deployment and configuration stacks:

2.1 laaS level

SALSA contains a number of cloud connector for automatically provision IaaS cloud resources and managing virtual machines. The prototype support OpenStack, Flexiant, Stratuslab and LocalMachine. The LocalMachine enables user to test application without cloud resources. Please check Section 5 to see how to describe the virtual machine configuration. In order to setup SALSA to run with those clouds, user need to provide a configuration file (./cloudUserParameters.ini) or /etc/cloudUserParameters.ini). The parameters of all supported providers are put into a single file as below:

[<mysite>@openstack]

username=<OpenStack username>
password=<OpenStack password>
tenant=<Project name, tenant name>
keystone_endpoint=<URL to keystone service, e.g http://.../identity/v2.0/>
port=<keystone port>
sshKeyName=<the keypair name, which created before in openstack>
location=<optional localtion information>

[<mysite>@flexiant]

email=<account email>
customerUUID=
password=
endpoint=<The endpoint to JADE API of the datacenter>
vdcUUID=<default value>
defaultProductOfferUUID=<default value>
clusterUUID=<default value>
networkUUID=<default value>
sshkey=<ssh key which will be push to the VM>

[<mysite>@stratuslab]

Endpoint=<VM service endpoint>
pdisk endpoint=<Storage service endpoint>

```
marketplace_endpoint=<Marketplace service endpoint>
username=<user name>
password=<password>
client_path=<local path to the client package>
```

Above configuration depends on the connector implemented and need to match with each provider.

2.2 Container level

SALSA enables the management with different type of containers (e.g. start, stop, create and remove containers) and configure the application level on top of this. The prototype support Tomcat and Docker.

- **Tomcat**: Developer defines the NodeType="tomcat". If there is no further information, SALSA automatically uses apt-get (on Ubuntu) to install Tomcat. Otherwise, user can provide a DeploymentArtifact, or define an action name "deploy" to manual configure Tomcat.
- **Docker**: Developer defines the NodeType="docker". If there is no further information, SALSA deploys default Ubuntu container and ready to deploy application stack on top of the container. If developer provides a DeploymentArtifact with type="Dockerfile", SALSA uses it for configure the Docker container. If the user-defined docker container contains Java, SALSA can push the pioneer to execute the upper stacks configuration.

2.3 Application level

SALSA supports deploying and configuring application via script (written by app. developer). The script MUST be provided as DeploymentArtifact. At this stack, SALSA support writing components (see Section 3). Not only script, SALSA supports some more artifact type (see Section 5).

The stacks are defined by HOSTON relationship in the application description (see Section 4)

3. Wiring application components

Each node has a number of scripts related to deployment actions (e.g. deploy, undeploy, start, stop, registerTo, etc). The deployment scripts can be written a BASH script. In order to wire 2 components (e.g. register a web service to a load balancer, or a database endpoint to web page) the deployment scripts need to share some variable. SALSA provides 2 commands, which is available on all Vitual machine instances.

```
- salsa-capability-set <capability ID> <value>
```

```
- salsa-requirement-get <requirement ID>
```

In the commands above, the capability ID and requirement ID are defined in the application description (e.g. in TOSCA)

For specific case of getting IP, on the value is send to the node which needs and is stored in global env variable. The script can get the IP by:

```
./etc/environment
IP_VALUE=$<ID_OF_SOURCE_NODE>_IP
or: IP_VALUE=$<ID_OF_RELATIONSHIP>_IP
```

The wired components are defined by CONNECTTO relationship in the application description (see Section 4) The following figure depicts the process of wiring application components:




Figure 1- Example of wiring a WebService with a LoadBalancer

4. Application specification

4.1 TOSCA description

SALSA uses TOSCA for describing applications. An application is called a Tosca-Definition which contains a number of Service Template. In SALSA, a Service Template can be considered as an atomic service, which can be deployed separately.

A Service Template has **ONE** Topology Template which describes its abstract structure. Following the TOSCA concept, all application components

are considered as Tosca-Nodes, or Node Template. Node Templates have dependencies to others, and be described via Relationship Template.

For execute the deployment, each Tosca-Nodes will have a number of Deployment-Artifacts which point to the Artifact repositories of the Node materials. These templates can be defined by other Tosca-Elements such as Node-Types, Relationship-Types, Artifact-Types, etc.

4.2 Extended TOSCA for SALSA

As the property for NodeTemplate is Any, SALSA use some custom Properties for the description . These properties are define and put under the <tosca:Properties> tag of each NodeTemplate with specific type.

4.2.1 SALSA NodeTemplate type

The NodeTemplate types define which components can be place on where, enable SALSA to select right module to execute the configuration: using cloud connector for VM, pioneer for others. Also SALSA can parse the correct runtime information corresponding to the type. In the NodeTemplate, put an attribute as type="salsa:typeName". Currently, following type can be parsed:

```
- salsa:software => for the script-based artifacts
- salsa:war => describe a web application
- salsa:docker => default docker node
- salsa:tomcat => default tomcat node
- salsa:os => default VM with Ubuntu
```

4.2.2 SALSA Artifact types

Artifact types define the artifact that is used for the deployment, enable SALSA can use appropriate mechanism to

In the ArtifactTemplate, put an attribute as type="salsa:typeName". Currently SALSA support:

4.2.3 SALSA custom properties

SALSA parses custom properties which are wrapped in a MappingProperties structure. Currently, 2 type of properties can be parsed.

```
- salsa:os => properties to describe VM
- salsa:action => properties to define custom actions for application lifecycle management.
```

4.2.4 Virtual Machine Node Properties

Below is an example of the custom VM Node deployment information stated in <tosca:Properties>.

The provider name is at the format: <site>@<connector>. This string is specified in the cloud configuration file, (default at ./cloudUserParameters.ini) or /etc/cloudUserParameters.ini) with the parameters suitable for a cloud (e.g. user, password, endpoint). User need to define the instance type (the VM configuration) and the based image for the VM. The additional packages are optional, which describe the pre-configured environment inside the VM.

4.2.5 Custom actions properties

A NodeTemplate can have action property which map from a name with a system command.

```
</MappingProperty>
</MappingProperties>
</tosca:Properties>
```

By default in SALSA, the "undeploy" action will firstly look for the "stop" action if available to execute to ensure the semantic of the application. If there is no "undeploy" script, SALSA will try to detect the artifact type and clean up the service by default.

4.2.6 Relationship types

The relationships represent the order of deployment between nodes. In a relationship, the source node will be deploy before the target node.

There are two types of relationship between nodes.

- salsa: HOSTON => This represents one node will be deploy on top of other node. SALSA uses this to recognize the stack of deployment. Currently, SALSA have VM stack and software stack, which show the software is deployed on top of the VM.
- salsa:CONNECTTO => This represents the relationship between two software nodes. One node will waiting for other nodes to be deployed, then get the IP of that node.
- salsa:LOCAL => Two node will be deployed on the same target. E.g. two software will be hosted by single VM. This type is used only when "OS" node is not specified. This will be replaced by HOSTON relationship when SALSA processes the TOSCA.