Memory Management Basics


Summary

- Understanding how the processor architecture drives the memory management features of OS and system programs (compilers, linkers)
- Understanding how different hardware designs lead to different memory management schemes by operating systems

Addresses issued by CPU

- During the entire 'on' time of the CPU
 - Addresses are "issued" by the CPU on address bus
 - One address to fetch instruction from location specified by PC
 - Zero or more addresses depending on instruction
 - e.g. mov \$0x300, r1 # move contents of address 0x300 to r1 --
 - > one extra address issued on address bus

Memory layout of a C program



```
$ size /bin/ls
text data bss dec hex filename
128069 4688 4824 137581 2196d /bin/ls
```

Desired from a multi-tasking system

- Multiple processes in RAM at the same time (multiprogramming)
- Processes should not be able to see/touch each other's code, data (globals), stack, heap, etc.
- Further advanced requirements
 - Process could reside anywhere in RAM
 - Process need not be continuous in RAM
 - Parts of process could be moved anywhere in RAM


Different 'times'

- Different actions related to memory management for a program are taken at different times. So let's know the different 'times'
- Compile time
 - When compiler is compiling your C code
- Load time
 - When you execute "./myprogram" and it's getting loaded in RAM by loader i.e. exec()
- Run time
 - When the process is alive, and getting scheduled by the OS


Different types of Address binding

- Compile time address binding
 - Address of code/variables is fixed by compiler
 - Very rigid scheme
 - Location of process in RAM can not be changed! Non-relocatable code.
- Load time address binding
 - Address of code/variables is fixed by loader
 - Location of process in RAM is decided at load time, but can't be changed later
 - Flexible scheme, relocatable code
- Run time address binding
 - Address of code/variables is fixed at the time of executing the code
 - Very flexible scheme , highly relocatable code
 - Location of process in RAM is decided at load time, but CAN be changed later also

Which binding is actually used, is mandated by processor features + OS



 Suppose the address issued by CPU reaches the RAM controller directly




- How does this impact the compiler and OS?
- When a process is running the addresses issued by it, will reach the RAM directly
- So exact addresses of globals, addresses in "jmp" and "call" must be part the machine instructions generated by compiler
 - How will the compiler know the addresses, at "compile time"?


1000: mov \$0x300, r1

1004: add r1, -3 1008: jnz 1000

Sequence of addressed sent by CPU: 1000, 0x300, 1004, 1008, 1000, 0x300, ...



- Solution: compiler assumes some fixed addresses for globals, code, etc.
- OS loads the program exactly at the same addresses specified in the executable file.
 Non-relocatable code.
- Now program can execute properly.



- Problem with this solution.
 - Programs once loaded in RAM must stay there, can't be moved
 - What about 2 programs?
 - Compilers being "programs", will make same assumptions and are likely to generate same/overlapping addresses for two different programs
 - Hence only one program can be in memory at a time!
 - No need to check for any memory boundary violations – all memory belongs to one process
- Example: DOS




Figure 9.6 Hardware support for relocation and limit registers.

- Base and Limit are two registers inside CPU's Memory Management Unit
- 'base' is added to the address generated by CPU
- The result is compared with base+limit and if less passed to memory, else hardware interrupt is raised

Memory Management Unit (MMU)





Figure 9.4 Memory management unit (MMU).

- Is part of the CPU chip, acts on every memory address issue by execution unit of the CPU
- In the scheme just discussed, the base, limit calculation parts are part of MMU



- Compiler's work
 - Assume that the process is one continous chunk in memory, with a size limit
 - Assume that the process starts at address zero (!) and calculate addresses for globals, code, etc. And accordingly generate machine code




Figure 9.6 Hardware support for relocation and limit registers.

OS's work

- While loading the process in memory – must load as one continous segment
- Fill in the 'base' register with the actual address of the process in RAM.
- Setup the limit to be the size of the process as set by compiler in the executable file. Remember the base+limit in OS's own data structures.





Figure 9.6 Hardware support for relocation and limit registers.

- Combined effect
 - "Relocatable code" –
 the process can go
 anywhere in RAM at the
 time of loading
 - Some memory violations can be detected a memory access beyond base+limit will raise interrupt, thus running OS in turn, which may take action against the process

Example scenario of memory in base+limit scheme



It should be possible to have relocatable code even with "simplest case"


By doing extra work during "loading".

How?

Next scheme: Segmentation Multiple base +limit pairs

- Multiple sets of base + limit registers
- Whenever an address is issued by execution unit of CPU, it will also include reference to some base register
 - And hence limit register paired to that base register will be used for error checking
- Compiler: can assume a separate chunk of memory for code, data, stack, heap, etc. And accordingly calculate addresses. Each "segment" starting at address 0.
- OS: will load the different 'sections' in different memory regions and accordingly set different 'base' registers

Next scheme: Multiple base +limit pairs



Next scheme: Multiple base +limit pairs, with further indirection

- Base + limit pairs can also be stored in some memory location (not in registers). Question: how will the cpu know where it's in memory?
 - One CPU register to point to the location of table in memory
- Segment registers still in use, they give an index in this table
- This is x86 segmentation
 - Flexibility to have lot more "base+limits" in the array/table in memory

Next scheme: Multiple base +limit pairs, with further indirection




Figure 9.22 IA-32 segmentation.

Problems with segmentation schemes

- OS needs to find a continuous free chunk of memory that fits the size of the "segment"
 - If not available, your exec() can fail due to lack of memory
- Suppose 50k is needed
 - Possible that mong 3 free chunks total 100K may be available, but no single chunk of 50k!
 - External fragmentation
- Solution to external fragmentation: **compaction** move the chunks around and make a continous big chunk available. Time consuming, tricky.

Solving external fragmentation problem

- Process should not be continous in memory!
- Divide the continuous process image in smaller chunks (let's say 4k each) and locate the chunks anywhere in the physical memory
 - Need a way to map the logical memory addresses into actual physical memory addresses




Figure 9.9 Paging model of logical and physical memory.




Figure 9.10 Paging example for a 32-byte memory with 4-byte pages.




Figure 9.8 Paging hardware.

Paging

- Process is assumed to be composed of equally sized "pages" (e.g. 4k page)
- Actual memory is considered to be divided into page "frames".
- CPU generated logical address is split into a page number and offset
- A page table base register inside CPU will give location of an in memory table called page table
- Page number used as offset in a table called page table, which gives the physical page frame number
- Frame number + offset are combined to get physical memory address

Paging

- Compiler: assume the process to be one continous chunk of memory (!) . Generate addresses accordingly
- OS: at exec() time allocate different frames to process, allocate a page table(!), setup the page table to map page numbers with frame numbers, setup the page table base register, start the process
- Now hardware will take care of all translations of logical addresses to physical addresses

X86 memory management




Figure 9.21 Logical to physical address translation in IA-32.

Segmentation in x86





Figure 9.22 IA-32 segmentation.

- The selector is automatically chosen using Code Segment (CS) register, or Data Segment (DS) register depending on which type of memory address is being fetched
- Descriptor table is in memory
- The location of Descriptor table (Global DT- GDT or Local DT – LDT) is given by a GDT-register i.e. GDTR or LDT-register i.e. LDTR

.



Paging in x86

- Depending on a flag setup in CR3 register, either 4 MB or 4 KB pages can be enabled
- Page directory, page table are both in memory

Figure 9.23 Paging in the IA-32 architecture.

Memory Management – Continued

More on Linking, Loading, Paging

Review of last class

- MMU: Hardware features for MM
- OS: Sets up MMU for a process, then schedules process
- Compiler : Generates object code for a particular OS + MMU architecture
- MMU: Detects memory violations and raises interrupt --> Effectively passing control to OS

More on Linking and Loading

- Static Linking: All object code combined at link time and a big object code file is created
- Static Loading: All the code is loaded in memory at the time of exec()
- Problem: Big executable files, need to load functions even if they do not execute
- Solution: Dynamic Linking and Dynamic Loading

Dynamic Linking

- Linker is normally invoked as a part of compilation process
 - Links
 - function code to function calls
 - references to global variables with "extern" declarations

Dynamic Linker

- Does not combine function code with the object code file
- Instead introduces a "stub" code that is indirect reference to actual code
- At the time of "loading" (or executing!) the program in memory, the "link-loader" (part of OS!) will pick up the relevant code from the library machine code file (e.g. libc.so.6)

Dynamic Linking on Linux

```
#include <stdio.h>
int main() {
 int a, b;
 scanf("%d%d", &a, &b);
 printf("%d %d\n", a, b);
 return 0;
}
```

PLT: Procedure Linkage Table used to call external procedures/functions whose address is to be resolved by the dynamic linker at run time.

Output of objdump -x -D

Disassembly of section .text:

000000000001189 <main>:

11d4: callq 1080 <printf@plt>

Disassembly of section .plt.got:

000000000001080 <printf@plt>:

1080: endbr64

1084: bnd jmpq *0x2f3d(%rip) # 3fc8 <pri><printf@GLIBC 2.2.5>

108b: nopl 0x0(%rax,%rax,1)

Dynamic Loading

Loader

- Loads the program in memory
- Part of exec() code
- Needs to understand the format of the executable file (e.g. the ELF format)

Dynamic Loading

- Load a part from the ELF file only if needed during execution
- Delayed loading
- Needs a more sophisticated memory management by operating system to be seen during this series of lectures

Dynamic Linking, Loading

- Dynamic linking necessarily demands an advanced type of loader that understands dynamic linking
 - Hence called 'link-loader'
 - Static or dynamic loading is still a choice
- Question: which of the MMU options will alllow for which type of linking, loading?

Continous memory management

What is Continous memory management?

- Entire process is hosted as one continous chunk in RAM
- Memory is typically divided into two partitions
 - One for OS and other for processes
 - OS most typically located in "high memory" addresses, because interrupt vectors map to that location (Linux, Windows)!

Hardware support needed: base + limit (or relocation + limit)




Figure 9.6 Hardware support for relocation and limit registers.

Problems faced by OS

- Find a continuous chunk for the process being forked
- Different processes are of different sizes
 - Allocate a size parameter in the PCB
- After a process is over free the memory occupied by it
- Maintain a list of free areas, and occupied areas
 - Can be done using an array, or linked list

Variable partition scheme




Figure 9.7 Variable partition.

Problem: how to find a "hole" to fit in new process

- Suppose there are 3 free memory regions of sizes 30k, 40k, 20k
- The newly created process (during fork() + exec()) needs 15k
- Which region to allocate to it?

Strategies for finding a free chunk


- 6k, 17k, 16k, 40k holes. Need 15k.
- Best fit: Find the smallest hole, larger than process. Ans: 16k
- Worst fit: Find the largest hole. Ans: 40k
- First fit: Find the "first" hole larger than the process. Ans: 17k

Problem: External fragmentation

- Free chunks: 30k, 40k, 20k
- The newly created process (during fork() + exec()) needs 50k
- Total free memory: 30+40+20 = 90k
 - But can't allocate 50k!

Solution to external fragmentation

- Compaction!
- OS moves the process chunks in memory to make available continous memory region
 - Then it must update the memory management information in PCB (e.g. base of the process) of each process
- Time consuming
- Possible only if the relocation+limit scheme of MMU is available



Another solution to external fragmentation: Fixed size partitions

- Fixed partition scheme
- Memory is divided by OS into chunks of equal size: e.g., say, 50k
 - If total 1M memory, then 20 such chunks
- Allocate one or more chunks to a process, such that the total size is >= the size of the process
 - E.g.if request is 50k, allocate 1 chunk
 - If request is 40k, still allocate 1 chunk
 - If request is 60k, then allocate 2 chunks
- Leads to internal fragmentation
 - space wasted in the case of 40k or 60k requests above

50K
50K

Kernel				
Kernel				
Free				
P1 (50 KB)				
P2 (80 KB) Unused (20 KB)				
Free				
P3 (120 KB)				
Unused (30 KB)				
Free				
Free				

Fixed partition scheme

- OS needs to keep track of
 - Which partition is free and which is used by which process
 - Free partitions can simply be tracked using a bitmap or a list of numbers
 - Each process's PCB will contain list of partitions allocated to it

Solution to internal fragmentation

- Reduce the size of the fixed sized partition
- How small then ?
 - Smaller partitions mean more overhead for the operating system in allocating deallocating

Paging

An extended version of fixed size partitions

- Partition = page
 - Process = logically continuous sequence of bytes, divided in 'page' sizes
 - Memory divided into equally sized page 'frames'

Important distinction

- Process need not be continous in RAM
- Different page sized chunks of process can go in any page frame
- Page table to map pages into frames

Logical address seen as

page number	page offset
р	d

Paging hardware




Figure 9.8 Paging hardware.

MMU's job

To translate a logical address generated by the CPU to a physical address:

1. Extract the page number p and use it as an index into the page table.

(Page table location is stored in a hardware register

Also stored in PCB of the process, so that it can be used to load the hardware register on a context switch)

- 2. Extract the corresponding frame number f from the page table.
- 3. Replace the page number p in the logical address with the frame number f.

Job of OS

- Allocate a page table for the process, at time of fork()/exec()
 - Allocate frames to process
 - Fill in page table entries
- In PCB of each process, maintain
 - Page table location (address)
 - List of pages frames allocated to this process
- During context switch of the process, load the PTBR using the PCB

Job of OS

- Maintain a list of all page frames
 - Allocated frames
 - Free Frames (called frame table)
 - Can be done using simple linked list
 - Innovative data structures can also be used to maintain free and allocated frames list (e.g. xv6 code)

_





Figure 9.11 Free frames (a) before allocation and (b) after allocation.

Disadvantage of Paging

- Each memory access results in two memory accesses!
 - One for page table, and one for the actual memory location!
 - Done as part of execution of instruction in hardware (not by OS!)
 - Slow down by 50%


Speeding up paging

- Translation Lookaside Buffer (TLB)
- Part of CPU hardware
- A cache of Page table entries
- Searched in parallel for a page number



Speedup due to TLB


- Hit ratio
- Effective memory access time
 - = Hit ratio * 1 memory access time + miss ratio * 2 memory access time
- Example: memory access time 10ns, hit ratio = 0.8, then effective access time = 0.80 × 10 + 0.20 × 20
 - = 12 nanoseconds




Memory protection with paging

Figure 9.13 Valid (v) or invalid (i) bit in a page table.

X86 PDE and PTE





Shared pages (e.g. library) with paging

Figure 9.14 Sharing of standard C library in a paging environment.


Paging: problem of large PT

- 64 bit address
- Suppose 20 bit offset
 - That means 2^20 = 1 MB pages
 - 44 bit page number: 2^44 that is trillion sized page table!
 - Can't have that big continuous page table!

Paging: problem of large PT

- 32 bit address
- Suppose 12 bit offset
 - That means 2^12 = 4 KB pages
 - 20 bit page number: 2^20 that is a million entries
 - Can't always have that big continuous page table as well, for each process!

Hierarchical paging






Figure 9.15 A two-level page-table scheme.

outer page	inner page	offset
p_1	p_2	d
42	10	12

More hierarchy

2nd outer page	outerpage	inner page	offset
p_{I}	p_2	p_3	d
32	10	10	12

Problems with hierarchical paging

- More number of memory accesses with each level!
 - Too slow!
- OS data structures also needed in that proportion

Hashed page table




Figure 9.17 Hashed page table.

Inverted page table




Figure 9.18 Inverted page table.

Normal page table – one per process --> Too much memory consumed

Inverted page table : global table – only one Needs to store PID in the table entry

Examples of systems using inverted page tables include the 64-bit Ultra SPARC and Power PC

virtual address consists of a triple: consists of a triple: offset>

Case Study: Oracle SPARC Solaris

- 64 bit SPARC processor, 64 bit Solaris OS
- Uses Hashed page tables
 - one for the kernel and one for all user processes.
 - Each hash-table entry : base + span (#pages)
 - Reduces number of entries required

Case Study: Oracle SPARC Solaris

- Cashing levels: TLB (on CPU), TSB(in Memory), Page Tables (in Memory)
 - CPU implements a TLB that holds translation table entries (TTE s) for fast hardware lookups.
 - A cache of these TTEs resides in a in-memory translation storage buffer (TSB), which includes an entry per recently accessed page
 - When a virtual address reference occurs, the hardware searches the TLB for a translation.
 - If none is found, the hardware walks through the in memory TSB looking for the TTE that corresponds to the virtual address that caused the lookup

Case Study: Oracle SPARC Solaris

- If a match is found in the TSB, the CPU copies the TSB entry into the TLB, and the memory translation completes.
- If no match is found in the TSB, the kernel is interrupted to search the hash table.
- The kernel then creates a TTE from the appropriate hash table and stores it in the TSB for automatic loading into the TLB by the CPU memory-management unit.
- Finally, the interrupt handler returns control to the MMU, which completes the address translation and retrieves the requested byte or word from main memory.

Swapping




Figure 9.19 Standard swapping of two processes using a disk as a backing store.

Swapping

- Standard swapping
 - Entire process swapped in or swapped out
 - With continous memory management
- Swapping with paging
 - Some pages are "paged out" and some "paged in"
 - Term "paging" refers to paging with swapping now




Figure 9.20 Swapping with paging.

Words of caution about 'paging'


- Not as simple as it sounds when it comes to implementation
 - Writing OS code for this is challenging

Some numbers and their 'meaning'

- These numbers occur very frequently in discussion
- 0x 80000000 = 2 GB = KERNBASE
- 0x 100000 = 1 MB = EXTMEM
- 0x 80100000 = 2GB + 1MB = KERNLINK
- 0x E000000 = 224 MB = PHYSTOP
- 0x FE000000 = 3.96 GB = 4064 MB = DEVSPACE
 - 4096 4064 = 32 MB left on top

X86 Memory Management

X86 address: protected mode address translation



X86 paging





Figure 8.23 Paging in the IA-32 architecture.

Segmentation + Paging




GDT Entry

31		16	15						
Base	0:15		Limit 0:15						
63 56	55 52	51 48	47 40	39 32					
Base 24:31	Flags	Limit 16:19	Access Byte	Base 16:23					

Page Directory Entry (PDE) Page Table Entry (PTE)


31		12 11 10 9 8 7 6 5 4 3 2 1 0		
	11 (fell Vi A) A) 25		Р	Present
	Page table physical page number	A G P O A C W U W P	W	Writable
			Ų	User
	PDE		WT	1=Write-through, 0=Write-back
			CD	Cache disabled
			Α	Accessed
31		1211100076542210	D	Dirty
31		121110 9 8 7 8 3 4 3 2 1 0	PS	Page size (0=4KB, 1=4MB)
Phys	Physical page number	A G P D A C W U W P	PAT	Page table attribute index
			G	Global page
	PTE		AVL	Available for system use

Segment selector



TI Table index (0=GDT, 1=LDT) RPL Requester privilege level

EFLAGS register



CR0

	31 30 29 28	1	9 18 1	7 16	15	6	5	4	3	2	1	0	
CR0	P C N G D W		A M	W P			N E	E T	T S		M P		
PE	Protection enabled	ET Extension type		ion type	NW Not write-through						through		
MP	Monitor coprocessor	NE	Numeric error		ic error	C	D		Cache disable				
EM	Emulation	WP	Write protect		rotect	P	G		Paging				
TS	Task switched	AM	Aliq	nm	ent mask								

PG: Paging enabled or not WP: Write protection on/off

PE: Protection Enabled --> protected mode.

CR2



CR3

CR3 Page-Directory-Table Base Address P P P C W D T

PWT Page-level writes transparent

PCT Page-level cache disable

CR4

31 11 10 9 8 4 3 2 1 0 D E AS CR4 C Е VME Virtual-8086 mode extensions Machine check enable MCE PVI Protected-mode virtual interrupts PGE Page-global enable PCE TSD Time stamp disable Performance counter enable OSFXSR OS FXSAVE/FXRSTOR support DE Debugging extensions PSE Page size extensions OSXMM- OS unmasked exception support **EXCPT** PAE Physical-address extension

mmu.h : paging related macros

```
#define PTXSHIFT
                    12 // offset of PTX in a linear address
#define PDXSHIFT
                 22 // offset of PDX in a linear address
#define PDX(va) (((uint)(va) >> PDXSHIFT) & 0x3FF)// page directory index
#define PTX(va) (((uint)(va) >> PTXSHIFT) & 0x3FF)// page table index
// construct virtual address from indexes and offset
#define PGADDR(d, t, o) ((uint)((d) << PDXSHIFT | (t) << PTXSHIFT |</pre>
(0)))
// +-----10-----+
// | Page Directory | Page Table | Offset within Page |
// |
        Index | Index |
// +-----+
// \--- PDX(va) --/ \--- PTX(va) --/
```

mmu.h : paging related macros

```
// Page directory and page table constants.
#define NPDENTRIES
                                // # directory
                        1024
entries per page directory
                        1024
                                // # PTEs per
#define NPTENTRIES
page table
#define PGSIZE
                        4096
                                // bytes mapped
by a page
#define PGROUNDUP(sz) (((sz)+PGSIZE-1) &
~ (PGSIZE-1))
#define PGROUNDDOWN(a) (((a)) & ~(PGSIZE-1))
```

mmu.h : paging related macros

```
// Page table/directory entry flags.
                       0x001 // Present
#define PTE P
                       0x002 // Writeable
#define PTE W
#define PTE U
                       0x004 // User
#define PTE PS
                       0x080 // Page Size
// Address in page table or page directory entry
#define PTE ADDR(pte) ((uint)(pte) & ~0xFFF) // get
all but last 12 bits
#define PTE FLAGS(pte) ((uint)(pte) & 0xFFF) // get
last 12 bits
```

mmu.h: Segmentation related macros

```
// various segment selectors.
#define SEG KCODE 1 // kernel code
#define SEG KDATA 2 // kernel data+stack
#define SEG UCODE 3 // user code
#define SEG UDATA 4 // user data+stack
#define SEG_TSS 5 // this process's task
state
```

mmu.h: Segmentation related macros

```
// various segment selectors.
#define SEG KCODE 1 // kernel code
#define SEG KDATA 2 // kernel data+stack
#define SEG UCODE 3 // user code
#define SEG UDATA 4 // user data+stack
#define SEG_TSS 5 // this process's task state
#define NSEGS 6
```

mmu.h: Segmentation related macros

struct segdesc { // 64 bit in size

```
uint lim_15_0 : 16; // Low bits of segment limit
 uint base_15_0 : 16; // Low bits of segment base address
 uint base_23_16: 8; // Middle bits of segment base address
 uint type: 4; // Segment type (see STS_ constants)
 uint s: 1; // 0 = system, 1 = application
 uint dpl: 2; // Descriptor Privilege Level
 uint p : 1; // Present
 uint lim_19_16 : 4; // High bits of segment limit
 uint avl : 1; // Unused (available for software use)
 uint rsv1 : 1; // Reserved
 uint db : 1; // 0 = 16-bit segment, 1 = 32-bit segment
 uint g: 1; // Granularity: limit scaled by 4K when set
 uint base_31_24 : 8; // High bits of segment base address
};
```

mmu.h: Segmentation related code

```
// Application segment type bits
                        // Executable segment
#define STA X
                  8x0
                        // Writeable (non-executable
#define STA W
                  0x2
segments)
#define STA R
                        // Readable (executable
                  0x2
segments)
// System segment type bits
                          // Available 32-bit TSS
#define STS_T32A
                    0x9
#define STS IG32
                          // 32-bit Interrupt Gate
                   0xE
#define STS TG32
                    0xF
                          // 32-bit Trap Gate
```

Code from bootasm.S bootmain.c is over! Kernel is loaded. Now kernel is going to prepare itself

main() in main.c

- Initializes "free list" of page frames
 - In 2 steps. Why?
- Sets up page table for kernel
- Detects configuration of all processors
- Starts all processors
 - Just like the first processor
- Creates the first process!

- Initializes
 - LAPIC on each processor, IOAPIC
 - Disables PIC
 - "Console" hardware (the standard I/O)
 - Serial Port
 - Interrupt Descriptor Table
 - Buffer Cache
 - Files Table
 - Hard Disk (IDE)


main() in main.c

```
int
                                void
main(void) {
                                kinit1(void *vstart, void
                                *vend) {
 kinit1(end,
P2V(4*1024*1024)); // phys
                                 initlock(&kmem.lock,
page allocator
                                "kmem");
 kvmalloc();
               // kernel page
                                 kmem.use_lock = 0;
table
                                 freerange(vstart, vend);
```

main() in main.c

```
void
freerange(void *vstart, void
*vend)
 char *p;
 p =
(char*)PGROUNDUP((uint)vst
art);
 for(; p + PGSIZE <=
(char*)vend; p += PGSIZE)
  kfree(p);
```

```
kfree(char *v) {
  struct run *r;
  if((uint)v % PGSIZE || v <</pre>
end | | V2P(v) >= PHYSTOP)
    panic("kfree");
  // Fill with junk to catch
dangling refs.
  memset(v, 1, PGSIZE);
  if(kmem.use lock)
    acquire(&kmem.lock);
  r = (struct run*)v;
  r->next = kmem.freelist;
  kmem.freelist = r;
  if(kmem.use lock)
    release(&kmem.lock); }
```



Back to main()

```
int
main(void) {
 kinit1(end,
P2V(4*1024*1024)); //
phys page allocator
 kvmalloc();
kernel page table
```


```
// Allocate one page
table for the machine
for the kernel address
// space for scheduler
processes.
void
kvmalloc(void)
 kpgdir = setupkvm();
 switchkvm();
```

```
// Allocate one page
   Back to
                       table for the machine
    main()
                       for the kernel address
int
                       // space for scheduler
                       processes.
main(void) {
                       void
 kinit1(end,
P2V(4*1024*1024)); //
                       kvmalloc(void)
phys page allocator
 kvmalloc();
                        kpgdir =
kernel page table
                       setupkvm(); // global
                       var kpgdir
                        switchkvm();
```


```
pde t*
                                for(k = kmap; k <
setupkvm(void)
                               &kmap[NELEM(kmap)];
                               k++)
                                  if(mappages(pgdir, k-
 pde_t *pgdir;
                               >virt, k->phys end - k-
 struct kmap *k;
                               >phys_start,
 if((pgdir = (pde_t*)kalloc())
                                         (uint)k-
== 0)
                               >phys_start, k->perm) <
  return 0;
                               0) {
 memset(pgdir, 0, PGSIZE);
                                   freevm(pgdir);
 if (P2V(PHYSTOP) >
                                   return 0;
(void*)DEVSPACE)
  panic("PHYSTOP too
                                 return pgdir;
high");
```


```
static struct kmap {
  void *virt;
  uint phys_start;
  uint phys_end;
  int perm;
} kmap[] = {
  { (void*)KERNBASE, 0, EXTMEM, PTE_W}, // I/O space
  { (void*)KERNLINK, V2P(KERNLINK), V2P(data), 0}, // kern text+rodata
  { (void*)data, V2P(data), PHYSTOP, PTE_W}, // kern data+memory
  { (void*)DEVSPACE, DEVSPACE, 0, PTE_W}, // more devices
};
```

kmap[] mappings done in kvmalloc(). This shows segmentwise, entries are done in page directory and page table for corresponding VA-> PA mappings





Remidner: PDE and PTE entries






Before mappages()





main()->seginit()


- Re-initialize GDT
- Once and forever now
- Just set 4 entries
 - All spanning 4 GB
 - Differing only in permissions and privilege level




After seginit()


- While running kernel code, necessary to switch CS, DS, SS to index 1,2,2 in GDT
- While running user code, necessary to switch CS, DS, SS to index 3,4,4 in GDT
- This happens automatically as part of "trap" handling (covered separately)

Memory Management




X86 page table hardware






Layout of process's VA space




Memory Layout of a user process

The "guard page" is just a mapping in page table. No frame allocated. It's marked as invalid. So if stack grows (due to many function calls), then OS will detect it with an exception



Memory Layout of a user process



On sbrk()


The system call to grow process's address space. Calls growproc()

growproc()

Allocate a frame, Add an entry in page table at the top (above proc->sz)
//This entry can't go beyond KERNBASE
Calls switchuvm()

Switchuvm()

Ultimately loads CR3, invalidating cache



exec()

```
sys_exec()
    exec(path, argv)
exec(parth, argv)
    ip = namei(path))
    readi(ip, (char*)&elf, 0, sizeof(elf)) != sizeof(elf)
    for(i=0, off=elf.phoff; i<elf.phnum; i++, off+=sizeof(ph)){
       if(readi(ip, (char*)&ph, off, sizeof(ph)) != sizeof(ph))
       if((sz = allocuvm(pgdir, sz, ph.vaddr + ph.memsz)) == 0)
       if(loaduvm(pgdir, (char*)ph.vaddr, ip, ph.off, ph.filesz) < 0)
    }
```

exec()

exec(parth, argv)

```
// Allocate two pages at the next page boundary.
// Make the first inaccessible. Use the second as the user
stack.
sz = PGROUNDUP(sz);
if((sz = allocuvm(pgdir, sz, sz + 2*PGSIZE)) == 0)
// Push argument strings, prepare rest of stack in ustack.
 for(argc = 0; argv[argc]; argc++) {
  sp = (sp - (strlen(argv[argc]) + 1)) \& ~3;
  if(copyout(pgdir, sp, argv[argc], strlen(argv[argc]) + 1) < 0)
```