```
function [U,FD grid,time steps] =
bs_timestepping(sigma,r,forcing,bc_right,init_cond,S_max,NS,T,Nt,theta)
% bs_timestepping
% Inputs:
                : volatility (real number)
   sigma
  r
                : risk-free return (real number)
응
   forcing
                : @-function describing the right-hand-side of the
 equation, forcing = @(R,t) ...
%
                    S is a vector (spatial grid), t is a real number
                    the output is a vector of the same dimension as S
응
  bc_right
                : @-function describing the boundary condition on the
right border, bc right = @(t) ...
                    t is a real number
    init cond
                : @-function describing the initial condition of the
problem, initial_cond = @(S) ...
                    S is a vector (spatial grid)
                : real value setting the upper extreme of the interval
    S max
in which the solution is computed
  NS
               : number of intervals in the discretization of
 [0,Rmax]
   T
                : final time of the equation
응
                : number of time steps
   Nt.
응
   theta
                : parameter for the theta-method time-stepping scheme:
2
                    theta = 0 --> Forward Euler
응
                    theta = 1 --> Backward Euler
                    theta = 0.5 --> Crank-Nicholson
2
% Outputs:
                : matrix containing the solution of the PDE
                   rows = spatial nodes, columns = time steps
               : spatial grid, contains the nodes on which the
  grid
 solution H is evaluated
  time_steps : time grid, contains the time steps at which H is
 computed
% set grid and grid-size
h = S_max/NS;
FD grid = linspace(0,S max,NS+1);
inner_grid = FD_grid(1:end-1);
% set time steps
dt = T/Nt;
time steps = dt*(0:Nt);
% initialize solution matrix
U = zeros(NS+1,Nt+1);
% set initial condition
U(:,1) = init cond(FD grid)';
U(end,:) = bc_right(time_steps);
```

1

```
% define auxiliary vectors
% for reading convenience and for computational efficiency
S = inner grid';
Ssq = inner_grid'.^2;
% build matrix A
   space-dependent but not time dependent
eta = sigma^2/h^2*Ssq;
nu = 0.5*r*S/h;
A_{up} = -0.5*eta(1:end-1) - nu(1:end-1);
A_{main} = eta + r;
A_down = -0.5*eta(2:end) + nu(2:end);
% correction term for vector f
corr_right = 0.5*sigma^2/h^2*S_max^2 + 0.5*r*S_max/h;
% initialize time
t_old = 0;
% build f_old with boundary corrections, evaluated at t=0
f_old = forcing(inner_grid,t_old);
f_old(end) = f_old(end) + corr_right*bc_right(t_old);
% Main time-stepping loop
for tn = 1:Nt
    % current time
    t_new = t_old + dt;
    % built f_new with boundary corrections
    f_new = forcing(inner_grid,t_new);
    f_new(end) = f_new(end) + corr_right*bc_right(t_new);
    % the system evolves according to the formula
    % (I + dt theta A) V_new = (I - dt (1-theta) A) V_old + dt f_tot
    % where f_tot = (1-theta) f_old + theta f_new
    % Define:
      X = (I + dt theta A)
    Y = (I - dt (1-theta) A)
    % build matrix X
    X_up = dt*theta*A_up;
    X_main = 1 + dt*theta*A_main;
    X_down = dt*theta*A_down;
    % build matrix Y
    Y up = -dt*theta*A up;
    Y_main = 1 - dt*theta*A_main;
    Y_down = -dt*theta*A_down;
    Y = spdiags([0;Y_up],1,NS,NS) + spdiags(Y_main,0,NS,NS) +...
        spdiags([Y_down;0],-1,NS,NS);
    % build vector f_tot
```

```
f_tot = (1-theta)*f_old + theta*f_new;

% solve the system and store the solution
RHS = Y*U(1:end-1,tn) + dt*f_tot;
U(1:end-1,tn+1) = thomas(X_down,X_main,X_up,RHS);

% update current time
f_old = f_new;

end

end

Not enough input arguments.

Error in bs_timestepping (line 30)
h = S_max/NS;
```

Published with MATLAB® R2020a