
ME531: Advanced Mechanics of Solids

Motion, Strain and Stress

 $Anshul\ Faye$ afaye@iitbhilai.ac.in $Room\ No.\ \#\ 106$



Consider an infinitesimally small volume element with reference volume dV going under deformation and the current volume is dv.

 $dv = d\mathbf{z} \cdot (d\mathbf{x} \times d\mathbf{y})$ or $dv = e_{ijk}dz_idx_idy_k$


deformation gradient for the motion is \mathbf{F} , then edges in the reference configuration can be mapped to the edges in undeformed configuration as,

 $dx_i = F_{ij}dX_I, dy_i = F_{ij}dY_I, \text{ and } dz_i = F_{ij}dZ_I$

$$dv = e_{ijk}(F_{ip}dZ_p)(F_{jq}dX_q)(F_{kr}dY_r)$$

It can be shown that, $e_{ijk}A_{ip}A_{jq}A_{kr} = e_{pqr} \det \mathbf{A}$.

Thus, $dv = e_{pqr}dZ_pdX_qdY_r \det \mathbf{F} \Rightarrow dv = JdV$, where $J = \det \mathbf{F}$ is called the *Jacobian* of deformation gradient tensor. The Jacobian is the ratio of elemental volume deformed configuration to its volume in undeformed configuration.



Deformation gradient F is used to map a vector in undeformed configuration to the deformed configuration. However, the same does not apply to the unit normal vector N to an infinitesimal surface element dS. To find the relation between the normal vector N and n (deformed configuration of N) we use the following relation.

dv = JdV

We now present the volume dV as $d\mathbf{S} \cdot d\mathbf{X}$, where $d\mathbf{X}$ is a line element in undeformed configuration, which deform to the line element $d\mathbf{x}$, and hence $d\mathbf{v} = d\mathbf{s} \cdot d\mathbf{x}$.

Now, we can write, $d\mathbf{s} \cdot d\mathbf{x} = Jd\mathbf{S} \cdot d\mathbf{X}$

Line element $d\mathbf{x}$ and $d\mathbf{X}$ are related as, $d\mathbf{x} = Fd\mathbf{X}$. Using this relation we can write,


$$d\mathbf{s} \cdot \mathbf{F} d\mathbf{X} = J d\mathbf{S} \cdot d\mathbf{X} \Rightarrow (\mathbf{F}^T d\mathbf{s} - J d\mathbf{S}) \cdot d\mathbf{X} = 0$$

This relation holds for any arbitrary $d\mathbf{X}$, which implies $\mathbf{F}^T d\mathbf{s} - J d\mathbf{S} = 0$.

Above gives us the *Nanson's formula* relating an area element in undeformed configuration to the area element in deformed configuration as $ds = JF^{-T}dS$.

Exercise

Plot the deformed shape of the cube which goes under the following motion.



$$x_1 = X_1 \cos(\pi X_3/2) - X_2 \sin(\pi X_3/2)$$

$$x_2 = X_1 \sin(\pi X_3/2) + X_2 \cos(\pi X_3/2)$$

$$x_3 = X_3$$

Displacement gradient

Using displacements we can write, x(X,t) = X + U(X,t) or $x_i = X_i + U_i$.

From the definition of deformation gradient,

$$F_{iJ} = \frac{\partial x_i}{\partial X_J} = \frac{\partial}{\partial X_J} (X_i + U_i) = \frac{\partial X_i}{\partial X_J} + \frac{\partial U_i}{\partial X_J}$$

$$F_{iJ} = \delta_{ij} + \frac{\partial U_i}{\partial X_J}$$
, or $\boldsymbol{F} = \boldsymbol{I} + \boldsymbol{\nabla}_X \boldsymbol{U}$

where, $\nabla_X U = \frac{\partial U_i}{\partial X_I}$ is called displacement gradient tensor.


In material description, displacement gradient tensor is

$$\nabla_X U(X,t) = F(X,t) - I \text{ or } \frac{\partial U_i}{\partial X_I} = F_{iJ} - \delta_{ij}.$$

In spatial description, displacement gradient tensor is

$$\nabla u(x,t) = I - F^{-1}(x,t) \text{ or } \frac{\partial u_i}{\partial x_J} = \delta_{ij} - F_{iJ}^{-1}.$$

Strain



strain tensor.

Squared length of the line element dX is $dX^2 = dX \cdot dX$.

Similarly, squared length of the line element $d\mathbf{x}$ is $dx^2 = d\mathbf{x} \cdot d\mathbf{x}$.

Let's examine the difference between the squared length of dx and dX as,

$$dx^{2} - dX^{2} = F_{im}dX_{m}F_{in}dX_{n} - dX_{m}\delta_{mn}dX_{n},$$

$$dx^{2} - dX^{2} = dX_{m}(F_{im}F_{in} - \delta_{mn})dX_{n} = d\mathbf{X} \cdot (\mathbf{F}^{T}\mathbf{F} - \mathbf{I})d\mathbf{X},$$

$$dx^{2} - dX^{2} = dX_{m}(F_{im}F_{in} - \delta_{mn})dX_{n} = d\mathbf{X} \cdot 2\mathbf{E}d\mathbf{X}.$$
where, $\mathbf{E} = \frac{1}{2}(\mathbf{F}^{T}\mathbf{F} - \mathbf{I})$ or $E_{ij} = \frac{1}{2}(F_{ki}F_{kj} - \delta_{ij})$ is called Green-Lagrange

Using the relation, $\mathbf{F} = \mathbf{I} + \nabla_X \mathbf{U}$ or $F_{ij} = \delta_{ij} + \frac{\partial U_i}{\partial X_i}$, we write,

$$E_{ij} = \frac{1}{2} \left[\left(\delta_{ki} + \frac{\partial U_k}{\partial X_i} \right) \left(\delta_{kj} + \frac{\partial U_k}{\partial X_j} \right) - \delta_{ij} \right]$$

$$E_{ij} = \frac{1}{2} \left[\frac{\partial U_i}{\partial X_i} + \frac{\partial U_j}{\partial X_i} + \frac{\partial U_k}{\partial X_i} \frac{\partial U_k}{\partial X_j} \right] \quad \text{or} \quad \boldsymbol{E} = \frac{1}{2} \left[\boldsymbol{\nabla}_X \boldsymbol{U} + (\boldsymbol{\nabla}_X \boldsymbol{U})^T + (\boldsymbol{\nabla}_X \boldsymbol{U})^T \boldsymbol{\nabla}_X \boldsymbol{U} \right]$$

Eulerian description of the Green-Lagrange strain tensor is called *Euler-Almansi* strain tensor and defined as,

$$e = \frac{1}{2} \left(\mathbf{I} - \mathbf{F}^{-T} \mathbf{F}^{-1} \right) \text{ or } e_{ij} = \frac{1}{2} \left(\delta_{ij} - F_{ki}^{-1} F_{kj} \right)$$

$$e = \frac{1}{2} \left[\nabla \mathbf{u} + (\nabla \mathbf{u})^T - (\nabla \mathbf{u})^T \nabla \mathbf{u} \right] \text{ or } e_{ij} = \frac{1}{2} \left[\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} - \frac{\partial u_k}{\partial x_i} \frac{\partial u_k}{\partial x_j} \right]$$

Strains in case of small deformations

When deformations are small, $\partial u_i/\partial x_j \ll 1$. Also, difference between reference and current coordinates become negligible, thus strain tensor become

$$E_{ij} \approx e_{ij} = \frac{1}{2} \left[\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} + \frac{\partial u_k}{\partial x_i} \frac{\partial u_k}{\partial x_j} \right] \approx \frac{1}{2} \left[\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right] = \varepsilon_{ij}$$
or
$$\varepsilon = \frac{1}{2} \left[\nabla u + (\nabla u)^T \right], \text{ which is known as } small \text{ } strain \text{ } tensor.$$

It can be noted that the small strain tensor is symmetric part of the displacement gradient tensor. Antisymmetric part of the displacement gradient tensor is known as infinitesimal rotation tensor (ω) . Thus,

$$\nabla u = \varepsilon + \omega$$
, where

$$\boldsymbol{\varepsilon} = \frac{1}{2} \left[\boldsymbol{\nabla} \boldsymbol{u} + (\boldsymbol{\nabla} \boldsymbol{u})^T \right] \text{ and } \boldsymbol{\omega} = \frac{1}{2} \left[\boldsymbol{\nabla} \boldsymbol{u} - (\boldsymbol{\nabla} \boldsymbol{u})^T \right].$$