ON SCRAPING VISCOUS FLUID FROM A PLANE SURFACE

3

REPRINTED FROM

Miszellaneen der Angewandten Mechanik (Festschrift Walter Tollmien) edited by M. Schäfer, Akademie-Verlag, Berlin (1962), pp. 313-15

a flat sheet pushing fluid before it. n is greater than I they usually represent flow in a corner produced by agents cance because it can represent flow of a viscous fluid when a flat scraper moves over flow velocity near the origin is infinite. The case when n=1 has physical signifiwhich can only be described by other types of solution. When n is less than 1 the seldom have much physical interest except as terms in series expansions. When expressed in polar co-ordinates can be found in the form $\psi = r^n f(\Theta)$ but they when the flow is so slow that inertia is negligible. Simple solutions of this equation The stream function ψ , representing two-dimensional fluid flow, satisfies $\nabla^4 \psi = 0$

The general solution of $\nabla^4 \psi = 0$ when n = 1 is

$$\psi = r(A\cos\Theta + B\sin\Theta + C\Theta\cos\Theta + D\Theta\sin\Theta). \tag{1}$$

surface (taken as $\Theta = 0$) it is convenient to superpose a velocity -U parallel to $\Theta=0$ so as to reduce the motion to steady flow. The radial and tangential velocities If (1) represents the flow in front of a scraper moving with velocity U over a flat

$$u = -\frac{1}{r} \frac{\partial \psi}{\partial \Theta}$$
 and $v = \frac{\partial \psi}{\partial r}$.

If the scraper is inclined at angle α to the flat plate the boundary conditions are

$$\psi = 0$$
, $\frac{1}{r} \frac{\partial \psi}{\partial \Theta} = U$ at $\Theta = 0$ and $\psi = \frac{\partial \psi}{\partial \Theta} = 0$ at $\Theta = \alpha$.

Using these conditions (1) becomes

$$\psi = \frac{U_r}{\alpha^2 - \sin^2 \alpha} \left\{ \alpha^2 \sin \Theta - \sin^2 \alpha \Theta \cos \Theta - \left(\frac{\alpha \sin^3 \alpha + \alpha^2 \cos \alpha - \cos \alpha \sin^2 \alpha}{\sin \alpha + \alpha \cos \alpha} \right) \Theta \sin \Theta \right\}.$$
 (2)*




Fig. 1. Streamlines of flow of viscous fluid for $\alpha = \frac{1}{2}\pi$.

the point of contact and μ is the viscosity If P and S are the stresses normal and tangential to the scraper at distance r from

$$P = \frac{2\mu U}{r} \left(\frac{\alpha \sin \alpha}{\alpha^2 - \sin^2 \alpha} \right), \tag{3}$$

$$S = \frac{2\mu U \sin \alpha - \alpha \cos \alpha}{r} \frac{1}{\alpha^2 - \sin^2 \alpha}.$$

(4)

that can be found using the approximate equations of lubrication theory. When α is small these tend to $P=6\mu U/r\alpha^2$ and $S=2\mu U/r\alpha$ which are the values

Resolving the stress in direction L at right angle to the plate and D parallel

$$L = P\cos\alpha + S\sin\alpha = \frac{2\mu U}{r} \left(\frac{\sin^2\alpha}{\alpha^2 - \sin^2\alpha} \right),$$

$$D = P \sin \alpha - S \cos \alpha = \frac{2\mu U}{r} \left(\frac{\alpha - \sin \alpha \cos \alpha}{\alpha^2 - \sin^2 \alpha} \right).$$

in [table 1, and are displayed in fig. 2. It will be seen that D decreases as α greater. The palette knives used by artists for removing paint from their palettes normal stress is of opposite sign to that due to tangential stress, but the latter is the in the range $0 < \alpha < \pi$. In the range $\frac{1}{2}\pi < \alpha < \pi$ the contribution to L due to perhaps unexpected feature of the calculations is that L does not change sign increases, and attains its least value $2\mu U/\pi r$ when $\alpha=\pi$. The most interesting and Values of L, D, P and S divided by $2\mu U/r$ for various values of α are given fact artists instinctively hold their palette knives in this position. is small and as will be seen in the figure this occurs only when α is nearly 180°. In are very flexible scrapers. They can therefore only be used at such an angle that P

^{*} Bditor's note. Fig. 1, which shows the streamlines for the case $\alpha=\frac{1}{2}\pi$, is taken from an article by Sir Geoffrey Taylor entitled 'Similarity solutions of hydrodynamic problems' published in Aeronautics and Astronautics (Pergamon Press, 1960) and not reprinted in these

<u>36]</u>




Fig. 2. Values of P, S, L and D divided by $2\mu U/r$.

180	165	150	135	120	105	90	75	60	45	3 0	15	0	8°		
0	0.08	0.20	0.33	0.50	0.73	1.07	1.61	2.61	4-8	10.8	43	8	$2\mu U$	Pr	
0.32	0.37	0.42	0.47	0.53	0.60	0.68	0.80	0.98	1.31	2.03	3.82	8	$2\mu U$	Sr	Table 1
0	0.014	0.04	0.10	0.21	0.38	0.68	1.19	2.15	4.30	10.3	42	8	$2\mu U$	Lr	
0.32	0.38	0.46	0.56	0.70	0.85	1.07	1.36	1.77	2.44	3.67	7.5	. 8	$2\mu U$	D_{r}	

Scraping Viscous Fluid from a Plane Surface

413

protuberances to hollows. way he can get the large values of L/D which are needed in forcing plaster from A plasterer on the other hand holds a smoothing tool so that α is small. In that

be relieved over a region comparable with the width of the gap. scraper and plate along a line will not occur so that infinite stress at r=0 will r=0 in this solution. In fact in any real situation continuous contact between Though the fluid velocity is everywhere finite the stress becomes infinite at