

Apache OpenOffice

Version 4.1

Draw Guide

AOO Documentation Team

Chapter 8

Tips and Tricks

Copyright

This document is Copyright © 2025 by The Apache Software Foundation. You may distribute it and/or modify it under the terms of the Creative Commons Attribution License, version 3.0 or later (<https://creativecommons.org/licenses/by/3.0/>).

Apache, Apache OpenOffice, and OpenOffice.org are trademarks of the Apache Software Foundation. Used with permission.

Acknowledgments

This book is updated from a previous version by the OOoAuthors team. The AOO Documentation Team appreciates the many contributions of Michael Scarborough and Michele Petrovsky.

Publication date and software version

Published December 20, 2025. Based on Apache OpenOffice 4.1.

Note for Mac Users

Some keystrokes and menu items differ on a Mac from those used in Windows and Linux. The table below gives some common substitutions for the instructions in this chapter. For a more detailed list, see the application Help.

Windows/Linux	Mac equivalent	Effect
Tools > Options menu selection	OpenOffice > Preferences	Access setup options
<i>Right-click</i>	<i>Control+click</i>	Open context menu
<i>Ctrl</i> (Control)	⌘ (Command)	Used with other keys
<i>F5</i>	<i>Shift+⌘+F5</i>	Open the Navigator
<i>F11</i>	<i>⌘+T</i>	Open Styles & Formatting window

Contents

Chapter 8

Tips and Tricks	1
Positioning Objects with Zoom	4
Zoom adjustments using the status bar	4
The Zoom Toolbar	5
Positioning Objects with Snap Functions	5
Snap to Grid	6
Snap to Snap Objects (Snap Lines and Snap Points)	8
Snap to Page Margin	9
Snap to Object Frame	10
Snap to Object Points	10
Help to Position Objects with Guiding Lines	10
Drawing to Scale	11
Splitting Drawings on Multiple Layers	11
An Example Drawing: House Plan and Furniture	13
Changing the Layer of a Drawing Object	15
Creating a Multi-page Document	15
Using the Pages Area	16
Using Page Backgrounds	16
Color Palette: Adding or Changing Single Colors	18
Changing Colors Using the Color Dialog	21
Creating Cool Effects	22
Duplication	22
Cross-fading	23

Positioning Objects with Zoom

With zoom, you can place objects with greater precision, as Figure 1 illustrates.




Figure 1: Using zoom to place objects with greater precision

Zoom adjustments using the status bar

The current zoom value is shown at the right-hand end of the status bar, next to the zoom slider, as you see below in Figure 2.




Figure 2: Zoom level on Status Bar

You can adjust the zoom value by using the slider, right-click on the zoom percent to select from a menu of preset values, or double-click to open the Zoom & View Layout dialog shown in Figure 3.




Figure 3: Zoom & View Layout

You can enter a zoom factor in the *Variable* field, select 100%, or use one of the three other choices shown in Figure 4. Note that the three options on the right side of the dialog are not available in Draw; they are active only for text documents.

- *Optimal*: The drawing or selected object, not the page, is enlarged so that it fits comfortably but optimally in the Draw page area.
- *Fit width and height*: The drawing page edges are set to show the entire page within the Draw page area. This is the same effect as choosing “Entire Page” from the right-click menu on the status bar.
- *Fit width*: The right and left page edges are set to the vertical edges of the Draw page area.

The exact effect of choosing one of these options depends on whether the Page pane is on or off.




Figure 4: Zoom values – Fit width and height, Fit width, and Optimal

The Zoom Toolbar

The Zoom toolbar provides additional zoom options. On the Standard toolbar (**View > Toolbars > Standard**), click on the downwards arrow of the **Zoom** button . You can also permanently display the toolbar shown in Figure 5 by clicking on **View > Toolbars > Zoom**.




Figure 5: Zoom Toolbar

	Zoom in. Enlarges the monitor picture. First, click on the button, then on the object. Alternatively, drag to create a zoom “window”.
	Zoom out. Makes the monitor picture smaller. Just click on the button.
	Returns objects to their original size.
	Changes display to the previous and next zoom factors. If these buttons are not visible, turn them on by clicking on the small black arrow on the title bar of the Zoom toolbar, then on Visible Buttons and finally on either of these two buttons.
	Shows the entire page.
	Zooms to page width.
	Resizes the display to include all objects on the page.
	Zooms the selected object to Optimal.
	Allows the whole drawing to be moved inside the Draw window, using the mouse.

Positioning Objects with Snap Functions

In Draw, objects can be accurately and consistently positioned using grid points, special snap points and lines, object frames, individual points on objects, or page edges. This function is known as *Snap*.

To use the snap function easily, work with the highest practical zoom value. You can use two different snap functions at the same time, for example, snapping to a

guideline and to the page edge. However, it is best to activate only those functions that you really need.

Examples for setting up the snap functions are found in Chapter 10 (Advanced Draw Techniques).

Snap to Grid

Use this function to move an object exactly to a grid point. This function can be switched on and off with **View > Grid > Snap to Grid**, as illustrated in Figure 6, and on the Options toolbar with the icon .




Figure 6: Exact positioning with the snap to grid function

Showing the Grid

To make the grid visible, choose **View > Grid > Display Grid**. Alternatively, turn the grid on (or off) with the icon  on the Options toolbar.

Changing the Color of the Grid Points

By default, the grid points are bright gray and not always easy to see. Go to **Tools > Options > OpenOffice > Appearance**. In the *Drawing / Presentation* section, you can change the color of the grid points as shown in Figure 7. On the *Color Settings* pull-down menu, select a more suitable or visible color, for example, black.




Figure 7: Changing the color of the grid points

Configuring the Grid

Under **Tools > Options > OpenOffice Draw > Grid**, you can change the grid settings (Figure 8).

There is no need to use the *Grid* section. Those settings can be changed directly from the icons on the Options toolbar.




Figure 8: Configuring the grid

Resolution: sets the horizontal and vertical distance between two grid points, like those in Figure 9.




Figure 9: Grids with different resolutions

Subdivisions: determines the number of steps between adjacent grid points. Intermediate steps, as shown in Figure 10, allow a larger separation between two grid points, so the drawing remains clearer. Objects can snap to intermediate points in exactly the same way as to grid points.




Figure 10: Grid with intermediate steps (subdivisions)

The snap field settings are largely self-explanatory. One important setting in this group is the *Snap range*. Grid points and snap lines are both visual help elements that are managed separately by Draw. If you have activated a snap function and then move an object, Draw looks in the vicinity of the object for these special help elements to determine the final position of the object. With the snap range setting, you can determine the extent of this search area. Exactly how large the snap area will be depends on the current environment: which particular snap functions are in use, how the grid is configured, and whether there may be collisions with other objects. It is usually necessary to experiment a little to find what best suits your needs.

Snap to Snap Objects (Snap Lines and Snap Points)

Unlike grid points, *Snap lines* and *Snap points* are created by the user. Snap lines run horizontally or vertically and appear as dashed lines. Snap points appear as small crosses, again with dashed lines.

Note

In Draw, the names of the buttons in the Options toolbar are *Display Guides* and *Snap to Guides*, when what is actually meant is *Display Snap line* and *Snap to Snap line*.

If you have activated this function, you can position objects exactly. Horizontal and vertical snap lines can be used together. Snap lines are not active immediately after

inserting them, but are turned on (or off) using the **Display Guides**  icon or the **View** menu, as shown in Figure 11. If the snap line is no longer needed, you can hide

it (or display it again) with the  icon or the **View** menu.




Figure 11: Objects 'connected' to snap lines (left) or to a snap point (right). Note that the snap point functions as if it were the intersection of two snap lines.

Inserting a Snap Line with the Mouse

To insert a snap line in a drawing:

- 1) Hover the mouse cursor over the vertical ruler to create a vertical snap line, or over the horizontal ruler to create a horizontal snap line. Click and hold the left mouse button.
- 2) Drag the mouse into the drawing area to produce a snap line.

The snap line can be moved at any time by dragging it with the mouse. Moving a snap line will not, however, move any objects that have already been snapped to that line.

Inserting Snap Points and Snap Lines Using Coordinates

The command **Insert > Snap point / line** opens a dialog like that in Figure 12, where you can specify X and Y coordinates and choose the type of snap object: point, vertical line, or horizontal line. You can also access this menu by right-clicking in the draw area and selecting **Insert Snap Point/Line**.




Figure 12: Setting a) snap object type and b) snap object position using X,Y coordinates

Editing Snap Points and Snap Lines

All snap objects can be edited after they are set. If you right-click a snap object, an appropriate menu opens, allowing you to edit or delete it. Snap points and lines can also be deleted by dragging them entirely off of the page.

Snap to Page Margin

You can activate snapping to the page margin in the dialog, like that in Figure 13, accessed via **Tools > Options > OpenOffice Draw > Grid**. It is also possible to combine this with snap lines and snapping to grid.




Figure 13: Objects positioned on the page margins

Snap to Object Frame

With this function, you can position one drawing object on the border of another. The connection point can lie anywhere on the object's border. To use this function, first deactivate *Snap to grid*. Figure 14 shows some examples. Note that a typical object border will touch the border of a round object at only one of its four points.




Figure 14: Objects positioned on the border of another object

Snap to Object Points

This function operates similarly to the one just described. The difference is that the connection point can lie at only one of the four corner points of both the object being moved and the target object, as Figure 15 demonstrates. This leads to the situation where two round objects have a connection point that does not lie on either object, but at one of the red circled points.




Figure 15: Objects connected to the object point of another object

Help to Position Objects with Guiding Lines

To simplify the positioning of objects, it is possible to make visible guidelines—extensions of the edges of an object—while it is being moved. These guidelines have no snap function.

Guidelines, like those in Figure 16, can be (de-)activated under **Tools > Options > OpenOffice Draw > View > Guides when moving**, or by clicking the  icon on the Options toolbar.




Figure 16: Working with guiding lines

Drawing to Scale

In Draw, a drawing is created within a predefined drawing area or canvas. This will usually be in the Letter or A4 format, depending on your local settings, and will be output to the printer you have set up on your computer, which is usually the *default printer*. Depending on the actual size of drawn objects, it is often necessary or convenient to reduce or enlarge a drawing by some scaling value. You can specify the scale you want under **Tools > Options > OpenOffice Draw > General**.

The scale and selected unit of measurement are automatically reflected in the rulers, the window position, and the window size. Scale settings can be stored permanently in a template that you can then use for new drawings.

The scale you use has no effect on basic drawing operations. Draw will automatically calculate the necessary values (for example, dimension lines). The grid spacing is independent of drawing scale, since the grid is not a drawing element, but only an optical drawing aid.

Note

If you want to insert elements into a drawing from the Gallery or Clipboard, draw them at the same scale as the drawing to maintain the proper size ratio.

Splitting Drawings on Multiple Layers

Layers allow you to group parts of a drawing. You can insert and extract single layers as desired. For example, in architecture, the floor plan, heating, and electrical wiring can all occupy separate layers. With complex drawings, this layer technique offers many advantages. You can make layers visible or invisible as needed, or you can protect a layer from further changes while you work.

In Draw, three layers are always present by default: Layout, Controls, and Dimension Lines. Layout is the default layer when you create a new drawing.



To change to a layer, click on its tab. Everything that is drawn will be placed on the currently selected layer. The Controls layer is for control elements, such as icons and pull-down menus, and is not usually used for ordinary drawing elements. The Dimension Lines layer is used whenever you insert a dimension line on a drawing (unless the layer is made invisible). Use **Insert > Layer** to insert a new layer into a drawing (Figure 17).




Figure 17: Inserting a new layer

On the **Insert Layer** dialog, you can specify the following properties:

- *Visible*: If this property is not activated, the layer will not be shown.
- *Printable*: If this property is not activated, the layer will not be printed. This is useful if you use a 'draft' layer for guides or annotations that you use in making the drawing, but should not appear in the final output.
- *Locked*: All objects on this layer are protected from deletion, editing, or moving. No additional objects can be added to a protected layer. This property is useful when a base plan is to be protected while adding a new layer with other details.

Right-click on a layer tab to bring up a menu that allows you to insert or delete a layer, rename an existing layer, or modify a layer. You can change the names of the user-defined layers; the default layer names cannot be changed.

If you choose **Modify**, the dialog is similar to Figure 17, but you cannot edit the Name. You can edit the Title and Description and change the layer's properties (Visible, Printable, Locked).

Tip

You can move objects on one layer while you are working on another layer. To avoid doing this accidentally, lock layers that you are not currently working on.

An Example Drawing: House Plan and Furniture

A popular application for programs like Draw is the “moving the furniture” scenario. You can easily draw the floor plan of a room or a house using Draw. The simplest way is to draw walls as thick lines. Draw single rectangles or polygons, then combine them: place them together, select them, and from the right-click menu choose **Shapes > Merge** to make a single figure, and add a hatching pattern. Before doing this, you should read the section “Drawing to Scale” on page 11.

For this example, a suitable unit of measurement is the centimeter. The drawing scale and grid settings depend on the size of the floor plan.

Use the Position and Size dialog (right-click and choose Position and Size) to easily position and dimension individual wall sections. Make sure the rectangles completely overlap (see Figure 18); otherwise, merging will produce uneven edges.




Figure 18: Wall corner from two rectangles. From upper to lower: before merging, after merging and after hatching

Figure 19 shows the finished floor plan. In addition, a chest of drawers has been added.

The body of the chest is drawn on the *Layout* layer; the pulled-out drawer and the open doors are drawn as a group and put on a separate user-defined layer (Layer 4 in our example). Figure 20 shows how this is done. Making the layer with the drawers and doors visible or hidden will show them open and closed (see Figure 21). Hidden layers are shown with a colored tab.




Figure 19: Floor plan with chest of drawers




Figure 20: Using layers for different parts of a drawing. (Left) Draw the body of the chest on the Layout layer. (Right) Create a new layer and draw the open drawers and doors, keeping the Layout layer visible to help you position the additional objects.




Figure 21: Making layers visible or hidden. (Left) Hide the Layout layer to see what is on Layer4. (Right) Show the Layout layer and hide Layer4 to show chest with drawers closed.

Caution



If you copy a drawing object to the Clipboard or into the Gallery, all layers other than the three standard layers (Layout, Controls, and Dimension Lines) are lost. Furthermore, all objects are pasted into the Layout layer. Reconstructing layers is much easier if you assemble objects on a layer into a group before copying.

Changing the Layer of a Drawing Object

Draw has no direct command to change layers. To move an object to another layer, change to the new layer, select the desired object or group, and then cut and paste it into position. Watch the status bar (the selected object's layer name is shown in the information field) to follow and check the change.


You can also click the object, hold the mouse button down for about two seconds until the cursor changes from a hand to a pointer with an open rectangle, then drag and drop it onto the appropriate layer.

Creating a Multi-page Document

Draw documents, like presentation (Impress) documents, can consist of multiple pages. As in Impress, tools to manage pages and backgrounds are available.

Pages are automatically named as *Slide 1*, *Slide 2*, and so on. This description is relative; if you move pages around, they are automatically renumbered. If you want to have fixed slide (page) names, you must name them yourself. Page names are useful for working with the Navigator, and when you want to insert single pages using **Insert > File** into another document.


Using the Pages Area



By default, the Pages area is docked on the left of the Draw window. It shows every page in the document as a small picture. Select a picture from the Pages area, and the corresponding page is loaded in the main workspace. Click on the page to activate it for editing.

The Pages area behaves similarly to the Styles and Formatting area. Drag on the gray separator line to change the width of the Pages pane. Click on the middle of this line to show or hide the pane. Double-click with the *Control* key pressed in the upper gray area to dock or undock the area, which can be turned into a floating window.

In the Pages area, you can drag and drop a picture to change the order of pages in the document; a black horizontal line indicates where the page will be inserted.



Using the context menu, you can insert or delete pages or duplicate pages with copy and paste (alternatively, create duplicate pages using **Insert > Duplicate Slide** on the menu).

Using Page Backgrounds

With background pages, you can set common settings for multiple pages of the Draw document. These include setting the color or graphics of the background, background objects, and fields such as page numbering and author.

Note

The terms used in this area may not be completely consistent, so that the terms Slide/Page and Master/Background/Page Template are sometimes used more or less interchangeably. When looking for information in Help, you may need to use alternative search terms.

Creating a Page Background

Change with **View > Master** to the Master view and note that a related Master View toolbar opens (Figure 22). If this toolbar does not appear, activate it with **View > Toolbars**. This toolbar offers switches for a new background page and for renaming the master page. These functions are also available by right-clicking on a page picture in the Pages area of the Master view. The button for deleting a master page is only available when you select a background page in the Pages area that has not yet been assigned to any page.




Figure 22: Master View toolbar

To return to normal mode, click the **Close Master View** button shown in Figure 22, or **View > Normal**.

You can edit background pages just like normal pages. With **Format > Page > Background**, you can set the color, pattern, or background picture. These settings are specific to each background page. In the Master view, you can set the page size and orientation; these settings apply to all pages.

If you insert drawing objects on a background page, they are visible on all pages that use this background. This is a convenient way, for example, to place a logo on every page.

Master pages are organized in layers just like normal pages. The layers of normal pages are associated with the layer of the same name on the Master page. Accordingly, the layers Layout/Control/Dimension Lines are considered to be a unit, and the Master page layer Background objects are associated with them.

With **Insert > Fields**, you can insert the date, time, page number, author, and filename. No other fields are available. With page number, you cannot insert a fixed page number; only a variable is allowed. The actual number appears on the page itself and is determined by the page's position. The number is automatically adjusted if the page is subsequently moved.

Assigning and Managing Page Backgrounds

You can open the Slide Design dialog (Figure 23) in two ways:

- Right-click on the page and choose **Page > Slide design**, or
- Look in the status bar to see which background page is the current one. Double-click in this field.

The Slide Design dialog (Figure 23) shows the available background pages for that page.




Figure 23: Slide design dialog

If the **Exchange background page** option is selected, the selected background page will be applied to *all* pages of the document, not just the currently active page.

The **Delete unused backgrounds** option deletes any backgrounds (as shown in the Slide Design dialog) that have not been assigned to a page.

Click the **Load** button to open the Load Slide Design dialog shown in Figure 24. From there, you can load previously prepared background pages. All Draw and Impress templates can be used for this purpose. Note, however, that using Impress templates will bring in only the background and not the other elements prepared in Impress.




Figure 24: Load Slide Design dialog

There is no special means of storing background pages as templates. Instead, you can load a document with the desired background page, and store this document as a document template with **File > Template > Save**.

Color Palette: Adding or Changing Single Colors

Draw, like all OpenOffice components, uses color palettes to represent colors. In addition, you can customize color palettes to suit your preferences. You can modify colors in a palette, add other colors, or create new color palettes.

Reach these options with **Tools > Options > OpenOffice > Colors** or with **Format > Area > Colors** (tab) (see Figure 25). The latter method allows color palettes to be loaded or stored for future use. Any modifications made to colors apply only to the currently active palette.

OpenOffice always uses the RGB color model internally. Other methods are also available for defining a color value.

The color values can be input directly as numbers. Choose between the RGB color model (base colors **R**ed, **G**reen, and **B**lue) and CMYK (base colors **C**yan, **M**agenta, **Y**ellow, and black**K**). The conversion to RGB values is made automatically.

Tip

Information about color models can be found under:

http://en.wikipedia.org/wiki/Color_model or with
[https://www.w3schools.com/html/tryit.asp?
filename=tryhtml_styles_color](https://www.w3schools.com/html/tryit.asp?filename=tryhtml_styles_color)

Individual color tones are produced by using different values of the base colors. The color value can be any integer value between 0 and 255. As an example, Red 3 has a red value of 184, a green value of 71, and a blue value of 0 in the RGB model. The CMYK color model uses percentages (in this case, 0%, 44%, 72%, and 28% respectively).

Change these values to manipulate the color tone. Either enter a number directly or use the spinners on the right side of each field. The change in color will be shown in the lower color field (see Figure 25). Click the **Modify** button to apply and store the new setting.

To add a new color to the current palette, enter a new name in the Name field and set the desired color values. Click **Add**. The new color will be added to the end of the palette and stored in the currently active palette.

You can also delete colors from a palette. Select a color from the **Color** pull-down menu, click the **Delete** button, then click **OK** to confirm the change.




Figure 25: The Colors tab in the Area dialog

Click on the **Edit** button to open a dialog where you can set individual colors (see Figure 26). Many more input possibilities are available in this dialog.

In the lower area, you can enter values in the RGB, CMYK, and HSB (Hue, Saturation, and Brightness) models.

The two color samples at the lower right show the current color (left) and the new color specified by the color value fields (right).




Figure 26: Color dialog

The color window permits a direct selection of color without any knowledge of color values. The color window is linked directly with the various color model input fields; if you click on a color in this window, the numbers change accordingly, and a preview of the color appears on the left of the two color fields (lower left in Figure 26; see also Method 2 below).


If you click **OK**, the color window closes, and the input field becomes active again. At this stage, you can select the color you just defined, give it a new name, and store it by clicking the **Add** button. The old color will then be overwritten (without any further warning).

Changing Colors Using the Color Dialog

Method 1

You can change the current color by modifying the individual color values explicitly. It is possible to change from one color model to another during this process, but settings are always calculated and stored according to the RGB model. This may result in some slight adjustment to your input values in the other models.

The color wheel to the right illustrates the HSB color model. This model defines color tone using three parameters: Hue (possible values from 0 to 359), Saturation (possible values from 0 to 100), and Brightness (possible values from 0 to 100). The hue number represents the angle on the color wheel; the other two are percentage values.



Method 2

You can select a new color by clicking on a point in the color window of the dialog (Figure 26). The chosen color is shown in a black circle, which can be dragged with the mouse. If this color is not quite right, you can fine-tune it as described above in Method 1 by changing the color values.

As you drag the small circle, you will see the value change in the number fields. The CMYK and RGB are more or less self-explanatory. To make the HSB model a little clearer, some additional comments are necessary.

To better understand the working of the HSB model, move the circle from left to right and top to bottom. Horizontal movements change the Saturation, and vertical movements change the Brightness. The Hue is chosen from the color bar to the right of the color window. You can click the bar to choose a specific hue, or click and drag to continuously adjust it.

Creating Cool Effects

Duplication

Duplication makes copies of an object while applying a set of changes (such as color or rotation) to the duplicates, as Figure 27 shows.

To start duplication, click an object or group, then choose **Edit > Duplicate**. The Duplicate dialog (Figure 28) appears.




Figure 27: Duplication example




Figure 28: Duplicate dialog

Choose the number of copies, their separation (placement), rotation, and so on. The choices above, when applied to a blue rectangle, produce the result shown in Figure 27.

Cross-fading

Cross-fading transforms one shape into another. The result is a new group of objects, including the two endpoints and the intermediate steps.




Figure 29: Cross-fading example

To do a cross-fade, like that in Figure 29, first select two objects as illustrated in Figure 30.




Figure 30: The two objects selected for cross fading

Then choose **Edit > Cross-fading**, as we did in Figure 31.




Figure 31: Cross-fading dialog

In the dialog, choose the number of increments (transition steps). You probably want to check the *Cross-fade attributes* and *Same orientation* options, as shown in Figure 29.

Which Object Goes in Front?

How do I tell Draw that I want  and not  ?

Select  (the object we want in front), right-click and choose **Arrange > Bring to Front** (or press *Ctrl+Shift+plus*). Or select  (the object we want behind), right-click and choose **Arrange > Send to Back**, or press *Ctrl+Shift+minus*.