# CICE: the Los Alamos Sea Ice Model Documentation and Software User's Manual

# Version 5.0 DRAFT

## LA-CC-06-012

Elizabeth C. Hunke, William H. Lipscomb, Adrian K. Turner, Nicole Jeffery, Scott Elliott Los Alamos National Laboratory Los Alamos NM 87545

September 17, 2013

## **Contents**

1 Introduction								
2	Cou	Coupling with other climate model components						
	2.1	<u>.</u>	5					
	2.2		7					
	2.3		8					
3	Mod	Model components 1						
	3.1	Tracers	2					
		3.1.1 Tracers that depend on other tracers (e.g., melt ponds)	3					
		3.1.2 Ice age	4					
		<del>-</del>	5					
			7					
		3.1.5 Brine height	8					
	3.2	· · · · · · · · · · · · · · · · · · ·	0					
		3.2.1 Reconstructing area and tracer fields	1					
		3.2.2 Locating departure triangles	3					
		3.2.3 Integrating fields	6					
		3.2.4 Updating state variables	7					
	3.3	Transport in thickness space	8					
	3.4	Mechanical redistribution	0					
	3.5		3					
		·	4					
			5					
		3.5.3 Revised approach	8					
	3.6	Thermodynamics						
		3.6.1 Melt ponds						
		3.6.2 Thermodynamic surface forcing balance						

		3.6.3	New temperatures						. :	52
		3.6.4	Growth and melting						. (	61
_										
4			mplementation							63
	4.1		ory structure							63
	4.2		oundary conditions and masks							67
		4.2.1	Grid domains and blocks							67
		4.2.2	Tripole grids							68
		4.2.3	Bio-grid							69
		4.2.4	Column configuration							69
		4.2.5	Boundary conditions							69
		4.2.6	Masks							70
	4.3		zation and coupling							70
	4.4		ng an appropriate time step							71
	4.5	Model	output							72
		4.5.1	History files					•		72
		4.5.2	Diagnostic files						•	73
		4.5.3	Restart files						•	73
	4.6	Execut	ion procedures						•	74
	4.7	Perform	mance						•	76
	4.8	Adding	g things						•	79
		4.8.1	Timers						•	79
		4.8.2	History fields							79
		4.8.3	Tracers							80
_	TD.									01
5		ıbleshoo								81
	5.1		setup							81
	5.2		xecution							82
	5.3	٠.	ging hints							82
	5.4		ı bugs							83
	5.5		dimensional output							83
	5.6	-	etation of albedos							83
	5.7	Prolife	rating subprocess parameterizations	•	•	•				84
	Acknowledgments and Copyright 84						84			
	Table of namelist options 85									
	Inde	ex of pri	mary variables and parameters						(	91
	General Index									
		iograph								08
		0 1	•							

## 1 Introduction

The Los Alamos sea ice model (CICE) is the result of an effort to develop a computationally efficient sea ice component for a fully coupled atmosphere—land global climate model. It was designed to be compatible with the Parallel Ocean Program (POP), an ocean circulation model developed at Los Alamos National Laboratory for use on massively parallel computers [61, 13, 14]. The current version of the model has been enhanced greatly through collaborations with members of the community.

CICE has several interacting components: a thermodynamic model that computes local growth rates of snow and ice due to vertical conductive, radiative and turbulent fluxes, along with snowfall; a model of ice dynamics, which predicts the velocity field of the ice pack based on a model of the material strength of the ice; a transport model that describes advection of the areal concentration, ice volumes and other state variables; and a ridging parameterization that transfers ice among thickness categories based on energetic balances and rates of strain. External routines would prepare and execute data exchanges with an external "flux coupler," which then passes the data to other climate model components such as POP.

This model release is CICE version 5.0, available from http://climate.lanl.gov/Models/CICE/. It updates CICE 4.1, which was released in May 2010:

- A method for prognosing sea ice salinity
- Two new explicit melt pond parameterizations (topo and level-ice)
- Sea ice biogeochemistry
- Elastic-Anisotropic-Plastic rheology
- Improved parameterization of form drag
- Gracefully handles the case when an internal layer melts completely
- Gregorian calendar with leap years
- Reduced memory and floating-point operations for tracer calculations
- Defined tracers for ice and snow enthalpy
- New history variables for melt ponds, ridging diagnostics, biogeochemistry and more
- Read/write variables on the extended grid, including ghost (halo) cells
- Parallelism option via OpenMP threads
- Improved parallel efficiency through halo masks and new block distributions
- Parallel I/O option via the PIO library
- CPP options for categories, layers and tracers
- Corrected bugs, particularly for nonstandard configurations.

With so many new parameterizations, we must admit that all combinations have not been tested. Also, different parameterizations for various sub-processes (e.g., snow infiltration by melt or sea water have been introduced as part of the new code options, which need to be unified or pulled out as separate options.

Generally speaking, subroutine names are given in *italic* and file names are **boldface** in this document. Symbols used in the code are typewritten, while corresponding symbols in this document are in the

	Atmosphere		Ocean			
	Provided by the flux coupler to the sea ice model					
$z_{o}$	Atmosphere level height	$F_{frzmlt}$	Freezing/melting potential			
$ec{U}_a$	Wind velocity	$T_w$	Sea surface temperature			
$Q_a$	Specific humidity	S	Sea surface salinity			
$ ho_a$	Air density	$\nabla H_{\circ}$	Sea surface slope			
$\Theta_a$	Air potential temperature	$ec{U}_w$	Surface ocean currents			
$T_a$	Air temperature					
$F_{sw\downarrow}$	Shortwave radiation (4 bands)					
$F_{L\downarrow}$	Incoming longwave radiation					
$F_{rain}$	Rainfall rate					
$F_{snow}$	Snowfall rate					
	Provided by the sea ice m	odel to th	e flux coupler			
$ec{ au}_a$	Wind stress	$F_{sw \Downarrow}$	Penetrating shortwave			
$F_s$	Sensible heat flux	$F_{water}$	Fresh water flux			
$F_l$	Latent heat flux	$F_{hocn}$	Net heat flux to ocean			
$F_{L\uparrow}$	Outgoing longwave	$F_{salt}$	Salt flux			
$F_{evap}$	Evaporated water	$ec{ au}_w$	ice-ocean stress			
$\alpha$	Surface albedo (4 bands)	$F_{bio}$	Biogeochemical fluxes			
$T_{sfc}$	Surface temperature					
	$a_i$ Ice fraction					
	$T_a^{ref}$ 2 m reference temperature (diagnostic)					
	$Q_a^{ref}$ 2 m reference humidity (diagnostic)					
	$F_{swabs}$ Absorbed shortwave (diagnostic)					

Table 1: Data exchanged between the CESM flux coupler and the sea ice model.

math font which, granted, looks a lot like italic. A comprehensive index, including a glossary of symbols with many of their values, appears at the end. The organization of this software distribution is described in Section 4.1; most files and subroutines referred to in this documentation are part of the CICE code found in cice/source/, unless otherwise noted.

We pronounce the model name as "sea ice," but there has been a small grass-roots movement underway to alter the model name's pronunciation from "sea ice" to what an Italian might say, chē'-chā or "chee-chay." Others choose to say sīs (English, rhymes with "ice"), sēs (French, like "cease"), or shē-ī-soo ("Shii-aisu," Japanese).

For more information about the CICE model and its user community, visit the web pages http://oceans11.lanl.gov/trac/CICE/wiki http://oceans11.lanl.gov/trac/CICE/wiki/CiceUsers http://oceans11.lanl.gov/trac/CICE/wiki/CiceCodeModifications http://oceans11.lanl.gov/trac/CICE/wiki/CiceDev

## Coupling with other climate model components

The sea ice model exchanges information with the other model components via a flux coupler. CICE has been coupled into numerous climate models with a variety of coupling techniques. This document is oriented primarily toward the CESM Flux Coupler [38] from NCAR, the first major climate model to incorpo2.1 Atmosphere 5

rate CICE. The flux coupler was originally intended to gather state variables from the component models, compute fluxes at the model interfaces, and return these fluxes to the component models for use in the next integration period, maintaining conservation of momentum, heat and fresh water. However, several of these fluxes are now computed in the ice model itself and provided to the flux coupler for distribution to the other components, for two reasons. First, some of the fluxes depend strongly on the state of the ice, and vice versa, implying that an implicit, simultaneous determination of the ice state and the surface fluxes is necessary for consistency and stability. Second, given the various ice types in a single grid cell, it is more efficient for the ice model to determine the net ice characteristics of the grid cell and provide the resulting fluxes, rather than passing several values of the state variables for each cell. These considerations are explained in more detail below.

The fluxes and state variables passed between the sea ice model and the CESM flux coupler are listed in Table 1. By convention, directional fluxes are positive downward.

The ice fraction  $a_i$  (aice)<sup>1</sup> is the total fractional ice coverage of a grid cell. That is, in each cell,

 $a_i = 0$  if there is no ice  $a_i = 1$  if there is no open water  $0 < a_i < 1$  if there is both ice and open water,

where  $a_i$  is the sum of fractional ice areas for each category of ice. The ice fraction is used by the flux coupler to merge fluxes from the ice model with fluxes from the other components. For example, the penetrating shortwave radiation flux, weighted by  $a_i$ , is combined with the net shortwave radiation flux through ice-free leads, weighted by  $(1-a_i)$ , to obtain the net shortwave flux into the ocean over the entire grid cell. The flux coupler requires the fluxes to be divided by the total ice area so that the ice and land models are treated identically (land also may occupy less than 100% of an atmospheric grid cell). These fluxes are "per unit ice area" rather than "per unit grid cell area."

In some coupled climate models (for example, recent versions of the U.K. Hadley Centre model) the surface air temperature and fluxes are computed within the atmosphere model and are passed to CICE. In this case the logical parameter <code>calc\_Tsfc</code> in <code>ice\_therm\_vertical</code> is set to false. The fields <code>fsurfn</code> (the net surface heat flux from the atmosphere), <code>flatn</code> (the surface latent heat flux), and <code>fcondtopn</code> (the conductive flux at the top surface) for each ice thickness category are copied or derived from the input coupler fluxes and are passed to the thermodynamic driver subroutine, <code>thermo\_vertical</code>. At the end of the time step, the surface temperature and effective conductivity (i.e., thermal conductivity divided by thickness) of the top ice/snow layer in each category are returned to the atmosphere model via the coupler. Since the ice surface temperature is treated explicitly, the effective conductivity may need to be limited to ensure stability. As a result, accuracy may be significantly reduced, especially for thin ice or snow layers. A more stable and accurate procedure would be to compute the temperature profiles for both the atmosphere and ice, together with the surface fluxes, in a single implicit calculation. This was judged impractical, however, given that the atmosphere and sea ice models generally exist on different grids and/or processor sets.

## 2.1 Atmosphere

The wind velocity, specific humidity, air density and potential temperature at the given level height  $z_{\circ}$  are used to compute transfer coefficients used in formulas for the surface wind stress and turbulent heat fluxes  $\vec{\tau}_a$ ,  $F_s$ , and  $F_l$ , as described below. Wind stress is arguably the primary forcing mechanism for the ice motion, although the ice—ocean stress, Coriolis force, and slope of the ocean surface are also important [64]. The sensible and latent heat fluxes,  $F_s$  and  $F_l$ , along with shortwave and longwave radiation,  $F_{sw\downarrow}$ ,  $F_{L\downarrow}$  and  $F_{L\uparrow}$ , are included in the flux balance that determines the ice or snow surface temperature when calc\_Tsfc

<sup>&</sup>lt;sup>1</sup>Typewritten equivalents used in the code are described in the index.

= true. As described in Section 3.6, these fluxes depend nonlinearly on the ice surface temperature  $T_{sfc}$ . The balance equation is iterated until convergence, and the resulting fluxes and  $T_{sfc}$  are then passed to the flux coupler.

The snowfall precipitation rate (provided as liquid water equivalent and converted by the ice model to snow depth) also contributes to the heat and water mass budgets of the ice layer. Melt ponds generally form on the ice surface in the Arctic and refreeze later in the fall, reducing the total amount of fresh water that reaches the ocean and altering the heat budget of the ice; this version includes two new melt pond parameterizations. Rain and all melted snow end up in the ocean.

Wind stress and transfer coefficients for the turbulent heat fluxes are computed in subroutine *atmo\_boundary\_layer* following [38]. For clarity, the equations are reproduced here in the present notation.

The wind stress and turbulent heat flux calculation accounts for both stable and unstable atmosphere–ice boundary layers. Define the "stability"

$$\Upsilon = \frac{\kappa g z_{\circ}}{u^{*2}} \left( \frac{\Theta^{*}}{\Theta_{a} (1 + 0.606 Q_{a})} + \frac{Q^{*}}{1/0.606 + Q_{a}} \right),$$

where  $\kappa$  is the von Karman constant, g is gravitational acceleration, and  $u^*$ ,  $\Theta^*$  and  $Q^*$  are turbulent scales for velocity, temperature and humidity, respectively:

$$u^* = c_u |\vec{U}_a|$$

$$\Theta^* = c_\theta (\Theta_a - T_{sfc})$$

$$Q^* = c_q (Q_a - Q_{sfc}).$$
(1)

The wind speed has a minimum value of 1 m/s. We have ignored ice motion in  $u^*$ , and  $T_{sfc}$  and  $Q_{sfc}$  are the surface temperature and specific humidity, respectively. The latter is calculated by assuming a saturated surface, as described in Section 3.6.2.

Neglecting form drag, the exchange coefficients  $c_u$ ,  $c_\theta$  and  $c_q$  are initialized as

$$\frac{\kappa}{\ln(z_{ref}/z_{ice})}$$

and updated during a short iteration, as they depend upon the turbulent scales. (For the case with form drag, see section 2.3.) Here,  $z_{ref}$  is a reference height of 10 m and  $z_{ice}$  is the roughness length scale for the given sea ice category.  $\Upsilon$  is constrained to have magnitude less than 10. Further, defining  $\chi=(1-16\Upsilon)^{0.25}$  and  $\chi\geq 1$ , the "integrated flux profiles" for momentum and stability in the unstable ( $\Upsilon<0$ ) case are given by

$$\psi_m = 2 \ln [0.5(1+\chi)] + \ln [0.5(1+\chi^2)] - 2 \tan^{-1} \chi + \frac{\pi}{2},$$
  
$$\psi_s = 2 \ln [0.5(1+\chi^2)].$$

In a departure from the parameterization used in [38], we use profiles for the stable case following [37],

$$\psi_m = \psi_s = -[0.7\Upsilon + 0.75(\Upsilon - 14.3)\exp(-0.35\Upsilon) + 10.7].$$

The coefficients are then updated as

$$c'_{u} = \frac{c_{u}}{1 + c_{u} (\lambda - \psi_{m}) / \kappa}$$

$$c'_{\theta} = \frac{c_{\theta}}{1 + c_{\theta} (\lambda - \psi_{s}) / \kappa}$$

$$c'_{q} = c'_{\theta}$$

2.2 Ocean 7

where  $\lambda = \ln(z_{\circ}/z_{ref})$ . The first iteration ends with new turbulent scales from equations (1). After five iterations the latent and sensible heat flux coefficients are computed, along with the wind stress:

$$C_{l} = \rho_{a} \left( L_{vap} + L_{ice} \right) u^{*} c_{q}$$

$$C_{s} = \rho_{a} c_{p} u^{*} c_{\theta}^{*} + 1,$$

$$\vec{\tau}_{a} = \frac{\rho_{a} u^{*2} \vec{U}_{a}}{|\vec{U}_{a}|},$$

where  $L_{vap}$  and  $L_{ice}$  are latent heats of vaporization and fusion,  $\rho_a$  is the density of air and  $c_p$  is its specific heat. Again following [37], we have added a constant to the sensible heat flux coefficient in order to allow some heat to pass between the atmosphere and the ice surface in stable, calm conditions.

The atmospheric reference temperature  $T_a^{ref}$  is computed from  $T_a$  and  $T_{sfc}$  using the coefficients  $c_u$ ,  $c_\theta$  and  $c_q$ . Although the sea ice model does not use this quantity, it is convenient for the ice model to perform this calculation. The atmospheric reference temperature is returned to the flux coupler as a climate diagnostic. The same is true for the reference humidity,  $Q_a^{ref}$ .

Additional details about the latent and sensible heat fluxes and other quantities referred to here can be found in Section 3.6.2.

For CICE run in stand-alone mode (i.e., uncoupled), the AOMIP shortwave and longwave radiation formulas are available in **ice\_forcing.F90**. In function *longwave\_rosati\_miyakoda*, downwelling longwave is computed as

$$F_{lw\downarrow} = \epsilon \sigma T_s^4 - \epsilon \sigma T_a^4 (0.39 - 0.05e_a^{1/2})(1 - 0.8f_{cld}) - 4\epsilon \sigma T_a^3 (T_s - T_a)$$

where the atmospheric vapor pressure (mb) is  $e_a = 1000Q_a/(0.622 + 0.378Q_a)$ ,  $\epsilon = 0.97$  is the ocean emissivity,  $\sigma$  is the Stephan-Boltzman constant,  $f_{cld}$  is the cloud cover fraction, and  $T_a$  is the surface air temperature (K). The first term on the right is upwelling longwave due to the mean (merged) ice and ocean surface temperature,  $T_s$  (K), and the other terms on the right represent the net longwave radiation patterned after [55]. The downwelling longwave formula of [53] is also available in function longwave\_parkinson\_washington:

$$F_{lw\downarrow} = \epsilon \sigma T_a^4 (1 - 0.261 \exp(-7.77 \times 10^{-4} T_a^2) (1 + 0.275 f_{cld})$$

The value of  $F_{lw\uparrow}$  is different for each ice thickness category, while  $F_{lw\downarrow}$  depends on the mean value of surface temperature averaged over all of the thickness categories and open water.

The AOMIP shortwave forcing formula (in subroutine *compute\_shortwave*) incorporates the cloud fraction and humidity through the atmospheric vapor pressure:

$$F_{sw\downarrow} = \frac{1353\cos^2 Z}{10^{-3}(\cos Z + 2.7)e_a + 1.085\cos Z + 0.1} \left(1 - 0.6f_{cld}^3\right) > 0$$

where  $\cos Z$  is the cosine of the solar zenith angle.

### 2.2 Ocean

New sea ice forms when the ocean temperature drops below its freezing temperature. In the Bitz and Lipscomb thermodynamics, [7]  $T_f = -\mu S$ , where S is the seawater salinity and  $\mu = 0.054$  °/ppt is the ratio of the freezing temperature of brine to its salinity (linear liquidus approximation). For the mushy thermodynamics,  $T_f$  is given by a piecewise linear liquidus relation. The ocean model calculates the new ice formation; if the freezing/melting potential  $F_{frzmlt}$  is positive, its value represents a certain amount of

frazil ice that has formed in one or more layers of the ocean and floated to the surface. (The ocean model assumes that the amount of new ice implied by the freezing potential actually forms.)

If  $F_{frzmlt}$  is negative, it is used to heat already existing ice from below. In particular, the sea surface temperature and salinity are used to compute an oceanic heat flux  $F_w$  ( $|F_w| \leq |F_{frzmlt}|$ ) which is applied at the bottom of the ice. The portion of the melting potential actually used to melt ice is returned to the coupler in  $F_{hocn}$ . The ocean model adjusts its own heat budget with this quantity, assuming that the rest of the flux remained in the ocean.

In addition to runoff from rain and melted snow, the fresh water flux  $F_{water}$  includes ice melt water from the top surface and water frozen (a negative flux) or melted at the bottom surface of the ice. This flux is computed as the net change of fresh water in the ice and snow volume over the coupling time step, excluding frazil ice formation and newly accumulated snow. Setting the namelist option update\_ocn\_f to true causes frazil ice to be included in the fresh water and salt fluxes.

There is a flux of salt into the ocean under melting conditions, and a (negative) flux when sea water is freezing. However, melting sea ice ultimately freshens the top ocean layer, since the ocean is much more saline than the ice. The ice model passes the net flux of salt  $F_{salt}$  to the flux coupler, based on the net change in salt for ice in all categories. In the present configuration, ice\_ref\_salinity is used for computing the salt flux, although the ice salinity used in the thermodynamic calculation has differing values in the ice layers.

A fraction of the incoming shortwave  $F_{sw\Downarrow}$  penetrates the snow and ice layers and passes into the ocean, as described in Section 3.6.2.

Many ice models compute the sea surface slope  $\nabla H_{\circ}$  from geostrophic ocean currents provided by an ocean model or other data source. In our case, the sea surface height  $H_{\circ}$  is a prognostic variable in POP—the flux coupler can provide the surface slope directly, rather than inferring it from the currents. (The option of computing it from the currents is provided in subroutine  $evp\_prep$ .) The sea ice model uses the surface layer currents  $\vec{U}_w$  to determine the stress between the ocean and the ice, and subsequently the ice velocity  $\vec{u}$ . This stress, relative to the ice,

$$\vec{\tau}_w = c_w \rho_w \left| \vec{U}_w - \vec{u} \right| \left[ \left( \vec{U}_w - \vec{u} \right) \cos \theta + \hat{k} \times \left( \vec{U}_w - \vec{u} \right) \sin \theta \right]$$

is then passed to the flux coupler (relative to the ocean) for use by the ocean model. Here,  $\theta$  is the turning angle between geostrophic and surface currents,  $c_w$  is the ocean drag coefficient,  $\rho_w$  is the density of seawater, and  $\hat{k}$  is the vertical unit vector. The turning angle is necessary if the top ocean model layers are not able to resolve the Ekman spiral in the boundary layer. If the top layer is sufficiently thin compared to the typical depth of the Ekman spiral, then  $\theta=0$  is a good approximation. Here we assume that the top layer is thin enough.

For CICE run in stand-alone mode (i.e., uncoupled), a thermodynamic slab ocean mixed-layer parameterization is available in **ice\_ocean.F90**. The turbulent fluxes are computed above the water surface using the same parameterizations as for sea ice, but with parameters appropriate for the ocean. The surface flux balance takes into account the turbulent fluxes, oceanic heat fluxes from below the mixed layer, and shortwave and longwave radiation, including that passing through the sea ice into the ocean. If the resulting sea surface temperature falls below the salinity-dependent freezing point, then new ice (frazil) forms. Otherwise, heat is made available for melting the ice.

## 2.3 Variable exchange coefficients

In the default CICE setup, atmospheric and oceanic neutral drag coefficients ( $c_u$  and  $c_w$ ) are assumed constant in time and space. These constants are chosen to reflect friction associated with an effective sea ice surface roughness at the ice-atmosphere and ice-ocean interfaces. Sea ice (in both Arctic and Antarctic)

contains pressure ridges as well as floe and melt pond edges that act as discrete obstructions to the flow of air or water past the ice, and are a source of form drag. Following [70] and based on recent theoretical developments [45, 44], the neutral drag coefficients can now be estimated from properties of the ice cover such as ice concentration, vertical extent and area of the ridges, freeboard and floe draft, and size of floes and melt ponds. The new parameterization allows the drag coefficients to be coupled to the sea ice state and therefore to evolve spatially and temporally. This parameterization is contained in the subroutine <code>neutral\_drag\_coeffs</code> and is accessed by setting <code>calc\_formdrag = .true.</code> in the namelist.

Following [70], consider the general case of fluid flow obstructed by N randomly oriented obstacles of height H and transverse length  $L_y$ , distributed on a domain surface area  $S_T$ . Under the assumption of a logarithmic fluid velocity profile, the general formulation of the form drag coefficient can be expressed as

$$C_d = \frac{NcS_c^2 \gamma L_y H}{2S_T} \left[ \frac{\ln(H/z_0)}{\ln(z_{ref}/z_0)} \right]^2, \tag{2}$$

where  $z_0$  is a roughness length parameter at the top or bottom surface of the ice,  $\gamma$  is a geometric factor, c is the resistance coefficient of a single obstacle, and  $S_c$  is a sheltering function that takes into account the shielding effect of the obstacle,

$$S_c = (1 - \exp(-s_l D/H))^{1/2},$$
 (3)

with D the distance between two obstacles and  $s_l$  an attenuation parameter.

As in the original drag formulation in CICE (sections 2.1 and 2.2),  $c_u$  and  $c_w$  along with the transfer coefficients for sensible heat,  $c_\theta$ , and latent heat,  $c_q$ , are initialized to a situation corresponding to neutral atmosphere–ice and ocean–ice boundary layers. The corresponding neutral exchange coefficients are then replaced by coefficients that explicitly account for form drag, expressed in terms of various contributions as

The contributions to form drag from ridges (and keels underneath the ice), floe edges and melt pond edges can be expressed using the general formulation of equation (2) (see [70] for details). Individual terms in equation (4) are fully described in [70]. Following [4] the skin drag coefficient is parametrized as

$$\mathtt{Cdn}_{-}(\mathtt{atm/ocn})_{-}\mathtt{skin} = a_i \left( 1 - m_{(s/k)} \frac{H_{(s/k)}}{D_{(s/k)}} \right) c_{s(s/k)}, \text{ if } \frac{H_{(s/k)}}{D_{(s/k)}} \ge \frac{1}{m_{(s/k)}}, \tag{5}$$

where  $m_s$  ( $m_k$ ) is a sheltering parameter that depends on the average sail (keel) height,  $H_s$  ( $H_k$ ), but is often assumed constant,  $D_s$  ( $D_k$ ) is the average distance between sails (keels), and  $c_{ss}$  ( $c_{sk}$ ) is the unobstructed atmospheric (oceanic) skin drag that would be attained in the absence of sails (keels) and with complete ice coverage,  $a_{ice} = 1$ .

Calculation of equations (2)–(5) requires that small-scale geometrical properties of the ice cover be related to average grid cell quantities already computed in the sea ice model. These intermediate quantities are briefly presented here and described in more detail in [70]. The sail height is given by

$$H_s = 2 \frac{v_{rdg}}{a_{rdg}} \left( \frac{\alpha \tan \alpha_k R_d + \beta \tan \alpha_s R_h}{\phi_r \tan \alpha_k R_d + \phi_k \tan \alpha_s R_h^2} \right),$$

and the distance between sails

$$D_s = 2H_s \frac{a_i}{a_{rdg}} \left( \frac{\alpha}{\tan \alpha_s} + \frac{\beta}{\tan \alpha_k} \frac{R_h}{R_d} \right),$$

where  $0<\alpha<1$  and  $0<\beta<1$  are weight functions,  $\alpha_s$  and  $\alpha_k$  are the sail and keel slope,  $\phi_s$  and  $\phi_k$  are constant porosities for the sails and keels, and we assume constant ratios for the average keel depth and sail height  $(H_k/H_s=R_h)$  and for the average distances between keels and between sails  $(D_k/D_s=R_d)$ . With the assumption of hydrostatic equilibrium, the effective ice plus snow freeboard is  $H_f=\bar{h}_i(1-\rho_i/\rho_w)+\bar{h}_s(1-\rho_s/\rho_w)$ , where  $\rho_i$ ,  $\rho_w$  and  $\rho_s$  are respectively the densities of sea ice, water and snow,  $\bar{h}_i$  is the mean ice thickness and  $\bar{h}_s$  is the mean snow thickness (means taken over the ice covered regions). For the melt pond edge elevation we assume that the melt pond surface is at the same level as the ocean surface surrounding the floes [20, 21, 22] and use the simplification  $H_p=H_f$ . Finally to estimate the typical floe size  $L_A$ , distance between floes,  $D_F$ , and melt pond size,  $L_P$  we use the parameterizations of [45] to relate these quantities to the ice and pond concentrations. All of these intermediate quantities are available as history output, along with Cdn\_atm, Cdn\_ocn and the ratio Cdn\_atm\_ocn\_n between the total atmospheric drag and the atmospheric neutral drag coefficient.

We assume that the total neutral drag coefficients are thickness category independent, but through their dependance on the diagnostic variables described above, they vary both spatially and temporally. The total drag coefficients and heat transfer coefficients will also depend on the type of stratification of the atmosphere and the ocean, and we use the parameterization described in section 2.1 that accounts for both stable and unstable atmosphere—ice boundary layers. In contrast to the neutral drag coefficients the stability effect of the atmospheric boundary layer is calculated separately for each ice thickness category. The stability of the ice—ocean boundary layer is currently not accounted for.

## 3 Model components

The Arctic and Antarctic sea ice packs are mixtures of open water, thin first-year ice, thicker multiyear ice, and thick pressure ridges. The thermodynamic and dynamic properties of the ice pack depend on how much ice lies in each thickness range. Thus the basic problem in sea ice modeling is to describe the evolution of the ice thickness distribution (ITD) in time and space.

The fundamental equation solved by CICE is [68]:

$$\frac{\partial g}{\partial t} = -\nabla \cdot (g\mathbf{u}) - \frac{\partial}{\partial h}(fg) + \psi, \tag{6}$$

where **u** is the horizontal ice velocity,  $\nabla = (\frac{\partial}{\partial x}, \frac{\partial}{\partial y})$ , f is the rate of thermodynamic ice growth,  $\psi$  is a ridging redistribution function, and g is the ice thickness distribution function. We define  $g(\mathbf{x}, h, t) dh$  as the fractional area covered by ice in the thickness range (h, h + dh) at a given time and location.

Equation (6) is solved by partitioning the ice pack in each grid cell into discrete thickness categories. The number of categories can be set by the user, with a default value  $N_C = 5$ . (Five categories, plus open water, are generally sufficient to simulate the annual cycles of ice thickness, ice strength, and surface fluxes [6, 41].) Each category n has lower thickness bound  $H_{n-1}$  and upper bound  $H_n$ . The lower bound of the thinnest ice category,  $H_0$ , is set to zero. The other boundaries are chosen with greater resolution for small h, since the properties of the ice pack are especially sensitive to the amount of thin ice [46]. The continuous function g(h) is replaced by the discrete variable  $a_{in}$ , defined as the fractional area covered by ice in the thickness range  $(H_{n-1}, H_n)$ . We denote the fractional area of open water by  $a_{i0}$ , giving  $\sum_{n=0}^{N_C} a_{in} = 1$  by definition.

Category boundaries are computed in  $init\_itd$  using one of several formulas, summarized in Table 2. Setting the namelist variable kcatbound equal to 0 or 1 gives lower thickness boundaries for any number of thickness categories  $N_C$ . Table 2 shows the boundary values for  $N_C = 5$ . A third option specifies the boundaries based on the World Meteorological Organization classification; the full WMO thickness distribution is used if  $N_C = 7$ ; if  $N_C = 5$  or 6, some of the thinner categories are combined. The original

distribution	original	round		WMO	
kcatbound	0	1		2	
$\overline{N_C}$	5	5	5	6	7
category		lower b	ound (1	m)	
1	0.00	0.00	0.00	0.00	0.00
2	0.64	0.60	0.30	0.15	0.10
3	1.39	1.40	0.70	0.30	0.15
4	2.47	2.40	1.20	0.70	0.30
5	4.57	3.60	2.00	1.20	0.70
6				2.00	1.20
7					2.00

Table 2: Lower boundary values for thickness categories, in meters, for the three distribution options (kcatbound). In the WMO case, the distribution used depends on the number of categories used.

formula (kcatbound = 0) is the default because it was used to create the restart files included with the code distribution. Users may substitute their own preferred boundaries in *init\_itd*.

In addition to the fractional ice area,  $a_{in}$ , we define the following state variables for each category n. In a change from previous CICE versions, we no longer carry snow and ice energy as separate variables; instead they and sea ice salinity are carried as tracers on snow and ice volume.

- $v_{in}$ , the ice volume, equal to the product of  $a_{in}$  and the ice thickness  $h_{in}$ .
- $v_{sn}$ , the snow volume, equal to the product of  $a_{in}$  and the snow thickness  $h_{sn}$ .
- $e_{ink}$ , the internal ice energy in layer k, equal to the product of the ice layer volume,  $v_{in}/N_i$ , and the ice layer enthalpy,  $q_{ink}$ . Here  $N_i$  is the total number of ice layers, with a default value  $N_i = 4$ , and  $q_{ink}$  is the negative of the energy needed to melt a unit volume of ice and raise its temperature to  $0^{\circ}$ C; it is discussed in Section 3.6. (NOTE: In the current code,  $e_i < 0$  and  $q_i < 0$  with  $e_i = v_i q_i$ .)
- $e_{snk}$ , the internal snow energy in layer k, equal to the product of the snow layer volume,  $v_{sn}/N_s$ , and the snow layer enthalpy,  $q_{snk}$ , where  $N_s$  is the number of snow layers. (Similarly,  $e_s < 0$  in the code.) CICE allows multiple snow layers, but the default value is  $N_s = 1$ .
- $S_i$ , the bulk sea ice salt content in layer k, equal to the product of the ice layer volume and the sea ice salinity tracer.
- $T_{sfn}$ , the surface temperature.

Since the fractional area is unitless, the volume variables have units of meters (i.e.,  $m^3$  of ice or snow per  $m^2$  of grid cell area), and the energy variables have units of  $J/m^2$ .

The three terms on the right-hand side of (6) describe three kinds of sea ice transport: (1) horizontal transport in (x, y) space; (2) transport in thickness space h due to thermodynamic growth and melting; and (3) transport in thickness space h due to ridging and other mechanical processes. We solve the equation by operator splitting in three stages, with two of the three terms on the right set to zero in each stage. We compute horizontal transport using the incremental remapping scheme of [12] as adapted for sea ice by [42]; this scheme is discussed in Section 3.2. Ice is transported in thickness space using the remapping scheme of [41], as described in Section 3.3. The mechanical redistribution scheme, based on [68], [56], [27], [19], and [43], is outlined in Section 3.4. To solve the horizontal transport and ridging equations, we need the

ice velocity  $\mathbf{u}$ , and to compute transport in thickness space, we must know the the ice growth rate f in each thickness category. We use the elastic-viscous-plastic (EVP) ice dynamics scheme of [31], as modified by [10], [29], [32] and [33], or a new elastic-anisotropic-plastic model [75, 74, 71] to find the velocity, as described in Section 3.5. Finally, we use a thermodynamic model to compute f (Section 3.6).

The order in which these computations are performed in the code itself was chosen so that quantities sent to the coupler are consistent with each other and as up-to-date as possible. The Delta-Eddington radiative scheme computes albedo and shortwave components simultaneously, and in order to have the most upto-date values available for the coupler at the end of the timestep, the order of radiation calculations is shifted. Albedo and shortwave components are computed after the ice state has been modified by both thermodynamics and dynamics, so that they are consistent with the ice area and thickness at the end of the step when sent to the coupler. However, they are computed using the downwelling shortwave from the beginning of the timestep. Rather than recompute the albedo and shortwave components at the beginning of the next timestep using new values of the downwelling shortwave forcing, the shortwave components computed at the end of the last timestep are scaled for the new forcing.

#### 3.1 **Tracers**

The basic conservation equations for ice area fraction  $a_{in}$ , ice volume  $v_{in}$ , and snow volume  $v_{sn}$  for each thickness category n are

$$\frac{\partial}{\partial t}(a_{in}) + \nabla \cdot (a_{in}\mathbf{u}) = 0, \tag{7}$$

$$\frac{\partial v_{in}}{\partial t} + \nabla \cdot (v_{in}\mathbf{u}) = 0, \qquad (8)$$

$$\frac{\partial v_{sn}}{\partial t} + \nabla \cdot (v_{sn}\mathbf{u}) = 0. \qquad (9)$$

$$\frac{\partial v_{sn}}{\partial t} + \nabla \cdot (v_{sn}\mathbf{u}) = 0. \tag{9}$$

(10)

The ice and snow volumes can be written equivalently in terms of tracers, ice thickness  $h_{in}$  and snow depth  $h_{sn}$ :

$$\frac{\partial h_{in}a_{in}}{\partial t} + \nabla \cdot (h_{in}a_{in}\mathbf{u}) = 0,$$

$$\frac{\partial h_{sn}a_{in}}{\partial t} + \nabla \cdot (h_{sn}a_{in}\mathbf{u}) = 0.$$

Although we maintain ice and snow volume instead of the thicknesses as state variables in CICE, the tracer form is used for volume transport (section 3.2). There are many other tracers available, whose values are contained in the trorn array. Their transport equations typically have one of the following three forms

$$\frac{\partial \left(a_{in}T_{n}\right)}{\partial t} + \nabla \cdot \left(a_{in}T_{n}\mathbf{u}\right) = 0, \tag{11}$$

$$\frac{\partial (a_{in}T_n)}{\partial t} + \nabla \cdot (a_{in}T_n\mathbf{u}) = 0,$$

$$\frac{\partial (v_{in}T_n)}{\partial t} + \nabla \cdot (v_{in}T_n\mathbf{u}) = 0,$$

$$\frac{\partial (v_{sn}T_n)}{\partial t} + \nabla \cdot (v_{sn}T_n\mathbf{u}) = 0.$$
(12)
$$\frac{\partial (v_{sn}T_n)}{\partial t} + \nabla \cdot (v_{sn}T_n\mathbf{u}) = 0.$$
(13)

$$\frac{\partial \left(v_{sn}T_{n}\right)}{\partial t} + \nabla \cdot \left(v_{sn}T_{n}\mathbf{u}\right) = 0. \tag{13}$$

Equation (11) describes the transport of surface temperature, whereas (12) and (13) describe the transport of ice and snow enthalpy, salt, and passive tracers such as volume-weighted ice age and snow age. Each tracer field is given an integer index, tror\_depend, which has the value 0, 1, or 2 depending on whether

13 **Tracers** 

the appropriate conservation equation is (11) (12), or (13), respectively. The total number of tracers is  $N_{tr} \ge 1$ . In the default configuration there are two tracers: surface temperature and volume-weighted ice age. Tracers for melt ponds(Sections 3.1.1 and 3.6.1), level ice area and level ice volume (used to diagnose ridged ice area and volume, Section 3.4) are also available. Users may add any number of additional tracers that are transported conservatively provided that transported is defined appropriately. See Section 4.8.3 for guidance on adding tracers.

#### 3.1.1 Tracers that depend on other tracers (e.g., melt ponds)

Tracers may be defined that depend on other tracers. Melt pond tracers provide an example (these equations pertain to cesm and topo tracers; level-ice tracers are similar with an extra factor of  $a_{lvl}$ , see Eq. 70–73). Conservation equations for pond area fraction  $a_{pnd}a_i$  and pond volume  $h_{pnd}a_{pnd}a_i$ , given the ice velocity u, are

$$\frac{\partial}{\partial t}(a_{pnd}a_i) + \nabla \cdot (a_{pnd}a_i\mathbf{u}) = 0, \tag{14}$$

$$\frac{\partial}{\partial t}(a_{pnd}a_i) + \nabla \cdot (a_{pnd}a_i\mathbf{u}) = 0,$$

$$\frac{\partial}{\partial t}(h_{pnd}a_{pnd}a_i) + \nabla \cdot (h_{pnd}a_{pnd}a_i\mathbf{u}) = 0.$$
(14)

(These equations represent quantities within one thickness category; all melt pond calculations are performed for each category, separately.) Equation (15) expresses conservation of melt pond volume, but in this form highlights that the quantity tracked in the code is the pond depth tracer  $h_{pnd}$ , which depends on the pond area tracer  $a_{pnd}$ . Likewise,  $a_{pnd}$  is a tracer on ice area (Eq. 14), which is a state variable, not a tracer.

For a generic quantity q that represents a mean value over the ice fraction,  $qa_i$  is the average value over the grid cell. Thus for cesm or topo melt ponds,  $h_{pnd}$  can be considered the actual pond depth,  $h_{pnd}a_{pnd}$ is the mean pond depth over the sea ice, and  $h_{pnd}a_{pnd}a_i$  is the mean pond depth over the grid cell. These quantities are illustrated in Figure 1.

Tracers may need to be modified for physical reasons outside of the "core" module or subroutine describing their evolution. For example, when new ice forms in open water, the new ice does not yet have ponds on it. Likewise when sea ice deforms, we assume that pond water (and ice) on the portion of ice that ridges is lost to the ocean.

When new ice is added to a grid cell, the *grid cell* total area of melt ponds is preserved within each category gaining ice,  $a_{pnd}^{t+\Delta t}a_i^{t+\Delta t}=a_{pnd}^ta_i^t$ , or

$$a_{pnd}^{t+\Delta t} = \frac{a_{pnd}^t a_i^t}{a_i^{t+\Delta t}}.$$

Similar calculations are performed for all tracer types, for example tracer-on-tracer dependencies such as  $h_{pnd}$ , when needed:

$$h_{pnd}^{t+\Delta t} = \frac{h_{pnd}^t a_{pnd}^t a_i^t}{a_{md}^{t+\Delta t} a_i^{t+\Delta t}}.$$

In this case (adding new ice),  $h_{pnd}$  does not change because  $a_{pnd}^{t+\Delta t}a_i^{t+\Delta t}=a_{pnd}^ta_i^t$ ,.

When ice is transferred between two thickness categories, we conserve the total pond area summed over categories n,

$$\sum_{n} a_{pnd}^{t+\Delta t}(n) a_{i}^{t+\Delta t}(n) = \sum_{n} a_{pnd}^{t}(n) a_{i}^{t}(n).$$




Figure 1: Melt pond tracer definitions. The graphic on the right illustrates the *grid cell* fraction of ponds or level ice as defined by the tracers. The chart on the left provides corresponding ice thickness and pond depth averages over the grid cell, sea ice and pond area fractions.

Thus,

$$\begin{aligned} a_{pnd}^{t+\Delta t}(m) &=& \frac{\sum_{n} a_{pnd}^{t}(n) a_{i}^{t}(n) - \sum_{n \neq m} a_{pnd}^{t+\Delta t}(n) a_{i}^{t+\Delta t}(n)}{a_{i}^{t+\Delta t}(m)} \\ &=& \frac{a_{pnd}^{t}(m) a_{i}^{t}(m) + \sum_{n \neq m} \Delta \left(a_{pnd} a_{i}\right)^{t+\Delta t}}{a_{i}^{t+\Delta t}(m)} \end{aligned}$$

This is more complicated because of the  $\Delta$  term on the right-hand side, which is handled manually in **ice\_itd.F90**. Such tracer calculations are scattered throughout the code, wherever there are changes to the ice thickness distribution.

Note that if a quantity such as  $a_{pnd}$  becomes zero in a grid cell's thickness category, then all tracers that depend on it also become zero. If a tracer should be conserved (e.g., aerosols and the liquid water in topo ponds), additional code must be added to track changes in the conserved quantity.

More information about the melt pond schemes is in section 3.6.1.

## **3.1.2** Ice age

The age of the ice,  $\tau_{age}$ , is treated as an ice-volume tracer (trcr\_depend = 1). It is initialized at 0 when ice forms as frazil, and the ice ages the length of the timestep during each timestep. Freezing directly onto the bottom of the ice does not affect the age, nor does melting. Mechanical redistribution processes and advection alter the age of ice in any given grid cell in a conservative manner following changes in ice area. The sea ice age tracer is validated in [30].

Tracers 15

Another age-related tracer, the area covered by first-year ice  $a_{FY}$ , is an area tracer (trcr\_depend = 0) that corresponds more closely to satellite-derived ice age data for first-year ice than does  $\tau_{age}$ . It is reinitialized each year on 15 September (yday = 259) in the northern hemisphere and 15 March (yday = 75) in the southern hemisphere, in non-leap years. This tracer is increased when new ice forms in open water, in subroutine  $add\_new\_ice$  in ice\_therm\_itd.F90. The first-year area tracer is discussed in [2].

## 3.1.3 Sea ice biogeochemistry

Ice algal photosynthesis leads to carbon fixation and pigment buildup throughout much of the pack ice in springtime, including warm layers in contact with seawater and the central ice matrix. Turbulence moves seed organisms and trace elements upward across the ocean interface from the mixed layer [3], and convection allows them to penetrate deep into the brine channel network. Gravity drainage is strongly coupled to carbonate and alkalinity relationships; bio-active gases including molecular oxygen, dimethyl sulfide (DMS) and methane exhibit dynamic cycling within and around the ice matrix. All may ultimately be transferred across the upper interface, into snow cover and toward the atmosphere. Chlorophyll is often concentrated in thin layers, capable of absorbing downwelling radiation and redistributing the implied heat locally.

Although biogeochemical activity occurs throughout the sea ice column, in the present release we restrict ourselves to simulations of activity taking place in the lowest few vertical centimeters. A thin intermediate zone located in this vicinity can be considered distinct because it is relatively warm, extremely porous and necessarily in close contact with the seawater nutrient supply. The ecosystems supported are therefore especially intense, so that they constitute a logical starting point for code development. The resulting band of biological activity will be referred to most often in what follows as the 'bottom zone.' It constitutes the dominant habitat for ice algae across most of the noncoastal Arctic and among land fast ice systems of the Southern Hemisphere. In the literature and some portions of the code, however, the alternate term 'skeletal layer' is used. For many purposes, the two are interchangeable. But in fact, the latter is a reference to dendritic structures more typically observable in the wintertime; 'bottom zone' is the more general term.

Ecological succession in the bottom zone interacts intimately with chemistry of the upper ocean–atmosphere system. Photosynthesis is constrained initially by light limitation but soon becomes a matter of resource availability [3, 11]. Radiation intensity dictates the timing of bloom inception. The direct inflow of salt laden water can then be filtered immediately for the dissolved nutrient forms, which are converted locally into biomass. In association with the carbon storage, considerable DMS and molecular oxygen are generated [17]. Melt and flush periods cause bottom ice organisms to be rejected from the matrix mechanically. The dominant primary producers among them are pennate diatoms, a class subject to rapid sinking [39]. Hence the amount of bottom layer biological activity dictates high latitude nutrient and trace gas levels in the early spring, then carbon drawdown moving into the period of breakup.

Light transmission passes into the bottom zone through overlying layers of snow and ice. Attenuation by the ice algae is integrated and averaged over the bottom three centimeters in which they reside. Our current CICE release treats inflow of the primary Arctic nutrients nitrate and silicate, along with the major pathway for nitrogen recycling via ammonia. Both fertilizers and byproducts are permitted to exchange back out of the porous bottom volume on a time scale of order hours [3, 39]. Biomass multiplies exponentially as light and nutrient restrictions are lifted, following the rising polar sun. Uptake accelerates until there is a transition to flux limitation [17]. At variable times and locations, a kinetic balance is often reached in which dissolved nitrogen is sequestered faster than it can leave the porous volume. Computational terms involved in the ecodynamic simulation resemble Michaelis-Menten enzyme kinetics, and have been adapted here from a series of pioneering ice biogeochemistry models [3, 36, 39]. CICE biogeochemical applications include a series of Pan-Arctic simulations, conceptually extending from primary production and carbon cycling to the release of trace gases into the ice domain [11, 17].

The bottom ice biogeochemistry module described here is designed for ready attachment of extra-

nutrient cycling, including byproduct and detrital processing. Our own mechanism for the generation of DMS is included in the release as an example. For full details please see descriptions and schematics in [17]. Generally speaking, the primary nutrient flow as nitrogen simultaneously supports formation of silicate frustules by the ice diatoms, along with carbon biomass production and the implied chlorophyll buildup. Synthesis of organosulfur metabolites is handled simultaneously and in direct proportion. DMS spins off of this subsystem at much higher levels than those familiar from open water studies, since the ice algae are especially abundant and suffer strong cryological, osmotic and oxidant stress in an extreme environmental regime [65]. The sulfur transformations are governed by a typical pattern of routing kinetics within and below the ice [17], which reduces the net yield of volatile gas but still permits considerable buildup and release during the spring thaw.

Biogeochemical processing is modelled as a single layer of reactive tracers attached to the sea ice bottom. Optional settings are available via the <code>zbgc\_nml</code> namelist in <code>ice\_in</code>. The prefix <code>tr\_bgc</code> signifies a biogeochemical tracer, while the postscript <code>\_sk</code> indicates that a particular quantity is restricted to the band of bottom or skeletal ice material. History fields are controlled in the <code>icefields\_bgc\_nml</code> namelist. As with other CICE history fields, the suffix <code>\_ai</code> indicates that the field is multiplied by ice area and is therefore a grid-cell-mean quantity.

Setting the flag solve\_skl\_bgc to true turns on a reduced 'NP' (Nitrogen-Plankton) biogeochemistry consisting of nitrate and one algal tracer. Ammonium (tr\_bgc\_Am\_sk), silicate (tr\_bgc\_Sil\_sk), dimethyl sulfoniopropionate (DMSP) in particulate form (tr\_bgc\_DMSPp\_sk), DMSP in dissolved form (tr\_bgc\_DMSPd\_sk), and volatile dimethyl sulfide (tr\_bgc\_DMS\_sk) may also be included by setting the respective flags to true in ice\_in.

All biogeochemical tracers  $(T_b)$  are brine concentrations multiplied by the skeletal layer thickness  $(h_{sk})$ . Bulk tracer concentrations are written to diagnostic files and are found by the expression  $T_b\phi_{sk}/h_{sk}$  where  $\phi_{sk}$  is the skeletal layer porosity. Both  $h_{sk}$  and  $\phi_{sk}$  are defined in **ice\_zbgc\_shared.F90**.

Tracers  $T_b$  are area conserved and follow the horizontal transport equation (11). The initial concentrations of tracers are specified in subroutine  $init\_bgc$  in  $ice\_zbgc.F90$ . Silicate and nitrate may be initialized and forced with climatology. Parameters  $sil\_data\_type$  and  $nit\_data\_type$  are set in  $ice\_in$  and take the values 'clim' (climatology) and 'default' (constant).  $nit\_data\_type$  may also take the value 'sss' which sets nitrate to the ocean salinity value. For climatology, the data directory  $bgc\_data\_dir$  must also be specified. If  $restore\_bgc$  is true, then values are linearly restored to climatology according to the restoring timescale trestore.

For each horizontal grid point, local biogeochemical tracer equations are solved in **ice\_algae.F90**. There are two types of ice—ocean tracer flux formulations: 'Jin2006' modelled after the growth rate dependent piston velocity of [36], and 'constant' modelled after the constant piston velocity of [17]. The formulation is specified in **ice\_in** by setting bgc\_flux\_type equal to 'Jin2006' or 'constant'.

In addition to horizontal advection and transport among thickness categories, biogeochemical tracers  $(T_b \text{ where } b = 1, \dots, N_b)$  satisfy a set of local coupled equations of the form

$$\frac{dT_b}{dt} = w_b \frac{\Delta T_b}{\Delta z} + R_b(T_j : j = 1, \dots, N_b)$$

where  $R_b$  represents the nonlinear biochemical reaction terms detailed in [17] and  $\Delta z$  is a length scale representing the molecular sublayer of the ice—ocean interface. Its value is absorbed in the piston velocity parameters. The piston velocity  $w_b$  depends on the particular tracer and the flux formulation.

For 'Jin2006', the piston velocity is a function of ice growth and melt rates. All tracers (algae included) flux with the same piston velocity during ice growth, dh/dt > 0:

$$w_b = -p_g \left| m_1 + m_2 \frac{dh}{dt} - m_3 \left( \frac{dh}{dt} \right)^2 \right|$$

Tracers 17

with parameters  $m_1$ ,  $m_2$ ,  $m_3$  and  $p_g$  defined in **skl\_biogeochemistry**. For ice melt, dh/dt < 0, all tracers with the exception of ice algae flux with

$$w_b = p_m \left| m_2 \frac{dh}{dt} - m_3 \left( \frac{dh}{dt} \right)^2 \right| \tag{16}$$

with  $p_m$  defined in **skl\_biogeochemistry**. The 'Jin2006' formulation also requires that for both expressions,  $|w_b| \leq 0.9h_{sk}/\Delta t$ . The concentration difference at the ice-ocean boundary for each tracer,  $\Delta T_b$ , depends on the sign of  $w_b$ . For growing ice,  $w_b < 0$ ,  $\Delta T_b = T_b/h_{sk} - T_{io}$ , where  $T_{io}$  is the ocean concentration of tracer i. For melting ice,  $w_b > 0$ ,  $\Delta T_b = T_b/h_{sk}$ .

In 'Jin2006', the algal tracer  $(N_a)$  responds to ice melt in the same manner as the other tracers (16). However, this is not the case for ice growth. Unlike dissolved nutrients, algae are able to cling to the ice matrix and resist expulsion during desalination. For this reason, algal tracers do not flux between ice and ocean during ice growth unless the ice algal brine concentration is less than the ocean algal concentration  $(N_o)$ . Then the ocean seeds the sea ice concentration according to

$$w_b \frac{\Delta N_a}{\Delta z} = \frac{N_o h_{sk} / \phi_{sk} - N_a}{\Delta t} \tag{17}$$

The 'constant' formulation uses a fixed piston velocity (PVc) for positive ice growth rates for all tracers except  $N_a$ . As in 'Jin2006', congelation ice growth seeds the sea ice algal population according to (17) when  $N_a < N_o h_{sk}/\phi_{sk}$ . For bottom ice melt, all tracers follow the prescription

$$w_b \frac{\Delta T_b}{\Delta z} = \left\{ \begin{array}{ll} T_b |dh_i/dt|/h_{sk} & \quad \text{if } |dh_i/dt|\Delta t/h_{sk} < 1 \\ T_b/\Delta t & \quad \text{otherwise.} \end{array} \right.$$

All of the necessary fluxes required for coupling to an ocean model component are contained in a single array, flux\_bio.

This bottom-specific biogeochemistry module necessarily simplifies the full sea ice ecosystem. For the moment, zooplankton comprise an imaginary tracer of indefinite mass that make their presence felt mainly through the recycling of ammonia [17, 36]. Consumer organisms are essentially siphoned off of the standard primary production pathway as a fixed fraction of overall growth [3]. Transfer velocities relating the upper water column to ice fluids and solutes are now parameterized as a function of off-line congelation rates, based on laboratory brine expulsion data [3, 17, 36]. Thus far we have tested removal from the active bottom zone as a single adjustable time constant, but results have not been formalized or adequately evaluated against data. Internally consistent connections with gravity drainage will be implemented in the vertical biogeochemistry module being developed for future release in CICE.

#### 3.1.4 Aerosols

Aerosols may be deposited on the ice and gradually work their way through it until the ice melts and they are passed into the ocean. They are defined as ice and snow volume tracers (Eq. 12 and 13), with the snow and ice each having two tracers for each aerosol species, one in the surface scattering layer (delta-Eddington SSL) and one in the snow or ice interior below the SSL.

Rather than updating aerosols for each change to ice/snow thickness due to evaporation, melting, snow—ice formation, etc., during the thermodynamics calculation, these changes are deduced from the diagnostic variables (melts, meltb, snoice, etc) in ice\_aerosol.F90. Three processes change the volume of ice or snow but do not change the total amount of aerosol, thus causing the aerosol concentration (the value of the tracer itself) to increase: evaporation, snow deposition and basal ice growth. Basal and lateral melting remove all aerosols in the melted portion. Surface ice and snow melt leave a significant fraction of the

aerosols behind, but they do "scavenge" a fraction of them given by the parameter kscav = [0.03, 0.2, 0.02, 0.02, 0.01, 0.01] (only the first 3 are used in CESM, for their 3 aerosol species). Scavenging also applies to snow–ice formation. When sea ice ridges, a fraction of the snow on the ridging ice is thrown into the ocean, and any aerosols in that fraction are also lost to the ocean.

As upper SSL or interior layers disappear from the snow or ice, aerosols are transferred to the next lower layer, or into the ocean when no ice remains. The atmospheric flux faero\_atm contains the rates of aerosol deposition for each species, while faero\_ocn has the rate at which the aerosols are transferred to the ocean.

The aerosol tracer flag tr\_aero must be set to true in **ice\_in**, and the number of aerosol species is set in **comp\_ice**; CESM uses 3. Results using the aerosol code in the context of CESM are documented in [28]. Global diagnostics are available when print\_global is true, and history variables include the mass density for each layer (snow and ice SSL and interior), and atmospheric and oceanic fluxes, for each species.

### 3.1.5 Brine height

The brine height,  $h_b$ , is the distance from the ice—ocean interface to the brine surface. When trlbrine is set true in **ice\_in** and TRBRI is set equal to 1 in **comp\_ice**, the brine surface can move relative to the ice surface. Physically, this occurs when the ice is permeable and there is a nonzero pressure head: the difference between the brine height and the equilibrium sea surface. Brine height motion is computed in **ice\_brine.F90** from thermodynamic variables (melts, meltb, meltt etc) and the ice microstructural state deduced from internal bulk salinities and temperature. In the current release, this tracer is for diagnostic purposes only; it is driven by the prognostic salinity parameterization but is not used for computing salinity. In future releases it will be used for transporting biogeochemical tracers vertically through the ice.

Brine height is transported horizontally as the fraction  $f_{bri} = h_b/h_i$ , a volume conserved tracer (Eq. 12). Note that unlike the sea ice porosity, brine height fraction may be greater than 1 when  $h_b > h_i$ .

Vertical transport processes are, generally, a result of the brine motion. Therefore the vertical transport equations for biogeochemical tracers will be defined only where brine is present. This region, from the ice—ocean interface to the brine height, defines the domain of the vertical bio-grid, whose resolution is independent of the sea ice vertical grid and is set at compile time (see Section 4.2.3). The ice microstructural state, determined in **ice\_brine.F90**, is computed from sea ice salinities and temperatures linearly interpolated to the bio-grid. When  $h_b > h_i$ , the upper surface brine is assumed to have the same microstructural properties as the ice surface.

Changes to  $h_b$  occur from ice and snow melt, ice bottom boundary changes, and from pressure adjustments. The computation of  $h_b$  at  $t + \Delta t$  is a two step process. First,  $h_b$  is updated from changes in ice and snow thickness, ie.

$$h_b' = h_b(t) + \Delta h_b|_{h_i, h_s}.$$

Second, pressure driven adjustments arising from meltwater flushing and snow loading are applied to  $h'_b$ . Brine flow due to pressure forces are governed by Darcy's equation

$$w = -\frac{\Pi^* \bar{\rho} g}{\mu} \frac{h_p}{h_i}.$$

The vertical component of the net permeability tensor  $\Pi^*$  is computed as

$$\Pi^* = \left(\frac{1}{h} \sum_{i=1}^N \frac{\Delta z_i}{\Pi_i}\right)^{-1}$$

Tracers 19

where the sea ice is composed of N vertical layers with ith layer thickness  $\Delta z_i$  and permeability  $\Pi_i$  (68). The average sea ice density is  $\bar{\rho}$  specified in **ice\_zbgc\_shared.F90**. The hydraulic head is  $h_p = h_b - h_{sl}$  where  $h_{sl}$  is the sea level given by

$$h_{sl} = \frac{\bar{\rho}}{\rho_w} h_i + \frac{\rho_s}{\rho_w} h_s.$$

Assuming constant  $h_i$  and  $h_s$  during Darcy flow, the rate of change of  $h_b$  is

$$\frac{\partial h_b}{\partial t} = -wh_p \tag{18}$$

where  $w_o = \Pi^* \bar{\rho} g/(h_i \mu \phi_{top})$  and  $\phi_{top}$  is the upper surface porosity. When the Darcy flow is downward into the ice  $(w_o < 0)$ , then  $\phi_{top}$  equals the sea ice porosity in the uppermost layer. However, when the flow is upwards into the snow, then  $\phi_{top}$  equals the snow porosity phi\_snow specified in ice\_in. If a negative number is specified for phi\_snow, then the default value is used: phi\_snow =  $1 - \rho_s/\rho_w$ .

Since  $h_{sl}$  remains relatively unchanged during Darcy flow, (18) has the approximate solution

$$h_b(t + \Delta t) \approx h_{sl}(t + \Delta t) + [h'_b - h_{sl}(t + \Delta t)] \exp\{-w\Delta t\}.$$

The contribution  $\Delta h_b|_{h_i,h_s}$  arises from snow and ice melt and bottom ice changes. Since the ice and brine bottom boundaries coincide, changes in the ice bottom from growth or melt,  $(\Delta h_i)_{bot}$ , equal the bottom brine boundary changes. The surface contribution from ice and snow melt, however, is opposite in sign. The ice contribution is as follows. If  $h_i > h_b$  and the ice surface is melting, ie.  $(\Delta h_i)_{top} < 0$ ), then melt water increases the brine height:

$$(\Delta h_b)_{top} = \frac{\rho_i}{\rho_o} \cdot \begin{cases} -(\Delta h_i)_{top} & \text{if } |(\Delta h_i)_{top}| < h_i - h_b \\ h_i - h_b & \text{otherwise.} \end{cases}$$

For snow melt ( $\Delta h_s < 0$ ), it is assumed that all snow melt water contributes a source of surface brine. The total change from snow melt and ice thickness changes is

$$\Delta h_b|_{h_i,h_s} = (\Delta h_b)_{top} - (\Delta h_i)_{bot} - \frac{\rho_s}{\rho_o} \Delta h_s.$$

The above brine height calculation is used only when  $h_i$  and  $h_b$  exceed a minimum thickness, thins, specified in **ice\_zbgc\_shared**. Otherwise

$$h_b(t + \Delta t) = h_b(t) + \Delta h_i$$

provided that  $|h_{sl} - h_b| \le 0.001$ . This formulation ensures small Darcy velocities when  $h_b$  first exceeds thins.

Both the volume fraction  $f_{bri}$  and the area-weighted brine height  $h_b$  can be written to the history file. The history variable fbri contains the volume-averaged brine fraction tracer

$$\frac{\sum f_{bri}v_i}{\sum v_i}$$
,

while hbri is comparable to hi  $(h_i)$ 

$$\frac{\sum f_{bri}h_ia_i}{\sum a_i},$$

where the sums are taken over thickness categories.

## 3.2 Horizontal transport

We wish to solve the continuity or transport equation (7) for the fractional ice area in each thickness category n. Equation (7) describes the conservation of ice area under horizontal transport. It is obtained from (6) by discretizing g and neglecting the second and third terms on the right-hand side, which are treated separately (Sections 3.3 and 3.4).

There are similar conservation equations for ice volume (eq. 8), snow volume (eq 9), ice energy and snow energy:

$$\frac{\partial e_{ink}}{\partial t} + \nabla \cdot (e_{ink}\mathbf{u}) = 0,$$
  
$$\frac{\partial e_{snk}}{\partial t} + \nabla \cdot (e_{snk}\mathbf{u}) = 0.$$

By default, ice and snow are assumed to have constant densities, so that volume conservation is equivalent to mass conservation. Variable-density ice and snow layers can be transported conservatively by defining tracers corresponding to ice and snow density, as explained in the introductory comments in **ice\_transport\_remap.F90**. Prognostic equations for ice and/or snow density may be included in future model versions but have not yet been implemented.

Two transport schemes are available: upwind and the incremental remapping scheme of [12] as modified for sea ice by [42]. The remapping scheme has several desirable features:

- It conserves the quantity being transported (area, volume, or energy).
- It is non-oscillatory; that is, it does not create spurious ripples in the transported fields.
- It preserves tracer monotonicity. That is, it does not create new extrema in the thickness and enthalpy fields; the values at time m+1 are bounded by the values at time m.
- It is second-order accurate in space and therefore is much less diffusive than first-order schemes (e.g., upwind). The accuracy may be reduced locally to first order to preserve monotonicity.
- It is efficient for large numbers of categories or tracers. Much of the work is geometrical and is performed only once per grid cell instead of being repeated for each quantity being transported.

The time step is limited by the requirement that trajectories projected backward from grid cell corners are confined to the four surrounding cells; this is what is meant by incremental remapping as opposed to general remapping. This requirement leads to a CFL-like condition,

$$\frac{\max |\mathbf{u}| \Delta t}{\Delta x} \le 1.$$

For highly divergent velocity fields the maximum time step must be reduced by a factor of two to ensure that trajectories do not cross. However, ice velocity fields in climate models usually have small divergences per time step relative to the grid size.

The remapping algorithm can be summarized as follows:

- 1. Given mean values of the ice area and tracer fields in each grid cell, construct linear approximations of these fields. Limit the field gradients to preserve monotonicity.
- 2. Given ice velocities at grid cell corners, identify departure regions for the fluxes across each cell edge. Divide these departure regions into triangles and compute the coordinates of the triangle vertices.

Horizontal transport 21

3. Integrate the area and tracer fields over the departure triangles to obtain the area, volume, and energy transported across each cell edge.

4. Given these transports, update the state variables.

Since all scalar fields are transported by the same velocity field, step (2) is done only once per time step. The other three steps are repeated for each field in each thickness category. These steps are described below.

## 3.2.1 Reconstructing area and tracer fields

First, using the known values of the state variables, the ice area and tracer fields are reconstructed in each grid cell as linear functions of x and y. For each field we compute the value at the cell center (i.e., at the origin of a 2D Cartesian coordinate system defined for that grid cell), along with gradients in the x and y directions. The gradients are limited to preserve monotonicity. When integrated over a grid cell, the reconstructed fields must have mean values equal to the known state variables, denoted by  $\bar{a}$  for fractional area,  $\tilde{h}$  for thickness, and  $\hat{q}$  for enthalpy. The mean values are not, in general, equal to the values at the cell center. For example, the mean ice area must equal the value at the centroid, which may not lie at the cell center.

Consider first the fractional ice area, the analog to fluid density  $\rho$  in [12]. For each thickness category we construct a field  $a(\mathbf{r})$  whose mean is  $\bar{a}$ , where  $\mathbf{r}=(x,y)$  is the position vector relative to the cell center. That is, we require

$$\int_{A} a \, dA = \bar{a} \, A,\tag{19}$$

where  $A = \int_A dA$  is the grid cell area. Equation (19) is satisfied if  $a(\mathbf{r})$  has the form

$$a(\mathbf{r}) = \bar{a} + \alpha_a \langle \nabla a \rangle \cdot (\mathbf{r} - \bar{\mathbf{r}}), \tag{20}$$

where  $\langle \nabla a \rangle$  is a centered estimate of the area gradient within the cell,  $\alpha_a$  is a limiting coefficient that enforces monotonicity, and  $\bar{\mathbf{r}}$  is the cell centroid:

$$\bar{\mathbf{r}} = \frac{1}{A} \int_{A} \mathbf{r} \, dA.$$

It follows from (20) that the ice area at the cell center ( $\mathbf{r} = 0$ ) is

$$a_c = \bar{a} - a_x \overline{x} - a_y \overline{y},$$

where  $a_x = \alpha_a(\partial a/\partial x)$  and  $a_y = \alpha_a(\partial a/\partial y)$  are the limited gradients in the x and y directions, respectively, and the components of  $\overline{\mathbf{r}}$ ,  $\overline{x} = \int_A x \, dA/A$  and  $\overline{y} = \int_A y \, dA/A$ , are evaluated using the triangle integration formulas described in Section 3.2.3. These means, along with higher-order means such as  $\overline{x^2}$ ,  $\overline{xy}$ , and  $\overline{y^2}$ , are computed once and stored.

Next consider the ice and snow thickness and enthalpy fields. Thickness is analogous to the tracer concentration T in [12], but there is no analog in [12] to the enthalpy. The reconstructed ice or snow thickness  $h(\mathbf{r})$  and enthalpy  $q(\mathbf{r})$  must satisfy

$$\int_{A} a h dA = \bar{a} \tilde{h} A, \tag{21}$$

$$\int_{A} a h q dA = \bar{a} \tilde{h} \hat{q} A, \qquad (22)$$

where  $\tilde{h} = h(\tilde{\mathbf{r}})$  is the thickness at the center of ice area, and  $\hat{q} = q(\hat{\mathbf{r}})$  is the enthalpy at the center of ice or snow volume. Equations (21) and (22) are satisfied when  $h(\mathbf{r})$  and  $q(\mathbf{r})$  are given by

$$h(\mathbf{r}) = \tilde{h} + \alpha_h \langle \nabla h \rangle \cdot (\mathbf{r} - \tilde{\mathbf{r}}), \tag{23}$$

$$q(\mathbf{r}) = \hat{q} + \alpha_q \langle \nabla q \rangle \cdot (\mathbf{r} - \hat{\mathbf{r}}), \tag{24}$$

where  $\alpha_h$  and  $\alpha_q$  are limiting coefficients. The center of ice area,  $\tilde{\mathbf{r}}$ , and the center of ice or snow volume,  $\hat{\mathbf{r}}$ , are given by

$$\tilde{\mathbf{r}} = \frac{1}{\bar{a} A} \int_A a \, \mathbf{r} \, dA,$$

$$\hat{\mathbf{r}} = \frac{1}{\bar{a}\,\tilde{h}\,A} \int_A a\,h\,\mathbf{r}\,dA.$$

Evaluating the integrals, we find that the components of  $\tilde{\mathbf{r}}$  are

$$\tilde{x} = \frac{a_c \overline{x} + a_x \overline{x^2} + a_y \overline{xy}}{\overline{a}},$$

$$\tilde{y} = \frac{a_c \overline{y} + a_x \overline{xy} + a_y \overline{y^2}}{\bar{a}},$$

and the components of  $\hat{\mathbf{r}}$  are

$$\hat{x} = \frac{c_1 \overline{x} + c_2 \overline{x^2} + c_3 \overline{xy} + c_4 \overline{x^3} + c_5 \overline{x^2 y} + c_6 \overline{xy^2}}{\bar{a} \, \tilde{h}},$$

$$\hat{y} = \frac{c_1 \overline{y} + c_2 \overline{x} \overline{y} + c_3 \overline{y^2} + c_4 \overline{x^2 y} + c_5 \overline{x} \overline{y^2} + c_6 \overline{y^3}}{\bar{a} \, \tilde{h}},$$

where

$$c_1 \equiv a_c h_c,$$

$$c_2 \equiv a_c h_x + a_x h_c,$$

$$c_3 \equiv a_c h_y + a_y h_c,$$

$$c_4 \equiv a_x h_x,$$

$$c_5 \equiv a_x h_y + a_y h_x,$$

$$c_6 \equiv a_y h_y.$$

From (23) and (24), the thickness and enthalpy at the cell center are given by

$$h_c = \tilde{h} - h_x \tilde{x} - h_y \tilde{y},$$

$$q_c = \hat{q} - q_x \hat{x} - q_y \hat{y},$$

where  $h_x$ ,  $h_y$ ,  $q_x$  and  $q_y$  are the limited gradients of thickness and enthalpy. The surface temperature is treated the same way as ice or snow thickness, but it has no associated enthalpy. Tracers obeying conservation equations of the form (12) and (13) are treated in analogy to ice and snow enthalpy, respectively.

We preserve monotonicity by van Leer limiting. If  $\bar{\phi}(i,j)$  denotes the mean value of some field in grid cell (i,j), we first compute centered gradients of  $\bar{\phi}$  in the x and y directions, then check whether these gradients give values of  $\phi$  within cell (i,j) that lie outside the range of  $\bar{\phi}$  in the cell and its eight neighbors. Let  $\bar{\phi}_{\max}$  and  $\bar{\phi}_{\min}$  be the maximum and minimum values of  $\bar{\phi}$  over the cell and its neighbors, and let

Horizontal transport 23

 $\phi_{\max}$  and  $\phi_{\min}$  be the maximum and minimum values of the reconstructed  $\phi$  within the cell. Since the reconstruction is linear,  $\phi_{\max}$  and  $\phi_{\min}$  are located at cell corners. If  $\phi_{\max} > \bar{\phi}_{\max}$  or  $\phi_{\min} < \bar{\phi}_{\min}$ , we multiply the unlimited gradient by  $\alpha = \min(\alpha_{\max}, \alpha_{\min})$ , where

$$\alpha_{\text{max}} = (\bar{\phi}_{\text{max}} - \bar{\phi})/(\phi_{\text{max}} - \bar{\phi}),$$

$$\alpha_{\min} = (\bar{\phi}_{\min} - \bar{\phi})/(\phi_{\min} - \bar{\phi}).$$

Otherwise the gradient need not be limited.

Earlier versions of CICE (through 3.14) computed gradients in physical space. Starting in version 4.0, gradients are computed in a scaled space in which each grid cell has sides of unit length. The origin is at the cell center, and the four vertices are located at (0.5, 0.5), (-0.5, 0.5), (-0.5, 0.5), and (0.5, -0.5). In this coordinate system, several of the above grid-cell-mean quantities vanish (because they are odd functions of x and/or y), but they have been retained in the code for generality.

## 3.2.2 Locating departure triangles

The method for locating departure triangles is discussed in detail by [12]. The basic idea is illustrated in Figure 2, which shows a shaded quadrilateral departure region whose contents are transported to the target or home grid cell, labeled H. The neighboring grid cells are labeled by compass directions: NW, N, NE, W, and E. The four vectors point along the velocity field at the cell corners, and the departure region is formed by joining the starting points of these vectors. Instead of integrating over the entire departure region, it is convenient to compute fluxes across cell edges. We identify departure regions for the north and east edges of each cell, which are also the south and west edges of neighboring cells. Consider the north edge of the home cell, across which there are fluxes from the neighboring NW and N cells. The contributing region from the NW cell is a triangle with vertices abc, and that from the N cell is a quadrilateral that can be divided into two triangles with vertices acd and ade. Focusing on triangle abc, we first determine the coordinates of vertices b and c relative to the cell corner (vertex a), using Euclidean geometry to find vertex c. Then we translate the three vertices to a coordinate system centered in the NW cell. This translation is needed in order to integrate fields (Section 3.2.3) in the coordinate system where they have been reconstructed (Section 3.2.1). Repeating this process for the north and east edges of each grid cell, we compute the vertices of all the departure triangles associated with each cell edge.

Figure 3, reproduced from [12], shows all possible triangles that can contribute fluxes across the north edge of a grid cell. There are 20 triangles, which can be organized into five groups of four mutually exclusive triangles as shown in Table 3. In this table,  $(x_1, y_1)$  and  $(x_2, y_2)$  are the Cartesian coordinates of the departure points relative to the northwest and northeast cell corners, respectively. The departure points are joined by a straight line that intersects the west edge at  $(0, y_a)$  relative to the northwest corner and intersects the east edge at  $(0, y_b)$  relative to the northeast corner. The east cell triangles and selecting conditions are identical except for a rotation through 90 degrees.

This scheme was originally designed for rectangular grids. Grid cells in CICE actually lie on the surface of a sphere and must be projected onto a plane. The projection used in CICE 4.0 maps each grid cell to a square with sides of unit length. Departure triangles across a given cell edge are computed in a coordinate system whose origin lies at the midpoint of the edge and whose vertices are at (-0.5, 0) and (0.5, 0). Intersection points are computed assuming Cartesian geometry with cell edges meeting at right angles. Let CL and CR denote the left and right vertices, which are joined by line CLR. Similarly, let DL and DR denote the departure points, which are joined by line DLR. Also, let IL and IR denote the intersection points  $(0, y_a)$  and  $(0,y_b)$  respectively, and let IC =  $(x_c, 0)$  denote the intersection of CLR and DLR. It can be shown that




Figure 2: In incremental remapping, conserved quantities are remapped from the shaded departure region, a quadrilateral formed by connecting the backward trajectories from the four cell corners, to the grid cell labeled H. The region fluxed across the north edge of cell H consists of a triangle (abc) in the NW cell and a quadrilateral (two triangles, acd and ade) in the N cell.




Figure 3: The 20 possible triangles that can contribute fluxes across the north edge of a grid cell.

Horizontal transport 25

Triangle	Triangle	Selecting logical
group	label	condition
1	NW	$y_a > 0$ and $y_1 \ge 0$ and $x_1 < 0$
	NW1	$y_a < 0$ and $y_1 \ge 0$ and $x_1 < 0$
	$\mathbf{W}$	$y_a < 0 \text{ and } y_1 < 0 \text{ and } x_1 < 0$
	W2	$y_a > 0$ and $y_1 < 0$ and $x_1 < 0$
2	NE	$y_b > 0$ and $y_2 \ge 0$ and $x_2 > 0$
	NE1	$y_b < 0$ and $y_2 \ge 0$ and $x_2 > 0$
	E	$y_b < 0 \text{ and } y_2 < 0 \text{ and } x_2 > 0$
	E2	$y_b > 0$ and $y_2 < 0$ and $x_2 > 0$
3	W1	$y_a < 0$ and $y_1 \ge 0$ and $x_1 < 0$
	NW2	$y_a > 0$ and $y_1 < 0$ and $x_1 < 0$
	E1	$y_b < 0$ and $y_2 \ge 0$ and $x_2 > 0$
	NE2	$y_b > 0$ and $y_2 < 0$ and $x_2 > 0$
4	H1a	$y_a y_b \ge 0$ and $y_a + y_b < 0$
	N1a	$y_a y_b \ge 0$ and $y_a + y_b > 0$
	H1b	$y_a y_b < 0$ and $\tilde{y}_1 < 0$
	N1b	$y_a y_b < 0$ and $\tilde{y}_1 > 0$
5	H2a	$y_a y_b \ge 0$ and $y_a + y_b < 0$
	N2a	$y_a y_b \ge 0$ and $y_a + y_b > 0$
	H2b	$y_a y_b < 0$ and $\tilde{y}_2 < 0$
	N2b	$y_a y_b < 0$ and $\tilde{y}_2 > 0$

Table 3: Evaluation of contributions from the 20 triangles across the north cell edge. The coordinates  $x_1$ ,  $x_2$ ,  $y_1$ ,  $y_2$ ,  $y_a$ , and  $y_b$  are defined in the text. We define  $\tilde{y}_1=y_1$  if  $x_1>0$ , else  $\tilde{y}_1=y_a$ . Similarly,  $\tilde{y}_2=y_2$  if  $x_2<0$ , else  $\tilde{y}_2=y_b$ .

 $y_a$ ,  $y_b$ , and  $x_c$  are given by

$$y_{a} = \frac{x_{CL}(y_{DM} - y_{DL}) + x_{DM}y_{DL} - x_{DL}y_{DM}}{x_{DM} - x_{DL}},$$

$$y_{b} = \frac{x_{CR}(y_{DR} - y_{DM}) - x_{DM}y_{DR} + x_{DR}y_{DM}}{x_{DR} - x_{DM}},$$

$$x_{c} = x_{DL} - y_{DL} \left(\frac{x_{DR} - x_{DL}}{y_{DR} - y_{DL}}\right)$$

Each departure triangle is defined by three of the seven points (CL, CR, DL, DR, IL, IR, IC).

Given a 2D velocity field  $\mathbf{u}$ , the divergence  $\nabla \cdot \mathbf{u}$  in a given grid cell can be computed from the local velocities and written in terms of fluxes across each cell edge:

$$\nabla \cdot \mathbf{u} = \frac{1}{A} \left[ \left( \frac{u_{NE} + u_{SE}}{2} \right) L_E + \left( \frac{u_{NW} + u_{SW}}{2} \right) L_W + \left( \frac{u_{NE} + u_{NW}}{2} \right) L_N + \left( \frac{u_{SE} + u_{SW}}{2} \right) L_S \right], \tag{25}$$

where L is an edge length and the indices N, S, E, W denote compass directions. Equation (25) is equivalent to the divergence computed in the EVP dynamics (Section 3.5). In general, the fluxes in this expression are not equal to those implied by the above scheme for locating departure regions. For some applications it may be desirable to prescribe the divergence by prescribing the area of the departure region for each edge. This can be done in CICE 4.0 by setting  $l_fixed_area = true$  in **ice\_transport\_driver.F90** and passing the prescribed departure areas (edgearea\_e and edgearea\_n) into the remapping routine. An extra triangle is then constructed for each departure region to ensure that the total area is equal to the prescribed value. This idea was suggested and first implemented by Mats Bentsen of the Nansen Environmental and Remote Sensing Center (Norway), who applied an earlier version of the CICE remapping scheme to an ocean model. The implementation in CICE 4.0 is somewhat more general, allowing for departure regions lying on both sides of a cell edge. The extra triangle is constrained to lie in one but not both of the grid cells that share the edge. Since this option has yet to be fully tested in CICE, the current default is  $l_fixed_area = false$ .

We made one other change in the scheme of [12] for locating triangles. In their paper, departure points are defined by projecting cell corner velocities directly backward. That is,

$$\mathbf{x}_{\mathbf{D}} = -\mathbf{u}\,\Delta t$$

where  $\mathbf{x}_D$  is the location of the departure point relative to the cell corner and  $\mathbf{u}$  is the velocity at the corner. This approximation is only first-order accurate. Accuracy can be improved by estimating the velocity at the midpoint of the trajectory.

### 3.2.3 Integrating fields

Next, we integrate the reconstructed fields over the departure triangles to find the total area, volume, and energy transported across each cell edge. Area transports are easy to compute since the area is linear in x and y. Given a triangle with vertices  $\mathbf{x_i} = (x_i, y_i)$ ,  $i \in \{1, 2, 3\}$ , the triangle area is

$$A_T = \frac{1}{2} |(x_2 - x_1)(y_3 - y_1) - (y_2 - y_1)(x_3 - x_1)|.$$

The integral  $F_a$  of any linear function  $f(\mathbf{r})$  over a triangle is given by

$$F_a = A_T f(\mathbf{x_0}),\tag{26}$$

Horizontal transport 27

where  $\mathbf{x}_0 = (x_0, y_0)$  is the triangle midpoint,

$$\mathbf{x}_0 = \frac{1}{3} \sum_{i=1}^3 \mathbf{x}_i.$$

To compute the area transport, we evaluate the area at the midpoint,

$$a(\mathbf{x}_0) = a_c + a_x x_0 + a_y y_0,$$

and multiply by  $A_T$ . By convention, northward and eastward transport is positive, while southward and westward transport is negative.

Equation (26) cannot be used for volume transport, because the reconstructed volumes are quadratic functions of position. (They are products of two linear functions, area and thickness.) The integral of a quadratic polynomial over a triangle requires function evaluations at three points,

$$F_h = \frac{A_T}{3} \sum_{i=1}^{3} f\left(\mathbf{x}_i'\right),\tag{27}$$

where  $\mathbf{x}_i' = (\mathbf{x}_0 + \mathbf{x}_i)/2$  are points lying halfway between the midpoint and the three vertices. [12] use this formula to compute transports of the product  $\rho T$ , which is analogous to ice volume. Equation (27) does not work for ice and snow energies, which are cubic functions—products of area, thickness, and enthalpy. Integrals of a cubic polynomial over a triangle can be evaluated using a four-point formula [66]:

$$F_q = A_T \left[ -\frac{9}{16} f(\mathbf{x}_0) + \frac{25}{48} \sum_{i=1}^3 f(\mathbf{x}_i'') \right]$$
 (28)

where  $\mathbf{x_i}'' = (3\mathbf{x_0} + 2\mathbf{x_i})/5$ . To evaluate functions at specific points, we must compute many products of the form  $a(\mathbf{x}) h(\mathbf{x})$  and  $a(\mathbf{x}) h(\mathbf{x}) q(\mathbf{x})$ , where each term in the product is the sum of a cell-center value and two displacement terms. In the code, the computation is sped up by storing some sums that are used repeatedly.

#### 3.2.4 Updating state variables

Finally, we compute new values of the state variables in each ice category and grid cell. The new fractional ice areas  $a'_{in}(i,j)$  are given by

$$a'_{in}(i,j) = a_{in}(i,j) + \frac{F_{aE}(i-1,j) - F_{aE}(i,j) + F_{aN}(i,j-1) - F_{aN}(i,j)}{A(i,j)}$$
(29)

where  $F_{aE}(i,j)$  and  $F_{aN}(i,j)$  are the area transports across the east and north edges, respectively, of cell (i,j), and A(i,j) is the grid cell area. All transports added to one cell are subtracted from a neighboring cell; thus (29) conserves total ice area.

The new ice volumes and energies are computed analogously. New thicknesses are given by the ratio of volume to area, and enthalpies by the ratio of energy to volume. Tracer monotonicity is ensured because

$$h' = \frac{\int_A a \, h \, dA}{\int_A a \, dA},$$

$$q' = \frac{\int_A a h q dA}{\int_A a h dA},$$

where h' and q' are the new-time thickness and enthalpy, given by integrating the old-time ice area, volume, and energy over a Lagrangian departure region with area A. That is, the new-time thickness and enthalpy are weighted averages over old-time values, with non-negative weights a and ah. Thus the new-time values must lie between the maximum and minimum of the old-time values.

## 3.3 Transport in thickness space

Next we solve the equation for ice transport in thickness space due to thermodynamic growth and melt,

$$\frac{\partial g}{\partial t} + \frac{\partial}{\partial h}(fg) = 0,$$

which is obtained from (6) by neglecting the first and third terms on the right-hand side. We use the remapping method of [41], in which thickness categories are represented as Lagrangian grid cells whose boundaries are projected forward in time. The thickness distribution function g is approximated as a linear function of h in each displaced category and is then remapped onto the original thickness categories. This method is numerically smooth and is not too diffusive. It can be viewed as a 1D simplification of the 2D incremental remapping scheme described above.

We first compute the displacement of category boundaries in thickness space. Assume that at time m the ice areas  $a_n^m$  and mean ice thicknesses  $h_n^m$  are known for each thickness category. (For now we omit the subscript i that distinguishes ice from snow.) We use a thermodynamic model (Section 3.6) to compute the new mean thicknesses  $h_n^{m+1}$  at time m+1. The time step must be small enough that trajectories do not cross; i.e.,  $h_n^{m+1} < h_{n+1}^{m+1}$  for each pair of adjacent categories. The growth rate at  $h = h_n$  is given by  $f_n = (h_n^{m+1} - h_n^m)/\Delta t$ . By linear interpolation we estimate the growth rate  $F_n$  at the upper category boundary  $H_n$ :

$$F_n = f_n + \frac{f_{n+1} - f_n}{h_{n+1} - h_n} (H_n - h_n).$$

If  $a_n$  or  $a_{n+1} = 0$ ,  $F_n$  is set to the growth rate in the nonzero category, and if  $a_n = a_{n+1} = 0$ , we set  $F_n = 0$ . The temporary displaced boundaries are given by

$$H_n^* = H_n + F_n \Delta t, \ n = 1 \text{ to } N - 1$$

The boundaries must not be displaced by more than one category to the left or right; that is, we require  $H_{n-1} < H_n^* < H_{n+1}$ . Without this requirement we would need to do a general remapping rather than an incremental remapping, at the cost of added complexity.

Next we construct g(h) in the displaced thickness categories. The ice areas in the displaced categories are  $a_n^{m+1}=a_n^m$ , since area is conserved following the motion in thickness space (i.e., during vertical ice growth or melting). The new ice volumes are  $v_n^{m+1}=(a_nh_n)^{m+1}=a_n^mh_n^{m+1}$ . For conciseness, define  $H_L=H_{n-1}^*$  and  $H_R=H_n^*$  and drop the time index m+1. We wish to construct a continuous function g(h) within each category such that the total area and volume at time m+1 are  $a_n$  and  $v_n$ , respectively:

$$\int_{H_L}^{H_R} g \, dh = a_n,\tag{30}$$

$$\int_{H_L}^{H_R} h \, g \, dh = v_n. \tag{31}$$

The simplest polynomial that can satisfy both equations is a line. It is convenient to change coordinates, writing  $g(\eta) = g_1 \eta + g_0$ , where  $\eta = h - H_L$  and the coefficients  $g_0$  and  $g_1$  are to be determined. Then (30) and (31) can be written as

$$g_1 \frac{\eta_R^2}{2} + g_0 \eta_R = a_n,$$

$$g_1 \frac{\eta_R^3}{3} + g_0 \frac{\eta_R^2}{2} = a_n \eta_n,$$




Figure 4: Linear approximation of the thickness distribution function g(h) for an ice category with left boundary  $H_L=0$ , right boundary  $H_R=1$ , fractional area  $a_n=1$ , and mean ice thickness  $h_n=0.2,\,0.4,\,0.6,\,$  and 0.8.

where  $\eta_R = H_R - H_L$  and  $\eta_n = h_n - H_L$ . These equations have the solution

$$g_0 = \frac{6a_n}{\eta_R^2} \left( \frac{2\eta_R}{3} - \eta_n \right), \tag{32}$$

$$g_1 = \frac{12a_n}{\eta_R^3} \left( \eta_n - \frac{\eta_R}{2} \right). \tag{33}$$

Since g is linear, its maximum and minimum values lie at the boundaries,  $\eta = 0$  and  $\eta_R$ :

$$g(0) = \frac{6a_n}{\eta_R^2} \left( \frac{2\eta_R}{3} - \eta_n \right) = g_0, \tag{34}$$

$$g(\eta_R) = \frac{6a_n}{\eta_R^2} \left( \eta_n - \frac{\eta_R}{3} \right). \tag{35}$$

Equation (34) implies that g(0) < 0 when  $\eta_n > 2\eta_R/3$ , i.e., when  $h_n$  lies in the right third of the thickness range  $(H_L, H_R)$ . Similarly, (35) implies that  $g(\eta_R) < 0$  when  $\eta_n < \eta_R/3$ , i.e., when  $h_n$  is in the left third of the range. Since negative values of g are unphysical, a different solution is needed when  $h_n$  lies outside the central third of the thickness range. If  $h_n$  is in the left third of the range, we define a cutoff thickness,  $H_C = 3h_n - 2H_L$ , and set g = 0 between  $H_C$  and  $H_R$ . Equations (32) and (33) are then valid with  $\eta_R$  redefined as  $H_C - H_L$ . And if  $h_n$  is in the right third of the range, we define  $H_C = 3h_n - 2H_R$  and set g = 0 between  $H_L$  and  $H_C$ . In this case, (32) and (33) apply with  $\eta_R = H_R - H_C$  and  $\eta_n = h_n - H_C$ .

Figure 4 illustrates the linear reconstruction of g for the simple cases  $H_L=0$ ,  $H_R=1$ ,  $a_n=1$ , and  $h_n=0.2$ , 0.4, 0.6, and 0.8. Note that g slopes downward ( $g_1<0$ ) when  $h_n$  is less than the midpoint thickness,  $(H_L+H_R)/2=1/2$ , and upward when  $h_n$  exceeds the midpoint thickness. For  $h_n=0.2$  and 0.8, g=0 over part of the range.

Finally, we remap the thickness distribution to the original boundaries by transferring area and volume between categories. We compute the ice area  $\Delta a_n$  and volume  $\Delta v_n$  between each original boundary  $H_n$  and

displaced boundary  $H_n^*$ . If  $H_n^* > H_n$ , ice moves from category n to n+1. The area and volume transferred are

$$\Delta a_n = \int_{H_n}^{H_n^*} g \, dh,\tag{36}$$

$$\Delta v_n = \int_{H_n}^{H_n^*} h \, g \, dh. \tag{37}$$

If  $H_n^* < H_N$ , ice area and volume are transferred from category n+1 to n using (36) and (37) with the limits of integration reversed. To evaluate the integrals we change coordinates from h to  $\eta = h - H_L$ , where  $H_L$  is the left limit of the range over which g > 0, and write  $g(\eta)$  using (32) and (33). In this way we obtain the new areas  $a_n$  and volumes  $v_n$  between the original boundaries  $H_{n-1}$  and  $H_n$  in each category. The new thicknesses,  $h_n = v_n/a_n$ , are guaranteed to lie in the range  $(H_{n-1}, H_n)$ . If g = 0 in the part of a category that is remapped to a neighboring category, no ice is transferred.

Other conserved quantities are transferred in proportion to the ice volume  $\Delta v_{in}$ . For example, the transferred ice energy in layer k is  $\Delta e_{ink} = e_{ink}(\Delta v_{in}/v_{in})$ .

The left and right boundaries of the domain require special treatment. If ice is growing in open water at a rate  $F_0$ , the left boundary  $H_0$  is shifted to the right by  $F_0\Delta t$  before g is constructed in category 1, then reset to zero after the remapping is complete. New ice is then added to the grid cell, conserving area, volume, and energy. If ice cannot grow in open water (because the ocean is too warm or the net surface energy flux is downward),  $H_0$  is fixed at zero, and the growth rate at the left boundary is estimated as  $F_0 = f_1$ . If  $F_0 < 0$ , all ice thinner than  $\Delta h_0 = -F_0\Delta t$  is assumed to have melted, and the ice area in category 1 is reduced accordingly. The area of new open water is

$$\Delta a_0 = \int_0^{\Delta h_0} g \, dh.$$

The right boundary  $H_N$  is not fixed but varies with  $h_N$ , the mean ice thickness in the thickest category. Given  $h_N$ , we set  $H_N = 3h_N - 2H_{N-1}$ , which ensures that g(h) > 0 for  $H_{N-1} < h < H_N$  and g(h) = 0 for  $h \ge H_N$ . No ice crosses the right boundary.

If the ice growth or melt rates in a given grid cell are too large, the thickness remapping scheme will not work. Instead, the thickness categories in that grid cell are treated as delta functions following [6], and categories outside their prescribed boundaries are merged with neighboring categories as needed. For time steps of less than a day and category thickness ranges of 10 cm or more, this simplification is needed rarely, if ever.

The linear remapping algorithm for thickness is not monotonic for tracers, although significant errors rarely occur. Usually they appear as snow temperatures (enthalpy) outside the physical range of values in very small snow volumes. In this case we transfer the snow and its heat and tracer contents to the ocean.

#### 3.4 Mechanical redistribution

The last term on the right-hand side of (6) is  $\psi$ , which describes the redistribution of ice in thickness space due to ridging and other mechanical processes. The mechanical redistribution scheme in CICE is based on [68], [56], [27], [19], and [43]. This scheme converts thinner ice to thicker ice and is applied after horizontal transport. When the ice is converging, enough ice ridges to ensure that the ice area does not exceed the grid cell area.

First we specify the participation function: the thickness distribution  $a_P(h) = b(h) g(h)$  of the ice participating in ridging. (We use "ridging" as shorthand for all forms of mechanical redistribution, including rafting.) The weighting function b(h) favors ridging of thin ice and closing of open water in preference to

Mechanical redistribution 31

ridging of thicker ice. There are two options for the form of b(h). If  $krdg_partic = 0$  in the namelist, we follow [68] and set

$$b(h) = \begin{cases} \frac{2}{G^*} \left(1 - \frac{G(h)}{G^*}\right) & \text{if } G(h) < G^* \\ 0 & \text{otherwise} \end{cases}$$
 (38)

where G(h) is the fractional area covered by ice thinner than h, and  $G^*$  is an empirical constant. Integrating  $a_P(h)$  between category boundaries  $H_{n-1}$  and  $H_n$ , we obtain the mean value of  $a_P$  in category n:

$$a_{Pn} = \frac{2}{G^*} (G_n - G_{n-1}) \left( 1 - \frac{G_{n-1} + G_n}{2G^*} \right), \tag{39}$$

where  $a_{Pn}$  is the ratio of the ice area ridging (or open water area closing) in category n to the total area ridging and closing, and  $G_n$  is the total fractional ice area in categories 0 to n. Equation (39) applies to categories with  $G_n < G^*$ . If  $G_{n-1} < G^* < G_n$ , then (39) is valid with  $G^*$  replacing  $G_n$ , and if  $G_{n-1} > G^*$ , then  $a_{Pn} = 0$ . If the open water fraction  $a_0 > G^*$ , no ice can ridge, because "ridging" simply reduces the area of open water. As in [68] we set  $G^* = 0.15$ .

If the spatial resolution is too fine for a given time step  $\Delta t$ , the weighting function (38) can promote numerical instability. For  $\Delta t=1$  hour, resolutions finer than  $\Delta x\sim 10$  km are typically unstable. The instability results from feedback between the ridging scheme and the dynamics via the ice strength. If the strength changes significantly on time scales less than  $\Delta t$ , the viscous-plastic solution of the momentum equation is inaccurate and sometimes oscillatory. As a result, the fields of ice area, thickness, velocity, strength, divergence, and shear can become noisy and unphysical.

A more stable weighting function was suggested by [43]:

$$b(h) = \frac{\exp[-G(h)/a^*]}{a^*[1 - \exp(-1/a^*)]}$$
(40)

When integrated between category boundaries, (40) implies

$$a_{Pn} = \frac{\exp(-G_{n-1}/a^*) - \exp(-G_n/a^*)}{1 - \exp(-1/a^*)}$$

This weighting function is used if  $krdg_partic = 1$  in the namelist. From (40), the mean value of G for ice participating in ridging is  $a^*$ , as compared to  $G^*/3$  for (38). For typical ice thickness distributions, setting  $a^* = 0.05$  with  $krdg_partic = 1$  gives participation fractions similar to those given by  $G^* = 0.15$  with  $krdg_partic = 0$ . See [43] for a detailed comparison of these two participation functions.

Thin ice is converted to thick, ridged ice in a way that reduces the total ice area while conserving ice volume and internal energy. There are two namelist options for redistributing ice among thickness categories. If  $krdg\_redist=0$ , ridging ice of thickness  $h_n$  forms ridges whose area is distributed uniformly between  $H_{\min}=2h_n$  and  $H_{\max}=2\sqrt{H^*h_n}$ , as in [27]. The default value of  $H^*$  is 25 m, as in earlier versions of CICE. Observations suggest that  $H^*=50$  m gives a better fit to first-year ridges [1], although the lower value may be appropriate for multiyear ridges [19]. The ratio of the mean ridge thickness to the thickness of ridging ice is  $k_n=(H_{\min}+H_{\max})/(2h_n)$ . If the area of category n is reduced by ridging at the rate  $r_n$ , the area of thicker categories grows simultaneously at the rate  $r_n/k_n$ . Thus the *net* rate of area loss due to ridging of ice in category n is  $r_n(1-1/k_n)$ .

The ridged ice area and volume are apportioned among categories in the thickness range  $(H_{\min}, H_{\max})$ . The fraction of the new ridge area in category m is

$$f_m^{\text{area}} = \frac{H_R - H_L}{H_{\text{max}} - H_{\text{min}}},\tag{41}$$

where  $H_L = \max(H_{m-1}, H_{\min})$  and  $H_R = \min(H_m, H_{\max})$ . The fraction of the ridge volume going to category m is

$$f_m^{\text{vol}} = \frac{(H_R)^2 - (H_L)^2}{(H_{\text{max}})^2 - (H_{\text{min}})^2}.$$
(42)

This uniform redistribution function tends to produce too little ice in the 3–5 m range and too much ice thicker than 10 m [1]. Observations show that the ITD of ridges is better approximated by a negative exponential. Setting  $krdq\_redist = 1$  gives ridges with an exponential ITD [43]:

$$g_R(h) \propto \exp[-(h - H_{\min})/\lambda]$$
 (43)

for  $h \geq H_{\min}$ , with  $g_R(h) = 0$  for  $h < H_{\min}$ . Here,  $\lambda$  is an empirical e-folding scale and  $H_{\min} = 2h_n$  (where  $h_n$  is the thickness of ridging ice). We assume that  $\lambda = \mu h_n^{1/2}$ , where  $\mu$  (mu\_rdg) is a tunable parameter with units  $m^{1/2}$ . Thus the mean ridge thickness increases in proportion to  $h_n^{1/2}$ , as in [27]. The value  $\mu = 4.0 \, \text{m}^{1/2}$  gives  $\lambda$  in the range 1-4 m for most ridged ice. Ice strengths with  $\mu = 4.0 \, \text{m}^{1/2}$  and krdg\_redist = 1 are roughly comparable to the strengths with  $H^* = 50 \, \text{m}$  and krdg\_redist = 0.

From (43) it can be shown that the fractional area going to category m as a result of ridging is

$$f_m^{\text{area}} = \exp[-(H_{m-1} - H_{\min})/\lambda] - \exp[-(H_m - H_{\min})/\lambda].$$
 (44)

The fractional volume going to category m is

$$f_m^{\text{vol}} = \frac{(H_{m-1} + \lambda) \exp[-(H_{m-1} - H_{\min})/\lambda] - (H_m + \lambda) \exp[-(H_m - H_{\min})/\lambda]}{H_{\min} + \lambda}.$$
 (45)

Equations (44) and (45) replace (41) and (42) when  $krdq_redist = 1$ .

Internal ice energy is transferred between categories in proportion to ice volume. Snow volume and internal energy are transferred in the same way, except that a fraction of the snow may be deposited in the ocean instead of added to the new ridge.

The net area removed by ridging and closing is a function of the strain rates. Let  $R_{\rm net}$  be the net rate of area loss for the ice pack (i.e., the rate of open water area closing, plus the net rate of ice area loss due to ridging). Following [19],  $R_{\rm net}$  is given by

$$R_{\text{net}} = \frac{C_s}{2} (\Delta - |D_D|) - \min(D_D, 0), \tag{46}$$

where  $C_s$  is the fraction of shear dissipation energy that contributes to ridge-building,  $D_D$  is the divergence, and  $\Delta$  is a function of the divergence and shear. These strain rates are computed by the dynamics scheme. The default value of  $C_s$  is 0.25.

Next, define  $R_{\text{tot}} = \sum_{n=0}^{N} r_n$ . This rate is related to  $R_{\text{net}}$  by

$$R_{\text{net}} = \left[ a_{P0} + \sum_{n=1}^{N} a_{Pn} \left( 1 - \frac{1}{k_n} \right) \right] R_{\text{tot}}.$$
 (47)

Given  $R_{\rm net}$  from (46), we use (47) to compute  $R_{\rm tot}$ . Then the area ridged in category n is given by  $a_{rn} = r_n \Delta t$ , where  $r_n = a_{Pn} R_{\rm tot}$ . The area of new ridges is  $a_{rn}/k_n$ , and the volume of new ridges is  $a_{rn}h_n$  (since volume is conserved during ridging). We remove the ridging ice from category n and use (41) and (42) (or 44) and (45)) to redistribute the ice among thicker categories.

Occasionally the ridging rate in thickness category n may be large enough to ridge the entire area  $a_n$  during a time interval less than  $\Delta t$ . In this case  $R_{\text{tot}}$  is reduced to the value that exactly ridges an area  $a_n$ 

3.5 Dynamics 33

during  $\Delta t$ . After each ridging iteration, the total fractional ice area  $a_i$  is computed. If  $a_i > 1$ , the ridging is repeated with a value of  $R_{\text{net}}$  sufficient to yield  $a_i = 1$ .

Two tracers for tracking the ridged ice area and volume are available. The actual tracers are for level (undeformed) ice area (alvl) and volume (vlvl), which are easier to implement for a couple of reasons: (1) ice ridged in a given thickness category is spread out among the rest of the categories, making it more difficult (and expensive) to track than the level ice remaining behind in the original category; (2) previously ridged ice may ridge again, so that simply adding a volume of freshly ridged ice to the volume of previously ridged ice in a grid cell may be inappropriate. Although the code currently only tracks level ice internally, both level ice and ridged ice are offered as history output. They are simply related:

$$a_{lvl} + a_{rdg} = a_i,$$
  
$$v_{lvl} + v_{rdg} = v_i.$$

Level ice area fraction and volume increase with new ice formation and decrease steadily via ridging processes. Without the formation of new ice, level ice asymptotes to zero because we assume that both level ice and ridged ice ridge, in proportion to their fractional areas in a grid cell (in the spirit of the ridging calculation itself which does not prefer level ice over previously ridged ice).

The ice strength P may be computed in either of two ways. If the namelist parameter kstrength = 0, we use the strength formula from [26]:

$$P = P^* h \exp[-C(1 - a_i)], \tag{48}$$

where  $P^* = 27,500 \,\mathrm{N/m}$  and C = 20 are empirical constants, and h is the mean ice thickness. Alternatively, setting kstrength = 1 gives an ice strength closely related to the ridging scheme. Following [56], the strength is assumed proportional to the change in ice potential energy  $\Delta E_P$  per unit area of compressive deformation. Given uniform ridge ITDs (krdg\_redist = 0), we have

$$P = C_f C_p \beta \sum_{n=1}^{N_C} \left[ -a_{Pn} h_n^2 + \frac{a_{Pn}}{k_n} \left( \frac{(H_n^{\text{max}})^3 - (H_n^{\text{min}})^3}{3(H_n^{\text{max}} - H_n^{\text{min}})} \right) \right], \tag{49}$$

where  $C_P = (g/2)(\rho_i/\rho_w)(\rho_w - \rho_i)$ ,  $\beta = R_{\rm tot}/R_{\rm net} > 1$  from (47), and  $C_f$  is an empirical parameter that accounts for frictional energy dissipation. Following [19], we set  $C_f = 17$ . The first term in the summation is the potential energy of ridging ice, and the second, larger term is the potential energy of the resulting ridges. The factor of  $\beta$  is included because  $a_{Pn}$  is normalized with respect to the total area of ice ridging, not the net area removed. Recall that more than one unit area of ice must be ridged to reduce the net ice area by one unit. For exponential ridge ITDs (krdq\_redist = 1), the ridge potential energy is modified:

$$P = C_f C_p \beta \sum_{n=1}^{N_C} \left[ -a_{Pn} h_n^2 + \frac{a_{Pn}}{k_n} \left( H_{\min}^2 + 2H_{\min} \lambda + 2\lambda^2 \right) \right]$$
 (50)

The energy-based ice strength given by (49) or (50) is more physically realistic than the strength given by (48). However, use of (48) is less likely to allow numerical instability at a given resolution and time step. See [43] for more details.

## 3.5 Dynamics

There are now different rheologies available in the CICE code. The elastic-viscous-plastic (EVP) model represents a modification of the standard viscous-plastic (VP) model for sea ice dynamics [26]. The elastic-anisotropic-plastic (EAP) model, on the other hand, explicitly accounts for the observed sub-continuum

anisotropy of the sea ice cover [75, 74]. If kdyn = 1 in the namelist then the EVP rheology is used (module **ice\_dyn\_evp.F90**), while kdyn = 2 is associated with the EAP rheology (**ice\_dyn\_eap.F90**). At times scales associated with the wind forcing, the EVP model reduces to the VP model while the EAP model reduces to the anisotropic rheology described in detail in [75, 71]. At shorter time scales the adjustment process takes place in both models by a numerically more efficient elastic wave mechanism. While retaining the essential physics, this elastic wave modification leads to a fully explicit numerical scheme which greatly improves the model's computational efficiency.

The EVP sea ice dynamics model is thoroughly documented in [31], [29], [32] and [33] and the EAP dynamics in [71]. Simulation results and performance of the EVP and EAP models have been compared with the VP model and with each other in realistic simulations of the Arctic respectively in [35] and [71]. Here we summarize the equations and direct the reader to the above references for details. The numerical implementation in this code release is that of [32] and [33], with revisions to the numerical solver as in [8]. The implementation of the EAP sea ice dynamics into CICE is described in detail in [71].

#### 3.5.1 Momentum

The force balance per unit area in the ice pack is given by a two-dimensional momentum equation [26], obtained by integrating the 3D equation through the thickness of the ice in the vertical direction:

$$m\frac{\partial \mathbf{u}}{\partial t} = \nabla \cdot \sigma + \vec{\tau}_a + \vec{\tau}_w - \hat{k} \times mf\mathbf{u} - mg\nabla H_o, \tag{51}$$

where m is the combined mass of ice and snow per unit area and  $\vec{\tau}_a$  and  $\vec{\tau}_w$  are wind and ocean stresses, respectively. The strength of the ice is represented by the internal stress tensor  $\sigma_{ij}$ , and the other two terms on the right hand side are stresses due to Coriolis effects and the sea surface slope. The parameterization for the wind and ice—ocean stress terms must contain the ice concentration as a multiplicative factor to be consistent with the formal theory of free drift in low ice concentration regions. A careful explanation of the issue and its continuum solution is provided in [33] and [10].

The momentum equation is discretized in time as follows, for the classic EVP approach. First, for clarity, the two components of (51) are

$$m\frac{\partial u}{\partial t} = \frac{\partial \sigma_{1j}}{\partial x_j} + \tau_{ax} + a_i c_w \rho_w |\mathbf{U}_w - \mathbf{u}| [(U_w - u)\cos\theta - (V_w - v)\sin\theta] + mfv - mg\frac{\partial H_o}{\partial x},$$

$$m\frac{\partial v}{\partial t} = \frac{\partial \sigma_{2j}}{\partial x_j} + \tau_{ay} + a_i c_w \rho_w |\mathbf{U}_w - \mathbf{u}| [(U_w - u)\sin\theta - (V_w - v)\cos\theta] - mfu - mg\frac{\partial H_o}{\partial y}.$$

In the code,  $vrel = a_i c_w \rho_w |\mathbf{U}_w - \mathbf{u}^k|$ , where k denotes the subcycling step. The following equations illustrate the time discretization and define some of the other variables used in the code.

$$\underbrace{\left(\frac{m}{\Delta t_e} + \mathtt{vrel} \cos \theta\right)}_{\mathtt{cca}} u^{k+1} - \underbrace{\left(mf + \mathtt{vrel} \sin \theta\right)}_{\mathtt{ccb}} v^{k+1} = \underbrace{\frac{\partial \sigma_{1j}^{k+1}}{\partial x_j}}_{\mathtt{strintx}} + \underbrace{\tau_{ax} - mg \frac{\partial H_{\circ}}{\partial x}}_{\mathtt{forcex}} + \mathtt{vrel} \underbrace{\left(U_w \cos \theta - V_w \sin \theta\right)}_{\mathtt{waterx}} + \underbrace{\frac{m}{\Delta t_e} u^k}_{\mathtt{valerx}},$$

$$\underbrace{(mf + \text{vrel} \sin \theta)}_{\text{ccb}} u^{k+1} + \underbrace{\left(\frac{m}{\Delta t_e} + \text{vrel} \cos \theta\right)}_{\text{cca}} v^{k+1} = \underbrace{\frac{\partial \sigma_{2j}^{k+1}}{\partial x_j}}_{\text{strinty}} + \underbrace{\tau_{ay} - mg \frac{\partial H_{\circ}}{\partial y}}_{\text{forcey}} + \text{vrel} \underbrace{(U_w \sin \theta + V_w \cos \theta)}_{\text{watery}} + \underbrace{\frac{m}{\Delta t_e} v^k}_{\text{vel}},$$

and  $vrel\cdot waterx(y) = taux(y)$ .

We solve this system of equations analytically for  $u^{k+1}$  and  $v^{k+1}$ . Define

$$\hat{u} = F_u + \tau_{ax} - mg \frac{\partial H_o}{\partial x} + \text{vrel} \left( U_w \cos \theta - V_w \sin \theta \right) + \frac{m}{\Delta t_e} u^k$$
 (52)

$$\hat{v} = F_v + \tau_{ay} - mg \frac{\partial H_o}{\partial y} + \text{vrel} \left( U_w \sin \theta + V_w \cos \theta \right) + \frac{m}{\Delta t_e} v^k, \tag{53}$$

Dynamics 35

where  $\mathbf{F} = \nabla \cdot \sigma^{k+1}$ . Then

$$\left(\frac{m}{\Delta t_e} + \operatorname{vrel}\cos\theta\right) u^{k+1} - \left(mf + \operatorname{vrel}\sin\theta\right) v^{k+1} = \hat{u}$$

$$\left(mf + \operatorname{vrel}\sin\theta\right) u^{k+1} + \left(\frac{m}{\Delta t_e} + \operatorname{vrel}\cos\theta\right) v^{k+1} = \hat{v}.$$

Solving simultaneously for  $u^{k+1}$  and  $v^{k+1}$ ,

$$u^{k+1} = \frac{a\hat{u} + b\hat{v}}{a^2 + b^2}$$
$$v^{k+1} = \frac{a\hat{v} - b\hat{u}}{a^2 + b^2},$$

where

$$a = \frac{m}{\Delta t_e} + \text{vrel}\cos\theta \tag{54}$$

$$b = mf + vrel \sin \theta. \tag{55}$$

When the subcycling is finished for each (thermodynamic) time step, the ice—ocean stress must be constructed from taux(y) and the terms containing vrel on the left hand side of the equations. This is done in subroutine *evp\_finish*. [CHECK akt changes and hibler-bryan stress]

#### 3.5.2 Internal stress

For convenience we formulate the stress tensor  $\sigma$  in terms of  $\sigma_1 = \sigma_{11} + \sigma_{22}$ ,  $\sigma_2 = \sigma_{11} - \sigma_{22}$ , and introduce the divergence,  $D_D$ , and the horizontal tension and shearing strain rates,  $D_T$  and  $D_S$  respectively.

Elastic-Viscous-Plastic

In the EVP model the internal stress tensor is determined from a regularized version of the VP constitutive law,

$$\frac{1}{E}\frac{\partial \sigma_1}{\partial t} + \frac{\sigma_1}{2\zeta} + \frac{P}{2\zeta} = D_D, \tag{56}$$

$$\frac{1}{E}\frac{\partial \sigma_2}{\partial t} + \frac{\sigma_2}{2\eta} = D_T, \tag{57}$$

$$\frac{1}{E}\frac{\partial \sigma_{12}}{\partial t} + \frac{\sigma_{12}}{2\eta} = \frac{1}{2}D_S, \tag{58}$$

where

$$\begin{split} D_D &= \dot{\epsilon}_{11} + \dot{\epsilon}_{22}, \\ D_T &= \dot{\epsilon}_{11} - \dot{\epsilon}_{22}, \\ D_S &= 2\dot{\epsilon}_{12}, \\ \dot{\epsilon}_{ij} &= \frac{1}{2} \left( \frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right), \\ \zeta &= \frac{P}{2\Delta}, \\ \eta &= \frac{P}{2\Delta e^2}, \\ \Delta &= \left[ D_D^2 + \frac{1}{e^2} \left( D_T^2 + D_S^2 \right) \right]^{1/2}, \end{split}$$

and P is a function of the ice thickness and concentration, described in Section 3.4. The dynamics component employs a "replacement pressure" (see [24], for example), which serves to prevent residual ice motion due to spatial variations of P when the rates of strain are exactly zero.

Viscosities are updated during the subcycling, so that the entire dynamics component is subcycled within the time step, and the elastic parameter E is defined in terms of a damping timescale T for elastic waves,  $\Delta t_e < T < \Delta t$ , as

$$E = \frac{\zeta}{T},$$

where  $T = E_{\circ} \Delta t$  and  $E_{\circ}$  (eyc) is a tunable parameter less than one. The stress equations (56–58) become

$$\begin{split} \frac{\partial \sigma_1}{\partial t} + \frac{\sigma_1}{2T} + \frac{P}{2T} &= \frac{P}{2T\Delta} D_D, \\ \frac{\partial \sigma_2}{\partial t} + \frac{e^2 \sigma_2}{2T} &= \frac{P}{2T\Delta} D_T, \\ \frac{\partial \sigma_{12}}{\partial t} + \frac{e^2 \sigma_{12}}{2T} &= \frac{P}{4T\Delta} D_S. \end{split}$$

All coefficients on the left-hand side are constant except for P, which changes only on the longer time step  $\Delta t$ . This modification compensates for the decreased efficiency of including the viscosity terms in the subcycling. (Note that the viscosities do not appear explicitly.) Choices of the parameters used to define E, T and  $\Delta t_e$  are discussed in Sections 3.5.3 and 4.4.

The bilinear discretization used for the stress terms  $\partial \sigma_{ij}/\partial x_j$  in the momentum equation is now used, which enabled the discrete equations to be derived from the continuous equations written in curvilinear coordinates. In this manner, metric terms associated with the curvature of the grid are incorporated into the discretization explicitly. Details pertaining to the spatial discretization are found in [32].

#### Elastic-Anisotropic-Plastic

In the EAP model the internal stress tensor is related to the geometrical properties and orientation of underlying virtual diamond shaped floes (see Fig. 5). In contrast to the isotropic EVP rheology, the anisotropic plastic yield curve within the EAP rheology depends on the relative orientation of the diamond shaped floes (unit vector **r** in Fig. 5), with respect to the principal direction of the deformation rate (not shown). Local anisotropy of the sea ice cover is accounted for by an additional prognostic variable, the structure tensor **A** defined by

$$\mathbf{A} = \int_{\mathbb{S}} \vartheta(\mathbf{r}) \mathbf{r} \mathbf{r} d\mathbf{r}.$$

where  $\mathbb S$  is a unit-radius circle;  $\mathbf A$  is a unit trace,  $2\times 2$  matrix. From now on we shall describe the orientational distribution of floes using the structure tensor. For simplicity we take the probability density function  $\vartheta(\mathbf r)$  to be Gaussian,  $\vartheta(z)=\omega_1\exp(-\omega_2z^2)$ , where z is the ice floe inclination with respect to the axis  $x_1$  of preferential alignment of ice floes (see Fig. 5),  $\vartheta(z)$  is periodic with period  $\pi$ , and the positive coefficients  $\omega_1$  and  $\omega_2$  are calculated to ensure normalization of  $\vartheta(z)$ , i.e.  $\int_0^{2\pi} \vartheta(z)dz=1$ . The ratio of the principal components of  $\mathbf A$ ,  $A_1/A_2$ , are derived from the phenomenological evolution equation for the structure tensor  $\mathbf A$ ,

$$\frac{D\mathbf{A}}{Dt} = \mathbf{F}_{iso}(\mathbf{A}) + \mathbf{F}_{frac}(\mathbf{A}, \boldsymbol{\sigma}), \tag{59}$$

where t is the time, and D/Dt is the co-rotational time derivative accounting for advection and rigid body rotation  $(D\mathbf{A}/Dt = d\mathbf{A}/dt - \mathbf{W} \cdot \mathbf{A} - \mathbf{A} \cdot \mathbf{W}^T)$  with  $\mathbf{W}$  being the vorticity tensor.  $\mathbf{F}_{iso}$  is a function that accounts for a variety of processes (thermal cracking, melting, freezing together of floes) that contribute to a

Dynamics 37




Figure 5: Geometry of interlocking diamond-shaped floes (taken from [75]).  $\phi$  is half of the acute angle of the diamonds. L is the edge length.  $n_1$ ,  $n_2$  and  $\tau_1$ ,  $\tau_2$  are respectively the normal and tangential unit vectors along the diamond edges.  $\mathbf{v} = L\boldsymbol{\tau}_2 \cdot \dot{\boldsymbol{\epsilon}}$  is the relative velocity between the two floes connected by the vector  $L\boldsymbol{\tau}_2$ .  $\mathbf{r}$  is the unit vector along the main diagonal of the diamond. Note that the diamonds illustrated here represent one possible realisation of all possible orientations. The angle z represents the rotation of the diamonds' main axis relative to their preferential orientation along the axis  $x_1$ .

more isotropic nature to the ice cover.  $\mathbf{F}_{frac}$  is a function determining the ice floe re-orientation due to fracture, and explicitly depends upon sea ice stress (but not its magnitude). Following [75], based on laboratory experiments by [57] we consider four failure mechanisms for the Arctic sea ice cover. These are determined by the ratio of the principal values of the sea ice stress  $\sigma_1$  and  $\sigma_2$ : (i) under biaxial tension, fractures form across the perpendicular principal axes and therefore counteract any apparent redistribution of the floe orientation; (ii) if only one of the principal stresses is compressive, failure occurs through axial splitting along the compression direction; (iii) under biaxial compression with a low confinement ratio,  $(\sigma_1/\sigma_2 < R)$ , sea ice fails Coulombically through formation of slip lines delineating new ice floes oriented along the largest compressive stress; and finally (iv) under biaxial compression with a large confinement ratio,  $(\sigma_1/\sigma_2 \ge R)$ , the ice is expected to fail along both principal directions so that the cumulative directional effect balances to zero.

The new anisotropic rheology requires solving the evolution Eq. (59) for the structure tensor in addition to the momentum and stress equations. The evolution equation for  $\mathbf{A}$  is solved within the EVP subcycling loop, and consistently with the momentum and stress evolution equations, we neglect the advection term for the structure tensor. Eq. (59) then reduces to the system of two equations:

$$\frac{\partial A_{11}}{\partial t} = -k_t \left( A_{11} - \frac{1}{2} \right) + M_{11},$$

$$\frac{\partial A_{12}}{\partial t} = -k_t A_{12} + M_{12},$$

where the first terms on the right hand side correspond to the isotropic contribution,  $F_{iso}$ , and  $M_{11}$  and  $M_{12}$ 

are the components of the term  $F_{frac}$  in Eq. (59) that are given in [75] and [71]. These evolution equations are discretized semi-implicitly in time. The degree of anisotropy is measured by the largest eigenvalue  $(A_1)$ of this tensor  $(A_2 = 1 - A_1)$ .  $A_1 = 1$  corresponds to perfectly aligned floes and  $A_1 = 0.5$  to a uniform distribution of floe orientation. Note that while we have specified the aspect ratio of the diamond floes, through prescribing  $\phi$ , we make no assumption about the size of the diamonds so that formally the theory is scale invariant.

As described in greater detail in [75], the internal ice stress for a single orientation of the ice floes can be calculated explicitly and decomposed, for an average ice thickness h, into its ridging (r) and sliding (s) contributions

$$\sigma^b(\mathbf{r}, h) = P_r(h)\sigma_r^b(\mathbf{r}) + P_s(h)\sigma_s^b(\mathbf{r}),$$

where  $P_r$  and  $P_s$  are the ridging and sliding strengths and the ridging and sliding stresses are functions of the angle  $\theta = \arctan(\dot{\epsilon}_{II}/\dot{\epsilon}_{I})$ , the angle y between the major principal axis of the strain rate tensor (not shown) and the structure tensor ( $x_1$  axis in Fig. 5), and the angle z defined in Fig. 5. In the stress expressions above the underlying floes are assumed parallel, but in a continuum-scale sea ice region the floes can possess different orientations in different places and we take the mean sea ice stress over a collection of floes to be given by the average

$$oldsymbol{\sigma}^{EAP}(h) = P_r(h) \int_{\mathbb{S}} \vartheta(\mathbf{r}) \left[ oldsymbol{\sigma}_r^b(\mathbf{r}) + k oldsymbol{\sigma}_s^b(\mathbf{r}) \right] d\mathbf{r},$$

where we have introduced the friction parameter  $k = P_s/P_r$  and where we identify the ridging ice strength  $P_r(h)$  with the strength P described in section 1 and used within the EVP framework.

As is the case for the EVP rheology, elasticity is included in the EAP description not to describe any physical effect, but to make use of the efficient, explicit numerical algorithm used to solve the full sea ice momentum balance. We use the analogous EAP stress equations,

$$\frac{\partial \sigma_1}{\partial t} + \frac{\sigma_1}{2T} = \frac{\sigma_1^{EAP}}{2T},\tag{60}$$

$$\frac{\partial \sigma_1}{\partial t} + \frac{\sigma_1}{2T} = \frac{\sigma_1^{EAP}}{2T}, \qquad (60)$$

$$\frac{\partial \sigma_2}{\partial t} + \frac{\sigma_2}{2T} = \frac{\sigma_2^{EAP}}{2T}, \qquad (61)$$

$$\frac{\partial \sigma_{12}}{\partial t} + \frac{\sigma_{12}}{2T} = \frac{\sigma_{12}^{EAP}}{2T},\tag{62}$$

where the anisotropic stress  $\sigma^{EAP}$  is defined in a look-up table for the current values of strain rate and structure tensor. The look-up table is constructed by computing the stress (normalized by the strength) from Eq. (60-62) for discrete values of the largest eigenvalue of the structure tensor,  $\frac{1}{2} \leq A_1 \leq 1$ , the angle  $0 \le \theta \le 2\pi$ , and the angle  $-\pi/2 \le y \le \pi/2$  between the major principal axis of the strain rate tensor and the structure tensor [71]. The updated stress, after the elastic relaxation, is then passed to the momentum equation and the sea ice velocities are updated in the usual manner within the subcycling loop of the EVP rheology. The structure tensor evolution equations are solved implicitly at the same frequency,  $\Delta t_e$ , as the ice velocities and internal stresses. Finally, to be coherent with our new rheology we compute the area loss rate due to ridging as  $|\dot{\epsilon}|\alpha_r(\theta)$ , with  $\alpha_r(\theta)$  and  $\alpha_s(\theta)$  given by [76],

$$\alpha_r(\theta) = \frac{\sigma_{ij}^r \dot{\epsilon}_{ij}}{P_r |\dot{\epsilon}|}, \qquad \alpha_s(\theta) = \frac{\sigma_{ij}^s \dot{\epsilon}_{ij}}{P_s |\dot{\epsilon}|}.$$

Both ridging rate and sea ice strength are computed in the outer loop of the dynamics.

#### 3.5.3 **Revised approach**

A modification of the standard elastic-viscous-plastic (EVP) approach for sea ice dynamics has been proposed by [8], that generalizes the EVP elastic modulus E and the time stepping approach for both momenDynamics 39

tum and stress to use an under-relaxation technique. In general terms, the momentum and stress equations become

$$\mathbf{u}^{k+1} = \mathbf{u}^k + \left(\breve{\mathbf{u}}^k - \mathbf{u}^{k+1}\right) \frac{1}{\beta}$$

$$\sigma^{k+1} = \sigma^k + \left(\breve{\sigma}^k - \sigma^{k+1}\right) \frac{1}{\alpha}$$

where  $\ddot{\mathbf{u}}$  and  $\ddot{\sigma}$  represent the converged VP solution and  $\alpha, \beta < 1$ .

### Momentum

The momentum equations become

$$\beta \frac{m}{\Delta t} \left( u^{k+1} - u^k \right) = \overline{u} + \text{vrel} \left( -u^{k+1} \cos \theta + v^{k+1} \sin \theta \right) + m f v^{k+1} - \frac{m}{\Delta t} u^{k+1}$$

$$\beta \frac{m}{\Delta t} \left( v^{k+1} - v^k \right) = \overline{v} - \text{vrel} \left( u^{k+1} \sin \theta + v^{k+1} \cos \theta \right) - m f u^{k+1} - \frac{m}{\Delta t} v^{k+1}$$

where

$$\overline{u} = F_u + \tau_{ax} - mg \frac{\partial H_o}{\partial x} + \text{vrel} \left( U_w \cos \theta - V_w \sin \theta \right) + \frac{m}{\Delta t} u^o$$
(63)

$$\overline{v} = F_v + \tau_{ay} - mg \frac{\partial H_o}{\partial y} + \text{vrel} \left( U_w \sin \theta + V_w \cos \theta \right) + \frac{m}{\Delta t} v^o, \tag{64}$$

 $\mathbf{u}^{\circ}$  is the initial value of velocity at the beginning of the subcycling (k=0), and we use  $\mathbf{u}^{k+1}$  for the ice-ocean stress and Coriolis terms. Eqs. (63) and (64) differ from Eqs. (52) and (53) only in the last term. Solving simultaneously for  $\mathbf{u}^{k+1}$  as before, we have

$$u^{k+1} = \frac{\tilde{a}\tilde{u} + b\tilde{v}}{\tilde{a}^2 + b^2}$$
$$v^{k+1} = \frac{\tilde{a}\tilde{v} - b\tilde{u}}{\tilde{a}^2 + b^2},$$

where

$$\tilde{a} = (1+\beta)\frac{m}{\Delta t} + \text{vrel}\cos\theta$$

$$\tilde{\mathbf{u}} = \overline{\mathbf{u}} + \beta\frac{m}{\Delta t}\mathbf{u}^k,$$
(65)

and b is the same as in Eq. (55).

#### Stress

In CICE's classic approach, the update to  $\sigma_1$  at subcycle step k+1 is

$$\sigma_1^{k+1} = \left(\sigma_1^k + \frac{P}{\Delta} \frac{\Delta t_e}{2T} \left(\dot{\epsilon} - \Delta\right)\right) * \left(1 + \frac{\Delta t_e}{2T}\right)$$
(66)

If we set

$$\alpha_1 = \frac{2T}{\Delta t_e},$$

then Eq. (66) becomes

$$\sigma_1^{k+1} \left( 1 + \alpha_1 \right) = \alpha_1 \sigma_1^k + \frac{P}{\Lambda} \left( \dot{\epsilon} - \Delta \right). \tag{67}$$

This is equivalent to Eq. (23) in [8], but using  $\sigma$  at the current subcycle k+1 in the last term on the right-hand side. Likewise, setting

 $\alpha_2 = \frac{2T}{e^2 \Delta t_e} = \frac{\alpha_1}{e^2}$ 

produces equations equivalent to Eq. (23) in [8] for  $\sigma_2$  and  $\sigma_{12}$ . Therefore the only change needed in the stress code is to use  $\alpha_1$  and  $\alpha_2$  instead of  $2T/\Delta t_e$  and  $2T/e^2\Delta t_e$ .

However, [8] introduce another change to the EVP stress equations by altering the form of Young's modulus in the elastic term: the coefficient of  $\partial \sigma_1/\partial t$  is 1/E, but it is  $e^2/E$  in the  $\sigma_2$  and  $\sigma_{12}$  equations. This change does not affect the VP equations to which the EVP equations should converge, but it does affect the transient path taken during the subcycling. Since EVP subcycling is finite, the numerical solutions obtained using this method differ from the original EVP code.

To implement this second change, we need define only  $\alpha_1 = 2T/\Delta t_e$  as above and incorporate the factor of  $e^2$  from  $\alpha_2$  into the equations for  $\sigma_2$  and  $\sigma_{12}$ :

$$\sigma_1^{k+1} (1 + \alpha_1) = \sigma_1^k + \alpha_1 \frac{P}{\Delta} D_D, 
\sigma_2^{k+1} (1 + \alpha_1) = \sigma_2^k + \frac{\alpha_1}{e^2} \frac{P}{\Delta} D_T, 
\sigma_{12}^{k+1} (1 + \alpha_1) = \sigma_{12}^k + \frac{\alpha_1}{2e^2} \frac{P}{\Delta} D_S.$$

To minimize code changes and unify the two approaches, we define and apply  $1/\alpha_1$  and  $\beta$  in the classic EVP code, and modify the elastic stress term. These under-relaxation parameters control the rate at which the iteration converges. Thus for classic EVP we set

$$\label{eq:arlx1i} \begin{array}{ll} {\tt arlx1i} & = & \displaystyle \frac{1}{\alpha_1} = \frac{\Delta t_e}{2T} \\ \\ {\tt brlx} & = & \displaystyle \beta = \frac{\Delta t}{\Delta t_e}. \end{array}$$

Then

$$\begin{array}{lll} \texttt{denom1} &=& \frac{1}{1+\texttt{arlx1i}} = \frac{1}{1+1/\alpha_1} = \frac{1}{1+\Delta t_e/2T} \\ \\ \texttt{c1} &=& \frac{P}{\Delta} \, \texttt{arlx1i} = \frac{P}{\Delta} \frac{\Delta t_e}{2T} \\ \\ \texttt{c0} &=& \frac{\texttt{c1}}{e^2} = \frac{P}{\Delta} \frac{\Delta t_e}{2Te^2}. \end{array}$$

The stress equations for stressp  $(\sigma_1)$  are unchanged; the modified equations for stressm  $(\sigma_2)$  and stress12  $(\sigma_{12})$  take the form

$$\begin{array}{lll} {\tt stressm} &=& {\tt stressm} + {\tt c0}\,D_T\,{\tt denom1} \\ {\tt stress12} &=& {\tt stress12} + {\tt 0.5}\,{\tt c0}\,D_S\,{\tt denom1}. \end{array}$$

For classic EVP,

$$cca = a = brlx \frac{m}{\Delta t} + vrel cos \theta = \frac{m}{\Delta t_e} + vrel cos \theta.$$

For revised EVP, arlx1i and brlx are defined separately from  $\Delta t$ ,  $\Delta t_e$ , T and e, and

$$\label{eq:cca} \mathtt{cca} = \tilde{a} = \left(1 + \mathtt{brlx}\right) \frac{m}{\Delta t} + \mathtt{vrel} \cos \theta = \left(1 + \beta\right) \frac{m}{\Delta t} + \mathtt{vrel} \cos \theta.$$

 $\tilde{\mathbf{u}}$  must also be defined for revised EVP as in Eq. (65). The extra terms in  $\tilde{a}$  and  $\tilde{\mathbf{u}}$  are multiplied by a flag (revp) that equals 1 for revised EVP and 0 for classic EVP. Revised EVP is activated by setting the namelist parameter revised\_evp = .true. Note that in the current implementation, only the modified version of the elastic term is available for either the classic (revised\_evp = .false.) or the revised EVP method. A final difference is that the revised approach initializes the stresses to 0 at the beginning of each time step, while the classic EVP approach uses the previous time step value.

### 3.6 Thermodynamics

The current CICE version includes three thermodynamics options, the "zero-layer" thermodynamics of [59] (ktherm=0), the Bitz and Lipscomb model [7] (ktherm=1) that assumes a fixed salinity profile, and a new "mushy" formulation (ktherm=2) in which salinity evolves [72]. For each thickness category, CICE computes changes in the ice and snow thickness and vertical temperature profile resulting from radiative, turbulent, and conductive heat fluxes. The ice has a temperature-dependent specific heat to simulate the effect of brine pocket melting and freezing, for ktherm = 1 and 2.

Each thickness category n in each grid cell is treated as a horizontally uniform column with ice thickness  $h_{in}=v_{in}/a_{in}$  and snow thickness  $h_{sn}=v_{sn}/a_{in}$ . (Henceforth we omit the category index n.) Each column is divided into  $N_i$  ice layers of thickness  $\Delta h_i=h_i/N_i$  and  $N_s$  snow layers of thickness  $\Delta h_s=h_s/N_s$ . The surface temperature (i.e., the temperature of ice or snow at the interface with the atmosphere) is  $T_{sf}$ , which cannot exceed  $0^{\circ}$ C. The temperature at the midpoint of the snow layer is  $T_s$ , and the midpoint ice layer temperatures are  $T_{ik}$ , where k ranges from 1 to  $N_i$ . The temperature at the bottom of the ice is held at  $T_f$ , the freezing temperature of the ocean mixed layer. All temperatures are in degrees Celsius unless stated otherwise.

Each ice layer has an enthalpy  $q_{ik}$ , defined as the negative of the energy required to melt a unit volume of ice and raise its temperature to  $0^{\circ}$ C. Because of internal melting and freezing in brine pockets, the ice enthalpy depends on the brine pocket volume and is a function of temperature and salinity. We can also define a snow enthalpy  $q_s$ , which depends on temperature alone.

Given surface forcing at the atmosphere-ice and ice-ocean interfaces along with the ice and snow thicknesses and temperatures/enthalpies at time m, the thermodynamic model advances these quantities to time m+1 (ktherm=2 also advances salinity). The calculation proceeds in two steps. First we solve a set of equations for the new temperatures, as discussed in Section 3.6.3. Then we compute the melting, if any, of ice or snow at the top surface, and the growth or melting of ice at the bottom surface, as described in Section 3.6.4. We begin by describing the surface forcing parameterizations, which are closely related to the ice and snow surface temperatures.

### 3.6.1 Melt ponds

Three explicit melt pond parameterizations are available in CICE, and all must use the delta-Eddington radiation scheme, described below. The default ('ccsm3') shortwave parameterization incorporates melt ponds implicitly by adjusting the albedo based on surface conditions.

For each of the three explicit parameterizations, a volume  $\Delta V_{melt}$  of melt water produced on a given category may be added to the melt pond liquid volume:

$$\Delta V_{melt} = \frac{r}{\rho_w} \left( \rho_i \Delta h_i + \rho_s \Delta h_s + F_{rain} \Delta t \right) a_i,$$

where

$$r = r_{min} + (r_{max} - r_{min}) a_i$$

is the fraction of the total melt water available that is added to the ponds,  $\rho_i$  and  $\rho_s$  are ice and snow densities,  $\Delta h_i$  and  $\Delta h_s$  are the thicknesses of ice and snow that melted, and  $F_{rain}$  is the rainfall rate. Namelist parameters are set for the level-ice (tr\_pond\_lvl) parameterization; in the cesm and topo pond schemes the standard values of  $r_{max}$  and  $r_{min}$  are 0.7 and 0.15, respectively.

Radiatively, the surface of an ice category is divided into fractions of snow, pond and bare ice. In these melt pond schemes, the actual pond area and depth are maintained throughout the simulation according to the physical processes acting on it. However, snow on the sea ice and pond ice may shield the pond and ice below from solar radiation. These processes do not alter the actual pond volume; instead they are used to define an "effective pond fraction" (and likewise, effective pond depth, snow fraction and snow depth) used only for the shortwave radiation calculation.

In addition to the physical processes discussed below, tracer equations and definitions for melt ponds are also described in Section 3.1 and Fig. 1.

### CESM formulation (tr\_pond\_cesm = .true.)

Melt pond area and thickness tracers are carried on each ice thickness category as in Section 3.1. Defined simply as the product of pond area,  $a_p$ , and depth,  $h_p$ , the melt pond volume,  $V_p$ , grows through addition of ice or snow melt water or rain water, and shrinks when the ice surface temperature becomes cold,

where  $dh_i$  and  $dh_s$  represent ice and snow melt at the top surface of each thickness category and  $r_2=0.01$ . Here,  $T_p$  is a reference temperature equal to -2°C. Pond depth is assumed to be a linear function of the pond fraction ( $h_p=\delta_p a_p$ ) and is limited by the category ice thickness ( $h_p\leq 0.9h_i$ ). The pond shape (pndaspect)  $\delta_p=0.8$  in the standard CESM pond configuration. The area and thickness are computed according to the assumed pond shape, and the pond area is then reduced in the presence of snow for the radiation calculation. Ponds are allowed only on ice at least 1 cm thick. This formulation differs slightly from that documented in [28].

### Topographic formulation (tr\_pond\_topo = .true.)

The principle concept of this scheme is that melt water runs downhill under the influence of gravity and collects on sea ice with increasing surface height starting at the lowest height [20, 21, 22]. Thus, the topography of the ice cover plays a crucial role in determining the melt pond cover. However, CICE does not explicitly represent the topography of sea ice. Therefore, we split the existing ice thickness distribution function into a surface height and basal depth distribution assuming that each sea ice thickness category is in hydrostatic equilibrium at the beginning of the melt season. We then calculate the position of sea level assuming that the ice in the whole grid cell is rigid and in hydrostatic equilibrium.

Once a volume of water is produced from ice and snow melting, we calculate the number of ice categories covered by water. At each time step, we construct a list of volumes of water  $\{V_{P1}, V_{P2}, ... V_{P,k-1}, V_{Pk}, V_{P,k+1}, ...\}$ , where  $V_{Pk}$  is the volume of water required to completely cover the ice and snow in the surface height categories from i=1 up to i=k. The volume  $V_{Pk}$  is defined so that if the volume of water  $V_P$  is such that  $V_{Pk} < V_P < V_{P,k+1}$  then the snow and ice in categories n=1 up to n=k+1 are covered in melt water. Figure 6a depicts the areas covered in melt water and saturated snow on the surface height (rather than thickness) categories  $h_{top,k}$ . Note in the CICE code, we assume that  $h_{top,n}/h_{in}=0.6$  (an arbitrary choice). The fractional area of the nth category covered in snow is  $a_{sn}$ . The volume  $V_{P1}$ , which is the region with vertical hatching, is the volume of water required to completely fill up the first thickness category, so that any extra melt water must occupy the second thickness category, and it is given by the expression

$$V_{P1} = a_{i1}(h_{top,2} - h_{top,1}) - a_{s1}a_{i1}h_{s1}(1 - V_{sw}),$$




Figure 6: (a) Schematic illustration of the relationship between the height of the pond surface  $h_{pnd,tot}$ , the volume of water  $V_{Pk}$  required to completely fill up to category k, the volume of water  $V_{P} - V_{Pk}$ , and the depth to which this fills up category k+1. Ice and snow areas  $a_i$  and  $a_s$  are also depicted. The volume calculation takes account of the presence of snow, which may be partially or completely saturated. (b) Schematic illustration indicating pond surface height  $h_{pnd,tot}$  and sea level  $h_{sl}$  measured with respect to the thinnest surface height category  $h_{i1}$ , the submerged portion of the floe  $h_{sub}$ , and hydraulic head  $\Delta H$ . A positive hydraulic head (pond surface above sea level) will flush melt water through the sea ice into the ocean; a negative hydraulic head can drive percolation of sea water up onto the ice surface. Here,  $\alpha=0.6$  and  $\beta=0.4$  are the surface height and basal depth distribution fractions. The height of the steps is the height of the ice above the reference level, and the width of the steps is the area of ice of that height. The illustration does not imply a particular assumed topography, rather it is assumed that all thickness categories are present at the sub-grid scale so that water will always flow to the lowest surface height class.

44 Model components

where  $V_{sw}$  is the fraction of the snow volume that can be occupied by water, and  $h_{s1}$  is the snow depth on ice height class 1. In a similar way, the volume required to fill up the first and second surface categories,  $V_{P2}$ , is given by

$$V_{P2} = a_{i1}(h_{top,3} - h_{top,2}) + a_{i2}(h_{top,3} - h_{top,2}) - a_{s2}a_{i2}h_{s2}(1 - V_{sw}) + V_{P1}.$$

The general expression for volume  $V_{Pk}$  is given by

$$V_{Pk} = \sum_{m=0}^{k} a_{im} (h_{top,k+1} - h_{top,k}) - a_{sk} a_{ik} h_{sk} (1 - V_{sw}) + \sum_{m=0}^{k-1} V_{Pm}.$$

(Note that we have implicitly assumed that  $h_{si} < h_{top,k+1} - h_{top,k}$  for all k.) No melt water can be stored on the thickest ice thickness category. If the melt water volume exceeds the volume calculated above, the remaining melt water is released to the ocean.

At each time step, the pond height above the level of the thinnest surface height class, that is, the maximum pond depth, is diagnosed from the list of volumes  $V_{Pk}$ . In particular, if the total volume of melt water  $V_P$  is such that  $V_{Pk} < V_P < V_{P,k+1}$  then the pond height  $h_{pnd,tot}$  is

$$h_{pnd,tot} = h_{par} + h_{top,k} - h_{top,1},$$

where  $h_{par}$  is the height of the pond above the level of the ice in class k and partially fills the volume between  $V_{P,k}$  and  $V_{P,k+1}$ . From Figure 6a we see that  $h_{top,k} - h_{top,1}$  is the height of the melt water, which has volume  $V_{Pk}$ , which completely fills the surface categories up to category k. The remaining volume,  $V_P - V_{Pk}$ , partially fills category k+1 up to the height  $h_{par}$  and there are two cases to consider: either the snow cover on category k+1, with height  $h_{s,k+1}$ , is completely covered in melt water (i.e.,  $h_{par} > h_{s,k+1}$ ), or it is not (i.e.,  $h_{par} \le h_{s,k+1}$ ). From conservation of volume, we see from Figure 6a that for an incompletely to completely saturated snow cover on surface ice class k+1,

$$V_P - V_{Pk} = h_{par} \left( \sum_{m=1}^k a_{ik} + a_{i,k+1} (1 - a_{s,k+1}) + a_{i,k+1} a_{s,k+1} V_{sw} \right)$$
for  $h_{par} \le h_{s,k+1}$ ,

and for a saturated snow cover with water on top of the snow on surface ice class k+1,

$$V_P - V_{Pk} = h_{par} \left( \sum_{m=1}^k a_{ik} + a_{i,k+1} (1 - a_{s,k+1}) \right) + a_{i,k+1} a_{s,k+1} V_{sw} h_{s,k+1}$$

$$+ a_{i,k+1} a_{s,k+1} (h_{par} - h_{s,k+1})$$
for  $h_{par} > h_{s,k+1}$ .

As the melting season progresses, not only does melt water accumulate upon the upper surface of the sea ice, but the sea ice beneath the melt water becomes more porous owing to a reduction in solid fraction [16]. The hydraulic head of melt water on sea ice (i.e., its height above sea level) drives flushing of melt water through the porous sea ice and into the underlying ocean. The mushy thermodynamics scheme (ktherm = 2) handles flushing. For ktherm  $\neq$  2 we model the vertical flushing rate using Darcy's law for flow through a porous medium

$$w = -\frac{\Pi_v}{\mu} \rho_o g \frac{\Delta H}{h_i},$$

where w is the vertical mass flux per unit perpendicular cross-sectional area (i.e., the vertical component of the Darcy velocity),  $\Pi_v$  is the vertical component of the permeability tensor (assumed to be isotropic in the horizontal),  $\mu$  is the viscosity of water,  $\rho_o$  is the ocean density, g is gravitational acceleration,  $\Delta H$  is the the hydraulic head, and  $h_i$  is the thickness of the ice through which the pond flushes. As proposed by [25] the vertical permeability of sea ice can be calculated from the liquid fraction  $\phi$ :

$$\Pi_v = 3 \times 10^{-8} \phi^3 \text{m}^2. \tag{68}$$

Since the solid fraction varies throughout the depth of the sea ice, so does the permeability. The rate of vertical drainage is determined by the lowest (least permeable) layer, corresponding to the highest solid fraction. From the equations describing sea ice as a mushy layer [18], the solid fraction is determined by:

$$\phi = \frac{c_i - S}{c_i - S_{br}(T)},$$

where S is the bulk salinity of the ice,  $S_{br}(T)$  is the concentration of salt in the brine at temperature T and  $c_i$  is the concentration of salt in the ice crystals (set to zero).

The hydraulic head is given by the difference in height between the upper surface of the melt pond  $h_{pnd,tot}$  and the sea level  $h_{sl}$ . The value of the sea level  $h_{sl}$  is calculated from

$$h_{sl} = h_{sub} - 0.4 \sum_{n=1}^{N} a_{in} h_{in} - \beta h_{i1}, \tag{69}$$

where  $0.4 \sum_{n=1}^{N} a_{in} h_{i,n}$  is the mean thickness of the basal depth classes, and  $h_{sub}$  is the depth of the submerged portion of the floe. Figure 6b depicts the relationship between the hydraulic head and the depths and heights that appear in equation (69). The depth of the submerged portion of the floe is determined from hydrostatic equilibrium to be

$$h_{sub} = \frac{\rho_m}{\rho_w} V_P + \frac{\rho_s}{\rho_w} V_s + \frac{\rho_i}{\rho_w} V_i,$$

where  $\rho_m$  is the density of melt water,  $V_P$  is the total pond volume,  $V_s$  is the total snow volume, and  $V_i$  is the total ice volume.

When the surface energy balance is negative, a layer of ice is formed at the upper surface of the ponds. The rate of growth of the ice lid is given by the Stefan energy budget at the lid-pond interface

$$\rho_i L_0 \frac{dh_{ipnd}}{dt} = k_i \frac{\partial T_i}{\partial z} - k_p \frac{\partial T_p}{\partial z},$$

where  $L_0$  is the latent heat of fusion of pure ice per unit volume,  $T_i$  and  $T_p$  are the ice surface and pond temperatures, and  $k_i$  and  $k_p$  are the thermal conductivity of the ice lid and pond respectively. The second term on the right hand-side is close to zero since the pond is almost uniformly at the freezing temperature [67]. Approximating the temperature gradient in the ice lid as linear, the Stefan condition yields the classic Stefan solution for ice lid depth

$$h_{ipnd} = \sqrt{\frac{2k_i}{\rho_s L}} \Delta T_i t,$$

where  $\Delta T$  is the temperature difference between the top and the bottom of the lid. Depending on the surface flux conditions the ice lid can grow, partially melt, or melt completely. Provided that the ice lid is thinner than a critical lid depth (1 cm is suggested) then the pond is regarded as effective, i.e. the pond affects the optical properties of the ice cover. Effective pond area and pond depth for each thickness category are passed to the radiation scheme for calculating albedo. Note that once the ice lid has exceeded the critical

thickness, snow may accumulate on the lid causing a substantial increase in albedo. In the current CICE model, melt ponds only affect the thermodynamics of the ice through the albedo. To conserve energy, the ice lid is dismissed once the pond is completely refrozen.

As the sea ice area shrinks due to melting and ridging, the pond volume over the lost area is released to the ocean immediately. In [21], the pond volume was carried as an ice area tracer, but in [22] and here, pond area and thickness are carried as separate tracers, as in Section 3.1.

Unlike the cesm and level-ice melt pond schemes, the liquid pond water in the topo parameterization is not virtual; it is withheld from being passed to the ocean model until the ponds drain. The refrozen pond lids are still virtual. Extra code needed to track and enforce conservation of water has been added to ice\_itd.F90 (subroutine zap\_small\_areas), ice\_mechred.F90 (subroutine ridge\_shift), ice\_therm\_itd.F90 (subroutines linear\_itd and lateral\_melt), and ice\_therm\_vertical.F90 (subroutine thermo\_vertical), along with global diagnostics in ice\_diagnostics.F90.

### Level-ice formulation (tr\_pond\_lvl = .true.)

This meltpond parameterization represents a combination of ideas from the empirical CESM melt pond scheme and the topo approach, and is documented in [34]. The ponds evolve according to physically based process descriptions, assuming a thickness-area ratio for changes in pond volume. A novel aspect of the new scheme is that the ponds are carried as tracers on the level (undeformed) ice area of each thickness category, thus limiting their spatial extent based on the simulated sea ice topography. This limiting is meant to approximate the horizontal drainage of melt water into depressions in ice floes. (The primary difference between the level-ice and topo meltpond parameterizations lies in how sea ice topography is taken into account when determining the areal coverage of ponds.) Infiltration of the snow by melt water postpones the appearance of ponds and the subsequent acceleration of melting through albedo feedback, while snow on top of refrozen pond ice also reduces the ponds' effect on the radiation budget.

Melt pond processes, described in more detail below, include addition of liquid water from rain, melting snow and melting surface ice, drainage of pond water when its weight pushes the ice surface below sea level or when the ice interior becomes permeable, and refreezing of the pond water. If snow falls after a layer of ice has formed on the ponds, the snow may block sunlight from reaching the ponds below. When melt water forms with snow still on the ice, the water is assumed to infiltrate the snow. If there is enough water to fill the air spaces within the snowpack, then the pond becomes visible above the snow, thus decreasing the albedo and ultimately causing the snow to melt faster. The albedo also decreases as snow depth decreases, and thus a thin layer of snow remaining above a pond-saturated layer of snow will have a lower albedo than if the melt water were not present.

The level-ice formulation assumes a thickness-area ratio for *changes* in pond volume, while the CESM scheme assumes this ratio for the total pond volume. Pond volume changes are distributed as changes to the area and to the depth of the ponds using an assumed aspect ratio, or shape, given by the parameter  $\delta_p$  (pndaspect),  $\delta_p = \Delta h_p/\Delta a_p$  and  $\Delta V = \Delta h_p\Delta a_p = \delta_p\Delta a_p^2 = \Delta h_p^2/\delta_p$ . Here,  $a_p = a_{pnd}a_{lvl}$ , the mean pond area over the ice.

Given the ice velocity  $\mathbf{u}$ , conservation equations for level ice fraction  $a_{lvl}a_i$ , pond area fraction  $a_{pnd}a_{lvl}a_i$ , pond volume  $h_{pnd}a_{pnd}a_{lvl}a_i$  and pond ice volume  $h_{ipnd}a_{pnd}a_{lvl}a_i$  are

$$\frac{\partial}{\partial t}(a_{lvl}a_i) + \nabla \cdot (a_{lvl}a_i\mathbf{u}) = 0, \tag{70}$$

$$\frac{\partial}{\partial t}(a_{pnd}a_{lvl}a_i) + \nabla \cdot (a_{pnd}a_{lvl}a_i\mathbf{u}) = 0, \tag{71}$$

$$\frac{\partial}{\partial t}(h_{pnd}a_{pnd}a_{lvl}a_i) + \nabla \cdot (h_{pnd}a_{pnd}a_{lvl}a_i\mathbf{u}) = 0, \tag{72}$$

$$\frac{\partial}{\partial t}(h_{ipnd}a_{pnd}a_{lvl}a_i) + \nabla \cdot (h_{ipnd}a_{pnd}a_{lvl}a_i\mathbf{u}) = 0.$$
 (73)

(We have dropped the category subscript here, for clarity.) Equations (72) and (73) express conservation of melt pond volume and pond ice volume, but in this form highlight that the quantities tracked in the code are the tracers  $h_{pnd}$  and  $h_{ipnd}$ , pond depth and pond ice thickness. Likewise, the level ice fraction  $a_{lvl}$  is a tracer on ice area fraction (Eq. 70), and pond fraction  $a_{pnd}$  is a tracer on level ice (Eq. 71).

*Pond ice.* The ponds are assumed to be well mixed fresh water, and therefore their temperature is  $0^{\circ}$ C. If the air temperature is cold enough, a layer of clear ice may form on top of the ponds. There are currently three options in the code for refreezing the pond ice. Only option A tracks the thickness of the lid ice using the tracer  $h_{ipnd}$  and includes the radiative effect of snow on top of the lid.

A. The frzpnd = 'hlid' option uses a Stefan approximation for growth of fresh ice and is invoked only when  $\Delta V_{melt}=0$ .

The basic thermodynamic equation governing ice growth is

$$\rho_i L \frac{\partial h_i}{\partial t} = k_i \frac{\partial T_i}{\partial z} \sim k_i \frac{\Delta T}{h_i}$$

assuming a linear temperature profile through the ice thickness  $h_i$ . In discrete form, the solution is

$$\Delta h_i = \begin{cases} \sqrt{\beta \Delta t} / 2 & \text{if } h_i = 0\\ \beta \Delta t / 2 h_i & \text{if } h_i > 0, \end{cases}$$

where

$$\beta = \frac{2k_i \Delta T}{\rho_i L}.$$

When  $\Delta V_{melt} > 0$ , any existing pond ice may also melt. In this case,

$$\Delta h_i = -\min\left(\frac{\max(F_\circ, 0)\Delta t}{\rho_i L}, h_i\right),\tag{74}$$

where  $F_{\circ}$  is the net downward surface flux.

In either case, the change in pond volume associated with growth or melt of pond ice is

$$\Delta V_{frz} = -\Delta h_i a_{pnd} a_{lvl} a_i \rho_i / \rho_0,$$

where  $\rho_0$  is the density of fresh water.

B. The frzpnd = 'cesm' option uses the same empirical function as in the CESM melt pond parameterization.

Radiative effects. Freshwater ice that has formed on top of a melt pond is assumed to be perfectly clear. Snow may accumulate on top of the pond ice, however, shading the pond and ice below. The depth of the snow on the pond ice is initialized as  $h_{ps}^0 = F_{snow} \Delta t$  at the first snowfall after the pond ice forms. From that time until either the pond ice or the pond snow disappears, the pond snow depth tracks the depth of snow on sea ice  $(h_s)$  using a constant difference  $\Delta$ . As  $h_s$  melts,  $h_{ps} = h_s - \Delta$  will be reduced to zero eventually, at which time the pond ice is fully uncovered and shortwave radiation passes through.

To prevent a sudden change in the shortwave reaching the sea ice (which can prevent the thermodynamics from converging), thin layers of snow on pond ice are assumed to be patchy, thus allowing the shortwave flux to increase gradually as the layer thins. This is done using the same parameterization for patchy snow as is used elsewhere in CICE, but with its own parameter  $h_{s1}$ :

$$a_{mnd}^{eff} = (1 - \min(h_{ps}/h_{s1}, 1)) a_{pnd} a_{lvl}.$$

If any of the pond ice melts, the radiative flux allowed to pass through the ice is reduced by the (roughly) equivalent flux required to melt that ice. This is accomplished (approximately) with  $a_{pnd}^{eff} = (1 - f_{frac})a_{pnd}a_{lvl}$ , where (see Eq. 74)

$$f_{frac} = \min\left(-\frac{\rho_i L \Delta h_i}{F_o \Delta t}, 1\right).$$

Snow infiltration by pond water. If there is snow on top of the sea ice, melt water may infiltrate the snow. It is a "virtual process" that affects the model's thermodynamics through the input parameters of the radiation scheme; it does not melt the snow or affect the snow heat content.

A snow pack is considered saturated when its percentage of liquid water content is greater or equal to 15% (Sturm and others, 2009). We assume that if the volume fraction of retained melt water to total liquid content

$$r_p = \frac{V_p}{V_p + V_s \rho_s / \rho_0} < 0.15,$$

then effectively there are no meltponds present, that is,  $a_{pnd}^{eff} = h_{pnd}^{eff} = 0$ . Otherwise, we assume that the snowpack is saturated with liquid water.

We assume that all of the liquid water accumulates at the base of the snow pack and would eventually melt the surrounding snow. Two configurations are therefore possible, (1) the top of the liquid lies below the snow surface and (2) the liquid water volume overtops the snow, and all of the snow is assumed to have melted into the pond. The volume of void space within the snow that can be filled with liquid melt water is

$$V_{mx} = h_{mx}a_p = \left(\frac{\rho_0 - \rho_s}{\rho_0}\right)h_s a_p,$$

and we compare  $V_p$  with  $V_{mx}$ .

Case 1: For  $V_p < V_{mx}$ , we define  $V_p^{eff}$  to be the volume of void space filled by the volume  $V_p$  of melt water:  $\rho_0 V_p = (\rho_0 - \rho_s) V_p^{eff}$ , or in terms of depths,

$$h_p^{eff} = \left(\frac{\rho_0}{\rho_0 - \rho_s}\right) h_{pnd}.$$

The liquid water under the snow layer is not visible and therefore the ponds themselves have no direct impact on the radiation ( $a_{pnd}^{eff}=h_{pnd}^{eff}=0$ ), but the effective snow thickness used for the radiation scheme is reduced to

$$h_s^{eff} = h_s - h_p^{eff} a_p = h_s - \frac{\rho_0}{\rho_0 - \rho_s} h_{pnd} a_p.$$

Here, the factor  $a_p = a_{pnd}a_{lvl}$  averages the reduced snow depth over the ponds with the full snow depth over the remainder of the ice; that is,  $h_s^{eff} = h_s(1 - a_p) + (h_s - h_p^{eff})a_p$ .

Case 2: Similarly, for  $V_p \ge V_{mx}$ , the total mass in the liquid is  $\rho_0 V_p + \rho_s V_s = \rho_0 V_p^{eff}$ , or

$$h_p^{eff} = \frac{\rho_0 h_{pnd} + \rho_s h_s}{\rho_0}.$$

Thus the effective depth of the pond is the depth of the whole slush layer  $h_p^{eff}$ . In this case,  $a_{pnd}^{eff} = a_{pnd}a_{lvl}$ .

Drainage. A portion 1-r of the available melt water drains immediately into the ocean. Once the volume changes described above have been applied and the resulting pond area and depth calculated, the pond depth may be further reduced if the top surface of the ice would be below sea level or if the sea ice becomes permeable.

We require that the sea ice surface remain at or above sea level. If the weight of the pond water would push the mean ice—snow interface of a thickness category below sea level, some or all of the pond water is removed to bring the interface back to sea level via Archimedes' Principle written in terms of the draft d,

$$\rho_i h_i + \rho_s h_s + \rho_0 h_p = \rho_w d \le \rho_w h_i.$$

There is a separate freeboard calculation in the thermodynamics which considers only the ice and snow and converts flooded snow to sea ice. Because the current melt ponds are "virtual" in the sense that they only have a radiative influence, we do not allow the pond mass to change the sea ice and snow masses at this time, although this issue may need to be reconsidered in the future, especially for the Antarctic.

The mushy thermodynamics scheme (ktherm = 2) handles flushing. For ktherm  $\neq$  2, the permeability of the sea ice is calculated using the internal ice temperatures  $T_i$  (computed from the enthalpies as in the sea ice thermodynamics). The brine salinity and liquid fraction are given by [51, eq 3.6]  $S_{br} = 1/(10^{-3} - 0.054/T_i)$  and  $\phi = S/S_{br}$ , where S is the bulk salinity of the combined ice and brine. The ice is considered permeable if  $\phi \geq 0.05$  with a permeability of  $p = 3 \times 10^{-8} \min(\phi^3)$  (the minimum being taken over all of the ice layers). A hydraulic pressure head is computed as  $P = g\rho_w \Delta h$  where  $\Delta h$  is the height of the pond and sea ice above sea level. Then the volume of water drained is given by

$$\Delta V_{perm} = -a_i d_p \min\left(h_{pnd}, \frac{pP\Delta t}{\mu h_i}\right),\,$$

where  $d_p$  is a scaling factor (dpscale), and  $\mu = 1.79 \times 10^{-3} \text{ kg m}^{-1} \text{ s}^{-1}$  is the dynamic viscosity.

Conservation elsewhere. When ice ridges and when new ice forms in open water, the level ice area changes and ponds must be handled appropriately. For example, when sea ice deforms, some of the level ice is transformed into ridged ice. We assume that pond water (and ice) on the portion of level ice that ridges is lost to the ocean. All of the tracer volumes are altered at this point in the code, even though  $h_{pnd}$  and  $h_{ipnd}$  should not change; compensating factors in the tracer volumes cancel out (subroutine  $ridge\_shift$  in ice\_mechred.F90).

When new ice forms in open water, level ice is added to the existing sea ice, but the new level ice does not yet have ponds on top of it. Therefore the fractional coverage of ponds on level ice decreases (thicknesses are unchanged). This is accomplished in **ice\_therm\_itd.F90** (subroutine *add\_new\_ice*) by maintaining the same mean pond area in a grid cell after the addition of new ice,

$$a'_{pnd}(a_{lvl} + \Delta a_{lvl})(a_i + \Delta a_i) = a_{pnd}a_{lvl}a_i,$$

and solving for the new pond area tracer  $a'_{pnd}$  given the newly formed ice area  $\Delta a_i = \Delta a_{lvl}$ .

### 3.6.2 Thermodynamic surface forcing balance

The net energy flux from the atmosphere to the ice (with all fluxes defined as positive downward) is

$$F_0 = F_s + F_l + F_{L\downarrow} + F_{L\uparrow} + (1 - \alpha)(1 - i_0)F_{sw},$$

where  $F_s$  is the sensible heat flux,  $F_l$  is the latent heat flux,  $F_{L\downarrow}$  is the incoming longwave flux,  $F_{L\uparrow}$  is the outgoing longwave flux,  $F_{sw}$  is the incoming shortwave flux,  $\alpha$  is the shortwave albedo, and  $i_0$  is the fraction of absorbed shortwave flux that penetrates into the ice. The albedo may be altered by the presence of melt ponds. Each of the explicit melt pond parameterizations (CESM, topo and level-ice ponds) should be used in conjunction with the Delta-Eddington shortwave scheme, described below.

Shortwave radiation: Delta-Eddington

Two methods for computing albedo and shortwave fluxes are available, the default ("ccsm3") method, described below, and a multiple scattering radiative transfer scheme that uses a Delta-Eddington approach.

Model components

"Inherent" optical properties (IOPs) for snow and sea ice, such as extinction coefficient and single scattering albedo, are prescribed based on physical measurements; reflected, absorbed and transmitted shortwave radiation ("apparent" optical properties) are then computed for each snow and ice layer in a self-consistent manner. Absorptive effects of inclusions in the ice/snow matrix such as dust and algae can also be included, along with radiative treatment of melt ponds and other changes in physical properties, for example granularization associated with snow aging. The Delta-Eddington formulation is described in detail in [9]. Since publication of this technical paper, a number of improvements have been made to the Delta-Eddington scheme, including a surface scattering layer and internal shortwave absorption for snow, generalization for multiple snow layers and more than four layers of ice, and updated IOP values.

The namelist parameters R\_ice and R\_pnd adjust the albedo of bare or ponded ice by the product of the namelist value and one standard deviation. For example, if R\_ice = 0.1, the albedo increases by  $0.1\sigma$ . Similarly, setting R\_snw = 0.1 decreases the snow grain radius by  $0.1\sigma$  (thus increasing the albedo). Two additional tuning parameters are available for this scheme, dT\_mlt and rsnw\_mlt. dT\_mlt is the temperature change needed for a change in snow grain radius from non-melting to melting, and rsnw\_mlt is the maximum snow grain radius when melting. See [9] for details; the CESM melt pond and Delta-Eddington parameterizations are further explained and validated in [28].

Shortwave radiation: CCSM3

In the parameterization used in the previous version of the Community Climate System Model (CCSM3), the albedo depends on the temperature and thickness of ice and snow and on the spectral distribution of the incoming solar radiation. Albedo parameters have been chosen to fit observations from the SHEBA field experiment. For  $T_{sf} < -1^{\circ}\mathrm{C}$  and  $h_i > \mathrm{ahmax}$ , the bare ice albedo is 0.78 for visible wavelengths ( $< 700\,\mathrm{nm}$ ) and 0.36 for near IR wavelengths ( $> 700\,\mathrm{nm}$ ). As  $h_i$  decreases from  $\mathrm{ahmax}$  to zero, the ice albedo decreases smoothly (using an arctangent function) to the ocean albedo, 0.06. The ice albedo in both spectral bands decreases by 0.075 as  $T_{sf}$  rises from  $-1^{\circ}\mathrm{C}$  to  $0^{\circ}\mathrm{C}$ . The albedo of cold snow ( $T_{sf} < -1^{\circ}\mathrm{C}$ ) is 0.98 for visible wavelengths and 0.70 for near IR wavelengths. The visible snow albedo decreases by 0.10 and the near IR albedo by 0.15 as  $T_{sf}$  increases from  $-1^{\circ}\mathrm{C}$  to  $0^{\circ}\mathrm{C}$ . The total albedo is an area-weighted average of the ice and snow albedos, where the fractional snow-covered area is

$$f_{snow} = \frac{h_s}{h_s + h_{snowpatch}},$$

and  $h_{snowpatch} = 0.02$  m. The envelope of albedo values is shown in Figure 7. This albedo formulation incorporates the effects of melt ponds implicitly; the explicit melt pond parameterization is not used in this case.

The net absorbed shortwave flux is  $F_{swabs} = \sum (1-\alpha_j)F_{sw\downarrow}$ , where the summation is over four radiative categories (direct and diffuse visible, direct and diffuse near infrared). The flux penetrating into the ice is  $I_0 = i_0 \, F_{swabs}$ , where  $i_0 = 0.70 \, (1-f_{snow})$  for visible radiation and  $i_0 = 0$  for near IR. Radiation penetrating into the ice is attenuated according to Beer's Law:

$$I(z) = I_0 \exp(-\kappa_i z),$$

where I(z) is the shortwave flux that reaches depth z beneath the surface without being absorbed, and  $\kappa_i$  is the bulk extinction coefficient for solar radiation in ice, set to  $1.4~\mathrm{m}^{-1}$  for visible wavelengths [15]. A fraction  $\exp(-\kappa_i h_i)$  of the penetrating solar radiation passes through the ice to the ocean  $(F_{swl})$ .

Longwave radiation, turbulent fluxes

While incoming shortwave and longwave radiation are obtained from the atmosphere, outgoing longwave radiation and the turbulent heat fluxes are derived quantities. Outgoing longwave takes the standard blackbody form,  $F_{L\uparrow} = \epsilon \sigma \left(T_{sf}^K\right)^4$ , where  $\epsilon = 0.95$  is the emissivity of snow or ice,  $\sigma$  is the Stefan-Boltzmann constant and  $T_{sf}^K$  is the surface temperature in Kelvin. (The longwave fluxes are partitioned such




Figure 7: Albedo as a function of ice thickness and temperature, for the two extrema in snow depth, for the default (CCSM3) shortwave option. Maximum snow depth is computed based on Archimedes' Principle for the given ice thickness. These curves represent the envelope of possible albedo values.

that  $\epsilon F_{L\downarrow}$  is absorbed at the surface, the remaining  $(1 - \epsilon) F_{L\downarrow}$  being returned to the atmosphere via  $F_{L\uparrow}$ .) The sensible heat flux is proportional to the difference between air potential temperature and the surface temperature of the snow or snow-free ice,

$$F_s = C_s \left( \Theta_a - T_{sf}^K \right).$$

 $C_s$  and  $C_l$  (below) are nonlinear turbulent heat transfer coefficients described in Section 2.1. Similarly, the latent heat flux is proportional to the difference between  $Q_a$  and the surface saturation specific humidity  $Q_{sf}$ :

$$F_l = C_l (Q_a - Q_{sf}),$$
  

$$Q_{sf} = (q_1/\rho_a) \exp(-q_2/T_{sf}^K),$$

where  $q_1=1.16378\times 10^7\,{\rm kg/m^3},\,q_2=5897.8\,{\rm K},\,T_{sf}^K$  is the surface temperature in Kelvin, and  $\rho_a$  is the surface air density.

The net downward heat flux from the ice to the ocean is given by [47]:

$$F_{bot} = -\rho_w c_w c_h u_* (T_w - T_f), \tag{75}$$

where  $\rho_w$  is the density of seawater,  $c_w$  is the specific heat of seawater,  $c_h = 0.006$  is a heat transfer coefficient,  $u_* = \sqrt{|\vec{\tau}_w|/\rho_w}$  is the friction velocity, and  $T_w$  is the sea surface temperature. A minimum value of  $u_*$  is available; we recommend  $u_{*\min} = 5 \times 10^{-4}$  m/s, but the optimal value may depend on the ocean forcing used and can be as low as 0.

 $F_{bot}$  is limited by the total amount of heat available from the ocean,  $F_{frzmlt}$ . Additional heat,  $F_{side}$ , is used to melt the ice laterally following [48] and [63].  $F_{bot}$  and the fraction of ice melting laterally are scaled so that  $F_{bot} + F_{side} \ge F_{frzmlt}$  in the case that  $F_{frzmlt} < 0$  (melting; see Section 3.6.4).

52 Model components

### 3.6.3 New temperatures

### **Zero-layer thermodynamics** (ktherm = 0)

An option for zero-layer thermodynamics [59] is available in this version of CICE by setting the namelist parameter heat\_capacity to false and changing the number of ice layers, nilyr, in ice\_domain\_size.F90 to 1. In the zero-layer case, the ice is fresh and the thermodynamic calculations are much simpler than in the other configurations, which we describe here.

# **Bitz and Lipscomb thermodynamics** (ktherm = 1)

The "BL99" thermodynamic sea ice model is based on [49] and [7], and is described more fully in [40]. The vertical salinity profile is prescribed and is unchanging in time. The snow is assumed to be fresh, and the midpoint salinity  $S_{ik}$  in each ice layer is given by

$$S_{ik} = \frac{1}{2} S_{\text{max}} \left[1 - \cos(\pi z^{\left(\frac{a}{z+b}\right)})\right],\tag{76}$$

where  $z \equiv (k-1/2)/N_i$ ,  $S_{\rm max} = 3.2$  ppt, and a = 0.407 and b = 0.573 are determined from a least-squares fit to the salinity profile observed in multiyear sea ice by [58]. This profile varies from S = 0 at the top surface (z = 0) to  $S = S_{\rm max}$  at the bottom surface (z = 1) and is similar to that used by [49]. Equation (76) is fairly accurate for ice that has drained at the top surface due to summer melting. It is not a good approximation for cold first-year ice, which has a more vertically uniform salinity because it has not yet drained. However, the effects of salinity on heat capacity are small for temperatures well below freezing, so the salinity error does not lead to significant temperature errors.

Temperature updates. Given the temperatures  $T_{sf}^m$ ,  $T_s^m$ , and  $T_{ik}^m$  at time m, we solve a set of finite-difference equations to obtain the new temperatures at time m+1. Each temperature is coupled to the temperatures of the layers immediately above and below by heat conduction terms that are treated implicitly. For example, the rate of change of  $T_{ik}$  depends on the new temperatures in layers k-1, k, and k+1. Thus we have a set of equations of the form

$$\mathbf{A}\mathbf{x} = \mathbf{b},\tag{77}$$

where A is a tridiagonal matrix, x is a column vector whose components are the unknown new temperatures, and b is another column vector. Given A and b, we can compute x with a standard tridiagonal solver.

There are four general cases: (1)  $T_{sf} < 0^{\circ}\text{C}$ , snow present; (2)  $T_{sf} = 0^{\circ}\text{C}$ , snow present; (3)  $T_{sf} < 0^{\circ}\text{C}$ , snow absent; and (4)  $T_{sf} = 0^{\circ}\text{C}$ , snow absent. For case 1 we have one equation (the top row of the matrix) for the new surface temperature,  $N_s$  equations for the new snow temperatures, and  $N_i$  equations for the new ice temperatures. For cases 2 and 4 we omit the equation for the surface temperature, which is held at  $0^{\circ}\text{C}$ , and for cases 3 and 4 we omit the snow temperature equations. Snow is considered absent if the snow depth is less than a user-specified minimum value, hs\_min. (Very thin snow layers are still transported conservatively by the transport modules; they are simply ignored by the thermodynamics.)

The rate of temperature change in the ice interior is given by [49]:

$$\rho_i c_i \frac{\partial T_i}{\partial t} = \frac{\partial}{\partial z} \left( K_i \frac{\partial T_i}{\partial z} \right) - \frac{\partial}{\partial z} [I_{pen}(z)], \tag{78}$$

where  $\rho_i=917~{\rm kg/m^3}$  is the sea ice density (assumed to be uniform),  $c_i(T,S)$  is the specific heat of sea ice,  $K_i(T,S)$  is the thermal conductivity of sea ice,  $I_{pen}$  is the flux of penetrating solar radiation at depth z, and z is the vertical coordinate, defined to be positive downward with z=0 at the top surface. If shortwave = 'default', the penetrating radiation is given by Beer's Law:

$$I_{pen}(z) = I_0 \exp(-\kappa_i z),$$

where  $I_0$  is the penetrating solar flux at the top ice surface and  $\kappa_i$  is an extinction coefficient. If shortwave = 'dEdd', then solar absorption is computed by the Delta-Eddington scheme.

The specific heat of sea ice is given to an excellent approximation by [52]

$$c_i(T,S) = c_0 + \frac{L_0 \mu S}{T^2},\tag{79}$$

where  $c_0=2106$  J/kg/deg is the specific heat of fresh ice at  $0^{\circ}$ C,  $L_0=3.34\times10^5$  J/kg is the latent heat of fusion of fresh ice at  $0^{\circ}$ C, and  $\mu=0.054$  deg/ppt is the (liquidus) ratio between the freezing temperature and salinity of brine.

Following [73] and [49], the standard thermal conductivity (conduct='MU71') is given by

$$K_i(T,S) = K_0 + \frac{\beta S}{T},\tag{80}$$

where  $K_0 = 2.03$  W/m/deg is the conductivity of fresh ice and  $\beta = 0.13$  W/m/ppt is an empirical constant. Experimental results [69] suggest that (80) may not be a good description of the thermal conductivity of sea ice. In particular, the measured conductivity does not markedly decrease as T approaches  $0^{\circ}$ C, but does decrease near the top surface (regardless of temperature).

An alternative parameterization based on the "bubbly brine" model of [54] for conductivity is available (conduct='bubbly'):

$$K_i = \frac{\rho_i}{\rho_0} \left( 2.11 - 0.011T + 0.09S/T \right), \tag{81}$$

where  $\rho_i$  and  $\rho_0=917~{\rm kg/m^3}$  are densities of sea ice and pure ice. Whereas the parameterization in (80) asymptotes to a constant conductivity of 2.03 W m<sup>-1</sup> K<sup>-1</sup> with decreasing T,  $K_i$  in (81) continues to increase with colder temperatures.

The equation for temperature changes in snow is analogous to (78), with  $\rho_s=330 \text{ kg/m}^3$ ,  $c_s=c_0$ , and  $K_s=0.30 \text{ W/m/deg}$  replacing the corresponding ice values. If shortwave = 'default', then the penetrating solar radiation is equal to zero for snow-covered ice, since most of the incoming sunlight is absorbed near the top surface. If shortwave = 'dEdd', however, then  $I_{pen}$  is nonzero in snow layers.

It is possible that more shortwave penetrates into an ice layer than is needed to completely melt the layer, or else it causes the computed temperature to be greater than the melting temperature, which until now has caused the vertical thermodynamics code to abort. A parameter frac=0.9 sets the fraction of the ice layer than can be melted through. A minimum temperature difference for absorption of radiation is also set, currently dTemp=0.02 (K). The limiting occurs in **ice\_therm\_vertical.F90**, for both the default and delta Eddington radiation schemes. If the available energy would melt through a layer, then penetrating shortwave is first reduced, possibly to zero, and if that is insufficient then the local conductivity is also reduced to bring the layer temperature just to the melting point.

We now convert (78) to finite-difference form. The resulting equations are second-order accurate in space, except possibly at material boundaries, and first-order accurate in time. Before writing the equations in full we give finite-difference expressions for some of the terms.

First consider the terms on the left-hand side of (78). We write the time derivatives as

$$\frac{\partial T}{\partial t} = \frac{T^{m+1} - T^m}{\Delta t},$$

where T is the temperature of either ice or snow and m is a time index. The specific heat of ice layer k is approximated as

$$c_{ik} = c_0 + \frac{L_0 \mu S_{ik}}{T_{ik}^m T_{ik}^{m+1}},\tag{82}$$

54 Model components

which ensures that energy is conserved during a change in temperature. This can be shown by using (79) to integrate  $c_i \, dT$  from  $T^m_{ik}$  to  $T^{m+1}_{ik}$ ; the result is  $c_{ik} (T^{m+1}_{ik} - T^m_{ik})$ , where  $c_{ik}$  is given by (82). The specific heat is a nonlinear function of  $T^{m+1}_{ik}$ , the unknown new temperature. We can retain a set of linear equations, however, by initially guessing  $T^{m+1}_{ik} = T^m_{ik}$  and then iterating the solution, updating  $T^{m+1}_{ik}$  in (82) with each iteration until the solution converges.

Next consider the first term on the right-hand side of (78). The first term describes heat diffusion and is discretized for a given ice or snow layer k as

$$\frac{\partial}{\partial z} \left( K \frac{\partial T}{\partial z} \right) = \frac{1}{\Delta h} \left[ K_k^* (T_{k-1}^{m+1} - T_k^{m+1}) - K_{k+1}^* (T_k^{m+1} - T_{k+1}^{m+1}) \right],$$

where  $\Delta h$  is the layer thickness and  $K_k$  is the effective conductivity at the upper boundary of layer k. This discretization is centered and second-order accurate in space, except at the boundaries. The flux terms on the right-hand side (RHS) are treated implicitly; i.e., they depend on the temperatures at the new time m+1. The resulting scheme is first-order accurate in time and unconditionally stable. The effective conductivity  $K^*$  at the interface of layers k-1 and k is defined as

$$K_k^* = \frac{2K_{k-1}K_k}{K_{k-1}h_k + K_k h_{k-1}},$$

which reduces to the appropriate values in the limits  $K_k \gg K_{k-1}$  (or vice versa) and  $h_k \gg h_{k-1}$  (or vice versa). The effective conductivity at the top (bottom) interface of the ice-snow column is given by  $K^* = 2K/\Delta h$ , where K and  $\Delta h$  are the thermal conductivity and thickness of the top (bottom) layer. The second term on the RHS of (78) is discretized as

$$\frac{\partial}{\partial z} \left[ I_{pen}(z) \right] = I_0 \frac{\tau_{k-1} - \tau_k}{\Delta h} = \frac{I_k}{\Delta h}$$

where  $\tau_k$  is the fraction of the penetrating solar radiation  $I_0$  that is transmitted through layer k without being absorbed.

We now construct a system of equations for the new temperatures. For  $T_{sf} < 0^{\circ} \text{C}$  we require

$$F_0 = F_{ct}, \tag{83}$$

where  $F_{ct}$  is the conductive flux from the top surface to the ice interior, and both fluxes are evaluated at time m+1. Although  $F_0$  is a nonlinear function of  $T_{sf}$ , we can make the linear approximation

$$F_0^{m+1} = F_0^* + \left(\frac{dF_0}{dT_{sf}}\right)^* (T_{sf}^{m+1} - T_{sf}^*),$$

where  $T_{sf}^*$  is the surface temperature from the most recent iteration, and  $F_0^*$  and  $(dF_0/dT_{sf})^*$  are functions of  $T_{sf}^*$ . We initialize  $T_{sf}^* = T_{sf}^m$  and update it with each iteration. Thus we can rewrite (83) as

$$F_0^* + \left(\frac{dF_0}{dT_{sf}}\right)^* (T_{sf}^{m+1} - T_{sf}^*) = K_1^* (T_{sf}^{m+1} - T_1^{m+1}),$$

Rearranging terms, we obtain

$$\left[ \left( \frac{dF_0}{dT_{sf}} \right)^* - K_1^* \right] T_{sf}^{m+1} + K_1^* T_1^{m+1} = \left( \frac{dF_0}{dT_{sf}} \right)^* T_{sf}^* - F_0^*,$$

the first equation in the set of equations (77). The temperature change in ice/snow layer k is

$$\rho_k c_k \frac{(T_k^{m+1} - T_k^m)}{\Delta t} = \frac{1}{\Delta h_k} [K_k^* (T_{k-1}^{m+1} - T_k^{m+1}) - K_{k+1} (T_k^{m+1} - T_{k+1}^{m+1})], \tag{84}$$

where  $T_0 = T_{sf}$  in the equation for layer 1. In tridiagonal matrix form, (84) becomes

$$-\eta_k K_k T_{k-1}^{m+1} + \left[1 + \eta_k (K_k + K_{k+1})\right] T_k^{m+1} - \eta_k K_{k+1} T_{k+1}^{m+1} = T_k^m + \eta_k I_k, \tag{85}$$

where  $\eta_k = \Delta t/(\rho_k c_k \Delta h_k)$ . In the equation for the bottom ice layer, the temperature at the ice-ocean interface is held fixed at  $T_f$ , the freezing temperature of the mixed layer; thus the last term on the LHS is known and is moved to the RHS. If  $T_{sf} = 0$ °C, then there is no surface flux equation. In this case the first equation in (77) is similar to (85), but with the first term on the LHS moved to the RHS.

These equations are modified if  $T_{sf}$  and  $F_{ct}$  are computed within the atmospheric model and passed to CICE (calc\_Tsfc = false; see Section 2). In this case there is no surface flux equation. The top layer temperature is computed by an equation similar to (85) but with the first term on the LHS replaced by  $\eta_1 F_{ct}$  and moved to the RHS. The main drawback of treating the surface temperature and fluxes explicitly is that the solution scheme is no longer unconditionally stable. Instead, the effective conductivity in the top layer must satisfy a diffusive CFL condition:

$$K^* \le \frac{\rho ch}{\Delta t}$$
.

For thin layers and typical coupling intervals ( $\sim 1$  hr),  $K^*$  may need to be limited before being passed to the atmosphere via the coupler. Otherwise, the fluxes that are returned to CICE may result in oscillating, highly inaccurate temperatures. The effect of limiting is to treat the ice as a poor heat conductor. As a result, winter growth rates are reduced, and the ice is likely to be too thin (other things being equal). The values of hs\_min and  $\Delta t$  must therefore be chosen with care. If hs\_min is too small, frequent limiting is required, but if hs\_min is too large, snow will be ignored when its thermodynamic effects are significant. Likewise, infrequent coupling requires more limiting, whereas frequent coupling is computationally expensive.

This completes the specification of the matrix equations for the four cases. We compute the new temperatures using a tridiagonal solver. After each iteration we check to see whether the following conditions hold:

- 1.  $T_{sf} \leq 0^{\circ} \text{C}$ .
- 2. The change in  $T_{sf}$  since the previous iteration is less than a prescribed limit,  $\Delta T_{\rm max}$ .
- 3.  $F_0 \ge F_{ct}$ . (If  $F_0 < F_{ct}$ , ice would be growing at the top surface, which is not allowed.)
- 4. The rate at which energy is added to the ice by the external fluxes equals the rate at which the internal ice energy is changing, to within a prescribed limit  $\Delta F_{\text{max}}$ .

We also check the convergence rate of  $T_{sf}$ . If  $T_{sf}$  is oscillating and failing to converge, we average temperatures from successive iterations to improve convergence. When all these conditions are satisfied—usually within two to four iterations for  $\Delta T_{\rm max} \approx 0.01 \, ^{\circ}{\rm C}$  and  $\Delta F_{max} \approx 0.01 \, ^{\circ}{\rm M/m^2}$ —the calculation is complete.

*Enthalpy*. To compute growth and melt rates (Section 3.6.4), we derive expressions for the enthalpy q. The enthalpy of snow (or fresh ice) is given by

$$q_s(T) = -\rho_s(-c_0T + L_0).$$

Sea ice enthalpy is more complex, because of brine pockets whose salinity varies inversely with temperature. Since the salinity is prescribed, there is a one-to-one relationship between temperature and enthalpy. The specific heat of sea ice, given by (79), includes not only the energy needed to warm or cool ice, but also the energy used to freeze or melt ice adjacent to brine pockets. Equation (79) can be integrated to give the energy  $\delta_e$  required to raise the temperature of a unit mass of sea ice of salinity S from T to T':

$$\delta_e(T, T') = c_0(T' - T) + L_0 \mu S\left(\frac{1}{T} - \frac{1}{T'}\right).$$

Model components

If we let  $T' = T_m \equiv -\mu S$ , the temperature at which the ice is completely melted, we have

$$\delta_e(T, T_m) = c_0(T_m - T) + L_0\left(1 - \frac{T_m}{T}\right).$$

Multiplying by  $\rho_i$  to change the units from J/kg to J/m<sup>3</sup> and adding a term for the energy needed to raise the meltwater temperature to 0°C, we obtain the sea ice enthalpy:

$$q_i(T,S) = -\rho_i \left[ c_0(T_m - T) + L_0 \left( 1 - \frac{T_m}{T} \right) - c_w T_m. \right]$$
 (86)

Note that (86) is a quadratic equation in T. Given the layer enthalpies we can compute the temperatures using the quadratic formula:

$$T = \frac{-b - \sqrt{b^2 - 4ac}}{2a},$$

where

$$a = c_0,$$
  
 $b = (c_w - c_0) T_m - \frac{q_i}{\rho_i} - L_0,$   
 $c = L_0 T_m.$ 

The other root is unphysical.

### Mushy thermodynamics (ktherm = 2)

The "mushy" thermodynamics option treats the sea ice as a mushy layer [18] in which the ice is assumed to be composed of microscopic brine inclusions surrounded by a matrix of pure water ice. Both enthalpy and salinity are prognostic variables. The size of the brine inclusions is assumed to be much smaller than the size of the ice layers, allowing a continuum approximation: a bulk sea-ice quantity is taken to be the liquid-fraction-weighted average of that quantity in the ice and in the brine.

Enthalpy and mushy physics. The mush enthalpy, q, is related to the temperature, T, and the brine volume,  $\phi$ , by

$$q = \phi q_{br} + (1 - \phi)q_i$$
  
=  $\phi \rho_w c_w T + (1 - \phi)(\rho_i c_i T - \rho_i L_0)$  (87)

where  $q_{br}$  is the brine enthalpy,  $q_i$  is the pure ice enthalpy,  $\rho_i$  and  $c_i$  are density and heat capacity of the ice,  $\rho_w$  and  $c_w$  are density and heat capacity of the brine and  $L_0$  is the latent heat of melting of pure ice. We assume that the specific heats of the ice and brine are fixed at the values of cp\_ice and cp\_ocn, respectively. The enthalpy is the energy required to raise the temperature of the sea ice to 0°C, including both sensible and latent heat changes. Since the sea ice contains salt, it usually will be fully melted at a temperature below 0°C. Equations (86) and (87) are equivalent except for the density used in the term representing the energy required to bring the melt water temperature to 0°C ( $\rho_i$  and  $\rho_w$  in equations (86) and (87), respectively).

The liquid fraction,  $\phi$ , of sea ice is given by

$$\phi = \frac{S}{S_{br}}$$

where the brine salinity,  $S_{br}$ , is given by the liquidus relation using the ice temperature.

Within the parameterizations of brine drainage the brine density is a function of brine salinity [51]:

$$\rho(S_{br}) = 1000.3 + 0.78237S_{br} + 2.8008 \times 10^{-4}S_{br}^2.$$

Outside the parameterizations of brine drainage the densities of brine and ice are fixed at the values of  $\rho_w$  and  $\rho_i$ , respectively.

The permeability of ice is computed from the liquid fraction as in [25]:

$$\Pi(\phi) = 3 \times 10^{-8} (\phi - \phi_{\Pi})$$

where  $\phi_{\Pi}$  is 0.05.

The liquidus relation used in the mushy layer module is based on observations of [5]. A piecewise linear relation can be fitted to observations of Z (the ratio of mass of salt (in g) to mass of pure water (in kg) in brine) to the melting temperature: Z = aT + b. Salinity is the mass of salt (in g) per mass of brine (in kg) so is related to Z by

$$\frac{1}{S} = \frac{1}{1000} + \frac{1}{Z}.$$

The data is well fitted with two linear regions,

$$S_{br} = \frac{(T+J_1)}{(T/1000+L_1)} l_0 + \frac{(T+J_2)}{(T/1000+L_2)} (1-l_0)$$

where

$$l_0 = \begin{cases} 1 & \text{if} \quad T \ge T_0 \\ 0 & \text{if} \quad T < T_0 \end{cases},$$

$$J_{1,2} = \frac{b_{1,2}}{a_{1,2}},$$

$$L_{1,2} = \frac{(1 + b_{1,2}/1000)}{a_{1,2}}.$$

 $T_0$  is the temperature at which the two linear regions meet. Fitting to the data,  $T_0 = -7.636$ °C,  $a_1 = -18.48 \text{ g kg}^{-1} \text{ K}^{-1}$ ,  $a_2 = -10.3085 \text{ g kg}^{-1} \text{ K}^{-1}$ ,  $b_1 = 0$  and  $b_2 = 62.4 \text{ g kg}^{-1}$ .

Two stage outer iteration. As for the BL99 thermodynamics [7] there are two qualitatively different situations that must be considered when solving for the vertical thermodynamics: the surface can be melting and at the melting temperature, or the surface can be colder than the melting temperature and not melting. In the BL99 thermodynamics these two situations were treated within the same iterative loop, but here they are dealt with separately. If at the beginning of the time step the ice surface is cold and not melting, we solve the ice temperatures assuming that this is also true at the end of the time step. Once we have solved for the new temperatures we test to see if the answer is consistent with this assumption. If the surface temperature is below the melting temperature then we have found the appropriate consistent solution. If the surface is above the melting temperature at the end of the initial solution attempt, we recalculate the new temperatures assuming the surface temperature is fixed at the melting temperature. Alternatively if the surface is at the melting temperature at the start of a time step, we assume initially that this is also the case at the end of the time step, solve for the new temperatures and then check that the surface conductive heat flux is less than the surface atmospheric heat flux as is required for a melting surface. If this is not the case, the temperatures are recalculated assuming the surface is colder than melting. We have found that solutions of the temperature equations that only treat one of the two qualitatively different solutions at a time are more numerically robust than if both are solved together. The surface state rarely changes qualitatively during the solution so the method is also numerically efficient.

Temperature updates. During the calculation of the new temperatures and salinities, the liquid fraction is held fixed at the value from the previous time step. Updating the liquid fraction during the Picard iteration described below was found to be numerically unstable. Keeping the liquid fraction fixed drastically improves the numerical stability of the method without significantly changing the solution.

Temperatures are calculated in a similar way to BL99 with an outer Picard iteration of an inner tridiagonal matrix solve. The conservation equation for the internal ice temperatures is

$$\frac{\partial q}{\partial t} = \frac{\partial}{\partial z} \left( K \frac{\partial T}{\partial z} \right) + w \frac{\partial q_{br}}{\partial z} + F$$

where q is the sea ice enthalpy, K is the bulk thermal conductivity of the ice, w is the vertical Darcy velocity of the brine,  $q_{br}$  is the brine enthalpy and F is the internally absorbed shortwave radiation. The first term on the right represents heat conduction and the second term represents the vertical advection of heat by gravity drainage and flushing.

The conductivity of the mush is given by

$$K = \phi K_{br} + (1 - \phi)K_i$$

where  $K_i = 2.3 \text{ W m}^{-1} \text{ K}^{-1}$  is the conductivity of pure ice and  $K_{br} = 0.5375 \text{ W m}^{-1} \text{ K}^{-1}$  is the conductivity of the brine. The thermal conductivity of brine is a function of temperature and salinity, but here we take it as a constant value for the middle of the temperature range experienced by sea ice,  $-10^{\circ}\text{C}$  [60], assuming the brine liquidus salinity at  $-10^{\circ}\text{C}$ .

We discretize the terms that include temperature in the heat conservation equation as

$$\frac{q_k^t - q_k^{t_0}}{\Delta t} = \frac{\frac{K_{k+1}^*}{\Delta z_{k+1}'} (T_{k+1}^t - T_k^t) - \frac{K_k^*}{\Delta z_k'} (T_k^t - T_{k-1}^t)}{\Delta h}$$
(88)

where the superscript signifies whether the quantity is evaluated at the start  $(t_0)$  or the end (t) of the time step and the subscript indicates the vertical layer. Writing out the temperature dependence of the enthalpy term we have

$$\frac{\left(\phi(c_w\rho_w - c_i\rho_i) + c_w\rho_w\right)T_k^t - (1 - \phi)\rho_iL - q_k^{t_0}}{\Delta t} = \frac{\frac{K_{k+1}^*}{\Delta z_{k+1}'}(T_{k+1}^t - T_k^t) - \frac{K_k^*}{\Delta z_k'}(T_k^t - T_{k-1}^t)}{\Delta h}$$

The mush thermal conductivities are fixed at the start of the timestep. For the lowest ice layer  $T_{k+1}$  is replaced with  $T_{bot}$ , the temperature of the ice base.  $\Delta h$  is the layer thickness and  $z'_k$  is the distance between the k-1 and k layer centers.

Similarly, for the snow layer temperatures we have the following discretized equation:

$$\frac{c_i \rho_s T_k^t - \rho_s L_0 - q_k^{t_0}}{\Delta t} = \frac{\frac{K_{k+1}^*}{\Delta z_{k+1}'} (T_{k+1}^t - T_k^t) - \frac{K_k^*}{\Delta z_k'} (T_k^t - T_{k-1}^t)}{\Delta h}.$$

For the upper-most layer (either ice layer or snow layer if it present)  $T_{k-1}$  is replaced with  $T_{sf}$ , the temperature of the surface.

If the surface is colder than the melting temperature then we also have to solve for the surface temperature,  $T_{sf}$ . Here we follow the methodology of BL99 described above.

These discretized temperature equations form a tridiagional matrix for the new temperatures and are solved with a standard tridiagonal solver. A Picard iteration is used to incorporate nonlinearity in the equations. The surface heat flux is a function of surface temperature and with each iteration, the surface heat flux is calculated with the new surface temperature until convergence is achieved. Convergence normally

occurs after a few iterations once the temperature changes during an iteration fall below  $5 \times 10^{-4}$  °C and the energy conservation error falls below  $0.9 \, \text{fermax}$ .

Salinity updates. Several physical processes alter the sea ice bulk salinity. New ice forms with the salinity of the sea water from which it formed. Gravity drainage reduces the bulk salinity of newly formed sea ice, while flushing of melt water through the ice also alters the salinity profile.

The salinity equation takes the form

$$\frac{\partial S}{\partial t} = w \frac{\partial S_{br}}{\partial z} + G$$

where w is a vertical Darcy velocity and G is a source term. The right-hand side depends indirectly on the bulk salinity through the liquid fraction  $(S = \phi S_{br})$ . Since  $\phi$  is fixed for the time step, we solve the salinity equation explicitly after the temperature equation is solved.

A. Gravity drainage. Sea ice initially retains all the salt present in the sea water from which it formed. Cold temperatures near the top surface of forming sea ice result in higher brine salinities there, because the brine is always at its melting temperature. This colder, saltier brine is denser than the underlying sea water and the brine undergoes convective overturning with the ocean. As the dense, cold brine drains out of the ice, it is replaced by fresher seawater, lowering the bulk salinity of the ice. Following [72], gravity drainage is assumed to occur as two simultaneously operating modes: a rapid mode operating principally near the ice base and a slow mode occurring everywhere.

*Rapid drainage* takes the form of a vertically varying upward Darcy flow. The contribution to the bulk salinity equation for the rapid mode is

$$\left. \frac{\partial S}{\partial t} \right|_{rapid} = w(z) \frac{\partial S_{br}}{\partial z}$$

where S is the bulk salinity and  $B_{br}$  is the brine salinity, specified by the liquidus relation with ice temperature. This equation is discretized using an upwind advection scheme,

$$\frac{S_k^t - S_k^{t_0}}{\Delta t} = w_k \frac{S_{brk+1} - S_{brk}}{\Delta z}.$$

The upward advective flow also carries heat, contributing a term to the heat conservation equation (88),

$$\left. \frac{\partial q}{\partial t} \right|_{rapid} = w(z) \frac{\partial q_{br}}{\partial z}$$

where  $q_{br}$  is the brine enthalpy. This term is discretized as

$$\frac{q_k^t - q_k^{t_0}}{\Delta t} \bigg|_{rapid} = w_k \frac{q_{br\,k+1} - q_{br\,k}}{\Delta z}.$$

$$w_k = \max_{j=k,n} \left( \tilde{w}_j \right)$$

where the maximum is taken over all the ice layers between layer k and the ice base.  $\tilde{w}_i$  is given by

$$\tilde{w}(z) = w\left(\frac{Ra(z) - Ra_c}{Ra(z)}\right). \tag{89}$$

where  $Ra_c$  is a critical Rayleigh number and Ra(z) is the local Rayleigh number at a particular level,

$$Ra(z) = \frac{g\Delta\rho\Pi(h-z)}{\kappa\eta}$$

where  $\Delta \rho$  is the difference in density between the brine at z and the ocean,  $\Pi$  is the minimum permeability between z and the ocean, h is the ice thickness,  $\kappa$  is the brine thermal diffusivity and  $\eta$  is the brine dynamic viscosity. Equation (89) reduces the flow rate for Rayleigh numbers below the critical Rayleigh number.

The unmodified flow rate, w, is determined from a hydraulic pressure balance argument for upward flow through the mush and returning downward flow through ice free channels:

$$w(z)\Delta x^2 = A_m \left(-\frac{\Delta P}{l} + B_m\right)$$

where

$$\frac{\Delta P}{l} = \frac{A_p B_p + A_m B_m}{A_m + A_p},$$

$$A_m = \frac{\Delta x^2}{\eta} \frac{n}{\sum_{k=1}^n \frac{1}{\Pi(k)}},$$

$$B_m = -\frac{g}{n} \sum_{k=1}^n \rho(k),$$

$$A_p = \frac{\pi a^4}{8\eta},$$

$$B_p = -\rho_p g.$$

There are three tunable parameters in the above parameterization, a, the diameter of the channel,  $\Delta x$ , the horizontal size of the mush draining through each channel, and  $Ra_c$ , the critical Rayleigh number.  $\rho_p$  is the density of brine in the channel which we take to be the density of brine in the mush at the level that the brine is draining from. l is the thickness of mush from the ice base to the top of the layer in question. We assume that  $\Delta x$  is proportional to l so that  $\Delta x = 2\beta l$ . a (a\_rapid\_mode),  $\beta$  (aspect\_rapid\_mode) and  $Ra_c$  (Ra\_c\_rapid\_mode) are all namelist parameters with default values of 0.5 mm, 1 and 10, respectively. The value  $\beta = 1$  gives a square aspect ratio for the convective flow in the mush.

The *slow drainage* mode takes the form of a simple relaxation of bulk salinity:

$$\frac{\partial S(z)}{\partial t}\Big|_{slow} = -\lambda(S(z) - S_c).$$

The decay constant,  $\lambda$ , is modeled as

$$\lambda = S^* \max \left( \frac{T_{bot} - T_{sf}}{h}, 0 \right)$$

where  $S^*$  is a tuning parameter for the drainage strength,  $T_{bot}$  is the basal ice temperature,  $T_{sf}$  is the upper surface temperature and h is the ice thickness. The bulk salinity relaxes to a value,  $S_c(z)$ , given by

$$S_c(z) = \phi_c S_{br}(z)$$

where  $S_{br}(z)$  is the brine salinity at depth z and  $\phi_c$  is a critical liquid fraction. Both  $S^*$  and  $\phi_c$  are namelist parameters, dSdt\_slow\_mode=  $1.5 \times 10^{-7} \ \mathrm{m \ s^{-1} \ K^{-1}}$  and phi\_c\_slow\_mode= 0.05.

B. Downwards flushing. Melt pond water drains through sea ice and flushes out brine, reducing the bulk salinity of the sea ice. This is modeled with the mushy physics option as a vertical Darcy flow through the ice that affects both the enthalpy and bulk salinity of the sea ice:

$$\left. \frac{\partial q}{\partial t} \right|_{flush} = w_f \frac{\partial q_{br}}{\partial z}$$

$$\left. \frac{\partial S}{\partial t} \right|_{flush} = w_f \frac{\partial S_{br}}{\partial z}$$

These equations are discretized with an upwind advection scheme. The flushing Darcy flow,  $w_f$ , is given by

$$w_f = \frac{\overline{\Pi}\rho_w g \Delta h}{h\eta},$$

where  $\overline{\Pi}$  is the harmonic mean of the ice layer permeabilities and  $\Delta h$  is the hydraulic head driving melt water through the sea ice. It is the difference in height between the top of the melt pond and sea level.

Basal boundary condition. In traditional Stefan problems the ice growth rate is calculated by determining the difference in heat flux on either side of the ice/ocean interface and equating this energy difference to the latent heat of new ice formed. Thus,

$$(1 - \phi_i)L_0\rho_i \frac{\partial h}{\partial t} = K \left. \frac{\partial T}{\partial z} \right|_i - K_w \left. \frac{\partial T}{\partial z} \right|_w \tag{90}$$

where  $(1-\phi_i)$  is the solid fraction of new ice formed and the right hand is the difference in heat flux at the ice-ocean interface between the ice side and the ocean side of the interface. However, with mushy layers there is usually no discontinuity in solid fraction across the interface, so  $\phi_i=1$  and equation (90) cannot be used explicitly. To circumvent this problem we set the interface solid fraction to be 0.15, a value that reproduces observations.  $\phi_i$  is a namelist parameter (phi\_imushy = 0.85). The basal ice temperature is set to the liquidus temperature  $T_f$  of the ocean surface salinity.

### 3.6.4 Growth and melting

Melting at the top surface is given by

$$q \, \delta h = \begin{cases} (F_0 - F_{ct}) \, \Delta t & \text{if } F_0 > F_{ct} \\ 0 & \text{otherwise} \end{cases}$$

where q is the enthalpy of the surface ice or snow layer<sup>2</sup> (recall that q < 0) and  $\delta h$  is the change in thickness. If the layer melts completely, the remaining flux is used to melt the layers beneath. Any energy left over when the ice and snow are gone is added to the ocean mixed layer. Ice cannot grow at the top surface due to conductive fluxes; however, snow-ice can form. New snowfall is added at the end of the thermodynamic time step.

Growth and melting at the bottom ice surface are governed by

$$q\,\delta h = (F_{cb} - F_{bot})\,\Delta t,\tag{91}$$

where  $F_{bot}$  is given by (75) and  $F_{cb}$  is the conductive heat flux at the bottom surface:

$$F_{cb} = \frac{K_{i,N+1}}{\Delta h_i} (T_{iN} - T_f).$$

If ice is melting at the bottom surface, q in (91) is the enthalpy of the bottom ice layer. If ice is growing, q is the enthalpy of new ice with temperature  $T_f$  and salinity  $S_{max}$  (ktherm = 1) or ocean surface salinity (ktherm = 2). This ice is added to the bottom layer.

 $<sup>^2</sup>$ The mushy thermodynamics option does not include the enthalpy associated with raising the meltwater temperature to  $0^{\circ}$ C in these calculations, unlike BL99, which does include it. This extra heat is returned to the ocean (or the atmosphere, in the case of evaporation) with the melt water.

In general, frazil ice formed in the ocean is added to the thinnest ice category. The new ice is grown in the open water area of the grid cell to a specified minimum thickness; if the open water area is nearly zero or if there is more new ice than will fit into the thinnest ice category, then the new ice is spread over the entire cell.

If the latent heat flux is negative (i.e., latent heat is transferred from the ice to the atmosphere), snow or snow-free ice sublimates at the top surface. If the latent heat flux is positive, vapor from the atmosphere is deposited at the surface as snow or ice. The thickness change of the surface layer is given by

$$(\rho L_v - q)\delta h = F_l \Delta t,$$

where  $\rho$  is the density of the surface material (snow or ice), and  $L_v = 2.501 \times 10^6 \,\mathrm{J/kg}$  is the latent heat of vaporization of liquid water at  $0^{\circ}\mathrm{C}$ . Note that  $\rho L_v$  is nearly an order of magnitude larger than typical values of q. For positive latent heat fluxes, the deposited snow or ice is assumed to have the same enthalpy as the existing surface layer.

After growth and melting, the various ice layers no longer have equal thicknesses. We therefore adjust the layer interfaces, conserving energy, so as to restore layers of equal thickness  $\Delta h_i = h_i/N_i$ . This is done by computing the overlap  $\eta_{km}$  of each new layer k with each old layer k:

$$\eta_{km} = \min(z_m, z_k) - \max(z_{m-1}, z_{k-1}),$$

where  $z_m$  and  $z_k$  are the vertical coordinates of the old and new layers, respectively. The enthalpies of the new layers are

$$q_k = \frac{1}{\Delta h_i} \sum_{m=1}^{N_i} \eta_{km} q_m.$$

Lateral melting is accomplished by multiplying the state variables by  $1-r_{side}$ , where  $r_{side}$  is the fraction of ice melted laterally [48, 63], and adjusting the ice energy and fluxes as appropriate. We assume a floe diameter of 300 m.

Snow ice formation. At the end of the time step we check whether the snow is deep enough to lie partially below the surface of the ocean (freeboard). From Archimedes' principle, the base of the snow is at sea level when

$$\rho_i h_i + \rho_s h_s = \rho_w h_i.$$

Thus the snow base lies below sea level when

$$h^* \equiv h_s - \frac{(\rho_w - \rho_i)h_i}{\rho_s} > 0.$$

In this case, for ktherm=1 (BL99) we raise the snow base to sea level by converting some snow to ice:

$$\delta h_s = \frac{-\rho_i h^*}{\rho_w},$$

$$\delta h_i = \frac{\rho_s h^*}{\rho_w}.$$

In rare cases this process can increase the ice thickness substantially. For this reason snow—ice conversions are postponed until after the remapping in thickness space (Section 3.3), which assumes that ice growth during a single time step is fairly small.

For ktherm=2 (mushy), we model the snow-ice formation process as follows: If the ice surface is below sea level then we replace some snow with the same thickness of sea ice. The thickness change chosen

is that which brings the ice surface to sea level. The new ice has a porosity of the snow, which is calculated as

$$\phi = 1 - \frac{\rho_s}{\rho_i}$$

where  $\rho_s$  is the density of snow and  $\rho_i$  is the density of fresh ice. The salinity of the brine occupying the above porosity within the new ice is taken as the sea surface salinity. Once the new ice is formed, the vertical ice and snow layers are regridded into equal thicknesses while conserving energy and salt.

# 4 Numerical implementation

CICE is written in FORTRAN90 and runs on platforms using UNIX, LINUX, and other operating systems. The code is parallelized via grid decomposition with MPI or OpenMP threads and includes some optimizations for vector architectures.

A second, "external" layer of parallelization involves message passing between CICE and the flux coupler, which may be running on different machines in a distributed system. The parallelization scheme for CICE was designed so that MPI could be used for the coupling along with MPI, OpenMP or no parallelization internally. The internal parallelization method is set at compile time with the NTASK definition in the compile script. Message passing between the ice model and the CESM flux coupler is accomplished with MPI, regardless of the type of internal parallelization used for CICE, although the ice model may be coupled to another system without using MPI.

# 4.1 Directory structure

The present code distribution includes make files, several scripts and some input files. The main directory is **cice**/, and a run directory (**rundir**/) is created upon initial execution of the script **comp\_ice**. One year of atmospheric forcing data is also available from the code distribution web site (see the **README** file for details).

cice/

README\_v5.0 basic information

bld/ makefiles

**Macros.** $\langle OS \rangle$ . $\langle SITE \rangle$ . $\langle machine \rangle$  macro definitions for the given operating system, used by **Makefile.** $\langle OS \rangle$ 

**Makefile.** $\langle OS \rangle$  primary makefile for the given operating system ( $\langle std \rangle$  works for most systems)

makedep.c perl script that determines module dependencies

comp\_ice script that sets up the run directory and compiles the code

csm\_share/ modules based on "shared" code in CESM

shr\_orb\_mod.F90 orbital parameterizations

doc/ documentation

cicedoc.pdf this document

PDF/ PDF documents of numerous publications related to CICE

drivers/ institution-specific modules

```
cice/ official driver for CICE v5.0 (LANL)
            CICE.F90 main program
            CICE.F90_debug debugging version of CICE.F90
            CICE_FinalMod.F90 routines for finishing and exiting a run
            CICE_InitMod.F90 routines for initializing a run
            CICE_RunMod.F90 main driver routines for time stepping
            ice_constants.F90 physical and numerical constants and parameters
ice.log.(OS).(SITE).(machine) sample diagnostic output files
input_templates/ input files that may be modified for other CICE configurations
      col/ column configuration files
            ice_in namelist input data (data paths depend on particular system)
      gx1/ \langle 1^{\circ} \rangle displaced pole grid files
            global_gx1.grid \langle 1^{\circ} \rangle displaced pole grid (binary)
            global_gx1.kmt \langle 1^{\circ} \rangle land mask (binary)
            ice.restart_file pointer for restart file name
            ice_in namelist input data (data paths depend on particular system)
            ice_in_v4.1 namelist input data for default CICE v4.1 configuration
            iced_gx1_v5.0 restart file used for initial condition 4 LAYER!
      gx3/ \langle 3^{\circ} \rangle displaced pole grid files
            global_gx3.grid \langle 3^{\circ} \rangle displaced pole grid (binary)
            global_gx3.kmt \langle 3^{\circ} \rangle land mask (binary)
            global_gx3.grid.nc \langle 3^{\circ} \rangle displaced pole grid (netCDF)
            global_gx3.kmt.nc \langle 3^{\circ} \rangle land mask (netCDF)
            ice.restart_file pointer for restart file name
            ice_in namelist input data (data paths depend on particular system)
            iced_gx3_v5.0 restart file used for initial condition 4 LAYER!
      convert_restarts.f90 Fortran code to convert restart files from v4.1 to v5.0 (4 ice layers)
io_binary/ binary history output modules
      ice_history_write.F90 subroutines with binary output calls
io_netcdf/ netCDF history output modules
      ice_history_write.F90 subroutines with netCDF output
io_pio/ parallel I/O history output modules
      ice_history_write.F90 subroutines with PIO output
      ice_pio.F90 subroutines specific to PIO
run_ice. (OS). (SITE). (machine) sample script for running on the given operating system
mpi/ modules that require MPI calls
```

Directory structure 65

ice\_boundary.F90 boundary conditions

ice\_broadcast.F90 routines for broadcasting data across processors

ice\_communicate.F90 routines for communicating between processors

ice\_exit.F90 aborts or exits the run

ice\_gather\_scatter.F90 gathers/scatters data to/from one processor from/to all processors

ice\_global\_reductions.F90 global sums, minvals, maxvals, etc., across processors

ice\_timers.F90 timing routines

serial/ same modules as in mpi/ but without MPI calls

**source**/ general CICE source code

ice\_aerosol.F90 handles most work associated with the aerosol tracers

ice\_age.F90 handles most work associated with the age tracer

ice\_algae.F90 skeletal layer biogeochemistry

ice\_atmo.F90 stability-based parameterization for calculation of turbulent ice-atmosphere fluxes

ice\_blocks.F90 for decomposing global domain into blocks

ice\_brine.F90 evolves the brine height tracer

ice\_calendar.F90 keeps track of what time it is

ice\_diagnostics.F90 miscellaneous diagnostic and debugging routines

ice\_distribution.F90 for distributing blocks across processors

ice\_domain.F90 decompositions, distributions and related parallel processing info

ice\_domain\_size.F90 domain and block sizes

ice\_dyn\_eap.F90 elastic-anisotropic-plastic dynamics component

ice\_dyn\_evp.F90 elastic-viscous-plastic dynamics component

ice\_dyn\_shared.F90 code shared by EVP and EAP dynamics

ice\_fileunits.F90 unit numbers for I/O

ice\_firstyear.F90 handles most work associated with the first-year ice area tracer

ice\_flux.F90 fluxes needed/produced by the model

ice\_forcing.F90 routines to read and interpolate forcing data for stand-alone ice model runs

ice\_grid.F90 grid and land masks

ice\_history.F90 initialization and accumulation of history output variables

ice\_history\_bgc.F90 history output of biogeochemistry variables

ice\_history\_mechred.F90 history output of ridging variables

ice\_history\_pond.F90 history output of melt pond variables

ice\_history\_shared.F90 code shared by all history modules

ice\_init.F90 namelist and initializations

ice\_itd.F90 utilities for managing ice thickness distribution

ice\_kinds\_mod.F90 basic definitions of reals, integers, etc.

ice\_lvl.F90 handles most work associated with the level ice area and volume tracers

ice\_mechred.F90 mechanical redistribution component (ridging)

ice\_meltpond\_cesm.F90 CESM melt pond parameterization

ice\_meltpond\_lvl.F90 level-ice melt pond parameterization

ice\_meltpond\_topo.F90 topo melt pond parameterization

ice\_ocean.F90 mixed layer ocean model

ice\_orbital.F90 orbital parameters for Delta-Eddington shortwave parameterization

ice\_read\_write.F90 utilities for reading and writing files

ice\_restart.F90 read/write core restart file

ice\_restart\_\langle tracer \rangle.F90 read/write tracer restart file

ice\_restoring.F90 basic restoring for open boundary conditions

ice\_shortwave.F90 shortwave and albedo parameterizations

ice\_spacecurve.F90 space-filling-curves distribution method

ice\_state.F90 essential arrays to describe the state of the ice

ice\_step\_mod.F90 routines for time stepping the major code components

ice\_therm\_0layer.F90 zero-layer thermodynamics of [59]

ice\_therm\_bl99.F90 multilayer thermodynamics of [7]

ice\_therm\_itd.F90 thermodynamic changes mostly related to ice thickness distribution

ice\_therm\_mushy.F90 mushy-theory thermodynamics of[72]

ice\_therm\_shared.F90 code shared by all thermodynamics parameterizations

ice\_therm\_vertical.F90 vertical growth rates and fluxes

ice\_transport\_driver.F90 driver for horizontal advection

ice\_transport\_remap.F90 horizontal advection via incremental remapping

ice\_zbgc.F90 driver for ice biogeochemistry and brine tracer motion

ice\_zbgc\_shared.F90 parameters and shared code for biogeochemistry and brine height

rundir/ execution or "run" directory created when the code is compiled using the comp\_ice script (gx3)

cice code executable

compile/ directory containing object files, etc.

grid horizontal grid file from cice/input\_templates/gx3/

ice.log.[ID] diagnostic output file

ice\_in namelist input data from cice/input\_templates/gx3/

hist/iceh.[timeID].nc output history file

kmt land mask file from cice/input\_templates/gx3/

restart/ restart directory

iced\_gx3\_v5.0 initial condition from cice/input\_templates/gx3/

ice.restart\_file restart pointer from cice/input\_templates/gx3/

run\_ice batch run script file from cice/input\_templates/




Figure 8: Grid parameters for a sample one-dimensional, 20-cell global domain decomposed into four local subdomains. Each local domain has one ghost (halo) cell on each side, and the physical portion of the local domains are labeled ilo:ihi. The parameter nx\_block is the total number of cells in the local domain, including ghost cells, and the same numbering system is applied to each of the four subdomains.

## 4.2 Grid, boundary conditions and masks

The spatial discretization is specialized for a generalized orthogonal B-grid as in [50] or [62]. The ice and snow area, volume and energy are given at the center of the cell, velocity is defined at the corners, and the internal ice stress tensor takes four different values within a grid cell; bilinear approximations are used for the stress tensor and the ice velocity across the cell, as described in [32]. This tends to avoid the grid decoupling problems associated with the B-grid. EVP is available on the C-grid through the MITgcm code distribution, http://mitgcm.org/cgi-bin/viewcvs.cgi/MITgcm/pkg/seaice.

Since ice thickness and thermodynamic variables such as temperature are given in the center of each cell, the grid cells are referred to as "T cells." We also occasionally refer to "U cells," which are centered on the northeast corner of the corresponding T cells and have velocity in the center of each. The velocity components are aligned along grid lines.

The user has several choices of grid routines: popgrid reads grid lengths and other parameters for a nonuniform grid (including tripole grids), and rectgrid creates a regular rectangular grid, including that used for the column configuration. The input files  $global\_gx3.grid$  and  $global\_gx3.kmt$  contain the  $\langle 3^{\circ} \rangle$  POP grid and land mask;  $global\_gx1.grid$  and  $global\_gx1.kmt$  contain the  $\langle 1^{\circ} \rangle$  grid and land mask. These are binary unformatted, direct access files produced on an SGI (Big Endian). If you are using an incompatible (Little Endian) architecture, choose rectangular instead of displaced\_pole in  $ice\_in$ , or follow procedures as for conejo ( $\langle OS \rangle$ . $\langle SITE \rangle$ . $\langle machine \rangle$  = Linux.LANL.conejo). There are netCDF versions of the gx3 grid files available.

### 4.2.1 Grid domains and blocks

In general, the global gridded domain is nx\_global xny\_global, while the subdomains used in the block distribution are nx\_block xny\_block. The physical portion of a subdomain is indexed as [ilo:ihi,jlo:jhi], with nghost "ghost" or "halo" cells outside the domain used for boundary conditions. These parameters are illustrated in Figure 8 in one dimension. The routines global\_scatter and global\_gather distribute information from the global domain to the local domains and back, respectively. If MPI is not being used for grid decomposition in the ice model, these routines simply adjust the indexing on the global domain to the

single, local domain index coordinates. Although we recommend that the user choose the local domains so that the global domain is evenly divided, if this is not possible then the furthest east and/or north blocks will contain nonphysical points ("padding"). These points are excluded from the computation domain and have little effect on model performance.

The user chooses a block size BLCKX×BLCKY and the number of processors NTASK in **comp\_ice**. Parameters in the *domain\_nml* namelist in **ice\_in** determine how the blocks are distributed across the processors, and how the processors are distributed across the grid domain. Recommended combinations of these parameters for best performance are given in Section 4.7. The script **comp\_in** computes the maximum number of blocks on each processor for typical Cartesian distributions, but for non-Cartesian cases MXBLCKS may need to be set in the script. The code will print this information to the log file before aborting, and the user will need to adjust MXBLCKS in **comp\_ice** and recompile. The code will also print a warning if the maximum number of blocks is too large. Although this is not fatal, it does require excess memory.

A loop at the end of routine *create\_blocks* in module **ice\_blocks.F90** will print the locations for all of the blocks on the global grid if dbug is set to be true. Likewise, a similar loop at the end of routine *create\_local\_block\_ids* in module **ice\_distribution.F90** will print the processor and local block number for each block. With this information, the grid decomposition into processors and blocks can be ascertained. The dbug flag must be manually set in the code in each case (independently of the dbug flag in **ice\_in**), as there may be hundreds or thousands of blocks to print and this information should be needed only rarely. This information is much easier to look at using a debugger such as Totalview.

# 4.2.2 Tripole grids

The tripole grid is a device for constructing a global grid with a normal south pole and southern boundary condition, which avoids placing a physical boundary or grid singularity in the Arctic Ocean. Instead of a single north pole, it has two "poles" in the north, both located on land, with a line of grid points between them. This line of points is called the "fold," and it is the "top row" of the physical grid. One pole is at the left-hand end of the top row, and the other is in the middle of the row. The grid is constructed by "folding" the top row, so that the left-hand half and the right-hand half of it coincide. Two choices for constructing the tripole grid are available. The one first introduced to CICE is called "U-fold", which means that the poles and the grid cells between them are U cells on the grid. Alternatively the poles and the cells between them can be grid T cells, making a "T-fold." Both of these options are also supported by the OPA/NEMO ocean model, which calls the U-fold an "f-fold" (because it uses the Arakawa C-grid in which U cells are on T-rows). The choice of tripole grid is given by the namelist variable ns\_boundary\_type, "tripole" for the U-fold and "tripoleT" for the T-fold grid.

In the U-fold tripole grid, the poles have U-index  $nx\_global/2$  and  $nx\_global$  on the top U-row of the physical grid, and points with U-index i and  $nx\_global - i$  are coincident. Let the fold have U-row index n on the global grid; this will also be the T-row index of the T-row to the south of the fold. There are ghost (halo) T- and U-rows to the north, beyond the fold, on the logical grid. The point with index i along the ghost T-row of index n+1 physically coincides with point  $nx\_global - i + 1$  on the T-row of index n. The ghost U-row of index n+1 physically coincides with the U-row of index n-1.

In the T-fold tripole grid, the poles have T-index 1 and and  $nx\_global/2 + 1$  on the top T-row of the physical grid, and points with T-index i and  $nx\_global - i + 2$  are coincident. Let the fold have T-row index n on the global grid. It is usual for the northernmost row of the physical domain to be a U-row, but in the case of the T-fold, the U-row of index n is "beyond" the fold; although it is not a ghost row, it is not physically independent, because it coincides with U-row n-1, and it therefore has to be treated like a ghost row. Points i on U-row n coincides with  $nx\_global - i + 1$  on U-row n-1. There are still ghost T- and U-rows n+1 to the north of U-row n. Ghost T-row n+1 coincides with T-row n-1, and ghost U-row n+1 coincides with U-row n-2.

The tripole grid thus requires two special kinds of treatment for certain rows, arranged by the haloupdate routines. First, within rows along the fold, coincident points must always have the same value. This is achieved by averaging them in pairs. Second, values for ghost rows and the "quasi-ghost" U-row on the T-fold grid are reflected copies of the coincident physical rows. Both operations involve the tripole buffer, which is used to assemble the data for the affected rows. Special treatment is also required in the scattering routine, and when computing global sums one of each pair of coincident points has to be excluded.

# 4.2.3 Bio-grid

The bio-grid is a vertical grid used for solving the brine height variable  $h_b$ . In the future, it will also be used for discretizing the vertical transport equations of biogeochemical tracers. The bio-grid is a non-dimensional vertical grid which takes the value zero at  $h_b$  and one at the ice-ocean interface. The number of grid levels is specified during compilation in **comp\_ice** by setting the variable NBGCLYR equal to an integer  $(n_b)$ .

Ice tracers and microstructural properties defined on the bio-grid are referenced in two ways: as  $\mathtt{bgrid} = n_b + 2$  points and as  $\mathtt{igrid} = n_b + 1$  points. For both  $\mathtt{bgrid}$  and  $\mathtt{igrid}$ , the first and last points reference  $h_b$  and the ice—ocean interface, respectively, and so take the values 0 and 1, respectively. For  $\mathtt{bgrid}$ , the interior points  $[2, n_b + 1]$  are spaced at  $1/n_b$  intervals beginning with  $\mathtt{bgrid}(2) = 1/(2n_b)$ . The  $\mathtt{igrid}$  interior points  $[2, n_b]$  are also equidistant with the same spacing, but physically coincide with points midway between those of  $\mathtt{bgrid}$ .

# 4.2.4 Column configuration

A column modeling capability is available. Because of the boundary conditions and other spatial assumptions in the model, this is not a single column, but a small array of columns (minimum grid size is 5x5). However, the code is set up so that only the single, central column is used (all other columns are designated as land). The column is located near Barrow (71.35N, 156.5W). Options for choosing the column configuration are given in **comp\_ice** (choose RES col) and in the namelist file, **input\_templates/col/ice\_in**. Here, istep0 and the initial conditions are set such that the run begins September 1 with no ice. The grid type is rectangular, dynamics are turned off (kdyn=0) and one processor is used.

History variables available for column output are ice and snow temperature, Tinz and Tsnz. These variables also include thickness category as a fourth dimension.

### 4.2.5 Boundary conditions

Open boundary conditions are the default in CICE; the physical domain can still be closed using the land mask. In our bipolar, displaced-pole grids, one row of grid cells along the north and south boundaries is located on land, and along east/west domain boundaries not masked by land, periodic conditions wrap the domain around the globe. CICE can be run on regional grids with open boundary conditions. Except for variables describing grid lengths, non-land halo cells along the grid edge must be filled by restoring them to specified values. The namelist variable restore\_ice turns this functionality on and off and currently uses the restoring timescale trestore (also used for restoring ocean sea surface temperature in stand-alone ice runs). This implementation is only intended to provide the "hooks" for a more sophisticated treatment; the rectangular grid option can be used to test this configuration. The 'displaced\_pole' grid option should not be used unless the regional grid contains land all along the north and south boundaries. For exact restarts using restoring, set restart\_ext = true in namelist to use the extended-grid subroutines.

Much of the infrastructure used in CICE, including the boundary routines, is adopted from POP. The boundary routines perform boundary communications among processors when MPI is in use and among blocks whenever there is more than one block per processor.

### **4.2.6** Masks

A land mask hm  $(M_h)$  is specified in the cell centers, with 0 representing land and 1 representing ocean cells. A corresponding mask uvm  $(M_u)$  for velocity and other corner quantities is given by

$$M_u(i,j) = \min\{M_h(l), l = (i,j), (i+1,j), (i,j+1), (i+1,j+1)\}.$$

The logical masks tmask and umask (which correspond to the real masks hm and uvm, respectively) are useful in conditional statements.

In addition to the land masks, two other masks are implemented in <code>evp\_prep</code> in order to reduce the dynamics component's work on a global grid. At each time step the logical masks <code>ice\_tmask</code> and <code>ice\_umask</code> are determined from the current ice extent, such that they have the value "true" wherever ice exists. They also include a border of cells around the ice pack for numerical purposes. These masks are used in the dynamics component to prevent unnecessary calculations on grid points where there is no ice. They are not used in the thermodynamics component, so that ice may form in previously ice-free cells. Like the land masks <code>hm</code> and <code>uvm</code>, the ice extent masks <code>ice\_tmask</code> and <code>ice\_umask</code> are for T cells and U cells, respectively.

Improved parallel performance may result from utilizing halo masks for boundary updates of the full ice state, incremental remapping transport, or for EVP or EAP dynamics. These options are accessed through the logical namelist flags maskhalo\_bound, maskhalo\_remap, and maskhalo\_dyn, respectively. Only the halo cells containing needed information are communicated.

Two additional masks are created for the user's convenience:  $lmask_n$  and  $lmask_s$  can be used to compute or write data only for the northern or southern hemispheres, respectively. Special constants (spval and spval\_dbl, each equal to  $10^{30}$ ) are used to indicate land points in the history files and diagnostics.

# 4.3 Initialization and coupling

The ice model's parameters and variables are initialized in several steps. Many constants and physical parameters are set in **ice\_constants.F90**. Namelist variables (Table 7), whose values can be altered at run time, are handled in *input\_data* and other initialization routines. These variables are given default values in the code, which may then be changed when the input file **ice\_in** is read. Other physical constants, numerical parameters, and variables are first set in initialization routines for each ice model component or module. Then, if the ice model is being restarted from a previous run, core variables are read and reinitialized in *restartfile*, while tracer variables needed for specific configurations are read in separate restart routines associated with each tracer or specialized parameterization. Finally, albedo and other quantities dependent on the initial ice state are set. Some of these parameters will be described in more detail in Table 7.

The restartfiles supplied with the code release include only the core variables on the default configuration, that is, with four vertical layers and the ice thickness distribution defined by kcatbound=0.

Three namelist variables control model initialization, ice\_ic, runtype, and restart, as described in Table 4. It is possible to do an initial run from a file **filename** in two ways: (1) set runtype = 'initial', restart = true and ice\_ic = **filename**, or (2) runtype = 'continue' and pointer\_file = **/restart/ice.restart\_file** where **/restart/ice.restart\_file** contains the line "./restart/filename". The first option is convenient when repeatedly starting from a given file when subsequent restart files have been written. An additional namelist option, restart\_ext specifies whether halo cells are included in the restart files. This option is useful for tripole and regional grids.

MPI is initialized in *init\_communicate* for both coupled and stand-alone MPI runs. The ice component communicates with a flux coupler or other climate components via external routines that handle the variables listed in Table 1. For stand-alone runs, routines in **ice\_forcing.F90** read and interpolate data from files, and are intended merely to provide guidance for the user to write his or her own routines. Whether the code is to be run in stand-alone or coupled mode is determined at compile time, as described below.

ice_ic	runtype/restart				
	initial/false	initial/true	continue/true (or false <sup>a</sup> )		
none	no ice	no ice <sup>b</sup>	restart using pointer_file		
default	SST/latitude dependent	SST/latitude dependent <sup>b</sup>	restart using pointer_file		
filename	no ice <sup>c</sup>	start from <b>filename</b>	restart using pointer_file		

Table 4: Ice initial state resulting from combinations of ice\_ic, runtype and restart. <sup>a</sup>If false, restart is reset to true. <sup>b</sup>restart is reset to false. <sup>c</sup>ice\_ic is reset to 'none.'

# 4.4 Choosing an appropriate time step

The time step is chosen based on stability of the transport component (both horizontal and in thickness space) and on resolution of the physical forcing. CICE allows the dynamics, advection and ridging portion of the code to be run with a shorter timestep,  $\Delta t_{dyn}$  (dt\_dyn), than the thermodynamics timestep  $\Delta t$  (dt). In this case, dt and the integer ndtd are specified, and dt\_dyn = dt/ndtd.

A conservative estimate of the horizontal transport time step bound, or CFL condition, under remapping yields

$$\Delta t_{dyn} < \frac{\min(\Delta x, \Delta y)}{2\max(u, v)}.$$

Numerical estimates for this bound for several POP grids, assuming max(u, v) = 0.5 m/s, are as follows:

grid label	N pole singularity	dimensions	$\min \sqrt{\Delta x \cdot \Delta y}$	$\max \Delta t_{dyn}$
gx3	Greenland	$100 \times 116$	$39 \times 10^3 \ \mathrm{m}$	10.8 hr
gx1	Greenland	$320 \times 384$	$18 \times 10^3 \text{ m}$	5.0 hr
p4	Canada	$900 \times 600$	$6.5 \times 10^3 \text{ m}$	1.8 hr

As discussed in section 3.4 and [43], the maximum time step in practice is usually determined by the time scale for large changes in the ice strength (which depends in part on wind strength). Using the strength parameterization of [56], as in eq. 49, limits the time step to  $\sim$ 30 minutes for the old ridging scheme (krdg\_partic=0), and to  $\sim$ 2 hours for the new scheme (krdg\_partic=1), assuming  $\Delta x = 10$  km. Practical limits may be somewhat less, depending on the strength of the atmospheric winds.

Transport in thickness space imposes a similar restraint on the time step, given by the ice growth/melt rate and the smallest range of thickness among the categories,  $\Delta t < \min(\Delta H)/2\max(f)$ , where  $\Delta H$  is the distance between category boundaries and f is the thermodynamic growth rate. For the 5-category ice thickness distribution used as the default in this distribution, this is not a stringent limitation:  $\Delta t < 19.4$  hr, assuming  $\max(f) = 40$  cm/day.

In the classic EVP or EAP approach (kdyn = 1 or 2, revised\_evp = .true.), the dynamics component is subcycled ndte (N) times per dynamics time step so that the elastic waves essentially disappear before the next time step. The subcycling time step  $(\Delta t_e)$  is thus

$$dte = dt_dyn/ndte$$
.

A second parameter,  $E_o$  (eyc), must be selected, which defines the elastic wave damping timescale T, described in Section 3.5, as eyc\*dt\_dyn. The forcing terms are not updated during the subcycling. Given the small step (dte) at which the EVP dynamics model is subcycled, the elastic parameter E is also limited by stability constraints, as discussed in [31]. Linear stability analysis for the dynamics component shows that the numerical method is stable as long as the subcycling time step  $\Delta t_e$  sufficiently resolves the damping timescale T. For the stability analysis we had to make several simplifications of the problem; hence the location of the boundary between stable and unstable regions is merely an estimate. In practice, the ratio

 $\Delta t_e$ : T:  $\Delta t$  = 1:40:120 provides both stability and acceptable efficiency for time steps ( $\Delta t$ ) on the order of 1 hour.

For the revised EVP approach (kdyn = 1, revised\_evp = .false.), the relaxation parameter arlx1i effectively sets the damping timescale in the problem, and brlx represents the effective subcycling [8]. In practice the parameters  $S_e > 0.5$  and  $\xi < 1$  are set, along with an estimate of the ice strength per unit mass, and these parameters are then calculated. [CHECK. More info? My parameters to namelist.]

Note that only T and  $\Delta t_e$  figure into the stability of the dynamics component;  $\Delta t$  does not. Although the time step may not be tightly limited by stability considerations, large time steps (e.g.,  $\Delta t = 1$  day, given daily forcing) do not produce accurate results in the dynamics component. The reasons for this error are discussed in [31]; see [35] for its practical effects. The thermodynamics component is stable for any time step, as long as the surface temperature  $T_{sfc}$  is computed internally. NEW THERMO?

# 4.5 Model output

### 4.5.1 History files

Model output data is averaged over the period(s) given by histfreq and histfreq.n, and written to binary or netCDF files prepended by history\_file in ice\_in. That is, if history\_file = 'iceh' then the filenames will have the form iceh.[timeID].nc or iceh.[timeID].da, depending on the output file format chosen in comp\_ice (set NETCDF). The netCDF history files are CF-compliant; header information for data contained in the netCDF files is displayed with the command ncdump -h filename.nc. Parallel netCDF output is available using the PIO library. With binary files, a separate header file is written with equivalent information. Standard fields are output according to settings in the icefields\_nml namelist in ice\_in. The user may add (or subtract) variables not already available in the namelist by following the instructions in section 4.8.2.

With this release, the history module has been divided into several modules based on the desired formatting and on the variables themselves. Parameters, variables and routines needed by multiple modules is in ice\_history\_shared.F90, while the primary routines for initializing and accumulating all of the history variables are in ice\_history.F90. These routines call format-specific code in the io\_binary, io\_netcdf and io\_pio directories. History variables specific to certain components or parameterizations are collected in their own history modules (ice\_history\_bgc.F90, ice\_history\_mechred.F90, ice\_history\_pond.F90).

The history modules allow output at different frequencies. Five output frequencies (1, h, d, m, y) are available simultaneously during a run. The same variable can be output at different frequencies (say daily and monthly) via its namelist flag,  $f_{-}\langle var \rangle$ , which is now a character string corresponding to histfreq or 'x' for none. (Grid variable flags are still logicals, since they are written to all files, no matter what the frequency is.) If there are no namelist flags with a given histfreq value, or if an element of histfreq is 0, then no file will be written at that frequency. The output period can be discerned from the filenames.

For example, in namelist:

```
histfreq = '1', 'h', 'd', 'm', 'y'
histfreq_n = 1, 6, 0, 1, 1
f_hi = '1'
f_hs = 'h'
f_Tsfc = 'd'
f_aice = 'm'
f_meltb = 'mh'
f_iage = 'x'
```

Here, hi will be written to a file on every timestep, hs will be written once every 6 hours, aice once a month, meltb once a month AND once every 6 hours, and Tsfc and iage will not be written.

Model output 73

From an efficiency standpoint, it is best to set unused frequencies in histfreq to 'x'. Having output at all 5 frequencies takes nearly 5 times as long as for a single frequency. If you only want monthly output, the most efficient setting is histfreq='m','x','x','x','x'. The code counts the number of desired streams (nstreams) based on histfreq.

The history variable names must be unique for netcdf, so in cases where a variable is written at more than one frequency, the variable name is appended with the frequency in files after the first one. In the example above, meltb is called meltb in the monthly file (for backward compatibility with the default configuration) and meltbh in the 6-hourly file.

Using the same frequency twice in histfreq will have unexpected consequences and currently will cause the code to abort. It is not possible at the moment to output averages once a month and also once every 3 months, for example.

If write\_ic is set to T in **ice\_in**, a snapshot of the same set of history fields at the start of the run will be written to the history directory in **iceh\_ic.[timeID].nc(da)**. Nine history variables are hard-coded for instantaneous output regardless of the averaging flag, at the frequency given by their namelist flag.

The normalized principal components of internal ice stress are computed in *principal\_stress* and written to the history file. This calculation is not necessary for the simulation; principal stresses are merely computed for diagnostic purposes and included here for the user's convenience.

Several history variables are available in two forms, a value representing an average over the sea ice fraction of the grid cell, and another that is multiplied by  $a_i$ , representing an average over the grid cell area. Our naming convention attaches the suffix " $_a$ i" to the grid-cell-mean variable names.

# 4.5.2 Diagnostic files

Like histfreq, the parameters diagfreq and diagfreq.n can be used to regulate how often output is written to a log file. The log file unit to which diagnostic output is written is set in ice\_fileunits.F90. If diag\_type = 'stdout', then it is written to standard out (or to ice.log.[ID] if you redirect standard out as in run\_ice); otherwise it is written to the file given by diag\_file. In addition to the standard diagnostic output (maximum area-averaged thickness, velocity, average albedo, total ice area, and total ice and snow volumes), the namelist options print\_points and print\_global cause additional diagnostic information to be computed and written. print\_global outputs global sums that are useful for checking global conservation of mass and energy. print\_points writes data for two specific grid points. Currently, one point is near the North Pole and the other is in the Weddell Sea; these may be changed in ice\_diagnostics.F90.

Timers are declared and initialized in **ice\_timers.F90**, and the code to be timed is wrapped with calls to *ice\_timer\_start* and *ice\_timer\_stop*. Finally, *ice\_timer\_print* writes the results to the log file. The optional "stats" argument (true/false) prints additional statistics. Calling *ice\_timer\_print\_all* prints all of the timings at once, rather than having to call each individually. Currently, the timers are set up as in Table 5. Section 4.8.1 contains instructions for adding timers.

The timings provided by these timers are not mutually exclusive. For example, the column timer (5) includes the timings from 6–10, and subroutine *bound* (timer 15) is called from many different places in the code, including the dynamics and advection routines.

The timers use MPI\_WTIME for parallel runs and the F90 intrinsic system\_clock for single-processor runs.

#### 4.5.3 Restart files

A binary unformatted file is created that contains all of the data that CICE needs for a full restart. The filename begins with the character string dumpfile, and the restart dump frequency is given by dumpfreq

Timer		
Index	Label	
1	Total	the entire run
2	Step	total minus initialization and exit
3	Dynamics	EVP
4	Advection	horizontal transport
5	Column	all vertical (column) processes
6	Thermo	vertical thermodynamics
7	Shortwave	SW radiation and albedo
8	Meltponds	melt ponds
9	Ridging	mechanical redistribution
10	Cat Conv	transport in thickness space
11	Coupling	sending/receiving coupler messages
12	ReadWrite	reading/writing files
13	Diags	diagnostics (log file)
14	History	history output
15	Bound	boundary conditions and subdomain communications
16	BGC	biogeochemistry

Table 5: CICE timers.

and dumpfreq.n. The pointer to the filename from which the restart data is to be read for a continuation run is set in pointer\_file. The code assumes that auxiliary tracer restart files will be identified using the same pointer and file name prefix, but with an additional character string in the file name that is associated with each tracer set.

Two new namelist flags provide further control of restart behavior. dump\_last = .true. causes a set of restart files to be written at the end of a run when it is otherwise not scheduled to occur. The flag use\_restart\_time enables the user to choose to use the model date provided in the restart files. If use\_restart\_time = .false. then the initial model date stamp is determined from the namelist parameters.

Routines for gathering, scattering and (unformatted) reading and writing of the "extended" global grid, including the physical domain and ghost (halo) cells around the outer edges, allow exact restarts on regional grids with open boundary conditions, and they will also simplify restarts on the various tripole grids. They are accessed by setting restart\_ext = .true. in namelist.

# 4.6 Execution procedures

To compile and execute the code: in the source directory,

- 1. Download the forcing data used for testing from the CICE website, http://climate.lanl.gov/Models/CICE/.
- 2. Create **Macros.\*** and **run\_ice.\*** files for your particular platform, if they do not already exist (type 'uname -s' at the prompt to get  $\langle OS \rangle$ ).
- 3. Alter directories in the script **comp\_ice**.
- 4. Run **comp\_ice** to set up the run directory and make the executable 'cice'.

Execution procedures 75

variable	options	description
RES	col, gx3, gx1	grid resolution
NTASK	(integer)	total number of processors
BLCKX	(integer)	number of grid cells on each block in the x-direction <sup>†</sup>
BLCKY	(integer)	number of grid cells on each block in the y-direction <sup>†</sup>
MXBLCKS	(integer)	maximum number of blocks per processor
NICELYR	(integer)	number of vertical layers in the ice
NSNWLYR	(integer)	number of vertical layers in the snow
NICECAT	(integer)	number of ice thickness categories
TRAGE	0 or 1	set to 1 for ice age tracer
TRFY	0 or 1	set to 1 for first-year ice area tracer
TRLVL	0 or 1	set to 1 for level and deformed ice tracers
TRPND	0 or 1	set to 1 for melt pond tracers
NTRAERO	(integer)	number of aerosol tracers
TRBRINE	set to 1 for brine height tracer	
NBGCLYR	(integer)	number of vertical layers for biogeochemical transport
NETCDF	yes/no/pio	use 'no' if netCDF library is unavailable, 'pio' for PIO
DITTO	yes/no	for reproducible diagnostics
THRD	yes/no	set to yes for OpenMP threaded parallelism
OMP_NUM_THREADS	(integer)	the number of OpenMP threads requested
NUMIN	(integer)	smallest unit number assigned to CICE files
NUMAX	(integer)	largest unit number assigned to CICE files

<sup>†</sup> Does not include ghost cells.

Table 6: Configuration options available in **comp\_ice**.

5. To clean the compile directory and start fresh, simply execute '/bin/rm -rf compile' from the run directory.

### In the run directory,

- 1. Alter atm\_data\_dir and ocn\_data\_dir in the namelist file ice\_in.
- 2. Alter the script **run\_ice** for your system.
- 3. Execute run\_ice.

#### If this fails, see Section 5.1.

This procedure creates the output log file **ice.log.[ID]**, and if npt is long enough compared with dumpfreq and histfreq, dump files **iced.[timeID]** and netCDF (or binary) history output files **iceh.[timeID].nc** (.da). Using the  $\langle 3^{\circ} \rangle$  grid, the log file should be similar to **ice.log.\langle OS \rangle**, provided for the user's convenience. These log files were created using MPI on 4 processors on the  $\langle 3^{\circ} \rangle$  grid.

Several options are available in **comp\_ice** for configuring the run, shown in Table 6. If NTASK = 1, then the **serial/** code is used, otherwise the code in **mpi/** is used. Loops over blocks have been threaded throughout the code, so that their work will be divided among OMP\_NUM\_THREADS if THRD is 'yes.' Note that the value of NTASK in **comp\_ice** must equal the value of nprocs in **ice\_in**. Generally the value of MXBLCKS computed by **comp\_ice** is sufficient, but sometimes it will need to be set explicitly, as discussed in Section 4.7. To conserve memory, match the tracer requests in **comp\_ice** with those in **ice\_in**. CESM

uses 3 aerosol tracers; the number given in **comp\_ice** must be less than or equal to the maximum allowed in **ice\_domain\_size.F90**.

The scripts define a number of environment variables, mostly as directories that you will need to edit for your own environment. \$SYSTEM\_USERDIR, which on machines at Oak Ridge National Laboratory points automatically to scratch space, is intended to be a disk where the run directory resides. SHRDIR is a path to the CESM shared code.

The 'reproducible' option (DITTO) makes diagnostics bit-for-bit when varying the number of processors. (The simulation results are bit-for-bit regardless, because they do not require global sums or max/mins as do the diagnostics.) This was done mainly by increasing the precision for the global reduction calculations, except for regular double-precision (r8) calculations involving MPI; MPI can not handle MPI\_REAL16 on some architectures. Instead, these cases perform sums or max/min calculations across the global block structure, so that the results are bit-for-bit as long as the block distribution is the same (the number of processors can be different).

CICE namelist variables available for changes after compile time appear in **ice.log.\*** with values read from the file **ice.in**; their definitions are given in Section 5.7. For example, to run for a different length of time, say three days, set npt = 72 in **ice.in**. At present, the user supplies the time step dt, the number of dynamics/advection/ridging subcycles ndtd, and for classic EVP, the number of EVP subcycles ndte; dte is then calculated in subroutine *init\_evp*. The primary reason for doing it this way is to ensure that ndte is an integer. (This is done differently for revised\_evp = .true.)

To restart from a previous run, set restart = .true. in ice\_in. There are two ways of restarting from a given file. The restart pointer file ice.restart\_file (created by the previous run) contains the name of the last written data file (iced.[timeID]). Alternatively, a filename can be assigned to ice\_ic in ice\_in. Consult Section 4.3 for more details. Restarts are exact for MPI or single processor runs.

### 4.7 Performance

Namelist options (*domain\_nml*) provide considerable flexibility for finding the most efficient processor and block configuration. Some of these choices are illustration in Figure 9. processor\_shape chooses between tall, thin processor domains (slenderX1 or slenderX2, often better for sea ice simulations on global grids where nearly all of the work is at the top and bottom of the grid with little to do in between) and close-to-square domains, which maximize the volume to surface ratio (and therefore on-processor computations to message passing, if there were ice in every grid cell). In cases where the number of processors is not a perfect square (4, 9, 16...), the processor\_shape namelist variable allows the user to choose how the processors are arranged. Here again, it is better in the sea ice model to have more processors in x than in y, for example, 8 processors arranged 4x2 (square-ice) rather than 2x4 (square-pop). The latter option is offered for direct-communication compatibility with POP, in which this is the default.

The distribution\_type options allow standard Cartesian distribution of blocks, redistribution via a 'rake' algorithm for improved load balancing across processors, and redistribution based on space-filling curves. There are also three additional distribution types ('roundrobin,' 'sectrobin,' 'sectcart') that improve land-block elimination rates and also allow more flexibility in the number of processors used. The rake and space-filling curve algorithms are primarily helpful when using squarish processor domains where some processors (located near the equator) would otherwise have little work to do. Processor domains need not be rectangular, however.

distribution\_wght chooses how the work-per-block estimates are weighted. The 'block' option is the default in POP, which uses a lot of array syntax requiring calculations over entire blocks (whether or not land is present), and is provided here for direct-communication compatibility with POP. The 'latitude' option weights the blocks based on latitude and the number of ocean grid cells they contain.

The rake distribution type is initialized as a standard, Cartesian distribution. Using the work-per-block

Performance 77




Figure 9: Distribution of 256 blocks across 16 processors, represented by colors, on the gx1 grid: (a) cartesian, slenderX1, (b) cartesian, slenderX2, (c) cartesian, square-ice (square-pop is equivalent here), (d) rake with block weighting, (e) rake with latitude weighting, (f) spacecurve. Each block consists of 20x24 grid cells, and white blocks consist entirely of land cells.

decomposition	cice load balance north/south	cice load balance radiation	number of neighbors	amount of data to communicate	land block elimination in decomp	flexibility wrt pe counts
1. cartesian square-pop	F	F	В	Α	F	С
2. cartesian slenderX1	Α	В	Α	С	F	F
3. cartesian slenderX2	В	С	В	В	F	F
4. spacecurve	D	D	В	В	Α	Α
5. roundrobin	Α	Α	D	D	Α	Α
6. sectrobin	В	Α	С	С	Α	Α
7. sectcart	В	Α	В	С	F	С

Figure 10: Scorecard for block distribution choices in CICE, courtesy T. Craig. For more information, see http://www.cesm.ucar.edu/events/ws.2012/Presentations/SEWG2/craig.pdf

estimates, blocks are "raked" onto neighboring processors as needed to improve load balancing characteristics among processors, first in the x direction and then in y.

Space-filling curves reduce a multi-dimensional space (2D, in our case) to one dimension. The curve is composed of a string of blocks that is snipped into sections, again based on the work per processor, and each piece is placed on a processor for optimal load balancing. This option requires that the block size be chosen such that the number of blocks in the x direction equals the number of blocks in the y direction, and that number must be factorable as  $2^n 3^m 5^p$  where n, m, p are integers. For example, a 16x16 array of blocks, each containing 20x24 grid cells, fills the gx1 grid (n = 4, m = p = 0). If either of these conditions is not met, a Cartesian distribution is used instead.

While the Cartesian distribution groups sets of blocks by processor, the 'roundrobin' distribution loops through the blocks and processors together, putting one block on each processor until the blocks are gone. This provides good load balancing but poor communication characteristics due to the number of neighbors and the amount of data needed to communicate. The 'sectrobin' and 'sectcart' algorithms loop similarly, but put groups of blocks on each processor to improve the communication characteristics. In the 'sectcart' case, the domain is divided into two (east-west) halves and the loops are done over each, sequentially. Figure 10 provides an overview of the pros and cons for the distribution types

(http://www.cesm.ucar.edu/events/ws.2012/Presentations/SEWG2/craig.pdf).

The maskhalo options in the namelist improve performance by removing unnecessary halo communications where there is no ice. There is some overhead in setting up the halo masks, which is done during the timestepping procedure as the ice area changes, but this option usually improves timings even for relatively small processor counts. T. Craig has found that performance improved by more than 20% for combinations of updated decompositions and masked haloes, in CESM's version of CICE.

The user provides the total number of processors and the block dimensions in the setup script (**comp\_ice**). When moving toward smaller, more numerous blocks, there is a point where the code becomes less efficient; blocks should not have fewer than about 20 grid cells in each direction. Squarish blocks optimize the volume-to-surface ratio for communications.

4.8 Adding things 79




Figure 11: Change in 'TimeLoop' timings from the 7-layer configuration using BL99 thermodynamics and EVP dynamics. Timings were made on a nondedicated machine, with variations of about  $\pm 3\%$  in identically configured runs (light grey). Darker grey indicates the time needed for extra required options; The Delta-Eddington radiation scheme is required for all melt pond schemes, and the level-ice pond parameterization additionally requires the level-ice tracers.

Figure 11 illustrates the computational expense of various options, relative to the total time (excluding initialization) of a 7-layer configuration using BL99 thermodynamics and EVP dynamics. Timings varied by about  $\pm 3\%$  in identically configured runs due to machine load.

Throughout the code, (i, j) loops have been combined into a single loop, often over just ocean cells or those containing sea ice. This was done to reduce unnecessary operations and to improve vector performance.

### 4.8 Adding things

#### **4.8.1** Timers

Timing any section of code, or multiple sections, consists of defining the timer and then wrapping the code with start and stop commands for that timer. Printing of the timer output is done simultaneously for all timers. To add a timer, first declare it (timer\_[tmr]) at the top of ice\_timers.F90 (we recommend doing this in both the mpi/ and serial/ directories), then add a call to get\_ice\_timer in the subroutine init\_ice\_timers. In the module containing the code to be timed, call ice\_timer\_start (timer\_[tmr]) at the beginning of the section to be timed, and a similar call to ice\_timer\_stop at the end. A use ice\_timers statement may need to be added to the subroutine being modified. Be careful not to have one command outside of a loop and the other command inside. Timers can be run for individual blocks, if desired, by including the block ID in the timer calls.

#### 4.8.2 History fields

To add a variable to be printed in the history output, search for 'example' in ice\_history\_shared.F90:

- 1. add a frequency flag for the new field
- 2. add the flag to the namelist (here and also in ice\_in)
- 3. add an index number

### and in ice\_history.F90:

- 1. broadcast the flag
- 2. add a call to define hist field
- 3. add a call to accum\_hist\_field

The example is for a standard, two-dimensional (horizontal) fields; for other array sizes, choose another history variable with a similar shape as an example. Some history variables, especially tracers, are grouped in other files according to their purpose (bgc, melt ponds, etc.).

To add an output frequency for an existing variable, see section 4.5.1.

#### 4.8.3 Tracers

Each optional tracer has its own module, **ice\_[tracer].F90**, which also contains as much of the additional tracer code as possible, and for backward compatibility of restart files, each new tracer has its own restart file. We recommend that the logical namelist variable <code>tr\_[tracer]</code> be used for all calls involving the new tracer outside of **ice\_[tracer].F90**, in case other users do not want to use that tracer.

A number of optional tracers are available in the code, including ice age, first-year ice area, melt pond area and volume, brine height, aerosols, and level ice area and volume (from which ridged ice quantities are derived). indexvolume!ice or snow Salinity, enthalpies, age, aerosols, level-ice volume, brine height and most melt pond quantities are volume-weighted tracers, while first-year area, pond area, level-ice area and all of the biogeochemistry tracers in this release are area-weighted tracers. In the absence of sources and sinks, the total mass of a volume-weighted tracer such as aerosol (kg) is conserved under transport in horizontal and thickness space (the mass in a given grid cell will change), whereas the aerosol concentration (kg/m) is unchanged following the motion, and in particular, the concentration is unchanged when there is surface or basal melting. The proper units for a volume-weighted mass tracer in the tracer array are kg/m.

In several places in the code, tracer computations must be performed on the conserved "tracer volume" rather than the tracer itself; for example, the conserved quantity is  $h_{pnd}a_{pnd}a_{lvl}a_i$ , not  $h_{pnd}$ . Conserved quantities are thus computed according to the tracer dependencies, and code must be included to account for new dependencies (e.g.,  $a_{lvl}$  and  $a_{pnd}$  in **ice\_itd.F90** and **ice\_mechred.F90**).

To add a tracer, follow these steps using one of the existing tracers as a pattern.

- 1. ice\_domain\_size.F90: increase max\_ntrcr
- 2. ice\_state.F90: declare nt\_[tracer]
- 3. ice\_[tracer].F90: create initialization, physics, restart routines
- 4. ice\_fileunits.F90: add new dump and restart file units
- 5. ice\_init.F90:
  - add new module and tr\_[tracer] to list of used modules and variables
  - add logical namelist variable tr\_[tracer]

Troubleshooting 81

- initialize namelist variable
- broadcast namelist variable
- print namelist variable to diagnostic output file
- increment number of tracers in use based on namelist input (ntrcr)
- define tracer types (trcr\_depend = 0 for ice area tracers, 1 for ice volume, 2 for snow volume)
- 6. ice\_itd.F90, ice\_mechred.F90: Account for new dependencies if needed.
- 7. **CICE\_InitMod.F90**: initialize tracer (includes reading restart file)
- 8. CICE\_RunMod.F90, ice\_step\_mod.F90:
  - call routine to write tracer restart file
  - call physics routines in ice\_[tracer].F90
- 9. ice\_history\_[tracer].F90: add history variables (Section 4.8.2)
- 10. **ice\_in**: add namelist variables to *tracer\_nml* and *icefields\_nml*
- 11. If strict conservation is necessary, add diagnostics as noted for topo ponds in Section 3.6.1.

# 5 Troubleshooting

# 5.1 Initial setup

The script **comp\_ice** is configured so that the files **grid**, **kmt**, **ice\_in**, **run\_ice**, **iced\_gx3\_v5.0** and **ice.restart\_file** are NOT overwritten after the first setup. If you wish to make changes to the original files in **input\_templates**/ rather than those in the run directory, either remove the files from the run directory before executing **comp\_ice** or edit the script.

The code may abort during the setup phase for any number of reasons, and often the buffer containing the diagnostic output fails to print before the executable exits. The quickest way to get the diagnostic information is to run the code in an interactive shell with just the command cice for serial runs or "mpirun -np N cice" for MPI runs, where N is the appropriate number of processors (or a command appropriate for your computer's software).

If the code fails to compile or run, or if the model configuration is changed, try the following:

- create **Macros.\***. **Makefile.\*** and **run\_ice.\*** files for your particular platform, if they do not already exist (type 'uname -s' at the prompt and compare the result with the file suffixes; we rename UNICOS/mp as UNICOS for simplicity).
- modify the INCLUDE directory path and other settings for your system in the scripts, **Macros.\*** and **Makefile.\*** files.
- alter directory paths, file names and the execution command as needed in run\_ice and ice\_in.
- ensure that nprocs in ice\_in is equal to NTASK in comp\_ice.
- ensure that the block size NXBLOCK, NYBLOCK in **comp\_ice** is **compatible** with the processor\_shape and other domain options in **ice\_in**

Troubleshooting

• if using the rake or space-filling curve algorithms for block distribution (distribution\_type in ice\_in) the code will abort if MXBLCKS is not large enough. The correct value is provided in the diagnostic output.

- if starting from a restart file, ensure that kcatbound is the same as that used to create the file (kcatbound = 0 for the files included in this code distribution). Other configuration parameters, such as NICECAT, must also be consistent between runs.
- for stand-alone runs, check that -Dcoupled is *not* set in the **Macros.\*** file.
- for coupled runs, check that -Dcoupled and other coupled-model-specific (e.g., CESM, popcice or hadgem) preprocessing options are set in the **Macros.**\* file.
- edit the grid size and other parameters in **comp\_ice**.
- remove the **compile**/ directory completely and recompile.

#### 5.2 Slow execution

On some architectures, underflows ( $10^{-300}$  for example) are not flushed to zero automatically. Usually a compiler flag is available to do this, but if not, try uncommenting the block of code at the end of subroutine *stress* in **ice\_dyn\_evp.F90**. You will take a hit for the extra computations, but it will not be as bad as running with the underflows.

### 5.3 Debugging hints

Several utilities are available that can be helpful when debugging the code. Not all of these will work everywhere in the code, due to possible conflicts in module dependencies.

debug\_ice (CICE.F90) A wrapper for *print\_state* that is easily called from numerous points during the timestepping loop (see CICE.F90\_debug, which can be substituted for CICE.F90).

print\_state (ice\_diagnostics.F90) Print the ice state and forcing fields for a given grid cell.

dbug = .true. (ice\_in) Print numerous diagnostic quantities.

print\_global (ice\_in) If true, compute and print numerous global sums for energy and mass balance analysis. This option can significantly degrade code efficiency.

print\_points (ice\_in) If true, print numerous diagnostic quantities for two grid cells, one near the north pole and one in the Weddell Sea. This utility also provides the local grid indices and block and processor numbers (ip, jp, iblkp, mtask) for these points, which can be used in conjunction with check\_step, to call *print\_state*. These flags are set in ice\_diagnostics.F90. This option can be fairly slow, due to gathering data from processors.

global\_minval, global\_maxval, global\_sum (ice\_global\_reductions.F90) Compute and print the minimum and maximum values for an individual real array, or its global sum.

5.4 Known bugs 83

### 5.4 Known bugs

Fluxes sent to the CESM coupler may have incorrect values in grid cells that change from an icefree state to having ice during the given time step, or vice versa, due to scaling by the ice area. The
authors of the CESM flux coupler insist on the area scaling so that the ice and land models are treated
consistently in the coupler (but note that the land area does not suddenly become zero in a grid cell,
as does the ice area).

- 2. With the old CCSM radiative scheme (shortwave = 'default'), a sizable fraction (more than 10%) of the total shortwave radiation is absorbed at the surface but should be penetrating into the ice interior instead. This is due to use of the aggregated, effective albedo rather than the bare ice albedo when snowpatch < 1.
- 3. The date-of-onset diagnostic variables, melt\_onset and frz\_onset, are not included in the restart file, and therefore may be incorrect for the current year if the run is restarted after Jan 1. Also, these variables were implemented with the Arctic in mind and may be incorrect for the Antarctic.
- 4. The single-processor *system\_clock* time may give erratic results on some architectures.
- 5. History files that contain time averaged data (hist\_avg = .true. in ice\_in) will be incorrect if restarting from midway through an averaging period.
- 6. In stand-alone runs, restarts from the end of ycycle will not be exact.
- 7. Using the same frequency twice in histfreq will have unexpected consequences and causes the code to abort.

# 5.5 Multi-dimensional output

CHECK An issue that has already arisen in the column configuration of the model is the format of the multidimensional history variables. Even though each history file includes only a single time slice or average, all netcdf history variables include the time dimension for use with external post-processing software such as NCO. When the time dimension is included for the four-dimensional variables (x, y, z, and categories; strictly speaking, time makes them 5D), the Ferret software package misinterprets the data. In order to look at these variables using Ferret, uncomment the lines indicated by the tag "ferret" in **ice\_history.F90** and comment out the lines that they replace.

### 5.6 Interpretation of albedos

The snow-and-ice albedo, albsni, and diagnostic albedos albice, albsno, and albpnd are merged over categories but not scaled (divided) by the total ice area. (This is a change from CICE v4.1 for albsni.) The latter three history variables represent completely bare or completely snow- or melt-pond-covered ice; that is, they do not take into account the snow or melt pond fraction (albsni does, as does the code itself during thermodyamic computations). This is to facilitate comparison with typical values in measurements or other albedo parameterizations. The melt pond albedo albpnd is only computed for the Delta-Eddington shortwave case.

With the Delta-Eddington parameterization, the albedo depends on the cosine of the zenith angle  $(\cos\varphi,\cos z)$  and is zero if the sun is below the horizon  $(\cos\varphi<0)$ . Therefore time-averaged albedo fields would be low if a diurnal solar cycle is used, because zero values would be included in the average for half of each 24-hour period. To rectify this, a separate counter is used for the averaging that is incremented only when  $\cos\varphi>0$ . The albedos will still be zero in the dark, polar winter hemisphere.

# 5.7 Proliferating subprocess parameterizations

With the addition of several alternative parameterizations for sea ice processes, a number of subprocesses now appear in multiple parts of the code with differing descriptions. For instance, sea ice porosity and permeability, along with the resulting flushing and flooding are calculated separately for mushy thermodynamics, topo melt ponds and level-ice melt ponds,, and for the brine height tracer, each employing its own equations. Likewise, the BL99 and mushy thermodynamics compute and freeboard and snow–ice formation differently, and the topo and level-ice melt pond schemes both allow fresh ice to grow atop melt ponds, using slightly different formulations for Stefan freezing. These various process parameterizations will be compared and their subprocess descriptions possibly unified in the future.

# **Acknowledgments and Copyright**

This work has been supported under the Department of Energy's Climate, Ocean and Sea Ice Modeling project through the Computer Hardware Applied Mathematics and Model Physics (CHAMMP) program, Climate Change Prediction Program (CCPP), Improving the Characterization of Clouds, Aerosols and the Cryosphere in Climate Models (Cloud-Cryo) program and Scientific Discovery through Advanced Computing (SCIDAC) program, with additional support from the T-3 Fluid Dynamics and Solid Mechanics Group at Los Alamos National Laboratory. Special thanks are due to the following people:

- members of the CESM Polar Climate Working Group, including David Bailey, Cecilia Bitz, Bruce Briegleb, Tony Craig, Marika Holland, John Dennis, Julie Schramm, Bonnie Light and Phil Jones,
- David Hebert and Olivier Lecomte for their melt pond work,
- Jonathan Gregory of the University of Reading and the U.K. MetOffice for supplying tripole T-fold code and documentation.
- Alison McLaren, Ann Keen and others working with the Hadley Centre GCM for testing non-standard model configurations and providing their code to us,
- Daniel Feltham and his research group for several new parameterizations and documentation,
- the many researchers who tested beta versions of CICE 5.0 and waited patiently for the official release.
- © Copyright 2013, LANS LLC. All rights reserved. Unless otherwise indicated, this information has been authored by an employee or employees of the Los Alamos National Security, LLC (LANS), operator of the Los Alamos National Laboratory under Contract No. DE-AC52-06NA25396 with the U.S. Department of Energy. The U.S. Government has rights to use, reproduce, and distribute this information. The public may copy and use this information without charge, provided that this Notice and any statement of authorship are reproduced on all copies. Neither the Government nor LANS makes any warranty, express or implied, or assumes any liability or responsibility for the use of this information. Beginning with version 4.0, the CICE code carries Los Alamos Software Release number LA-CC-06-012.

# **Table of namelist options**

variable	options/format	description	recommended value
setup_nml		Time	
days_per_year	360 <b>or</b> 365	number of days in a model year	365
use_leap_years	true/false	if true, include leap days	
year_init	уууу	the initial year, if not using restart	
istep0	integer	initial time step number	0
dt	seconds	thermodynamics time step length	3600.
npt	integer	total number of time steps to take	3000.
ndtd	integer	number of dynamics/advection/ridging	1
110.00	mogor	steps per thermo timestep	-
		Initialization/Restarting	
runtype	initial	start from ice_ic	
11 -	continue	restart using pointer_file	
ice_ic	default	latitude and sst dependent	default
	none	no ice	
	path/file	restart file name	
restart	true/false	initialize using restart file	.true.
use_restart_time	true/false	set initial date using restart file	.true.
restart_dir	path/	path to restart directory	
restart_ext	true/false	read/write halo cells in restart files	
restart_file	filename prefix	output file for restart dump	'iced'
pointer_file	pointer filename	contains restart filename	
dumpfreq	У	write restart every dumpfreq_n years	У
	m	write restart every dumpfreq_n months	_
	d	write restart every dumpfreq_n days	
dumpfreq_n	integer	frequency restart data is written	1
dump_last	true/false	if true, write restart on last time step of simulation	
		Model Output	
diagfreq	integer	frequency of diagnostic output in dt	24
	e.g., 10	once every 10 time steps	
diag_type	stdout	write diagnostic output to stdout	
	file	write diagnostic output to file	
diag_file	filename	diagnostic output file (script may reset)	
print_global	true/false	print diagnostic data, global sums	.false.
print_points	true/false	print diagnostic data for two grid points	.false.
latpnt	real	latitude of (2) diagnostic points	
lonpnt	real	longitude of (2) diagnostic points	
dbug	true/false	if true, write extra diagnostics	.false.

Table 7: Namelist options (continued next page).

variable	options/format	description	recommended value
		Model Output, continued	
histfreq	string array	defines output frequencies	
-	У	write history every histfreq_n years	
	m	write history every histfreq_n months	
	d	write history every histfreq_n days	
	h	write history every histfreq_n hours	
	1	write history every time step	
	X	unused frequency stream (i.e., do not write)	
histfreq_n	integer array	frequency history output is written	
_	0	do not write to history	
hist_avg	true	write time-averaged data	.true.
_	false	write snapshots of data	
history_dir	path/	path to history output directory	
history_file	filename prefix	output file for history	'iceh'
write_ic	true/false	write initial condition	
incond_dir	path/	path to initial condition directory	
incond_file	filename prefix	output file for initial condition	'iceh'
runid	string	label for run (currently CESM only)	
$grid\_nml$		Grid	
grid_format	nc	read netCDF grid and kmt files	bin'
	bin	read direct access, binary file	
grid_type	rectangular	defined in rectgrid	displaced_pole
	displaced_pole	read from file in <i>popgrid</i>	
	tripole	read from file in <i>popgrid</i>	
grid_file	filename	name of grid file to be read	'grid'
kmt_file	filename	name of land mask file to be read	'kmt'
kcatbound	0	original category boundary formula	0
	1	new formula with round numbers	
	2	WMO standard categories	
	-1	one category	
domain_nml		Domain	
nprocs	integer	number of processors to use	
processor_shape	slenderX1	1 processor in the y direction (tall, thin)	
	slenderX2	2 processors in the y direction (thin)	
	square-ice	more processors in x than y, $\sim$ square	
	square-pop	more processors in y than x, $\sim$ square	
distribution_type	cartesian	distribute blocks in 2D Cartesian array	
	roundrobin	ADD DESCRIPTION	
	sectcart		
	sectrobin		
	rake	redistribute blocks among neighbors	
	spacecurve	distribute blocks via space-filling curves	

Table 7: Namelist options (continued).

variable	options/format	description	recommended value
		Domain, continued	
distribution_weight	block	full block size sets work_per_block	
	latitude	latitude/ocean sets work_per_block	
ew_boundary_type	cyclic	periodic boundary conditions in x-direction	
2 21	open	Neumann boundary conditions in x	
	closed	Dirichlet boundary conditions in x	
ns_boundary_type	cyclic	periodic boundary conditions in y-direction	
1 11	open	Neumann boundary conditions in y	
	closed	Dirichlet boundary conditions in y	
	tripole	U-fold tripole boundary conditions in y	
	tripoleT	T-fold tripole boundary conditions in y	
maskhalo_dyn	true/false	mask unused halo cells for dynamics	
maskhalo_remap	true/false	mask unused halo cells for transport	
maskhalo_bound	true/false	mask unused halo cells for boundary updates	
tracer_nml		Tracers	
tr_iage	true/false	ice age	
restart_age	true/false	restart tracer values from file	
tr_FY	true/false	first-year ice area	
restart_FY	true/false	restart tracer values from file	
tr_lvl	true/false	level ice area and volume	
restart_lvl	true/false	restart tracer values from file	
tr_pond_cesm	true/false	CESM melt ponds	
restart_pond_cesm	true/false	restart tracer values from file	
tr_pond_topo	true/false	topo melt ponds	
restart_pond_topo	true/false	restart tracer values from file	
tr_pond_lvl	true/false	level-ice melt ponds	
restart_pond_lvl	true/false	restart tracer values from file	
tr_aero	true/false	aerosols	
restart_aero	true/false	restart tracer values from file	
mushy_nml		Mushy thermodynamics	
a_rapid_mode	real	brine channel diameter	$0.5 \times 10^{-3}$
Rac_rapid_mode	real	critical Rayleigh number	10
aspect_rapid_mode	real	brine convection aspect ratio	1
dSdt_slow_mode	real	drainage strength parameter	$-1.5 \times 10^{-7}$
phi_c_slow_mode	real	critical liquid fraction	0.05
phi_i_mushy	real	solid fraction at lower boundary	0.85
zbgc_nml		Biogeochemistry	
tr_brine	true/false	brine height tracer	
restart_hbrine	true/false	restart tracer values from file	
solve_skl_bgc	true/false	biogeochemistry	
restart_bgc	true/false	restart tracer values from file	
restore_bgc	true/false	restore nitrate/silicate to data	
bgc_data_dir	path/	data directory for bgc	

Table 7: Namelist options (continued).

variable	options/format	description	recommended value
		Diagonal aminton continued	
has floor tons	T: ~2006	Biogeochemistry, continued	
bgc_flux_type	Jin2006	ice-ocean flux velocity of [36] constant ice-ocean flux velocity	
a:1 da+a +a	constant		
sil_data_type	default clim	default forcing value for silicate	
n:+ do+o +	default	silicate forcing from ocean climatology [23] default forcing value for nitrate	
nit_data_type	clim	nitrate forcing from ocean climatology [23]	
		nitrate forcing equals salinity	
tr_bgc_C_sk	sss true/false	algal carbon tracer	
tr_bgc_chl_sk	true/false	algal chlorophyll tracer	
tr_bgc_Am_sk	true/false	ammonium tracer	
tr_bgc_Sil_sk	true/false	silicate tracer	
tr_bgc_DMSPp_sk	true/false	particulate DMSP tracer	
tr_bgc_DMSPd_sk	true/false	dissolved DMSP tracer	
tr_bgc_DMS_sk	true/false	DMS tracer	
phi_snow	real	snow porosity for brine height tracer	
PIII DIIOW	1041	show porosity for orme neight tracer	
ice_nml		Physical Parameterizations	
kitd	0	delta function ITD approximation	1
	1	linear remapping ITD approximation	
kdyn	0	dynamics OFF	1
	1	EVP dynamics	
	2	EAP dynamics	
revised_evp	true/false	use revised EVP formulation	
ndte	integer	number of EVP subcycles	120
advection	remap	linear remapping advection	remap
	upwind	donor cell advection	
kstrength	0	ice strength formulation [26]	1
	1	ice strength formulation [56]	
krdg_partic	0	old ridging participation function	1
	1	new ridging participation function	
krdg_redist	0	old ridging redistribution function	1
	1	new ridging redistribution function	
mu_rdg	real	e-folding scale of ridged ice	
ktherm	0	zero-layer thermodynamic model	
	1	Bitz and Lipscomb thermodynamic model	
	2	mushy-layer thermodynamic model	
conduct	MU71	conductivity [49]	
	bubbly	conductivity [54]	1.6.1.
shortwave	default	NCAR CCSM3 distribution method	default
- 111	dEdd	Delta-Eddington method	1.6
albedo_type	default	NCAR CCSM3 albedos	default
- 1 h i	constant	four constant albedos	
albicev	$0 < \alpha < 1$	visible ice albedo for thicker ice	
albicei albsnowv	$0 < \alpha < 1$ $0 < \alpha < 1$	near infrared ice albedo for thicker ice	
albsnowv	$0 < \alpha < 1$ $0 < \alpha < 1$	visible, cold snow albedo	
		near infrared, cold snow albedo albedo is constant above this thickness	0.2 m
ahmax	real	aidedo is constant adove this thickness	0.3 m

Table 7: Namelist options (continued).

variable	options/format	description	recommended value
		Physical Parameterizations, continued	
R_ice	real	tuning parameter for sea ice albedo	
		from Delta-Eddington shortwave	
R_pnd	real	for ponded sea ice albedo	
R_snw	real	for snow (broadband albedo)	
dT_mlt	real	$\Delta$ temperature per $\Delta$ snow grain radius	
rsnw_mlt	real	maximum melting snow grain radius	
hp1	real	critical ice lid thickness for topo ponds	0.01 m
hs0	real	snow depth of transition to bare sea ice	0.03 m
hs1	real	snow depth of transition to pond ice	0.03 m
dpscale	real	time scale for flushing in permeable ice	$1 \times 10^{-3}$
frzpnd	hlid	Stefan refreezing with pond ice thickness	'hlid'
-	cesm	CESM refreezing empirical formula	
snowinfil	true/false	snow infiltration on/off	.true.
rfracmin	$0 \le r_{min} \le 1$	minimum melt water added to ponds	0.15
rfracmax	$0 \le r_{max} \le 1$	maximum melt water added to ponds	1.0
pndaspect	real	aspect ratio of pond changes (depth:area)	0.8
		Forcing	
atmbndy	default	stability-based boundary layer	default
	constant	bulk transfer coefficients	
fyear_init	уууу	first year of atmospheric forcing data	
ycycle	integer	number of years in forcing data cycle	
atm_data_format	nc	read netCDF atmo forcing files	bin
	bin	read direct access, binary files	
atm_data_type	default	constant values defined in the code	
	LYq	AOMIP/Large-Yeager forcing data	
	monthly	monthly forcing data	
	ncar	NCAR bulk forcing data	
	oned	column forcing data	
atm_data_dir	path/	path to atmospheric forcing data directory	
calc_formdrag	true/false	calculate form drag	
calc_strair	true	calculate wind stress and speed	
	false	read wind stress and speed from files	
calc_Tsfc	true/false	calculate surface temperature	.true.
precip_units	mks	liquid precipitation data units	• • • • • • • • • • • • • • • • • • • •
proorplanies	mm_per_month	inquia precipitation data units	
	mm_per_sec	(same as MKS units)	
ustar_min	real	minimum value of ocean friction velocity	0.0005 m/s
update_ocn_f	true	include frazil water/salt fluxes in ocn fluxes	0.0000 1110
apaace_ocn_r	false	do not include (when coupling with POP)	
oceanmixed_ice	true/false	active ocean mixed layer calculation	.true. (if uncoupled)
ocn_data_format	nc	read netCDF ocean forcing files	bin
ocii_uata_10filldt		_	MIII
	bin	read direct access, binary files	

Table 7: Namelist options (continued).

variable	options/format	description	recommended value
		Forcing, continued	
sss_data_type	default	constant values defined in the code	
	clim	climatological data	
	ncar	POP ocean forcing data	
sst_data_type	default	constant values defined in the code	
	clim	climatological data	
	ncar	POP ocean forcing data	
ocn_data_dir	path/	path to oceanic forcing data directory	
oceanmixed_file	filename	data file containing ocean forcing data	
restore_sst	true/false	restore sst to data	
trestore	integer	sst restoring time scale (days)	
restore_ice	true/false	restore ice state along lateral boundaries	
icefields_[tracer_]nml		History Fields	
$f_{-}\langle var \rangle$	string	frequency units for writing $\langle var \rangle$ to history	
	У	write history every histfreq_n years	
	m	write history every histfreq_n months	
	d	write history every histfreq_n days	
	h	write history every histfreq_n hours	
	1	write history every time step	
	X	do not write $\langle var \rangle$ to history	
	md	e.g., write both monthly and daily files	
$ extsf{f}\langle var angle extsf{ai}$		grid cell average of $\langle var \rangle$ ( $\times a_i$ )	

Table 7: Namelist options (continued).

# Index of primary variables and parameters **CHECK**

This index defines many of the symbols used frequently in the ice model code. Values appearing in this list are fixed or recommended; most namelist parameters are indicated (•) with their default values. For other namelist options, see Table 7. All quantities in the code are expressed in MKS units (temperatures may take either Celsius or Kelvin units).

# A

a11, a12	structure tensor components	
a2D	history field accumulations, 2D	
a3Dz	history field accumulations, 3D vertical	
a3Db	history field accumulations, 3D vertical	
a3Dc	history field accumulations, 3D olo grid	
a4Di	history field accumulations, 3D categories, vertical ice	
a4Db		
a4Ds	history field accumulations, 4D categories, vertical bio grid history field accumulations, 4D categories, vertical snow	
a_min	·	0.001
	minimum area concentration for computing velocity	0.001
a_rapid_mode advection		raman
ahmax	<ul><li>type of advection algorithm used ('remap' or 'upwind')</li><li>thickness above which ice albedo is constant</li></ul>	remap 0.3 m
		0.3 m 0.15
aice_extmin	minimum value for ice extent diagnostic	0.13
aice_init	concentration of ice at beginning of timestep	
aice0	fractional open water area	
aice(n)	total concentration of ice in grid cell (in category n)	
albedo_type	• type of albedo parameterization ('default' or 'constant')	
albent	counter for averaging albedo	
albice	bare ice albedo	
albicei	• near infrared ice albedo for thicker ice	
albicev	• visible ice albedo for thicker ice	0.06
albocn	ocean albedo	0.06
albpnd	melt pond albedo	
albsno	snow albedo	
albsnowi	• near infrared, cold snow albedo	
albsnowv	• visible, cold snow albedo	9
algalN	algal nitrogen concentration	mmol/m <sup>3</sup>
alv(n)dr(f)	albedo: visible (near IR), direct (diffuse)	
$alv(n)dr(f)_ai$	grid-box-mean value of alv(n)dr(f)	9
amm	ammonia/um concentration	mmol/m <sup>3</sup>
ANGLE	for conversions between the POP grid and latitude-longitude grids	radians
ANGLET	ANGLE converted to T-cells	radians
aparticn	participation function	
apeff_ai	grid-cell-mean effective pond fraction	
apondn	area concentration of melt ponds	
arlx1i	relaxation constant for dynamics (stress)	
araftn	area fraction of rafted ice	
aredistrn	redistribution function: fraction of new ridge area	
ardgn	fractional area of ridged ice	
aspect_rapid_mode	• brine convection aspect ratio	1
astar	e-folding scale for participation function	0.05
atm_data_dir	<ul> <li>directory for atmospheric forcing data</li> </ul>	
atm_data_format	• format of atmospheric forcing files	
atm_data_type	• type of atmospheric forcing	
atmbndy	• atmo boundary layer parameterization ('default' or 'constant')	
avail_hist_fields	type for history field data	
awtidf	weighting factor for near-ir, diffuse albedo	0.36218
awtidr	weighting factor for near-ir, direct albedo	0.00182
awtvdf	weighting factor for visible, diffuse albedo	0.63282
awtvdr	weighting factor for visible, direct albedo	0.00318

• data directory for bgc

# B

bgc\_data\_dir

oge_data_dii	• data directory for oge	
bgc_flux_type	• ice–ocean flux velocity	
bgc_tracer_type	tracer_type for bgc tracers	
bgrid	nondimensional vertical grid points for bio grid	
bignum	a large number	$10^{30}$
block	data type for blocks	
block_id	global block number	
block_size_x(y)	number of cells along $x(y)$ direction of block	
blockGlobalID	global block IDs	
blockLocalID	local block IDs	
blockLocation	processor location of block	
blocks_ice	local block IDs	
bphi	porosity of ice layers on bio grid	
brlx	relaxation constant for dynamics (momentum)	
bTiz	temperature of ice layers on bio grid	
C		
$\operatorname{c}\langle n  angle$	real(n)	
calc_formdrag	• calculate form drag	
calc_strair	• if true, calculate wind stress	T
calc_Tsfc	• if true, calculate surface temperature	T
Cdn_atm	atmospheric drag coefficient	
Cdn_ocn	ocean drag coefficient	
Cf	ratio of ridging work to PE change in ridging	17.
cgrid	vertical grid points for ice grid (compare bgrid)	
char_len	length of character variable strings	80
char_len_long	length of longer character variable strings	256
check_step	time step on which to begin writing debugging data	
check_umax	if true, check for ice speed > umax_stab	
cldf	cloud fraction	
cm_to_m	cm to meters conversion	0.01
coldice	value for constant albedo parameterization	0.70
coldsnow	value for constant albedo parameterization	0.81
conduct	• conductivity parameterization	0.01
congel	basal ice growth	m
cosw	cosine of the turning angle in water	1.
coszen	cosine of the zenith angle	1.
Ср	proportionality constant for potential energy	$kg/m^2/s^2$
cp_air	specific heat of air	1005.0 J/kg/K
cp_ice	specific heat of fresh ice	2106. J/kg/K
cp_ocn	specific heat of sea water	4218. J/kg/K
cp_wv	specific heat of water vapor	$1.81 \times 10^3 \text{ J/kg/K}$
cp063	diffuse fresnel reflectivity (above)	0.063
cp455	diffuse fresnel reflectivity (below)	0.455
Cs	fraction of shear energy contributing to ridging	0.455
Cstar	constant in Hibler ice strength formula	20.
cxm	combination of HTN values	۷٠.
	combination of HTN values	
cxp	combination of HTE values	
cym	Comoniation of 111E values	

 $J/m^2$ 

0.95

eice(n)

emissivity

94	Index of primary v	ariables and parameters
daymo	number of days in one month	
daycal	day number at end of month	
days_per_year	• number of days in one year	365
dbl_kind	definition of double precision	selected_real_kind(13)
dbug	write extra diagnostics	.false.
Delta	function of strain rates (see Section 3.5)	1/s
denom1	combination of constants for stress equation	
depressT	ratio of freezing temperature to salinity of brine	0.054 deg/ppt
dhbr_bt	change in brine height at the bottom of the column	
dhbr_top	change in brine height at the top of the column	
dhsn	depth difference for snow on sea ice and pond ice	
diag_file	• diagnostic output file (alternative to standard out)	
diag_type	• where diagnostic output is written	stdout
diagfreq	• how often diagnostic output is written (10 = once per 10 dt)	
distrb	distribution data type	
distrb_info	block distribution information	
distribution_type	<ul> <li>method used to distribute blocks on processors</li> </ul>	
$distribution\_weight$	<ul> <li>weighting method used to compute work per block</li> </ul>	
divu	strain rate I component, velocity divergence	1/s
divu_adv	divergence associated with advection	1/s
dms	dimethyl sulfide concentration	mmol/m <sup>3</sup>
dmsp	dimethyl sulfoniopropionate concentration	mmol/m <sup>3</sup>
dpscale	• time scale for flushing in permeable ice	$1 \times 10^{-3}$
dragio	drag coefficient for water on ice	0.00536
dSdt_slow_mode	• drainage strength parameter	
dsnow	change in snow thickness	m
dt	• thermodynamics time step	3600. s
dt_dyn	dynamics/ridging/transport time step	
dT_mlt	• $\Delta$ temperature per $\Delta$ snow grain radius	1. deg
dte	subcycling time step for EVP dynamics ( $\Delta t_e$ )	S
dte2T	dte / 2(damping time scale)	4.4
dtei	1/dte, where dte is the EVP subcycling time step	1/s
dump_file	• output file for restart dump	
dumpfreq	• dump frequency for restarts, y, m or d	
dumpfreq_n	• restart output frequency	
dump_last	• if true, write restart on last time step of simulation	
dxhy	combination of HTE values	
dxt	width of T cell $(\Delta x)$ through the middle	m
dxu	width of U cell $(\Delta x)$ through the middle	m
dyhx dyn_dt	combination of HTN values	0
•	dynamics and transport time step ( $\Delta t_{dyn}$ )	S
dyt dyu	height of T cell $(\Delta y)$ through the middle height of U cell $(\Delta y)$ through the middle	m m
dvidtd	ice volume tendency due to dynamics/transport	m m/s
dvidtt	ice volume tendency due to thermodynamics	m/s
dvirdg(n)dt	ice volume ridging rate (category n)	m/s
E		
all all all	strain rata tancar agmananta	
e11, e12, e22	strain rate tensor components	1/4
ecci	yield curve minor/major axis ratio, squared	1/4 1/m <sup>2</sup>

energy of melting of ice per unit area (in category n)

emissivity of snow and ice.....

# $\mathbf{F}$

faero_atm	aerosol deposition rate	kg/m²/s
faero_ocn	aerosol flux to the ocean	kg/m <sup>2</sup> /s
$fcondtop(n)(_f)$	conductive heat flux	$W/m^2$
fcor_blk	Coriolis parameter	1/s
ferrmax	max allowed energy flux error (thermodynamics)	$1.\times10^{-3} \text{ W/m}^2$
ffracn	fraction of fsurfn used to melt pond ice	
fhocn	net heat flux to ocean	$ m W/m^2$
fhocn_ai	grid-box-mean net heat flux to ocean (fhocn)	$ m W/m^2$
field_loc_center	field centered on grid cell	1
field_loc_Eface	field centered on east face	4
field_loc_NEcorner	field on northeast corner	2
field_loc_Nface	field centered on north face	3
field_loc_noupdate	ignore location of field	-1
field_loc_unknown	unknown location of field	0
field_loc_Wface	field centered on west face	5
field_type_angle	angle field type	3
field_type_noupdate	ignore field type	-1
field_type_scalar	scalar field type	1
field_type_unknown	unknown field type	0
field_type_vector	vector field type	2
first_ice	flag for initial ice formation	
flat	latent heat flux	$ m W/m^2$
floediam	effective floe diameter for lateral melt	300. m
floeshape	floe shape constant for lateral melt	0.66
flux_bio	all biogeochemistry fluxes passed to ocean	
flux_bio_ai	all biogeochemistry fluxes passed to ocean, grid cell mean	
flw	incoming longwave radiation	$W/m^2$
flwout	outgoing longwave radiation	$ m W/m^2$
fm	Coriolis parameter * mass in U cell	kg/s
fpond	fresh water flux to ponds	kg/m²/s
fr_resp	bgc respiration fraction	0.05
frain	rainfall rate	kg/m²/s
frazil	frazil ice growth	m
fresh	fresh water flux to ocean	kg/m <sup>2</sup> /s
fresh_ai	grid-box-mean fresh water flux (fresh)	kg/m²/s
frz_onset	day of year that freezing begins	0
frzmlt	freezing/melting potential	$W/m^2$
frzmlt_init	freezing/melting potential at beginning of time step	$W/m^2$
frzmlt_max	maximum magnitude of freezing/melting potential	1000. W/m $^2$
frzpnd	• Stefan refreezing of melt ponds	'hlid'
fsalt	net salt flux to ocean	kg/m <sup>2</sup> /s
fsalt_ai	grid-box-mean salt flux to ocean (fsalt)	kg/m <sup>2</sup> /s
fsens	sensible heat flux	$W/m^2$
fsnow	snowfall rate	kg/m <sup>2</sup> /s
fsnowrdg	snow fraction that survives in ridging	0.5
$fsurf(n)(_f)$	net surface heat flux excluding fcondtop	W/m <sup>2</sup>
fsw	incoming shortwave radiation	W/m <sup>2</sup>
fswabs	total absorbed shortwave radiation	$W/m^2$
fswfac	scaling factor to adjust ice quantities for updated data	
fswint	shortwave absorbed in ice interior	$W/m^2$

# G

gravit grid_file grid_format	gravitational acceleration	9.80616 m/s <sup>2</sup>
grid_type	• 'rectangular' or 'displaced_pole' or 'column'	
grow_net	specific biogeochemistry growth rate per grid cell	$s^{-1}$
Gstar	piecewise-linear ridging participation function parameter	0.15
Н		
halo_info	information for updating ghost cells	
heat_capacity	• if true, use salinity-dependent thermodynamics	T
hfrazilmin	minimum thickness of new frazil ice	0.05 m
hi_min	minimum ice thickness for thinnest ice category	0.01 m
hi_ssl	ice surface scattering layer thickness	0.05 m
hicen	ice thickness in category n	m
hin_old	ice thickness prior to growth/melt	m
hin_max	category thickness limits	m
hist_avg	• if true, write averaged data instead of snapshots	T
histfreq	• units of history output frequency: y, m, w, d or 1	
histfreq_n	• integer output frequency in histfreq units	
history_dir	• path to history output files	
history_file	• history output file prefix	
hm	land/boundary mask, thickness (T-cell)	
hmix	ocean mixed layer depth	20. m
hour	hour of the year	
hp0	pond depth at which shortwave transition to bare ice occurs	0.2 m
hp1	• critical ice lid thickness for topo ponds (dEdd)	0.01 m
hpmin	minimum melt pond depth (shortwave)	0.005 m
hpondn	melt pond depth	m
hs_min	minimum thickness for which $T_s$ is computed	$1. \times 10^{-4} \text{ m}$
hs0	• snow depth at which transition to ice occurs (dEdd)	0.03 m
hs1	• snow depth of transition to pond ice	0.03 m
hs_ssl	snow surface scattering layer thickness	0.04 m
Hstar	determines mean thickness of ridged ice	25. m
HTE	length of eastern edge ( $\Delta y$ ) of T-cell	m
HTN	length of northern edge $(\Delta x)$ of T-cell	m
HTS	length of southern edge $(\Delta x)$ of T-cell	m
HTW	length of western edge of $(\Delta y)$ T-cell	m
I		
i(j)_glob	global domain location for each grid cell	
i0vis	fraction of penetrating visible solar radiation	0.70
iblkp	block on which to write debugging data	
i(j)block	Cartesian i,j position of block	
ice_hist_field	type for history variables	
ice_ic	• choice of initial conditions (see Table 4)	
ice_stdout	unit number for standard output	
ice_stderr	unit number for standard error output	
ice_ref_salinity	reference salinity for ice-ocean exchanges	4. ppt

Index of primary v	ariables and parameters	9/
icetmask	ice extent mask (T-cell)	
iceumask	ice extent mask (U-cell)	
idate	the date at the end of the current time step (yyyymmdd)	
idate0	initial date	
ierr	general-use error flag	
igrid	interface points for vertical bio grid	
i(j)hi	last i(j) index of physical domain (local)	
i(j)lo	first i(j) index of physical domain (local)	
incond_dir	• directory to write snapshot of initial condition	
incond_file	• prefix for initial condition file name	
int_kind	definition of an integer	selected real kind(6)
integral_order	polynomial order of quadrature integrals in remapping	
ip, jp	local processor coordinates on which to write debugging data	. 3
istep	local step counter for time loop	
istep0	• number of steps taken in previous run	0
istep1	total number of steps at current time step	. 0
Iswabs	shortwave radiation absorbed in ice layers	$ m W/m^2$
15 w a 0 5	shortwave radiation absorbed in ice tayers	**/111
K		
kappav	visible extinction coefficient in ice, wavelength<700nm	$1.4 \ \mathrm{m}^{-1}$
kcatbound	• category boundary formula	
kdyn	• type of dynamics (1 = EVP, 0 = off)	. 1
kg_to_g	kg to g conversion factor	
kice	thermal conductivity of fresh ice (BL99)	
kitd	• type of itd conversions (0 = delta function, 1 = linear remap)	-
kmt_file	• input file for land mask info	
krdg_partic	• ridging participation function	. 1
krdg_redist	• ridging redistribution function	
krgdn	mean ridge thickness per thickness of ridging ice	
kseaice	thermal conductivity of ice for zero-layer thermodynamics	. 2.0 W/m/deg
ksno	thermal conductivity of snow	_
kstrength	• ice stength formulation (1= Rothrock 1975, 0 = Hibler 1979)	_
ktherm	• thermodynamic formulation (0 = zero-layer, 1 = BL99, 2 = mushy	
${f L}$		
l_brine	flag for brine pocket effects	
l_conservation_chec	ckif true, check conservation when ridging	
l_fixed_area	flag for prescribing remapping fluxes	
latpnt	<ul> <li>desired latitude of diagnostic points</li> </ul>	degrees N
latt(u)_bounds	latitude of T(U) grid cell corners	degrees N
Lfresh	latent heat of melting of fresh ice = Lsub - Lvap	J/kg
lhcoef	transfer coefficient for latent heat	-
lmask_n(s)	northern (southern) hemisphere mask	
local_id	local address of block in current distribution	
log_kind	definition of a logical variable	. kind(.true.)
-	•	•

98	Index of primary	variables and parameters
lonpnt lont(u)_bounds Lsub ltripole_grid Lvap	• desired longitude of diagnostic points longitude of T(U) grid cell corners latent heat of sublimation for fresh water	degrees E degrees E $2.835 \times 10^6$ J/kg $2.501 \times 10^6$ J/kg
M		
m_min m_to_cm m1 m2 m2_to_km2 maskhalo_bound maskhalo_dyn maskhalo_remap master_task	minimum mass for computing velocity meters to cm conversion constant for lateral melt rate constant for lateral melt rate m² to km² conversion • turns on bound_state halo masking • turns on dynamics halo masking • turns on transport halo masking task ID for the controlling processor	$0.01 \text{ kg/m}^2$ 100. $1.6 \times 10^{-6} \text{ m/s deg}^{-m2}$ 1.36 $1 \times 10^{-6}$
max_blocks max_ntrer maxraft mday meltb	maximum number of blocks per processor maximum number of tracers available	5 1. m
meltl melts meltt	lateral ice melt snow melt top ice melt	m m m
min_salin mlt_onset month monthp	threshold for brine pockets	0.1 ppt
mps_to_empdy mtask mu_rdg my_task	m per s to cm per day conversion	$8.64\times10^6$
N		
n_aero nblocks nblocks_tot nblocks_x(y) nbtrcr	number of aerosol species number of blocks on current processor total number of blocks in decomposition total number of blocks in x(y) direction	
ncat ncat_hist ndte	number of biology tracers number of ice categories number of categories written to history • number of subcycles	5 120
ndtd new_day new_hour new_month new_year	• number of dynamics/advection steps under thermo flag for beginning new day flag for beginning new hour flag for beginning new month flag for beginning new year	1
nghost ngroups	number of rows of ghost cells surrounding each subdomain number of groups of flux triangles in remapping	1 5

nit nitrate concentration mmol/m<sup>3</sup>

nit\_data\_type • forcing type for nitrate

nlt\_bgc\_[chem] ocean sources and sinks for biogeochemistry

nml\_filename namelist file name

nprocs • total number of processors
npt • total number of time steps (dt)

ns\_boundary\_type

• type of north-south boundary condition
nslyr

number of snow layers in each category
number of solar spectral intervals

nstreams number of history output streams (frequencies)

 $\operatorname{nt}_{-}\langle trcr \rangle$  tracer index

ntrace number of fields being transported

ntrcr number of tracers

nu\_diag unit number for diagnostics output file nu\_dump unit number for dump file for restarting

nu\_dump\_eap unit number for EAP dynamics dump file for restarting

nu\_dump\_[tracer] unit number for tracer dump file for restarting

nu\_forcing unit number for forcing data file

nu\_grid unit number for grid file

nu\_hdr unit number for binary history header file

nu\_historyunit number for history filenu\_kmtunit number for land mask filenu\_nmlunit number for namelist input filenu\_restartunit number for restart input file

nu\_restart\_eap unit number for EAP dynamics restart input file

nu\_restart\_[tracer] unit number for tracer restart input file
nu\_rst\_pointer unit number for pointer to latest restart file
num\_avail\_hist\_fields\_[shape]number of history fields of each array shape
nvar number of horizontal grid fields written to history
nvarz number of category, vertical grid fields written to history
nx(y)\_block total number of gridpoints on block in x(y) direction

nx(y)\_global number of physical gridpoints in x(y) direction, global domain

nyr year number

# 0

ocean\_bio concentrations of bgc constituents in the ocean oceanmixed\_file • data file containing ocean forcing data • if true, use internal ocean mixed layer

ocn\_data\_dir
ocn\_data\_format

• directory for ocean forcing data
• format of ocean forcing files

opening rate of ice opening due to divergence and shear 1/s

### P

p001 1/1000 p01 1/100 p025 1/40 p027 1/36 p05 1/20

0.8

mg C/m<sup>2</sup>/s

1/10 p1 1/9 p111 15/100 p15 p166 1/6 p2 1/5 2/9 p222 p25 1/4 p333 1/3 2/5 p4 p5 1/2 25/48 p52083 -9/16 p5625m 3/5 **p6** 2/3 p666 p75 3/4

phi\_c\_slow\_mode

phi\_i\_mushy phi\_sk

phi\_snow

pi pi2 pih

piq

pi(j,b,m)loc plat

plon pndaspect

pointer\_file potT PP\_net

precip\_units print\_global

print\_points processor\_shape

prs\_sig Pstar puny

• critical liquid fraction

• solid fraction at lower boundary skeletal layer porosity

• snow porosity for brine height tracer

 $\pi$  $2\pi$  $\pi/2$  $\pi/4$ 

x (y, block, task) location of diagnostic points grid latitude of diagnostic points

grid longitude of diagnostic points

• aspect ratio of pond changes (depth:area) .

• input file for restarting

atmospheric potential temperature total primary productivity per grid cell

• liquid precipitation data units

• if true, print global data ..... F F • if true, print point data .....

• descriptor for processor aspect ratio

N/m replacement pressure

 $2.75 \times 10^4 \text{N/m}$ ice strength parameter .....  $1 \times 10^{-11}$ a small positive number .....

# 0

Qa specific humidity at 10 m kg/kg  $m W/m^2$ deep ocean heat flux qdp

for saturated specific humidity over ice .....  $1.16378 \times 10^7 \text{kg/m}^3$ qqqice  $6.275724 \times 10^6 \text{kg/m}^3$ qqqocn for saturated specific humidity over ocean ...

Qref 2m atmospheric reference specific humidity kg/kg

# R

R\_C2N algal carbon to nitrate factor 7. mole/mole R\_gC2molC mg/mmol carbon 12.01 mg/mole R\_chl2N algal chlorophyll to nitrate factor 3. mg/mmol

R\_ice • parameter for Delta-Eddington ice albedo R\_pnd parameter for Delta-Eddington pond albedo

 $10^{30}$ 

Index of primary va	ariables and parameters	101
refindx	refractive index of sea ice	1.310
revp	real(revised_evp)	
restart	• if true, initialize using restart file instead of defaults	T
restart_age	• if true, read age restart file	
restart_bgc	• if true, read bgc restart file	
restart_dir	• path to restart/dump files	
restart_file	• restart file prefix	
restart_[tracer]	• if true, read tracer restart file	
restart_ext	• if true, read/write halo cells in restart file	
restore_bgc	• if true, restore nitrate/silicate to data	
restore_ice	• if true, restore ice state along lateral boundaries	
restore_sst	• restore sst to data	
revised_evp	• if true, use revised EVP parameters and approach	
rfracmin	• minimum melt water fraction added to ponds	0.15
rfracmax	• maximum melt water fraction added to ponds	1.0
rhoa	air density	kg/m <sup>3</sup>
rhofresh	density of fresh water	$1000.0 \text{ kg/m}^3$
rhoi	density of ice	917. kg/m <sup>3</sup>
rhos	density of snow	330. kg/m <sup>3</sup>
rhosi	average sea ice density (for hbrine tracer)	940. kg/m <sup>3</sup>
rhow	density of seawater	$1026. \text{ kg/m}^3$
rnilyr	real(nlyr)	1020. Kg/III
rside	fraction of ice that melts laterally	
rsnw_fresh	freshly fallen snow grain radius	$100. \times 10^{-6} \text{ m}$
rsnw_melt	• melting snow grain radius	$1000. \times 10^{-6} \mathrm{m}$
rsnw_nonmelt	nonmelting snow grain radius	$500. \times 10^{-6} \text{ m}$
rsnw_sig	standard deviation of snow grain radius	$250. \times 10^{-6} \text{ m}$
runid	• identifier for run	230. × 10 m
runtype	• type of initialization used	
runtype	type of initialization used	
$\mathbf{S}$		
11 12 22		
s11, s12, s22	stress tensor components	
salinz	ice salinity profile	ppt
saltmax	max salinity, at ice base (BL99)	3.2 ppt
scale_factor	scaling factor for shortwave radiation components	
sec	seconds elasped into idate	0.6400
secday	number of seconds in a day	86400.
shcoef	transfer coefficient for sensible heat	
shear	strain rate II component	1/s
shlat	southern latitude of artificial mask edge	30°N
shortwave	• flag for shortwave parameterization ('default' or 'dEdd')	
sig1(2)	principal stress components (diagnostic)	2
sil	silicate concentration	mmol/m <sup>3</sup>
sil_data_type	• forcing type for silicate	
sinw	sine of the turning angle in water	0.
sk_l	skeletal layer thickness	0.03 m
snoice	snow-ice formation	m —
snowinfil	• snow infiltration on/off	T
snowpatch	length scale for parameterizing nonuniform snow coverage	0.02 m
solve_skl_bgc	• biogeochemistry on/off	1030
spval	special value (single precision)	$10^{30}$
cavel dbl	enocial value (double precision)	1000

special value (double precision) ......

 $spval\_dbl$ 

sst	sea surface temperature	С
sst_data_type	• source of surface temperature data	
Sswabs	shortwave radiation absorbed in snow layers	$W/m^2$
stefan-boltzmann	Stefan-Boltzmann constant	$5.67 \times 10^{-8} \text{ W/m}^2 \text{K}^4$
stop_now	if 1, end program execution	
strairx(y)	stress on ice by air in the $x(y)$ -direction (centered in U cell)	$N/m^2$
strairx(y)T	stress on ice by air, $x(y)$ -direction (centered in T cell)	$N/m^2$
strax(y)	wind stress components from data	$N/m^2$
strength	ice strength (pressure)	N/m
stress12	internal ice stress, $\sigma_{12}$	N/m
stressm	internal ice stress, $\sigma_{11} - \sigma_{22}$	N/m
stressp	internal ice stress, $\sigma_{11} + \sigma_{22}$	N/m
strintx(y)	divergence of internal ice stress, $x(y)$	$N/m^2$
strocnx(y)	ice-ocean stress in the $x(y)$ -direction (U-cell)	$N/m^2$
strocnx(y)T	ice-ocean stress, x(y)-dir. (T-cell)	$N/m^2$
strtltx(y)	surface stress due to sea surface slope	$N/m^2$
swv(n)dr(f)	incoming shortwave radiation, visible (near IR), direct (diffuse)	$W/m^2$
<b>T</b>		
$\mathbf{T}$		

Tair	air temperature at 10 m	K
tarea	area of T-cell	$m^2$
tarean	area of northern hemisphere T-cells	$m^2$
tarear	1/tarea	$1/m^2$
tareas	area of southern hemisphere T-cells	$m^2$
tcstr	string identifying T grid for history variables	
tday	absolute day number	
Tf	freezing temperature	C
Tffresh	freezing temp of fresh ice	273.15 K
thinS	minimum ice thickness for brine tracer	
time	total elapsed time	S
time_beg	beginning time for history averages	
time_bounds	beginning and ending time for history averages	
time_end	ending time for history averages	
time_forc	time of last forcing update	S
Timelt	melting temperature of ice top surface	0. C
tinyarea	puny * tarea	$m^2$
TLAT	latitude of cell center	radians
TLON	longitude of cell center	radians
tmask	land/boundary mask, thickness (T-cell)	
tmass	total mass of ice and snow	kg/m <sup>2</sup>
Tmin	minimum allowed internal temperature	-100. C
Tmltz	melting temperature profile of ice	
Tocnfrz	temperature of constant freezing point parameterization	-1.8 C
tr_aero	• if true, use aerosol tracers	
tr_bgc_[tracer]	• if true, use biogeochemistry tracers	
tr_brine	• if true, use brine height tracer	
tr_FY	• if true, use first-year area tracer	
tr_iage	• if true, use ice age tracer	
tr_lvl	• if true, use level ice area and volume tracers	
tr_pond_cesm	• if true, use CESM melt pond scheme	
tr_pond_lvl	• if true, use level-ice melt pond scheme	
tr_pond_topo	• if true, use topo melt pond scheme	

wind

write\_history

wind speed

if true, write history now

m/s

Index of primary varia	ables and parameters	103
trcr	ice tracers	
trcr_depend	tracer dependency on basic state variables	
Tref	2m atmospheric reference temperature	K
trestore	• restoring time scale	days
tripole	if true, block lies along tripole boundary	•
tripoleT	if true, tripole boundary is T-fold; if false, U-fold	
Tsf_errmax	max allowed $T_{sf}$ error (thermodynamics)	$5. \times 10^{-4} \text{deg}$
Tsfc(n)	temperature of ice/snow top surface (in category n)	С
Tsmelt	melting temperature of snow top surface	0. C
TTTice	for saturated specific humidity over ice	5897.8 K
TTTocn	for saturated specific humidity over ocean	5107.4 K
U		
uarea	area of U-cell	$m^2$
uarear	1/uarea	$\mathrm{m}^{-2}$
uatm	wind velocity in the x direction	m/s
ULAT	latitude of U-cell centers	radians
ULON	longitude of U-cell centers	radians
umask	land/boundary mask, velocity (U-cell)	TWOTWIE
umax_stab	ice speed threashold (diagnostics)	1. m/s
umin	min wind speed for turbulent fluxes	1. m/s
uocn	ocean current in the x-direction	m/s
update_ocn_f	• if true, include frazil ice fluxes in ocean flux fields	
use_leap_years	• if true, include leap days	
use_restart_time	• if true, use date from restart file	
ustar_min	<ul> <li>minimum friction velocity under ice</li> </ul>	
ucstr	string identifying U grid for history variables	
uvel	x-component of ice velocity	m/s
uvel_init	x-component of ice velocity at beginning of time step	m/s
uvm	land/boundary mask, velocity (U-cell)	
V		
vatm	wind velocity in the y direction	m/s
vice(n)	volume per unit area of ice (in category n)	m
vicen_init	ice volume at beginning of timestep	m
viscosity_dyn	dynamic viscosity of brine	$1.79 \times 10^{-3}$ kg/m/s
vocn	ocean current in the y-direction	m/s
vonkar	von Karman constant	0.4
vraftn	volume of rafted ice	m
vrdgn	volume of ridged ice	m
vredistrn	redistribution function: fraction of new ridge volume	
vsno(n)	volume per unit area of snow (in category n)	m
vvel	y-component of ice velocity	m/s
vvel_init	y-component of ice velocity at beginning of time step	m/s
W		
warmice	value for constant albedo parameterization	0.68
warmsno	value for constant albedo parameterization	0.77
warmsno	wind speed	m/a

# Y

ycycle yday yield_curve yieldstress11(12, 22) year_init	<ul> <li>number of years in forcing data cycle day of the year</li> <li>type of yield curve</li> <li>yield stress tensor components</li> <li>the initial year</li> </ul>	ellipse
${f Z}$		
zlvl zref zTrf zvir	atmospheric level height reference height for stability	m 10. m 2. m 0.606

# Index

advection, see transport	distribution
aerosols, 14, 17–18, 65, 75, 79, 80	block, see blocks
albedo, 4, 12, 49, 66, 70, 83	thickness, 75, <i>see</i> thickness distribution
anisotropic, <i>see</i> elastic-anisotropic-plastic dynamics	drag, see form drag
AOMIP, 7, 89	drainage, 46, 48–49, 57–59
area, ice, see ice fraction	flushing, 18, 44–45, 49, 60, 84
bilinear, 36, 67	gravity, 15, 17, 59–60
biogeochemistry, 4, 15–18, 18, 65, 66, 69, 74, 79, 80	dynamics
blocks, 65, 67–68, 75, 76–79, 82	elastic-anisotropic-plastic, see elastic
boundary	elastic-viscous-plastic, see elastic
communication, 69, 74, 76–78	ridging, see ridging
condition, 45, 61, 65, 66, <i>67–70</i> , 74	transport, see transport
	EAD alore and a transition of a few and a
layer, 6–10	EAP, see elastic-anisotropic-plastic dynamics
thickness category, 10, 28–30	elastic
brine height, see height, brine	-anisotropic-plastic dynamics, 12, 33, <i>36</i> – <i>38</i> , 65, 70, 71, 74, 79
C-grid, 67, 68	-viscous-plastic dynamics, 12, 33–36, 38–41, 65,
categories, thickness, <i>see</i> thickness distribution	70–72, 74, 79
CESM/CCSM, 4, 13, 18, 42, 46, 47, 49, 50, 63, 66,	waves, 34, 36, 71
75, 76, 78, 82–84	energy, see enthalpy
CFL condition, 20, 28, 55, 71	enthalpy, 11, 12, 21, 22, 27, 30, 41, 55–56, 58–60,
cloud, 7	61–62
column configuration, 64, 67, 69, 83	evaporation, 4, 17, 61, 62
concentration, see ice fraction	EVP, see elastic-viscous-plastic dynamics
conductivity, 5, 45, 52–55, 58	•
conservation, 5, 13, 14, 16, 20, 27, 28, 30–32, 44,	first-year area, 14, 65, 75, 79
46, 49, 54, 59, 62, 63, 73, 80, 81	floe size, 9, 10, 38, 62, 95
conservation equation, see transport	flushing, see drainage, flushing
continuity equation, see transport	flux coupler, 4–8, 12, 17, 55, 63, 70, 74, 82, 83
Coriolis, 5, 34, 39	form drag, 6, 8–10, 79
coupling, see flux coupler	fraction, ice, see ice fraction
currents, ocean, 4, 8	frazil, 8, 14, 62
	freeboard, 9, 10, 49, 62, 84
damping timescale, 36, 71, 72	freezing potential, 4, 7
Darcy flow, 18, 19, 44, 58–61	fresh water flux, 4, 6, 8, 13, 32
Delta-Eddington, see radiation	, , , , ,
density	grid
atmosphere, 4, 5, 7, 51	bio, 18
brine, 57, 60	extended, 74
fresh water, 47	horizontal, 23, 36, 63–66, 67–69, 69–71, 75, 76
ice or snow, 10, 19, 20, 42, 52, 56, 62, 63	regional, 69, 70, 74
ocean, 8, 45, 51, 60	tripole, 67, 68, 70, 74, 84
desalination, see drainage	vertical, 18, 69, 75
diagnostics, 4, 7, 13, 16–18, 46, 65, 70, 73, 74, 75,	
81–83	Hadley Centre, 5, 82, 84

106 INDEX

halo, 67, 69, 70, 74, 78, 79	namelist, 8–10, 16, 31, 33, 34, 41, 42, 50, 52, 60, 61,
height	64–66, 68–70, 72–74, 76, 78, 80, 85–90
brine, 18–19, 69, 75, 80, 84	National Center for Atmospheric Research, see NCAR
reference, 4–6	NCAR, 4, 88–90
sea surface, see sea level	0.1.001
history, 10, 16, 18, 19, 33, 64-66, 69, 70, 72-75,	Oak Ridge National Laboratory, 76
79–80, 81, 83	ocean, 7–8
humidity	currents, see currents, ocean
reference, 4, 7	density, see density, ocean
specific, 4–7, 51	heat, 4, 8, 30, 51, 61
•	mixed layer, see mixed layer
ice, see individual variables	salinity, see salinity, ocean
age, 12, 13, 14, 65, 75, 79, 80	stress, see ice-ocean stress
fraction, 5, 9–11, 20, 21, 27–33, 36, 42, 43, 46,	surface height, see height, sea surface
78, 83	surface slope, see slope, sea surface
growth, 10, 11, 16, 17, 19, 28, 30, 45, 47, 55,	temperature, see temperature, ocean
61, <i>61–63</i> , 66	open water, 5, 7, 10, 15, 30, 31, 32, 49, 62
level, 13, 14, 33, 46, 47, 49, 65, 75, 79, 80	OpenMP, 63, 75
ice-ocean stress, 4, 5, 8, 34, 35, 39	D 11.10 D DOD
initial condition, 16, 41, 64, 66, 69–70, 73	Parallel Ocean Program, see POP
internal stress, 33–41, 67, 73	parallelization, 63–65, 70, 72, 73, 75
	permeability, 45, 49, 57, 60, 84
keels, 9	PIO, 64, 72, 75
	POP, 3, 8, 67, 69, 71, 76, 90
LANL, 3, 84	porosity
latent heat, 4–7, 9, 45, 49, <i>51</i> , 53, 56, 61, 62	ice, see liquid fraction
lateral melt, 17, 51, 62	snow, 19, 43, 44, 48, 63
leads, see open water	pressure
level ice, see ice, level	hydraulic, 43–45, 49, 60
liquid fraction, 16, 18, 19, 45, 49, 56, 58–60, 63, 84	ice strength, see strength
liquidus, 7, 53, 56–59, 61	replacement, 36
longwave, see radiation, longwave	nadiation
Los Alamos National Laboratory, see LANL	radiation
Los Alamos National Security, LLC, 84	Delta-Eddington, 12, 17, 41, 49, 53, 66, 79, 83
1 (4 (7 70 70 70	longwave, 4, 5, 7, 8, 49, 50
masks, 64–67, <i>70</i> , 78, 79	shortwave, 4, 5, 7, 8, 12, 47, 49–50, 52, 53, 83
mechanical distribution, see ridging	rain, 4, 6, 8, 42
melt pond, 6, 9, 10, 13–14, 41–50, 66, 75, 79, 80, 83,	reference
84	height, see height, reference
cesm, 42	humidity, see humidity, reference
level-ice, 46–49	temperature, see temperature, reference
topo, 14, 42–46	remapping
melt water, 3, 6, 8, 18, 41–49, 56, 59–61	incremental, 11, 20–30, 66, 70, 71
melting potential, 4, 8, 61	linear, see transport, thickness
mixed layer, 8, 15, 41, 55, 61, 66	reproducible, 75, 76
momentum equation, 31, 34–35, 38–39	restart, 64, 66, 69, 70, 73–74, 76, 83
monotonicity, 20–22, 27, 30	restoring, 16, 66, 69
MPI, 63–65, 67, 69, 70, 73, 75, 76, 81	revised EVP, see elastic-viscous-plastic
mushy, see thermodynamics	ridging, 3, 9–11, 14, 18, 30–33, 38, 66, 74, 80

INDEX 107

roughness, 6, 8–10	zero-layer, 52
	thickness
sails, 9	distribution, 3, 7, 10–12, 14, 21, 28–33, 41, 42,
salinity	65, 66, 70, 71
brine, 45, 49, 53, 55–60, 63	ice or snow, 10, 11, 18, 21-22, 27, 30, 34, 36,
ice, 8, 11, 12, 41, 52, 53, 55, 59–61	41, 47, 50, 61–63, 67
ocean, 4, 7, 8, 61	space, see transport, thickness
salt, see salinity	timers, 65, 73, 79, 83
sea level, 8, 10, 19, 42–45, 48, 49, 61, 62	tracers, 11, 12–20, 20–23, 30, 33, 42, 46, 47, 49, 65,
sensible heat, 4–7, 9, 49, <i>51</i> , 56	66, 69, 70, 74, 75, 79, <i>80–81</i> , 98, 99
shortwave, see radiation, shortwave	transport, 10, 11, 13, 14, 52, 80
slope, sea surface, 4, 5, 8, 34	horizontal, 3, 11–13, 16, 18, 20–27, 36, 37, 46,
snow, 41–63, 83	66, 70, 71, 74
infiltration by water, 3, 42–44, 46, 48	thickness, 11, 16, 28–30, 71, 74
melt, 8, 17–19, 42	vertical, 18, 58, 59, 61, 69, 75
precipitation, 3, 4, 6, 17, 61	tripole, see grid, tripole
snow-ice, 18, 62–63, 84	turbulent fluxes
solar, see radiation, shortwave	latent heat, see latent heat
solid fraction, see liquid fraction	sensible heat, see sensible heat
space-filling curve, 66, 76, 78, 82	wind stress, see wind stress
specific humidity, see humidity, specific	. 1 00 50 61
SST, see salinity, ocean	upwind, 20, 59, 61
stability, 5–7, 10, 31, 54, 55, 65, 71–72	van Leer, 22
state variables, 4, 5, 11, 27, 66	velocity
Stefan growth, 45, 47, 61, 84	Darcy, see Darcy flow
strain rate, 3, 32, <i>35–38</i>	friction, 51
strength, 3, 31–33, 38, 71, 72	ice, 3, 6, 8, 10, 12, 13, 20, 21, 23, 26, 33–41, 46,
stress	67
ice-ocean, see ice-ocean stress	piston, 16, 17
principal, 37, 73	volume
tensor, see internal stress	brine, 56
wind, see wind stress	ice or snow, 8, 11, 12, 14, 17, 18, 20, 22, 27–34,
subcycling, 34–40, 71–72, 76	45, 67
sublimation, see evaporation	pond, 13, 41–49
surface height, see sea level	polita, 13, 11 15
	water, open, see open water
temperature, 91	wind
atmospheric, 4, 5, 7, 47, 51	stress, 4–6, 7, 34
freezing, 7, 41, 45, 53	velocity, 4–6, 71
ice or snow, 11, 18, 30, 41–63, 69	WMO, 10, 11
ocean, 4, 7, 8, 51, 55, 61, 69	
potential, 4, 5	zenith angle, 7, 83
reference, 4, 7, 42	zero-layer, see thermodynamics
surface, 5–7, 11, 12, 22, 42, 45, 50, 51, 54, 55,	
58, 60, 72	
thermodynamics, 41–63, 66	
Bitz and Lipscomb, 52–56, 79	
mushy, 56–61, 79, 84	

# References

[1] T. L. Amundrud, H. Malling, and R. G. Ingram. Geometrical constraints on the evolution of ridged sea ice. *J. Geophys. Res.*, 109, 2004. C06005, doi:10.1029/2003JC002251.

- [2] K. C. Armour, L. Thompson C. M. Bitz, and E. C. Hunke. Controls on Arctic sea ice from rst-year and multi-year ice survivability. *J. Climate*, 24:2378–2390, 2011.
- [3] K. Arrigo, J. Kremer, and C. Sullivan. A simulated antarctic fast ice ecosystem. *J. Geophys. Res.*, 98:6929–6946, 1993.
- [4] S. P. S. Arya. A drag partition theory for determining the large-scale roughness parameter and wind stress on the arctic pack ice. *J. Geophys. Res.*, 80:3447–3454, 1975.
- [5] A. Assur. Composition of sea ice and its tensile strength. In *Arctic sea ice; conference held at Easton, Maryland, February 24–27, 1958*, volume 598 of *Publs. Natl. Res. Coun. Wash.*, pages 106–138, Washington, DC, US, 1958.
- [6] C. M. Bitz, M. M. Holland, A. J. Weaver, and M. Eby. Simulating the ice-thickness distribution in a coupled climate model. *J. Geophys. Res.–Oceans*, 106:2441–2463, 2001.
- [7] C. M. Bitz and W. H. Lipscomb. An energy-conserving thermodynamic sea ice model for climate study. *J. Geophys. Res.*—Oceans, 104:15669–15677, 1999.
- [8] S. Bouillon, T. Fichefet, V. Legat, and G. Madec. The revised elastic-viscous-plastic method. *Ocean Modelling*, page submitted, 2013.
- [9] B. P. Briegleb and B. Light. A Delta-Eddington multiple scattering parameterization for solar radiation in the sea ice component of the Community Climate System Model. NCAR Tech. Note NCAR/TN-472+STR, National Center for Atmospheric Research, 2007.
- [10] W. M. Connolley, J. M. Gregory, E. C. Hunke, and A. J. McLaren. On the consistent scaling of terms in the sea ice dynamics equation. *J. Phys. Oceanogr.*, 34:1776–1780, 2004.
- [11] C. Deal, M. Jin, S. Elliott, E. Hunke, M. Maltrud, and N. Jeffery. Large scale modeling of primary production and ice algal biomass within arctic sea ice in 1992. *J. Geophys. Res.*, 114:10.1029/2010JC006409, 2011.
- [12] J. K. Dukowicz and J. R. Baumgardner. Incremental remapping as a transport/advection algorithm. *J. Comput. Phys.*, 160:318–335, 2000.
- [13] J. K. Dukowicz, R. D. Smith, and R. C. Malone. A reformulation and implementation of the Bryan-Cox-Semtner ocean model on the connection machine. *J. Atmos. Oceanic Technol.*, 10:195–208, 1993.
- [14] J. K. Dukowicz, R. D. Smith, and R. C. Malone. Implicit free-surface method for the Bryan-Cox-Semtner ocean model. *J. Geophys. Res.–Oceans*, 99:7991–8014, 1994.
- [15] E. E. Ebert, J. L. Schramm, and J. A. Curry. Disposition of solar radiation in sea ice and the upper ocean. *J. Geophys. Res.—Oceans*, 100:15,965–15,975, 1995.
- [16] H. Eicken, T. C. Grenfell, D. K. Perovich, J. A. Richter-Menge, and K. Frey. Hydraulic controls of summer arctic pack ice albedo. *J. Geophys. Res.*, 109:C08007, doi:10.1029/2003JC001989, 2004.

[17] S. Elliott, C. Deal, G. Humphries, E. Hunke, M. Jin N. Jeffery and, M. Levasseur, and J. Stefels. Pan-Arctic simulation of coupled nutrient-sulfur cycling due to sea ice biology. *J. Geophys. Res.—Biogeosciences*, page submitted, 2012.

- [18] D. L. Feltham, N. Untersteiner, J. S. Wettlaufer, and M. G. Worster. Sea ice is a mushy layer. *Geophys. Res. Lett.*, 33:L14501, doi:10.1029/2006GL026290, 2006.
- [19] G. M. Flato and W. D. Hibler. Ridging and strength in modeling the thickness distribution of Arctic sea ice. *J. Geophys. Res.–Oceans*, 100:18611–18626, 1995.
- [20] D. Flocco and D. L. Feltham. A continuum model of melt pond evolution on Arctic sea ice. *J. Geophys. Res.*, 112:C08016, doi:10.1029/2006JC003836, 2007.
- [21] D. Flocco, D. L. Feltham, and A. K. Turner. Incorporation of a physically based melt pond scheme into the sea ice component of a climate model. *J. Geophys. Res.*, 115:C08012, doi:10.1029/2009JC005568, 2010.
- [22] D. Flocco, D. Schroeder, D. L. Feltham, and E. C. Hunke. Impact of melt ponds on arctic sea ice simulations from 1990 to 2007. *J. Geophys. Res.*, 2012. submitted.
- [23] H.E. Garcia, R.A. Locarnini, T. P. Boyer, and J. I. Antonov. World Ocean Atlas 2005, Vol. 4, Nutrients (Phosphate, Nitrate, Silicate). NOAA Atlas NESDIS 64, NOAA, 2006.
- [24] C. A. Geiger, W. D. Hibler, and S. F. Ackley. Large-scale sea ice drift and deformation: Comparison between models and observations in the western Weddell Sea during 1992. *J. Geophys. Res.–Oceans*, 103:21893–21913, 1998.
- [25] K. M. Golden, H. Eicken, A. L. Heaton, J. Miner, D. J. Pringle, and J. Zhu. Thin and thinner: Sea ice mass balance measurements during SHEBA. *Geophys. Res. Lett.*, 34:L16501, doi:10.1029/2007GL030447, 2007.
- [26] W. D. Hibler. A dynamic thermodynamic sea ice model. J. Phys. Oceanogr., 9:817–846, 1979.
- [27] W. D. Hibler. Modeling a variable thickness sea ice cover. Mon. Wea. Rev., 108:1943–1973, 1980.
- [28] M. M. Holland, D. A. Bailey, B. P. Briegleb, B. Light, and E. Hunke. Improved sea ice shortwave radiation physics in CCSM4: The impact of melt ponds and aerosols on arctic sea ice. *J. Clim.*, 25:14131430, 2012.
- [29] E. C. Hunke. Viscous-plastic sea ice dynamics with the EVP model: Linearization issues. *J. Comput. Phys.*, 170:18–38, 2001.
- [30] E. C. Hunke and C. M. Bitz. Age characteristics in a multidecadal arctic sea ice simulation. *J. Geophys. Res.*, 114:C08013, doi:10.1029/2008JC005186, 2009.
- [31] E. C. Hunke and J. K. Dukowicz. An elastic-viscous-plastic model for sea ice dynamics. *J. Phys. Oceanogr.*, 27:1849–1867, 1997.
- [32] E. C. Hunke and J. K. Dukowicz. The Elastic-Viscous-Plastic sea ice dynamics model in general orthogonal curvilinear coordinates on a sphere—Effect of metric terms. *Mon. Wea. Rev.*, 130:1848– 1865, 2002.
- [33] E. C. Hunke and J. K. Dukowicz. The sea ice momentum equation in the free drift regime. Technical Report LA-UR-03-2219, Los Alamos National Laboratory, 2003.

[34] E. C. Hunke, D. A. Hebert, and O. Lecomte. Level-ice melt ponds in the Los Alamos Sea Ice Model, CICE. *Ocean Mod.*, pages published online, http://dx.doi.org/10.1016/j.ocemod.2012.11.008, 2012.

- [35] E. C. Hunke and Y. Zhang. A comparison of sea ice dynamics models at high resolution. *Mon. Wea. Rev.*, 127:396–408, 1999.
- [36] M. Jin, C. J. Deal, J. Wang, K. H. Shin, N. Tanaka, T. E. Whitledge, S. H. Lee, and R. R. Gradinger. Controls of the landfast ice-ocean ecosystem offshore Barrow, Alaska. *Ann. Glaciol.*, 44:63–72, 2006.
- [37] R. E. Jordan, E. L. Andreas, and A. P. Makshtas. Heat budget of snow-covered sea ice at North Pole 4. *J. Geophys. Res.–Oceans*, 104:7785–7806, 1999.
- [38] B. G. Kauffman and W. G. Large. The CCSM coupler, version 5.0.1. Technical note, National Center for Atmospheric Research, August 2002. http://www.ccsm.ucar.edu/models/.
- [39] D. Lavoie, K. Denman, and C. Michel. Modeling ice algal growth and decline in a seasonally ice-covered region of the Arctic (Resolute Passage, Canadian Archipelago). *J. Geophys. Res.*, 110:C11009, doi:10.1029/2005JC002922, 2005.
- [40] W. H. Lipscomb. *Modeling the Thickness Distribution of Arctic Sea Ice*. PhD thesis, Dept. of Atmospheric Sciences, Univ. of Washington, Seattle, 1998.
- [41] W. H. Lipscomb. Remapping the thickness distribution in sea ice models. *J. Geophys. Res.–Oceans*, 106:13,989–14,000, 2001.
- [42] W. H. Lipscomb and E. C. Hunke. Modeling sea ice transport using incremental remapping. *Mon. Wea. Rev.*, 132:1341–1354, 2004.
- [43] W. H. Lipscomb, E. C. Hunke, W. Maslowski, and J. Jakacki. Improving ridging schemes for high-resolution sea ice models. *J. Geophys. Res.—Oceans*, 112:C03S91, doi:10.1029/2005JC003355, 2007.
- [44] P. Lu, Z. Li, B. Cheng, and M. Lepparanta. A parameterization of the ice-ocean drag coefficient. *J. Geophys. Res.*, 116:10.1029/2010JC006878, 2011.
- [45] C. Lüpkes, V. M. Gryanik, J. Hartmann, and E. L. Andreas. A parametrization, based on sea ice morphology, of the neutral atmospheric drag coefficients for weather prediction and climate models. *J. Geophys. Res.*, 117:10.1029/2012JD017630, 2012.
- [46] G. A. Maykut. Large-scale heat exchange and ice production in the central Arctic. *J. Geophys. Res.*—*Oceans*, 87:7971–7984, 1982.
- [47] G. A. Maykut and M. G. McPhee. Solar heating of the Arctic mixed layer. *J. Geophys. Res.–Oceans*, 100:24691–24703, 1995.
- [48] G. A. Maykut and D. K. Perovich. The role of shortwave radiation in the summer decay of a sea ice cover. *J. Geophys. Res.*, 92(C7):7032–7044, 1987.
- [49] G. A. Maykut and N. Untersteiner. Some results from a time dependent thermodynamic model of sea ice. *J. Geophys. Res.*, 76:1550–1575, 1971.
- [50] R. J. Murray. Explicit generation of orthogonal grids for ocean models. *J. Comput. Phys.*, 126:251–273, 1996.

[51] Dirk Notz. *Thermodynamic and Fluid-Dynamical Processes in Sea Ice*. PhD thesis, University of Cambridge, UK, 2005.

- [52] N. Ono. Specific heat and heat of fusion of sea ice. In H. Oura, editor, *Physics of Snow and Ice*, volume 1, pages 599–610. Institute of Low Temperature Science, Hokkaido, Japan, 1967.
- [53] C. L. Parkinson and W. M. Washington. A large-scale numerical model of sea ice. *J. Geophys. Res.*, 84:311–337, 1979.
- [54] D. J. Pringle, H. Eicken, H. J. Trodahl, and L. G. E. Backstrom. Thermal conductivity of landfast Antarctic and Arctic sea ice. *J. Geophys. Res.*, 112:C04017, doi:10.1029/2006JC003641, 2007.
- [55] A. Rosati and K. Miyakoda. A general circulation model for upper ocean simulation. *J. Phys. Oceanogr.*, 18:1601–1626, 1988.
- [56] D. A. Rothrock. The energetics of the plastic deformation of pack ice by ridging. *J. Geophys. Res.*, 80:4514–4519, 1975.
- [57] E. M. Schulson. Brittle failure of ice. Eng. Fract. Mech., 68:1839–1887, 2001.
- [58] W. Schwarzacher. Pack ice studies in the Arctic Ocean. J. Geophys. Res., 64:2357–2367, 1959.
- [59] A. J. Semtner. A model for the thermodynamic growth of sea ice in numerical investigations of climate. *J. Phys. Oceanogr.*, 6:379–389, 1976.
- [60] G. Siedler and H. Peters. Physical properties (general) of sea water, in landolt-börnstein: Numerical data and functional relationships in science and technology. *New Series / Oceanography*, 3a:233–264, 1986.
- [61] R. D. Smith, J. K. Dukowicz, and R. C. Malone. Parallel ocean general circulation modeling. *Physica D*, 60:38–61, 1992.
- [62] R. D. Smith, S. Kortas, and B. Meltz. Curvilinear coordinates for global ocean models. Technical Report LA-UR-95-1146, Los Alamos National Laboratory, 1995.
- [63] M. Steele. Sea ice melting and floe geometry in a simple ice-ocean model. *J. Geophys. Res.*, 97(C11):17729–17738, 1992.
- [64] M. Steele, J. Zhang, D. Rothrock, and H. Stern. The force balance of sea ice in a numerical model of the Arctic Ocean. *J. Geophys. Res.–Oceans*, 102:21061–21079, 1997.
- [65] J. Stefels, M. Steinke, S. Turner, G. Malin, and S. Belviso. Environmental constraints on the production and removal of the climatically active gas dimethylsuphide. *Biogeochemistry*, 83:245–275, 2007.
- [66] A. H. Stroud. *Approximate Calculation of Multiple Integrals*. Prentice-Hall, Englewood Cliffs, New Jersey, 1971. 431 pp.
- [67] P. D. Taylor and D. L. Feltham. A model of melt pond evolution on sea ice. *J. Geophys. Res.*, 109:C12007, doi:10.1029/2004JC002361, 2004.
- [68] A. S. Thorndike, D. A. Rothrock, G. A. Maykut, and R. Colony. The thickness distribution of sea ice. J. Geophys. Res., 80:4501–4513, 1975.
- [69] H. J. Trodahl, S. O. F. Wilkinson, M. J. McGuiness, and T. G. Haskell. Thermal conductivity of sea ice: dependence on temperature and depth. *Geophys. Res. Lett.*, 28:1279–1282, 2001.

[70] M. Tsamados, D. L. Feltham, D. Schroeder, D. Flocco, S. L. Farrell, N. T. Kurtz, S. W. Laxon, and S. Bacon. Impact of variable atmospheric and oceanic form drag on simulations of arctic sea ice. *J. Geophys. Res. Oceans*. In review.

- [71] M. Tsamados, D. L. Feltham, and A. V. Wilchinsky. Impact of a new anisotropic rheology on simulations of arctic sea ice. *J. Geophys. Res. Oceans*, 118:91–107, 2013.
- [72] A. K. Turner, E. C. Hunke, and C. M. Bitz. Two modes of sea-ice gravity drainage: a parameterization for large-scale modeling. *J. Geophys. Res.*, 118:2279–2294, doi:10.1002/jgrc.20171, 2013.
- [73] N. Untersteiner. Calculations of temperature regime and heat budget of sea ice in the Central Arctic. *J. Geophys. Res.*, 69:4755–4766, 1964.
- [74] J. Weiss and E. M. Schulson. Coulombic faulting from the grain scale to the geophysical scale: lessons from ice. *J. of Physics D: Applied Physics*, 42:doi 10.1088/0022–3727/42/21/214, 2009.
- [75] A. V. Wilchinsky and D. Feltham. Modelling the rheology of sea ice as a collection of diamond-shaped oes. *J. Non-Newtonian Fluid Mech.*, 138:22–32, 2006.
- [76] A. V. Wilchinsky and D. L. Feltham. Dependence of sea ice yield-curve shape on ice thickness. *J. Phys. Oceanogr.*, 34(12):2852–2856, 2004.