
Practical 1: Configure Routers for Syslog, NTP and SSH operation

Topology:



Addressing Table:

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	gig0/0	192.168.1.1	255.255.255.0	N/A
	Se0/1/0	10.1.1.1	255.255.255.252	N/A
R2	Se0/1/0	10.1.1.2	255.255.255.252	N/A
IX2	Se0/1/1	10.2.2.2	255.255.255.252	N/A
R3	gig0/0	192.168.3.1	255.255.255.0	N/A
	Se0/1/0	10.2.2.1	255.255.255.252	N/A
PC-A	NIC	192.168.1.5	255.255.255.0	192.168.1.1
PC-B	NIC	192.168.1.6	255.255.255.0	192.168.1.1
PC-C	NIC	192.168.3.5	255.255.255.0	192.168.3.1

Objectives:

- Configure OSPF MD5 authentication.
- Configure NTP.
- Configure routers to log messages to the syslog server.
- Configure R3 to support SSH connections.

■ Configure Router with password

Step 1: Configure password for vty lines

Execute Command on all routers

R(config) # line vty 0 4

R(config-line) #password vtypa55

R(config-line) #login

Step 2: Configure secret on router

Execute Command on all routers

R(config) # enable secret enpa55

Step 3: Configure OSPF on routers

R1(config) #router ospf 1

R1(config-router) #network 192.168.1.0 0.0.0.255 area 0

R1(config-router) #network 10.1.1.0 0.0.0.3 area 0

R2(config) #router ospf 1

R2(config-router) #network 10.1.1.0 0.0.0.3 area 0

R2(config-router) #network 10.2.2.0 0.0.0.3 area 0

R3(config) #router ospf 1

R3(config-router) #network 192.168.3.0 0.0.0.255 area 0

R3(config-router) #network 10.2.2.0 0.0.0.3 area 0

Step 4: Test Connectivity

PC-A > ping 192.168.3.5

Successful

PC-B > ping 192.168.3.5

Successful

Part 1: Configure OSPF MD5 Authentication

Step 1: Test connectivity. All devices should be able to ping all other IP addresses.

Step 2: Configure OSPF MD5 authentication for all the routers in area 0.

R1(config)# router ospf 1

R1(config-router)# area 0 authentication message-digest

R2(config)# router ospf 1

R2(config-router)# area 0 authentication message-digest

R3(config)# router ospf 1

R3(config-router)# area 0 authentication message-digest

Step 3: Configure the MD5 key for all the routers in area 0. Configure an MD5 key on the serial interfaces on R1, R2 and R3. Use the password MD5pa55 for key 1.

R1(config)# interface s0/1/0

R1(config-if)# ip ospf message-digest-key 1 md5 MD5pa55

R2(config)# interface s0/1/0

R2(config-if)# ip ospf message-digest-key 1 md5 MD5pa55

R2(config-if)# interface s0/1/1

R2(config-if)# ip ospf message-digest-key 1 md5 MD5pa55

R3(config)# interface s0/1/0

R3(config-if)# ip ospf message-digest-key 1 md5 MD5pa55

Step 4: Verify configurations.

a. Verify the MD5 authentication configurations using the commands show ip ospf interface.

b. Verify end-to-end connectivity.

Output should be shown in all the routers:

R# show ip ospf interface

Message-digest Authentication Enabled

Youngest key ID is 1

Part 2: Configure NTP

Step 1: Enable NTP authentication on PC-A.

- a. On PC-A, click NTP under the Services tab to verify NTP service is enabled.
- b. To configure NTP authentication, click Enable under Authentication. Use key 1 and password NTPpa55

for authentication.

Step 2: Configure R1, R2, and R3 as NTP clients.

R1(config)# ntp server 192.168.1.5

STUD--Talks: Follow us on **with Open to the STUD--Talks:** Follow us on **your Open to the STUD--Talks:** Follow us on the **your Open to the STUD--Talks:** Follow us on the **your Open to the STUD--Talks:** Follow us on the **your Open to the STUD--Talks:** Follow us on the **your Open to the STUD--Talks:** Follow us on the **your Open to the**

R2(config)# ntp server 192.168.1.5

R3(config)# ntp server 192.168.1.5

Verify client configuration using the command show ntp status.

Step 3: Configure routers to update hardware clock. Configure R1, R2, and R3 to periodically update the hardware clock with the time learned from NTP.

R1(config)# ntp update-calendar

R2(config)# ntp update-calendar

R3(config)# ntp update-calendar

Verify that the hardware Clock was Updated

R# show clock

Step 4: Configure NTP authentication on the routers. Configure NTP authentication on R1, R2, and R3 using key 1 and password NTPpa55.

R1(config)# ntp authenticate

R1(config)# ntp trusted-key 1

R1(config)# ntp authentication-key 1 md5 NTPpa55

R2(config)# ntp authenticate

R2(config)# ntp trusted-key 1

R2(config)# ntp authentication-key 1 md5 NTPpa55

R3(config)# ntp authenticate

R3(config)# ntp trusted-key 1

R3(config)# ntp authentication-key 1 md5 NTPpa55

Step 5: Configure routers to timestamp log messages.

Execute commands on all routers

R1(config)# service timestamps log datetime msec

R2(config)# service timestamps log datetime msec

R3(config)# service timestamps log datetime msec

Part 3: Configure Routers to Log Messages to the Syslog Server

Step 1: Configure the routers to identify the remote host (Syslog Server) that will receive logging messages.

R1(config)# logging host 192.168.1.6

R2(config)# logging host 192.168.1.6

R3(config)# logging host 192.168.1.6

The router console will display a message that logging has started.

Step 2: Verify logging configuration.

Use the command

R# show logging

to verify logging has been enabled.

Step 3: Examine logs of the Syslog Server.

From the Services tab of the Syslog Server's dialogue box, select the Syslog services button. Observe the logging messages received from the routers.

Note: Log messages can be generated on the server by executing commands on the router. For example, entering and exiting global configuration mode will generate an informational configuration message. You may need to click a different service and then click Syslog again to refresh the message display.



Part 4: Configure R3 to Support SSH Connections

Step 1: Configure a domain name of consecurity.com on R3.

R3(config)# ip domain-name ccnasecurity.com

Step 2: Configure users for login to the SSH server on R3.

Create a user ID of SSHadmin with the highest possible privilege level and a secret password of sshpa55.

R3(config)# username SSHadmin privilege 15 secret sshpa55

Step 3: Configure the incoming vty lines on R3. Use the local user accounts for mandatory login and validation. Accept only SSH connections.

R3(config)# line vty 0 4

R3(config-line)# login local

R3(config-line)# transport input ssh

Step 4: Erase existing key pairs on R3. Any existing RSA key pairs should be erased on the router.

R3(config)# crypto key zeroize rsa

Note: If no keys exist, you might receive this message: % No Signature RSA Keys found in configuration.

Step 5: Generate the RSA encryption key pair for R3.

The router uses the RSA key pair for authentication and encryption of transmitted SSH data. Configure the RSA keys with a modulus of 1024. The default is 512, and the range is from 360 to 2048.

R3(config)# crypto key generate rsa

The name for the keys will be: R3.ccnasecurity.com



Choose the size of the key modulus in the range of 360 to 2048 for your General Purpose Keys. Choosing a key modulus greater than 512 may take a few minutes

How many bits in the modulus [512]: 1024

% Generating 1024 bit RSA keys, keys will be non-exportable...[OK]

Note: The command to generate RSA encryption key pairs for R3 in Packet Tracer differs from those used in the lab.

Step 6: Verify the SSH configuration.

Use the show ip ssh command to see the current settings. Verify that the authentication timeout and retries are at their default values of 120 and 3.

R3# show ip ssh

SSH enabled-version 1.99

Authentication time out: 120 secs; Authentication retries: 3

R#

STUD--Talks

Step 7: Configure SSH timeouts and authentication parameters.

The default SSH timeouts and authentication parameters can be altered to be more restrictive. Set the timeout to 90 seconds, the number of authentication retries to 2, and the version to 2.

R3(config)# ip ssh time-out 90

R3(config)# ip ssh authentication-retries 2

R3(config)# ip ssh version 2

Verify the SSH configuration

R3# show ip ssh

SSH enabled-version 2.0

Authentication time out: 90 secs; Authentication retries : 2

R#

Step 8: Attempt to connect to R3 via Telnet from PC-C.

Open the Desktop of PC-C. Select the Command Prompt icon. From PC-C, enter the command to connect to

R3 via Telnet.

PC> telnet 192.168.3.1

This connection should fail because R3 has been configured to accept only SSH connections on the virtual terminal lines.

Step 9: Connect to R3 using SSH on PC-C.

Open the Desktop of PC-C. Select the Command Prompt icon. From PC-C, enter the command to connect to R3 via SSH. When prompted for the password, enter the password configured for the administrator shpa55.

PC> ssh -1 SSHadmin 192.168.3.1

Password: sshpa55

STUD--Talks

Step 10: Connect to R3 using SSH on R2.


To troubleshoot and maintain R3, the administrator at the ISP must use SSH to access the router CLI. From the CLI of R2, enter the command to connect to R3 via SSH version 2 using the SSHadmin user account. When prompted for the password, enter the password configured for the administrator: ciscosshpa55.

R2# ssh -v 2 -l SSHadmin 10.2.2.1

Password: sshpa55

Practical 2: Configure AAA Authentication on Cisco routers

Topology:



Addressing Table:

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	gig0/0	192.168.1.1	255.255.255.0	N/A
PC0	NIC	192.168.1.2	255.255.255.0	192.168.1.1
PC1	NIC	192.168.1.3	255.255.255.0	192.168.1.1

Objectives:

- Configure a local user account on R1 and configure authenticate on the console and vty lines using local AAA.
- Verify local AAA authentication from the R1 console and the PC0 client and PC1 Client.

■ Configure Router:

Step 1: Configure password for vty lines

R1(config) # line vty 0 4

R1(config-line) #password vtypa55

R1(config-line) #login

Step 2: Configure secret on router

R1(config) # enable secret enpa55

Step 3: Configure OSPF on routers

R1(config) #router ospf 1

R1(config-router) #network 192.168.1.0 0.0.0.255 area 0

Step 4: Configure OSPF MD5 authentication for all router in area 0

R1(config) #router ospf 1

R1(config-router)# area 0 authentication message-digest

Step 5: Configure MD5 key for all routers in area 0

R1(config)# int gig0/0

R1(config-if)# ip ospf message-digest-key 1 md5 pa55

Step 6: Verify configurations.

- a. Verify the MD5 authentication configurations using the commands show ip ospf interface.
- b. Verify end-to-end connectivity.

Output should be shown in all the routers:

R1# show ip ospf interface

Message-digest Authentication Enabled

Youngest key ID is 1

Part 1: Configure Local AAA Authentication for Console Access on R1

Step 1: Test Connectivity

PC0 > ping 192.168.1.3

Successful

PC1 > ping 192.168.1.2

Successful

Step 2: Configure Local username on R1

R1(config)# username admin secret adminpa55

Step 3: Configure local AAA authentication for console access on R1.

R1(config)# aaa new-model

R1(config)# aaa authentication login default local

Step 4: Configure the line console to use the defined AAA authentication method.

R1(config)# line console 0

R1(config-line)# login authentication default

Step 5: Verify the AAA authentication method.

R1(config-line)# end

User Access Verification

Username: admin

Password: adminpa55

R1>

Part 2: Configure Local AAA Authentication for vty Lines on R1

Step 1: Configure domain name and crypto key for use with SSH.

R1(config)# ip domain-name ccnasecurity.com

R1(config)# crypto key generate rsa

How many bits in the modulus [512]: 1024

Step 2: Configure a named list AAA authentication method for the vty lines on R1.

R1(config)# aaa authentication login SSH-LOGIN local

Step 3: Configure the vty lines to use the defined AAA authentication method.

R1(config)# line vty 0 4

R1(config-line)# login authentication SSH-LOGIN

R1(config-line)# transport input ssh

R1(config-line)# end

Step 4: Verify the AAA authentication method.

PC0> ssh -1 Admin 192.168.1.1

Password: adminpa55

R1>


PC1> ssh –1 Admin 192.168.1.1

Password: adminpa55

R1>

Practical 3: Configuring Extended ACLs

A]
Topology:



STUD--Talks

Addressing Table:

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	gig0/0	172.22.34.65	255.255.255.224	N/A
	gig0/1	172.22.34.97	255.255.255.240	N/A
	gig0/2	172.22.34.1	255.255.255.192	N/A
Server	NIC	172.22.34.62	255.255.255.192	172.22.34.1
PC1	NIC	172.22.34.66	255.255.255.224	172.22.34.65
PC2	NIC	172.22.34.98	255.255.255.240	172.22.34.97

Objectives:

- Configure, Apply and Verify an Extended Numbered ACL
- Configure, Apply and Verify an Extended Named ACL

Scenario:

- o PC1 Should be allowed only FTP access
- o PC2 Should be allowed only web access
- o Both PCs must ping server but not each other's

■ Configure Router:

Step 1: Configure password for vty lines

R1(config) # line vty 0 4

R1(config-line) #password vtypa55

R1(config-line) #login

Step 2: Configure secret on router

R1(config) # enable secret enpa55

Part 1: Configure, Apply and Verify an Extended Numbered ACL

Step 1: Configure an ACL to permit FTP and ICMP. (Use Router 2911)

R1(config)# access-list 100 permit tcp 172.22.34.64 0.0.0.31 host

172.22.34.62 eq ftp

R1(config)# access-list 100 permit icmp 172.22.34.64 0.0.0.31 host

172.22.34.62

Step 2: Apply the ACL on the correct interface to filter traffic.

R1(config)# int gig 0/0

R1(config-if)# ip access-group 100 in



Step 3: Verify the ACL implementation.

a. Ping from PC1 to Server.

PC1> ping 172.22.34.62

(Successful)

b. FTP from PC1 to Server. The username and password are both cisco.

PC1> ftp 172.22.34.62

c. Exit the FTP service of the Server.

ftp> quit

d. Ping from PC1 to PC2.

PC1> ping 172.22.34.98

(Unsuccessful) destination host unreachable

Part 2: Configure, Apply and Verify an Extended Named ACL

Step 1: Configure an ACL to permit HTTP access and ICMP.

R1(config)# ip access-list extended HTTP_ONLY

R1(config-ext-nacl)# permit tcp 172.22.34.96 0.0.0.15 host 172.22.34.62 eq www

R1(config-ext-nacl)# permit icmp 172.22.34.96 0.0.0.15 host 172.22.34.62

Step 2: Apply the ACL on the correct interface to filter traffic.

R1(config)# int gig0/1

R1(config-if)# ip access-group HTTP_ONLY in

Step 3: Verify the ACL implementation.

a. Ping from PC2 to Server.

PC2> ping 172.22.34.62

(Successful)

b. FTP from PC2 to Server

PC2> ftp 172.22.34.62

(Unsuccessful)

c. Open the web browser on PC2.

URL -> http://172.22.34.62

(Successful)

d. Ping from PC2 to PC1.


PC> ping 172.22.34.66

(Unsuccessful)



B]

Topology:



Addressing Table:

Device	Interface	IP Address	Subnet Mask	Default Gateway
RTA	gig0/0	10.101.117.49	255.255.255.248	N/A
	gig0/1	10.101.117.33	255.255.255.240	N/A
	gig0/2	10.101.117.1	255.255.255.224	N/A
PCA	NIC	10.101.117.51	255.255.255.248	10.101.117.49
PCB	NIC	10.101.117.35	255.255.255.240	10.101.117.33
SWA	VLAN 1	10.101.117.50	255.255.255.248	10.101.117.49
SWB	VLAN 1	10.101.117.34	255.255.255.240	10.101.117.33
SWC	VLAN 1	10.101.117.2	255.255.255.224	10.101.117.1

Objectives:

Configure, Apply and Verify an Extended Numbered ACL

Scenario:

- Device on one LAN are allowed to remotely access device in another LAN using SSH protocol
- o Besides ICMP all traffic from other network is denied

■ Configure Switch and Router:

Step 1: Configure the IP address on switch

SWA(config)# int vlan 1

SWA(config-if)# ip address 10.101.117.50 255.255.255.248

SWA(config-if)# no shut

SWA(config-if)# ip default-gateway 10.101.117.49

SWB(config)# int vlan 1

SWB(config-if)# ip address 10.101.117.34 255.255.255.240

SWB(config-if)# no shut

SWB(config-if)# ip default-gateway 10.101.117.33

SWC(config)# int vlan 1

SWC(config-if)# ip address 10.101.117.2 255.255.255.224

SWC(config-if)# no shut

SWC(config-if)# ip default-gateway 10.101.117.1

Step 2: Configure the secret on router and switch

RTA/SW(config)# enable secret enpa55

Step 3: Configure the console password on router and switch

RTA/SW(config)# line console 0

RTA/SW(config)# password tyit

RTA/SW(config)# login

Step 4: Test connectivity

Ping from PCA to PC-B.

PCA>ping 10.101.117.35

(Successful)

Ping from PCA to SWC.

PCA>ping 10.101.117.2

(Successful)

Ping from PCB to SWC.

PCB>ping 10.101.117.2

(Successful)

Part 1: Configure Switch and Router to support SSH Connection

Step 1: Configure domain name and crypto key for use with SSH.

RTA/SW(config)# ip domain-name ccnasecurity.com

Step 2: Configure users to login to SSH

RTA/SW(config)# username admin secret adminpa55

Step 3: Configure incoming vty lines

RTA/SW(config)# line vty 0 4

RTA/SW(config-line)# login local

RTA/SW(config)# crypto key generate rsa

How many bits in the modulus [512]: 1024

Step 4: Verify the SSH Connection

PCA> ssh -1 Admin 10.101.117.34

Password: adminpa55

SWB>

PCA> ssh -1 Admin 10.101.117.2

Password: adminpa55

SWC>

PCB> ssh -1 Admin 10.101.117.50

Password: adminpa55

SWA>

PCB> ssh -1 Admin 10.101.117.2

Password: adminpa55

SWC>

SWC> ssh -1 Admin 10.101.117.50

Password: adminpa55

SWA>

SWC> ssh -1 Admin 10.101.117.34

Password: adminpa55

SWB>

SWB> exit

Part 2: Configure, Apply and Verify an Extended Numbered ACL

Step 1: Configure the extended ACL.

RTA(config)# access-list 199 permit tcp 10.101.117.32 0.0.0.15 10.101.117.0 0.0.0.31 eq 22

RTA(config)# access-list 199 permit icmp any any

Step 2: Apply the extended ACL.

RTA(config)# int gig0/2

RTA(config-if)# ip access-group 199 out

Step 3: Verify the extended ACL implementation.

a. Ping from PCB to all of the other IP addresses in the network.

PCB> ping 10.101.117.51

(Successful)

PCB> ping 10.101.117.2

(Successful)

b. SSH from PCB to SWC.

PCB> ssh -1 Admin 10.101.117.2

Password:adminpa55

SWC>



c. Exit the SSH session to SWC

SWC>exit

d. Ping from PCA to all of the other IP addresses in the network.

PCA> ping 10.101.117.35

(Successful)

PCA> ping 10.101.117.2

(Successful)

e. SSH from PCA to SWC

PCA> ssh -1 Admin 10.101.117.2

Connection timed out. Remote host not responding

f. SSH from PCA to SWB.

PCA> ssh -1 Admin 10.101.117.34

Password: adminpa55

SWB>

g. After logging into SWB, do not log out. SSH to SWC in privileged EXEC mode.

SWB# ssh -1 Admin 10.101.117.2

Password: adminpa55

SWC>






Practical 4: Configure IP ACLs to Mitigate Attacks

A]

Topology:



Addressing Table:

Device	Interface	IP Address	Subnet Mask	Default Gateway
	gig0/0	192.168.1.1	255.255.255.0	N/A
R1	Se0/1/0 (DCE)	10.1.1.1	255.255.255.252	N/A
	Se0/1/0	10.1.1.2	255.255.255.252	N/A
R2	Se0/1/1 (DCE)	10.2.2.2	255.255.255.252	N/A
	Lo0	192.168.2.1	255.255.255.0	N/A
R3	gig0/0	192.168.3.1	255.255.255.0	N/A
	Se0/1/0	10.2.2.1	255.255.255.252	N/A
PC-A	Fa0	192.168.1.3	255.255.255.0	192.168.1.1
PC-C	Fa0	192.168.3.3	255.255.255.0	192.168.3.1

Objectives:

- Verify connectivity among devices before firewall configuration.
- Use ACLs to ensure remote access to the routers is available only from management station PC-C.
- Configure ACLs on R1 and R3 to mitigate attacks.
- Verify ACL functionality.

■ Configure Router:

Step 1: Configure secret on router

R(config) # enable secret enpa55

Step 2: Configure console password on router

R(config) # line console 0

R(config-line) #password conpa55

R(config-line) #login

Step 3: Configure SSH login on router

Execute command on all routers

R(config)# ip domain-name ccnasecurity.com

R(config)# username admin secret adminpa55

R(config)# line vty 0 4

R(config-line)# login local

R(config-line)# crypto key generate rsa

How many bits in the modulus [512]: 1024

Step 4: Configure loop back address on Router 2

R2(config)#int loopback 0

R2(config-if)#ip address 192.168.2.1 255.255.255.0

R2(config-if)# no shut

Step 5: Configure static routing on routers

Execute command on all routers

R1(config)#ip route 192.168.3.0 255.255.255.0 10.1.1.2

STUD--Talks: Follow us on **with One of the STUD--Talks:** Follow us on **state of the STUD--Talks:** Follow us on the **state of the STUD--Talks:** Follow us of the **state of the STUD--Talks:**

R1(config)#ip route 10.2.2.0 255.255.255.252 10.1.1.2

R1(config)#ip route 192.168.2.0 255.255.255.0 10.1.1.2

R2(config)#ip route 192.168.1.0 255.255.255.0 10.1.1.1

R2(config)#ip route 192.168.3.0 255.255.255.0 10.2.2.1

R3(config)#ip route 192.168.1.0 255.255.255.0 10.2.2.2

R3(config)#ip route 192.168.2.0 255.255.255.0 10.2.2.2

R3(config)#ip route 10.1.1.0 255.255.255.0 10.2.2.2

Part 2: Verify Basic Network Connectivity

Step 1: From PC-A, verify connectivity to PC-C and R2.

PCA> ping 192.168.3.3

(Successful)

PCA> ping 192.168.2.1

(Successful)

PCA> ssh -1 admin 192.168.2.1

Password: adminpa55

R2>exit

Step 2: From PC-C, verify connectivity to PC-A and R2.

PCC> ping 192.168.1.3

(Successful)

PCC> ping 192.168.2.1

(Successful)

PCC> ssh -l admin 192.168.2.1

Password: adminpa55

R2>exit

Open a web browser to the PC-A server (192.168.1.3) to display the web page.

Close the browser when done.

Desktop->Web Browser->192.168.1.3

(Successful)

Part 3: Secure Access to Routers

Step 1: Configure ACL 10 to block all remote access to the routers except from PC-C

Execute command on all routers

R(config)# access-list 10 permit host 192.168.3.3

Step 2: Apply ACL 10 to ingress traffic on the VTY lines.

Execute command on all routers

R(config)# line vty 0.4

R(config-line)# access-class 10 in

Step 3: Verify exclusive access from management station PC-C.

PCC> ssh -1 admin 192.168.2.1

Password: adminpa55

R2>exit

Step 4: Verify denial from PC-A.

PCA> ssh -l admin 192.168.2.1

Connection refused by remote host

Part 4: Create a Numbered IP ACL 120 on R1

Step 1: Verify that PC-C can access the PC-A via HTTPS using the web browser.

Be sure to disable HTTP and enable HTTPS on server PC-A in Services tab.

Step 2: Configure ACL 120 to specifically permit and deny the specified traffic.

R1(config)# access-list 120 permit udp any host 192.168.1.3 eq domain

R1(config)# access-list 120 permit tcp any host 192.168.1.3 eq smtp

R1(config)# access-list 120 permit tcp any host 192.168.1.3 eq ftp

R1(config)# access-list 120 deny tcp any host 192.168.1.3 eq 443

R1(config)# access-list 120 permit tcp host 192.168.3.3 host 10.1.1.1 eq 22

Step 3: Apply the ACL to interface

R1(config)# int se0/1/0

R1(config-if)# ip access-group 120 in

Step 4: Verify that PC-C cannot access PC-A via HTTPS using the web browser.

Desktop->Web Browser->192.168.1.3

(Unsuccessful) Request timed out

Part 5: Modify an Existing ACL on R1

Step 1: Verify that PC-A cannot successfully ping the loopback interface on R2.

PCA> ping 192.168.2.1

(Unsuccessful) Request timed out

Step 2: Make any necessary changes to ACL 120 to permit and deny the specified traffic.

R1(config)# access-list 120 permit icmp any any echo-reply

R1(config)# access-list 120 permit icmp any any unreachable

R1(config)# access-list 120 deny icmp any any

R1(config)# access-list 120 permit ip any any

Step 3: Verify that PC-A can successfully ping the loopback interface on R2.

PCA> ping 192.168.2.1 (Successful)

Part 6: Create a Numbered IP ACL 110 on R3

Step 1: Configure ACL 110 to permit only traffic from the inside network.

R3(config)# access-list 110 permit ip 192.168.3.0 0.0.0.255 any

Step 2: Apply the ACL to interface

R3(config)# int gig0/1

R3(config-if)# ip access-group 110 in

Part 7: Create a Numbered IP ACL 100 on R3

Step 1: Configure ACL 100 to block all specified traffic from the outside network.

R3(config)# access-list 100 permit tcp 10.0.0.0 0.255.255.255 host 192.168.3.3 eq 22

R3(config)# access-list 100 deny ip 10.0.0.0 0.255.255.255 any

R3(config)# access-list 100 deny ip 172.16.0.0 0.15.255.255 any

R3(config)# access-list 100 deny ip 192.168.0.0 0.0.255.255 any

R3(config)# access-list 100 deny ip 127.0.0.0 0.255.255.255 any

R3(config)# access-list 100 deny ip 224.0.0.0 15.255.255.255 any

R3(config)# access-list 100 permit ip any any

Step 2: Apply the ACL to interface

R3(config)# interface se0/1/0

R3(config-if)# ip access-group 100 in

Step 3: Confirm that the specified traffic entering interface Serial is handled correctly.

PCC> ping 192.168.1.3

(Unsuccessful)

PCC> ssh -l admin 192.168.2.1

Password: adminpa55


R2>exit





 \mathbf{B}

Topology:



Addressing Table:

Device	Interface	IPv6 Address/Prefix	Default Gateway
PC1	NIC	2001:DB8:1:10::10/64	FE80::1
PC2	NIC	2001:DB8:1:11:11/64	FE80::1
R1	gig0/0	2001:DB8:1:10::1/64	FE80::1
	se0/1/0	2001:DB8:1:1::1/64	FE80::1
	gig0/1	2001:DB8:1:11::1/64	FE80::1
R3	se0/1/0	2001:DB8:1:1::2/64	FE80::2
	se0/1/1	2001:DB8:1:2::2/64	FE80::2
R3	gig0/0	2001:DB8:1:30::1/64	FE80::3
	se0/1/0	2001:DB8:1:2::1/64	FE80::3
Server	NIC	2001:DB8:1:30::30/64	FE80::3

Objective:

- Configure, Apply, and Verify an IPv6 ACL
- Configure, Apply, and Verify a Second IPv6 ACL

■ Configure Router:

Step 1: Configure secret on router

Execute command on all routers

R(config)# enable secret enpa55

Step 2: Assign static ipv6 address

R1(config)# int gig0/0

R1(config-if)# ipv6 address 2001:DB8:1:10::1/64

R1(config-if)# ipv6 address FE80::1 link-local

R1(config-if)# no shut

R1(config)# int gig0/1

R1(config-if)# ipv6 address 2001:DB8:1:11::1/64

R1(config-if)# ipv6 address FE80::1 link-local

R1(config-if)# no shut

R1(config)# int se0/1/0

R1(config-if)# ipv6 address 2001:DB8:1:1::1/64

R1(config-if)# ipv6 address FE80::1 link-local

R1(config-if)# no shut

R2(config)# int se0/1/0

R2(config-if)# ipv6 address 2001:DB8:1:1::2/64

R2(config-if)# ipv6 address FE80::2 link-local

R2(config-if)# no shut

R2(config)# int se0/1/1



R2(config-if)# ipv6 address 2001:DB8:1:2::2/64

R2(config-if)# ipv6 address FE80::2 link-local

R2(config-if)# no shut

R3(config)# int gig0/0

R3(config-if)# ipv6 address 2001:DB8:1:30::1/64

R3(config-if)# ipv6 address FE80::3 link-local

R3(config-if)# no shut

R3(config)# int se0/1/0

R3(config-if)# ipv6 address 2001:DB8:1:2::1/64

R3(config-if)# ipv6 address FE80::3 link-local

R3(config-if)# no shut

Step 3: Enable IPv6 routing

R1(config)# ipv6 unicast-routing

R1(config)# ipv6 route 2001:DB8:1:2::0/64 2001:DB8:1:1::2

R1(config)# ipv6 route 2001:DB8:1:30::0/64 2001:DB8:1:1::2

R2(config)# ipv6 unicast-routing

R2(config)#ipv6 route 2001:DB8:1:10::0/64 2001:DB8:1:1::1

R2(config)# ipv6 route 2001:DB8:1:11::0/64 2001:DB8:1:1::1

R2(config)# ipv6 route 2001:DB8:1:30::0/64 2001:DB8:1:2::1

R3(config)# ipv6 unicast-routing

R3(config)# ipv6 route 2001:DB8:1:10::0/64 2001:DB8:1:2::2

R3(config)#ipv6 route 2001:DB8:1:11::0/64 2001:DB8:1:2::2

R3(config)# ipv6 route 2001:DB8:1:1::0/64 2001:DB8:1:2::2

Step 4: Verify connectivity

PC1> ping 2001:DB8:1:30::30

(Successful)

PC2> ping 2001:DB8:1:30::30

(Successful)

Part 2: Configure, Apply, and Verify an IPv6 ACL

Step 1: Configure an ACL that will block HTTP and HTTPS access.

R1(config)# ipv6 access-list BLOCK_HTTP

R1(config-ipv6-acl)# deny tcp any host 2001:DB8:1:30::30 eq www

R1(config-ipv6-acl)# deny tcp any host 2001:DB8:1:30::30 eq 443

R1(config-ipv6-acl)# permit ipv6 any any

R1(config-ipv6-acl)# exit

Step 2: Apply the ACL to the correct interface.

R1(config)# int gig0/1

R1(config-if)# ipv6 traffic-filter BLOCK_HTTP in

Step 3: Verify the ACL implementation

Open a web browser to the PC1 to display the web page.

Desktop->Web Browser->http://2001:DB8:1:30::30

(Successful)

Desktop->Web Browser->https://2001:DB8:1:30::30

(Successful)



Open a web browser to the PC2 to display the web page.

Desktop->Web Browser->http://2001:DB8:1:30::30

(Unsuccessful) – Request Timeout

Desktop->Web Browser->https://2001:DB8:1:30::30

(Unsuccessful) – Request Timeout

PC2> ping 2001:DB8:1:30::30

(Successful)

Part 3: Configure, Apply, and Verify a Second IPv6 ACL

Step 1: Create an access list to block ICMP.

R3(config)# ipv6 access-list BLOCK_ICMP

R3(config-ipv6-acl)# deny icmp any any

R3(config-ipv6-acl)# permit ipv6 any any

R3(config-ipv6-acl)# exit

Step 2: Apply the ACL to the correct interface.

R3(config)# int gig0/0

R3(config-if)# ipv6 traffic-filter BLOCK_ICMP out

Step 3: Verify that the proper access list functions.

PC2> ping 2001:DB8:1:30::30

(Unsuccessful) - Destination host unreachable

PC1> ping 2001:DB8:1:30::30

(Unsuccessful) - Destination host unreachable

Open a web browser to the PC1 to display the web page.

Desktop->Web Browser->http://2001:DB8:1:30::30

(Successful)

Desktop->Web Browser->https://2001:DB8:1:30::30

(Successful)








Practical 5: Configuring a Zone-Based Policy Firewall (ZPF)

\mathbf{A}

Topology:



Addressing Table:

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	gig0/0	192.168.1.1	255.255.255.0	N/A
	Se0/1/0 (DCE)	10.1.1.1	255.255.255.252	N/A
	Se0/1/0	10.1.1.2	255.255.255.252	N/A
R2	Se0/1/1 (DCE)	10.2.2.2	255.255.255.252	N/A
R3	gig0/0	192.168.3.1	255.255.255.0	N/A
	Se0/1/0	10.2.2.1	255.255.255.252	N/A
PC-A	NIC	192.168.1.3	255.255.255.0	192.168.1.1
PC-C	NIC	192.168.3.3	255.255.255.0	192.168.3.1

Objectives:

- Verify connectivity among devices before firewall configuration.
- Configure a zone-based policy (ZPF) firewall on R3.
- Verify ZPF firewall functionality using ping, SSH, and a web browser.

■ Configure Router:

Step 1: Configure console password on router

Execute command on all routers

R(config) # line console 0

R(config-line) #password conpa55

R(config-line) #login

Step 2: Configure password for vty lines

Execute command on all routers

R(config)# line vty 0 4

R(config-line)# password vtypa55

R(config-line)# login

Step 3: Configure secret on router

R(config) # enable secret enpa55

Step 4: Configure SSH login on router

Execute command on all routers

R(config)# ip domain-name ccnasecurity.com

R(config)# username admin secret adminpa55

R(config)# line vty 0 4

R(config-line)# login local

R(config-line)# crypto key generate rsa

How many bits in the modulus [512]: 1024

STUD--Talks: Follow us on **with O for more videos and updates**

Step 5: Configure static routing on routers

Execute command on all routers

R(config)#ip route destination-network-address subnetmask next-hop-destination-address

Part 2: Verify Basic Network Connectivity

Step 1: Check connectivity from PCA to PCC

PCA>ping 192.168.3.3

(Successful)

Step 2: Access R2 using SSH.

PCC>ssh -l admin 10.2.2.2

Password:adminpa55

R2>exit

Step 3: From PC-C, open a web browser to the PC-A server.

Desktop -> Web Browser

URL: http://192.168.1.3

(Successful)

Part 3: Create the Firewall Zones on R3

Step 1: Verify that the Security Technology package

R3# show version

Step 2: Enable the Security Technology package

R3(config)# license boot module c1900 technology-package securityk9

Step 3: Save the running-config and reload the router

R3#copy run start

R3# reload

STUD--Talks: Follow us on | or for more videos and updates

Step 4: Verify that the Security Technology package

R3# show version

Step 5: Create an internal zone.

R3(config)# zone security IN-ZONE

R3(config-sec-zone)# exit

Step 6: Create an external zone.

R3(config)# zone security OUT-ZONE

R3(config-sec-zone)# exit

Part 4: Identify Traffic Using a Class-Map

Step 1: Create an ACL that defines internal traffic.

R3(config)# access-list 101 permit ip 192.168.3.0 0.0.0.255 any

Step 2: Create a class map referencing the internal traffic ACL

R3(config)# class-map type inspect match-all IN-NET-CLASS-MAP

R3(config-cmap)# match access-group 101

R3(config-cmap)# exit

Part 5: Specify Firewall Policies

Step 1: Create a policy map to determine what to do with matched traffic.

R3(config)# policy-map type inspect IN-2-OUT-PMAP

Step 2: Specify a class type of inspect and reference class map IN-NET-CLASS-MAP.

R3(config-pmap)# class type inspect IN-NET-CLASS-MAP

STUD--Talks: Follow us on **with O for more videos and updates**

Step 3: Specify the action of inspect for this policy map.

R3(config-pmap-c)# inspect

R3(config-pmap-c)# exit

R3(config-pmap)# exit

Part 6: Apply Firewall Policies

Step 1: Create a pair of zones.

R3(config)# zone-pair security IN-2-OUT-ZPAIR source IN-ZONE destination OUTZONE

Step 2: Specify the policy map for handling the traffic between the two zones.

R3(config-sec-zone-pair)# service-policy type inspect IN-2-OUT-PMAP

R3(config-sec-zone-pair)# exit

R3(config)#

Step 3: Assign interfaces to the appropriate security zones.

R3(config)# int g0/0

R3(config-if)# zone-member security IN-ZONE

R3(config-if)# exit

R3(config)# int s0/1/0

R3(config-if)# zone-member security OUT-ZONE

R3(config-if)# exit

Step 4: Copy the running configuration to the startup configuration.

R3# copy run start

R3# reload

Part 7: Test Firewall Functionality from IN-ZONE to OUT ZONE

Step 1: From internal PC-C, ping the external PC-A server.

PCC>ping 192.168.1.3

(Successful)

Step 2: Access R2 using SSH.

PCC>ssh –1 admin 10.2.2.2

Password:

R2>

Step 3: View established sessions

R3# show policy-map type inspect zone-pair sessions

Session 175216232 (192.168.3.3:1028)=>(10.2.2.2:22) tcp SIS_OPEN/TCP_ESTAB

Step 4: From PC-C, exit the SSH session on R2 and close the command prompt window.

R2>exit

Step 5: From internal PC-C, open a web browser to the PC-A server web page.

Desktop -> Web Browser

URL: http://192.168.1.3

(Successful)

Step 6: View established sessions

R3# show policy-map type inspect zone-pair sessions

STUD--Talks: Follow us on **with O f** or more videos and updates

Session 565266624 (192.168.3.3:1031)=>(192.168.1.3:80) tcp SIS_OPEN/TCP_ESTAB

Part 8: Test Firewall Functionality from OUT-ZONE to IN-ZONE

Step 1: From internal PC-A, ping the external PC-C server.

PCA>ping 192.168.3.3

(Unsuccessful – Request timed out)

Step 2: From R2, ping PC-C.


R2# ping 192.168.3.3

(Unsuccessful – Request timed out)



Security In Computing Practical's <u>Practical 6: Configure IOS Intrusion Prevention System (IPS)</u> <u>Using the CLI</u>

Topology:



Addressing Table:

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	gig0/0	192.168.1.1	255.255.255.0	N/A
	Se0/1/0	10.1.1.1	255.255.255.252	N/A
	Se0/1/0	10.1.1.2	255.255.255.252	N/A
R2	Se0/1/1	10.2.2.2	255.255.255.252	N/A
R3	gig0/0	192.168.3.1	255.255.255.0	N/A
	Se0/1/0	10.2.2.1	255.255.255.252	N/A
Syslog	NIC	192.168.1.50	255.255.255.0	192.168.1.1
PC-A	NIC	192.168.1.2	255.255.255.0	192.168.1.1
PC-C	NIC	192.168.3.2	255.255.255.0	192.168.3.1

Objectives

- Enable IOS IPS.
- Configure logging.
- Modify an IPS signature.
- Verify IPS

Part 1: Configure router

Step 1: Configure secret on router

Execute command on all routers

R(config)# enable secret enpa55

Step 2: Configure console password on router

Execute command on all routers

R(config)# line console 0

R(config-line)# password conpa55

R(config-line)# login

Step 3: Configure SSH login on router

Execute command on all routers

R(config)# ip domain-name ccnasecurity.com

R(config)# username admin secret adminpa55

R(config)# line vty 0 4

R(config-line)# login local

R(config)# crypto key generate rsa

How many bits in the modulus [512]: 1024

Step 4: Configure OSPF on routers

Execute command on router 1

R1(config)#router ospf 1

R1(config-router)# network 192.168.1.0 0.0.0.255 area 0

R1(config-router)# network 10.1.1.0 0.0.0.3 area 0

Execute command on router 2

R2(config)#router ospf 1

STUD--Talks: Follow us on **willing** [9] for more videos and updates

R2(config-router)# network 10.1.1.0 0.0.0.3 area 0

R2(config-router)# network 10.2.2.0 0.0.0.3 area 0

Execute command on router 3

R3(config)#router ospf 1

R3(config-router)# network 10.2.2.0 0.0.0.3 area 0

R3(config-router)# network 192.168.3.0 0.0.0.255 area 0

Part 2: Enable IOS IPS

Step 1: Enable the Security Technology package

R1# show version

Technology Package License Information for Module: 'c1900'

Technology Technology-package Technology-package
Current Type Next reboot

ipbase ipbasek9 Permanent ipbasek9

security None None None
data None None None

(When command "show version" is given the above result comes, remember for further practical's)

R1(config)# license boot module c1900 technology-package securityk9

(Type yes)

R1# copy run start

R1# reload

R1# show version

Technology P	ackage License	Information i	for Module: 'c1900'
Technology	Technology-package		Technology-package
	Current	Type	Next reboot
ipbase	ipbasek9	Permanent	ipbasek9
security	securityk9	Evaluation	securityk9
data	disable	None	None

(When command "show version" is given again the above result comes to check If security is enabled or not, remember for further practical's)

Step 2: Verify network connectivity

PCA> ping 192.168.3.2

(Successful)

PCC> ping 192.168.1.2

(Successful)

Step 3: Create an IOS IPS configuration directory in flash.

R1# mkdir ipsdir

Create directory filename [ipsdir]? <Enter>

Step 4: Configure the IPS signature storage location.

R1(config)# ip ips config location flash:ipsdir

Step 5: Create an IPS rule

R1(config)# ip ips name iosips

Step 6: Enable logging.

R1(config)# ip ips notify log

R1# clock set hr:min:sec date month year

R1(config)# service timestamps log datetime msec

R1(config)# logging host 192.168.1.50

Step 7: Configure IOS IPS to use the signature categories.

R1(config)# ip ips signature-category

R1(config-ips-category)# category all

R1(config-ips-category-action)# retired true

STUD--Talks: Follow us on **with Open to the STUD--Talks:** Follow us on **STUD--Talks:** Follow us on **Talks:**

R1(config-ips-category-action)# exit

R1(config-ips-category)# category ios_ips basic

R1(config-ips-category-action)# retired false

R1(config-ips-category-action)# exit

R1(config-ips-cateogry)# exit

Do you want to accept these changes? [confirm] <Enter>

Step 8: Apply the IPS rule to an interface.

R1(config)# int gig0/0

R1(config-if)# ip ips iosips out

Step 9: Use show commands to verify IPS.

R1# show ip ips all

(Output)

Step 10: View the syslog messages.

Click the Syslog server->Services tab-> SYSLOG

(Output)

Part 3: Modify the Signature

Step 1: Change the event-action of a signature.

R1(config)# ip ips signature-definition

R1(config-sigdef)# signature 2004 0

R1(config-sigdef-sig)# status

R1(config-sigdef-sig-status)# retired false

R1(config-sigdef-sig-status)# enabled true

R1(config-sigdef-sig-status)# exit

R1(config-sigdef-sig)# engine

STUD--Talks: Follow us on **with O** for more videos and updates

R1(config-sigdef-sig-engine)# event-action produce-alert

R1(config-sigdef-sig-engine)# event-action deny-packet-inline

R1(config-sigdef-sig-engine)# exit

R1(config-sigdef-sig)# exit

R1(config-sigdef)# exit

Do you want to accept these changes? [confirm] <Enter>

Step 2: Use show commands to verify IPS.

R1# show ip ips all

(Output)

Step 3: Verify that IPS is working properly.

PCC> ping 192.168.1.2(Unsuccessful – Request timed out)

PCA> ping 192.168.3.2(Successful)

Step 4: View the syslog messages.

Click the Syslog server->Services tab-> SYSLOG



