UNIT-4

Child window Control:

These programs display a grid of rectangles. When you click the mouse in a rectangle, the program draws an X. When you click again, the X disappears. Although the CHECKER1 and CHECKER2 versions of this program use only one a window, the CHECKER3 version uses a child window for each rectangle. The rectangles are Maintained by a separate window procedure named ChildProc. If we wanted to, we could add a facility to ChildProc to send a message to its parent window procedure (WndProc) whenever a rectangle is checked or unchecked. Here's how: The child window procedure can determine the window handle of its parent by calling GetParent, hwndParent = GetParent (hwnd); where hwnd is the window handle of the child window. It can then send a message to the parent window procedure:

SendMessage (hwndParent, message, wParam, lParam);

What would message be set to? Well, anything you want, really, as long as the numeric value is set to WM USER or above. These numbers represent a range of messages that do not conflict with the predefined WM messages. Perhaps for this message the child window could set wParam to its child window ID. The lParam could then be set to a 1 if the child window were being checked and a 0 if it were being unchecked. That's one possibility. This in effect creates a "child window control." The child window processes mouse and keyboard messages and notifies the parent window when the child window's state has changed. In this way, the child window becomes a high-level input device for the parent window. It encapsulates a specific functionality with regard to its graphical appearance on the screen, its response to user input, and its method of notifying another window when an important input event has occurred. Although you can create your own child window controls, you can also take advantage of several predefined window classes (and window procedures) that your program can use to create standard child window controls that you've undoubtedly seen in other Windows programs. These controls take the form of buttons, check boxes, edit boxes, list boxes, combo boxes, text strings, and scroll bars. For instance, if you want to put a button labeled "Recalculate" in a corner of your spreadsheet program, you can create it with a single CreateWindow call. You don't have to worry about the mouse logic or button painting logic or making the button flash when it's clicked. That's all done in Windows. All you

have to do is trap WM COMMAND messages that's how the button informs your window procedure.

Dialog Boxes

Dialog boxes are most often used for obtaining additional input from the user beyond what can be easily managed through a menu. The programmer indicates that a menu item invokes a dialog box by adding an ellipsis (...) to the menu item. A dialog box generally takes the form of a popup window containing various child window controls. The size and placement of these controls are specified in a "dialog box template" in the program's resource script file. Although a programmer can define a dialog box template "manually," these days dialog boxes are usually interactively designed in the Visual C++ Developer Studio. Developer Studio then generates the dialog template. When a program invokes a dialog box based on a template, Microsoft Windows 98 is responsible for creating the dialog box popup window and the child window controls, and for providing a window procedure to process dialog box messages, including all keyboard and mouse input. The code within Windows that does all this is sometimes referred to as the "dialog box manager." Many of the messages that are processed by that dialog box window procedure located within Windows are also passed to a function within your own program, called a "dialog box procedure" or "dialog procedure." The dialog procedure is similar to a normal window procedure, but with some important differences. Generally, you will not be doing much within the dialog procedure beyond initializing the child window controls when the dialog box is created, processing messages from the child window controls, and ending the dialog box. Dialog procedures generally do not process WM PAINT messages, nor do they directly process keyboard and mouse input.

However, adding a dialog box to a program is a bit more involved than adding an icon or a menu. We'll begin with a simple dialog box to give you a feel for the interconnections between these various pieces.

Modeless Dialog Boxes

At the beginning of this chapter, I explained that dialog boxes can be either "modal" or modeless." So far we've been looking at modal dialog boxes, the more common of the two types. Modal dialog boxes (except system modal dialog boxes) allow the user to switch between the dialog box and other programs. However, the user cannot switch to another window in the program that initiated the dialog box until the modal dialog box is destroyed. Modeless dialog boxes allow the user to switch between the dialog box and the window that created it as well as between the dialog box and other programs. The modeless dialog box is thus more akin to the regular popup windows that your program might create. Modeless dialog boxes are preferred when the user would find it convenient to keep the dialog box displayed for a while. For instance, word processors often use modeless dialog boxes for the text Find and Change dialogs. If the Find dialog box were modal, the user would have to choose Find from the menu, enter the string to be found, end the dialog box to return to the document, and then repeat the entire process to search for another occurrence of the same string. Allowing the user to switch between the document and the dialog box is much more convenient. As you've seen, modal dialog boxes are created using DialogBox. The function returns a value only after the dialog box is destroyed. It returns the value specified in the second parameter of the

EndDialog call that was used within the dialog box procedure to terminate the dialog box. Modeless dialog boxes are created using CreateDialog. This function takes the same parameters as DialogBox:

```
hDlgModeless = CreateDialog (hInstance, szTemplate, hwndParent, DialogProc);
```

The difference is that the CreateDialog function returns immediately with the window handle of the dialog box. Normally, you store this window handle in a global variable.

Differences Between Modal and Modeless Dialog Boxes

Working with modeless dialog boxes is similar to working with modal dialog boxes, but there are

several important differences. First, modeless dialog boxes usually include a caption bar and a system menu box. These are actually the default options when you create a dialog box in Developer Studio. The STYLE statement in the dialog box template for a modeless dialog box will look something like this:

```
STYLE WS_POPUP | WS_CAPTION | WS_SYSMENU | WS_VISIBLE
```

The caption bar and system menu allow the user to move the modeless dialog box to another area of the display using either the mouse or the keyboard. You don't normally provide a caption bar and system menu with a modal dialog box, because the user can't do anything in the underlying window anyway. The second big difference: Notice that the WS_VISIBLE style is included in our sample STYLE statement. In Developer Studio, select this option from the More Styles tab of the Dialog Properties dialog. If you omit WS_VISIBLE, you must call ShowWindow after the CreateDialog call:


```
hDlgModeless = CreateDialog ( . . . );
ShowWindow (hDlgModeless, SW SHOW)
```

Bitmaps, Device Contexts and BitBlt

Example: bmp one

GDI

The Graphics Device Interface (GDI) is a Microsoft Windows application programming interface and core operating system component responsible for representing graphical objects and transmitting them to output devices such as monitors and printers.



GDI is responsible for tasks such as drawing lines and curves, rendering fonts and handling palettes. It is not directly responsible for drawing windows, menus, etc.; that task is reserved for the user subsystem, which resides in user32.dll and is built atop GDI.

Using GDI, it is very easy to draw on multiple devices, such as a screen and a printer, and expect proper reproduction in each case.

The really great thing about MS Windows is that unlike DOS, you don't need to know anything about what video hardware you are using to display graphics. Instead, windows provides an API called the Graphics Device Interface, or GDI. The GDI uses a set of generic graphics objects that can be used to draw to the screen, to memory, or even to printers.

Usage: Simple games that do not require fast graphics rendering may use GDI. However, GDI is relatively hard to use for advanced animation, and lacks a notion for synchronizing with individual video frames in the video card

Device Contexts

The GDI revolves around an object called the Device Context (DC), represented by the data type HDC (Handle to Device Context). An HDC is basically a handle to something you can draw on; it can represent the entire screen, an entire window, the client area of a window, a bitmap stored in memory, or a printer. The nice part is that you don't even need to know which one it refers to, you can use it basically the same way, which is especially handy for writing custom drawing functions which you can then use on any of these devices without changing it for each one.

An HDC like most GDI objects is opaque, meaning that you can't access it's data directly... but you can pass it to various GDI functions that will operate on it, either to draw something, get information about it, or change the object in some way.

For example, if you wanted to draw on a window, first you would retreive an HDC representing the window with GetDC(), then you could use any of the GDI functions that take an HDC like BitBlt() for drawing images, TextOut() for drawing text, LineTo() for lines and so on.

Bitmaps

Besides different linked and tree based data structures, the Linux kernel provides API for bit arrays or bitmap. Bit arrays are heavily used in the Linux kernel and following source code files contain common API for work with such structures:

- lib/bitmap.c
- include/linux/bitmap.h

Declaration:

we must know how to declare it in the Linux kernel. There are two common method to declare own bit array. The first simple way to declare a bit array is to array of unsigned long. For example:

unsigned long my bitmap[8]

The second way is to use the DECLARE_BITMAP macro which is defined in the include/linux/types.h header file:

#define DECLARE BITMAP(name,bits) \

unsigned long name[BITS_TO_LONGS(bits)]

We can see that DECLARE BITMAP macro takes two parameters:

- name name of bitmap;
- bits amount of bits in bitmap;

Bitmaps can be loaded much like icons in earlier examples, there is **LoadBitmap()** for the most basic functionality of simply loading a bitmap resource, and **LoadImage()** can be used to load bitmaps from a *.bmp file just as it can for icons.

One of the quirks of GDI is that you can't draw to bitmap objects (HBITMAP type) directly. Remember that drawing operations are abstracted by Device Contexts, so in order to use these drawing functions on a bitmap, you need to create a Memory DC, and then select the HBITMAP into it with SelectObject(). The effect is that the "device" that the HDC refers to is the bitmap in memory, and when you operate on the HDC, the resulting graphic operations are applied to the bitmap. As I mentioned, this is actually a very conveiniant way of doing things, as you can write code that draws to an HDC and you can use it on a Window DC or a Memory DC without any checks or changes.

You do have the option of manipulating the bitmap data in memory yourself. You can do this with Device Independent Bitmaps (DIB), and you can even combine GDI and manual operations on the DIB. However for the time being, this is beyond the scope of the basic tutorial and for now we're just cover the simpler GDI operations on their own.

GDI Leaks

Once you're finished with an HDC, it's very important to release it (just how you do that depends on how you got it, which we'll talk about in a bit). GDI objects are limited in number. In versions of windows prior to Windows 95, they were not only incredibly limited but also shared system wide, so that if one program used up too many, none of the rest would be able to draw anything! Fortunately this isn't the case any longer, and you could get away with using up quite a lot of resources in Windows 2000 or XP before anything too bad happened... but it's easy to forget to free GDI objects and they can quickly run your program out of GDI resources under Windows 9x. Theoretically you shouldn't be able to drain the system of GDI resources in NT systems (NT/2K/XP) but it still happens in extreme cases, or if you hit the right bug on the nose.

If your program runs fine for a few minutes and then starts drawing strangely or not at all, it's a good sign that you're leaking GDI resources. HDCs aren't the only GDI objects you need to be careful about releasing, but generally it's ok to keep things like bitmaps and fonts around for the entire lifetime of your program, since it's much more efficient than reloading them each time you need them.

Also, an HDC can only contain one of each type of object (bitmap, font, pen...) at a time, and when you select a new one in it will return the last one. It's very important that you deal with this object properly. If you ignore it completely, it might be lost and pile up in memory as a GDI leak. When an HDC is created, it's also created with some default objects selected into it... it's a good idea to store these when they are returned to you, and then when you are completed drawing with the HDC select them back into it.

This is particularly important as you can't delete a GDI object while it is selected into an HDC. To clean up properly, you should reselect the default object back into the HDC releasing the object you had selected into it, which you can then DeleteObject() successfully. Trying to delete a bitmap you created while that bitmap is selected into an HDC will fail, and probably leak the bitmap if you assume it has been cleaned up from that point on.

Even Microsoft engineers get caught by this, there was a bug in one of the Windows screensavers and it turns out it was because the default bitmap wasn't getting replaced causing a leak and eventually the screensaver ran out of GDI resources. Be warned! It's an easy mistake to make.

Displaying Bitmaps

The simplest drawing operations on a window occur by handling WM_PAINT. When your window is first displayed, restored from being minimised, or uncovered from having another window on top of it, Windows sends the WM_PAINT message to the window to let it know that it needs to redraw it's contents. When you draw something on the screen it is NOT permanent, it's only there until something else draws over it, and you will need to redraw it when that part of your window becomes visible to the user again.

```
HBITMAP g_hbmBall = NULL;

case WM_CREATE:

g_hbmBall = LoadBitmap(GetModuleHandle(NULL),

MAKEINTRESOURCE(IDB_BALL));

if(g_hbmBall == NULL)

MessageBox(hwnd, "Could not load IDB_BALL!", "Error", MB_OK |

MB_ICONEXCLAMATION);
```

break:

The first step is of course loading the bitmap, this is quite simple with a bitmap resource, there are no significant differences from loading other resource types. Then we can get down to drawing...

```
case WM_PAINT:

{

BITMAP bm;

PAINTSTRUCT ps;

HDC hdc = BeginPaint(hwnd, &ps);

HDC hdcMem = CreateCompatibleDC(hdc);

HBITMAP hbmOld = SelectObject(hdcMem, g_hbmBall);

GetObject(g_hbmBall, sizeof(bm), &bm);

BitBlt(hdc, 0, 0, bm.bmWidth, bm.bmHeight, hdcMem, 0, 0, SRCCOPY);

SelectObject(hdcMem, hbmOld);

DeleteDC(hdcMem);

EndPaint(hwnd, &ps);

}
break;
```

Getting the Window DC

To start off we declare a couple of variables we need. Notice that the first one is a BITMAP, not an HBITMAP is a struct that holds information about an HBITMAP which is the actual GDI object. We need a way to get the height and width of the HBITMAP so we use GetObject() which contrary to it's name doesn't really get an object, but rather information about an existing one. "GetObjectInfo" would have been a more appropriate label. GetObject() works for various GDI object types which it can distinguish based on the value of the second parameter, the size of the structure.

The PAINTSTRUCT is a structure that contains information about the window being painted and what exactly is going on with the paint message. For most simple tasks, you can simply ignore the information it contains, but it's required for the call to BeginPaint(). BeginPaint() as it's name suggests is designed specifically for handling the WM_PAINT message. When not

handling a WM_PAINT message you would use GetDC() which we will see in the timer animation examples in a while... but in WM_PAINT, it's important to use BeginPaint() and EndPaint().

BeginPaint() returns us an HDC that represents the HWND that we pass to it, the one that WM_PAINT is being handled for. Any drawing operation we perform on this HDC will immediately display on the screen.

Setting up a Memory DC for the Bitmap

As I mention above, in order to draw on or with bitmaps, we need to create a DC in memory... the easiest way to do that here is to **CreateCompatibleDC()** with the one we already have. This gives us a Memory DC that is compatible with the color depth and display properties of the HDC for the window.

Now we call SelectObject() to select the bitmap into the DC being careful to store the default bitmap so that we can replace it later on and not leak GDI objects.

Drawing

Once we've gotten the dimentions of the bitmap filled into the BITMAP struct, we can call **BitBlt()** to copy the image from our Memory DC to the Window DC, thus displaying on the screen. As always, you can look up each parameter in MSDN, but in short they are: The destination, the position and size, the source and source position, and finally the Raster Operation (ROP code), which specifies how to do the copy. In this case, we want a simple exact copy of the source made, no fancy stuff.

BitBlt() is probably the all time function in all of the Win32 API and is the staple diet of anyone learning to write games or other graphics applications in windows. It was probably the first API that I memorised all the parameters to.

Cleanup

At this point the bitmap should be on the screen, and we need to clean up after ourselves. The first thing to do is restore the Memory DC to the state it was when we got it, which means replacing our bitmap with the default one that we saved. Next we can delete it altogether with DeleteDC().

Finally we release the Window DC we got from BeginPaint() using EndPaint().

Destroying an HDC is a little confusing sometimes because there are at least 3 ways to do it depending on how you got it in the first place. Here's a list of the common methods of gaining an HDC, and how to release it when you're done.

- GetDC() ReleaseDC()
- BeginPaint() EndPaint()
- CreateCompatibleDC() DeleteDC()

And finally, at the termination of our program, we want to free any resources that we allocated. Technically speaking this isn't absolutely required, since modern Windows platforms are pretty good at freeing everything when your program exists, but it's always a good idea to keep track of your own objects because if get lazy and don't delete them they have a habit of getting loose. And no doubt, there are still bugs in windows especially older versions that won't clean up all of your GDI objects if you don't do a thorough job.

```
case WM_DESTROY:
DeleteObject(g_hbmBall);
PostQuitMessage(0);
break;
```