#### **NAME**

fgetpos, fseek, fsetpos, ftell, rewind - reposition a stream

#### **LIBRARY**

Standard C library (libc, -lc)

#### **SYNOPSIS**

```
#include <stdio.h>
```

```
int fseek(FILE *stream, long offset, int whence);
long ftell(FILE *stream);
```

void rewind(FILE \*stream);

int fgetpos(FILE \*restrict stream, fpos\_t \*restrict pos);
int fsetpos(FILE \*stream, const fpos\_t \*pos);

#### **DESCRIPTION**

The **fseek**() function sets the file position indicator for the stream pointed to by *stream*. The new position, measured in bytes, is obtained by adding *offset* bytes to the position specified by *whence*. If whence is set to **SEEK\_SET**, **SEEK\_CUR**, or **SEEK\_END**, the offset is relative to the start of the file, the current position indicator, or end-of-file, respectively. A successful call to the **fseek**() function clears the end-of-file indicator for the stream and undoes any effects of the **ungetc**(3) function on the same stream.

The **ftell**() function obtains the current value of the file position indicator for the stream pointed to by *stream*.

The **rewind()** function sets the file position indicator for the stream pointed to by *stream* to the beginning of the file. It is equivalent to:

```
(void) fseek(stream, 0L, SEEK_SET)
```

except that the error indicator for the stream is also cleared (see **clearerr**(3)).

The **fgetpos**() and **fsetpos**() functions are alternate interfaces equivalent to **ftell**() and **fseek**() (with *whence* set to **SEEK\_SET**), setting and storing the current value of the file offset into or from the object referenced by *pos*. On some non-UNIX systems, an *fpos\_t* object may be a comple x object and these routines may be the only way to portably reposition a text stream.

If the stream refers to a regular file and the resulting stream offset is beyond the size of the file, subsequent writes will extend the file with a hole, up to the offset, before committing any data. See **lseek**(2) for details on file seeking semantics.

## **RETURN VALUE**

The **rewind()** function returns no value. Upon successful completion, **fgetpos()**, **fseek()**, **fseepos()** return 0, and **ftell()** returns the current offset. Otherwise, -1 is returned and errno is set to indicate the error.

#### **ERRORS**

#### **EINVAL**

The *whence* argument to **fseek**() was not **SEEK\_SET**, **SEEK\_END**, or **SEEK\_CUR**. Or: the resulting file offset would be negative.

#### **ESPIPE**

The file descriptor underlying *stream* is not seekable (e.g., it refers to a pipe, FIFO, or socket).

The functions **fgetpos**(), **fseek**(), **fsetpos**(), and **ftell**() may also fail and set *errno* for any of the errors specified for the routines **fflush**(3), **fstat**(2), **lseek**(2), and **malloc**(3).

### **ATTRIBUTES**

For an explanation of the terms used in this section, see **attributes**(7).

Interface	Attribute	Value
fseek(), ftell(), rewind(), fgetpos(), fsetpos()	Thread safety	MT-Safe

## **STANDARDS**

POSIX.1-2001, POSIX.1-2008, C99.

# SEE ALSO

 $\textbf{lseek}(2),\,\textbf{fseeko}(3)$