NAME

userfaultfd - create a file descriptor for handling page faults in user space

LIBRARY

Standard C library (libc, -lc)

SYNOPSIS

```
#include <fcntl.h> /* Definition of O_* constants */
#include <sys/syscall.h> /* Definition of SYS_* constants */
#include dinux/userfaultfd.h> /* Definition of UFFD_* constants */
#include <unistd.h>
```

int syscall(SYS_userfaultfd, int fla gs);

Note: glibc provides no wrapper for **userfaultfd**(), necessitating the use of **syscall**(2).

DESCRIPTION

userfaultfd() creates a new userfaultfd object that can be used for delegation of page-fault handling to a user-space application, and returns a file descriptor that refers to the new object. The new userfaultfd object is configured using **ioctl**(2).

Once the userfaultfd object is configured, the application can use $\mathbf{read}(2)$ to receive userfaultfd notifications. The reads from userfaultfd may be blocking or non-blocking, depending on the value of fla~gs used for the creation of the userfaultfd or subsequent calls to $\mathbf{fcntl}(2)$.

The following values may be bitwise ORed in *fla gs* to change the behavior of **userfaultfd**():

O CLOEXEC

Enable the close-on-exec flag for the new userfaultfd file descriptor. See the description of the **O_CLOEXEC** flag in **open**(2).

O_NONBLOCK

Enables non-blocking operation for the userfaultfd object. See the description of the **O_NON-BLOCK** flag in **open**(2).

UFFD_USER_MODE_ONLY

This is an userfaultfd-specific flag that was introduced in Linux 5.11. When set, the userfaultfd object will only be able to handle page faults originated from the user space on the registered regions. When a kernel-originated fault was triggered on the registered range with this userfaultfd, a **SIGBUS** signal will be delivered.

When the last file descriptor referring to a userfaultfd object is closed, all memory ranges that were registered with the object are unregistered and unread events are flushed.

Userfaultfd supports three modes of registration:

UFFDIO_REGISTER_MODE_MISSING (since Linux 4.10)

When registered with **UFFDIO_REGISTER_MODE_MISSING** mode, user-space will receive a page-fault notification when a missing page is accessed. The faulted thread will be stopped from execution until the page fault is resolved from user-space by either an **UFFDIO_COPY** or an **UFFDIO_ZEROPAGE** ioctl.

UFFDIO_REGISTER_MODE_MINOR (since Linux 5.13)

When registered with **UFFDIO_REGISTER_MODE_MINOR** mode, user-space will receive a page-fault notification when a minor page fault occurs. That is, when a backing page is in the page cache, but page table entries don't yet exist. The faulted thread will be stopped from execution until the page fault is resolved from user-space by an **UFFDIO_CONTINUE** ioctl.

UFFDIO_REGISTER_MODE_WP (since Linux 5.7)

When registered with **UFFDIO_REGISTER_MODE_WP** mode, user-space will receive a page-fault notification when a write-protected page is written. The faulted thread will be stopped from execution until user-space write-unprotects the page using an **UFFDIO_WRITEPROTECT** ioctl.

Multiple modes can be enabled at the same time for the same memory range.

Since Linux 4.14, a userfaultfd page-fault notification can selectively embed faulting thread ID information into the notification. One needs to enable this feature explicitly using the **UFFD_FEA-TURE_THREAD_ID** feature bit when initializing the userfaultfd context. By default, thread ID reporting is disabled.

Usage

The userfaultfd mechanism is designed to allow a thread in a multithreaded program to perform user-space paging for the other threads in the process. When a page fault occurs for one of the regions registered to the userfaultfd object, the faulting thread is put to sleep and an event is generated that can be read via the userfaultfd file descriptor. The fault-handling thread reads events from this file descriptor and services them using the operations described in **ioctl_userfaultfd**(2). When servicing the page fault events, the fault-handling thread can trigger a wake-up for the sleeping thread.

It is possible for the faulting threads and the fault-handling threads to run in the context of different processes. In this case, these threads may belong to different programs, and the program that executes the faulting threads will not necessarily cooperate with the program that handles the page faults. In such non-cooperative mode, the process that monitors userfaultfd and handles page faults needs to be aware of the changes in the virtual memory layout of the faulting process to avoid memory corruption.

Since Linux 4.11, userfaultfd can also notify the fault-handling threads about changes in the virtual memory layout of the faulting process. In addition, if the faulting process invokes **fork**(2), the userfaultfd objects associated with the parent may be duplicated into the child process and the userfaultfd monitor will be notified (via the **UFFD_EVENT_FORK** described below) about the file descriptor associated with the userfault objects created for the child process, which allows the userfaultfd monitor to perform user-space paging for the child process. Unlike page faults which have to be synchronous and require an explicit or implicit wakeup, all other events are delivered asynchronously and the non-cooperative process resumes execution as soon as the userfaultfd manager executes **read**(2). The userfaultfd manager should carefully synchronize calls to **UFFDIO_COPY** with the processing of events.

The current asynchronous model of the event delivery is optimal for single threaded non-cooperative user-faultfd manager implementations.

Since Linux 5.7, userfaultfd is able to do synchronous page dirty tracking using the new write-protect register mode. One should check against the feature bit **UFFD_FEATURE_PAGEFAULT_FLAG_WP** before using this feature. Similar to the original userfaultfd missing mode, the write-protect mode will generate a userfaultfd notification when the protected page is written. The user needs to resolve the page fault by unprotecting the faulted page and kicking the faulted thread to continue. For more information, please refer to the "Userfaultfd write-protect mode" section.

Userfaultfd operation

After the userfaultfd object is created with **userfaultfd**(), the application must enable it using the **UFF-DIO_API ioctl**(2) operation. This operation allows a handshake between the kernel and user space to determine the API version and supported features. This operation must be performed before any of the other **ioctl**(2) operations described below (or those operations fail with the **EINVAL** error).

After a successful **UFFDIO_API** operation, the application then registers memory address ranges using the **UFFDIO_REGISTER ioctl**(2) operation. After successful completion of a **UFFDIO_REGISTER** operation, a page fault occurring in the requested memory range, and satisfying the mode defined at the registration time, will be forwarded by the kernel to the user-space application. The application can then use the **UFFDIO_COPY**, **UFFDIO_ZEROPAGE**, or **UFFDIO_CONTINUE ioctl**(2) operations to resolve the page fault.

Since Linux 4.14, if the application sets the **UFFD_FEATURE_SIGBUS** feature bit using the **UFFD_OIO_API ioctl**(2), no page-fault notification will be forwarded to user space. Instead a **SIGBUS** signal is delivered to the faulting process. With this feature, userfaultfd can be used for robustness purposes to simply catch any access to areas within the registered address range that do not have pages allocated, without having to listen to userfaultfd events. No userfaultfd monitor will be required for dealing with such memory accesses. For example, this feature can be useful for applications that want to prevent the kernel from automatically allocating pages and filling holes in sparse files when the hole is accessed through a memory

mapping.

The UFFD_FEATURE_SIGBUS feature is implicitly inherited through fork(2) if used in combination with UFFD FEATURE FORK.

Details of the various **ioctl**(2) operations can be found in **ioctl_userfaultfd**(2).

Since Linux 4.11, events other than page-fault may enabled during **UFFDIO_API** operation.

Up to Linux 4.11, userfaultfd can be used only with anonymous private memory mappings. Since Linux 4.11, userfaultfd can be also used with hugetlbfs and shared memory mappings.

Userfaultfd write-protect mode (since Linux 5.7)

Since Linux 5.7, userfaultfd supports write-protect mode for anonymous memory. The user needs to first check availability of this feature using **UFFDIO_API** ioctl against the feature bit **UFFD_FEA-TURE_PAGEFAULT_FLAG_WP** before using this feature.

Since Linux 5.19, the write-protection mode was also supported on shmem and hugetlbfs memory types. It can be detected with the feature bit **UFFD_FEATURE_WP_HUGETLBFS_SHMEM**.

To register with userfaultfd write-protect mode, the user needs to initiate the **UFFDIO_REGISTER** ioctl with mode **UFFDIO_REGISTER_MODE_WP** set. Note that it is legal to monitor the same memory range with multiple modes. For example, the user can do **UFFDIO_REGISTER** with the mode set to **UFFDIO_REGISTER_MODE_MISSING** | **UFFDIO_REGISTER_MODE_WP**. When there is only **UFFDIO_REGISTER_MODE_WP** registered, user-space will *not* receive any notification when a missing page is written. Instead, user-space will receive a write-protect page-fault notification only when an existing but write-protected page got written.

After the **UFFDIO_REGISTER** ioctl completed with **UFFDIO_REGISTER_MODE_WP** mode set, the user can write-protect any existing memory within the range using the ioctl **UFFDIO_WRITEPROTECT** where *uffdio_writeprotect.mode* should be set to **UFFDIO_WRITEPROTECT_MODE_WP**.

When a write-protect event happens, user-space will receive a page-fault notification whose *uffd_msg.page-fault.flags* will be with **UFFD_PAGEFAULT_FLAG_WP** flag set. Note: since only writes can trigger this kind of fault, write-protect notifications will always have the **UFFD_PAGEFAULT_FLAG_WRITE** bit set along with the **UFFD_PAGEFAULT_FLAG_WP** bit.

To resolve a write-protection page fault, the user should initiate another **UFFDIO_WRITEPROTECT** ioctl, whose *uffd_msg.pagefault.flags* should have the flag **UFFDIO_WRITEPROTECT_MODE_WP** cleared upon the faulted page or range.

Userfaultfd minor fault mode (since Linux 5.13)

Since Linux 5.13, userfaultfd supports minor fault mode. In this mode, fault messages are produced not for major faults (where the page was missing), but rather for minor faults, where a page exists in the page cache, but the page table entries are not yet present. The user needs to first check availability of this feature using the **UFFDIO_API** ioctl with the appropriate feature bits set before using this feature: **UFFD_FEATURE_MINOR_HUGETLBFS** since Linux 5.13, or **UFFD_FEATURE_MINOR_SHMEM** since Linux 5.14.

To register with userfaultfd minor fault mode, the user needs to initiate the **UFFDIO_REGISTER** ioctl with mode **UFFD_REGISTER_MODE_MINOR** set.

When a minor fault occurs, user-space will receive a page-fault notification whose *uffd_msg.pagefault.flags* will have the **UFFD_PAGEFAULT_FLAG_MINOR** flag set.

To resolve a minor page fault, the handler should decide whether or not the existing page contents need to be modified first. If so, this should be done in-place via a second, non-userfaultfd-registered mapping to the same backing page (e.g., by mapping the shmem or hugetlbfs file twice). Once the page is considered "up to date", the fault can be resolved by initiating an **UFFDIO_CONTINUE** ioctl, which installs the page table entries and (by default) wakes up the faulting thread(s).

Minor fault mode supports only hugetlbfs-backed (since Linux 5.13) and shmem-backed (since Linux 5.14) memory.

Reading from the userfaultfd structure

Each **read**(2) from the userfaultfd file descriptor returns one or more *uffd_msg* structures, each of which describes a page-fault event or an event required for the non-cooperative userfaultfd usage:

```
struct uffd_msg {
                              /* Type of event */
    __u8 event;
    . . .
    union {
        struct {
            __u64 flags; /* Flags describing fault */
             __u64 address; /* Faulting address */
             union {
                 __u32 ptid; /* Thread ID of the fault */
             } feat;
        } pagefault;
                            /* Since Linux 4.11 */
/* Userfault file descriptor
        struct {
             __u32 ufd;
                                 of the child process */
        } fork;
                             /* Since Linux 4.11 */
        struct {
            __u64 from; /* Old address of remapped area */
__u64 to; /* New address of remapped area */
__u64 len; /* Original mapping length */
        } remap;
            struct {
        } remove;
    } arg;
    /* Padding fields omitted */
} __packed;
```

If multiple events are available and the supplied buffer is large enough, **read**(2) returns as many events as will fit in the supplied buffer. If the buffer supplied to **read**(2) is smaller than the size of the *uffd_msg* structure, the **read**(2) fails with the error **EINVAL**.

The fields set in the *uffd_msg* structure are as follows:

event The type of event. Depending of the event type, different fields of the arg union represent details required for the event processing. The non-page-fault events are generated only when appropriate feature is enabled during API handshake with **UFFDIO_API ioctl**(2).

The following values can appear in the *event* field:

UFFD_EVENT_PAGEFAULT (since Linux 4.3)

A page-fault event. The page-fault details are available in the pagefault field.

UFFD_EVENT_FORK (since Linux 4.11)

Generated when the faulting process invokes **fork**(2) (or **clone**(2) without the **CLONE_VM** flag). The event details are available in the *fork* field.

UFFD_EVENT_REMAP (since Linux 4.11)

Generated when the faulting process invokes **mremap**(2). The event details are available in the *remap* field.

UFFD_EVENT_REMOVE (since Linux 4.11)

Generated when the faulting process invokes **madvise**(2) with **MADV_DONTNEED** or **MADV REMOVE** advice. The event details are available in the *remove* field.

UFFD_EVENT_UNMAP (since Linux 4.11)

Generated when the faulting process unmaps a memory range, either explicitly using **munmap**(2) or implicitly during **mmap**(2) or **mremap**(2). The event details are available in the *remove* field.

pagefault.address

The address that triggered the page fault.

pagefault.flags

A bit mask of flags that describe the event. For **UFFD_EVENT_PAGEFAULT**, the following flag may appear:

UFFD_PAGEFAULT_FLAG_WP

If this flag is set, then the fault was a write-protect fault.

UFFD_PAGEFAULT_FLAG_MINOR

If this flag is set, then the fault was a minor fault.

UFFD_PAGEFAULT_FLAG_WRITE

If this flag is set, then the fault was a write fault.

If neither UFFD_PAGEFAULT_FLAG_WP nor UFFD_PAGEFAULT_FLAG_MINOR are set, then the fault was a missing fault.

pagefault.feat.pid

The thread ID that triggered the page fault.

fork.ufd

The file descriptor associated with the userfault object created for the child created by **fork**(2).

remap.from

The original address of the memory range that was remapped using **mremap**(2).

remap.to

The new address of the memory range that was remapped using **mremap**(2).

remap.len

The original length of the memory range that was remapped using **mremap**(2).

remove.start

The start address of the memory range that was freed using **madvise**(2) or unmapped

remove.end

The end address of the memory range that was freed using **madvise**(2) or unmapped

A **read**(2) on a userfaultfd file descriptor can fail with the following errors:

EINVAL

The userfaultfd object has not yet been enabled using the UFFDIO_API ioctl(2) operation

If the **O_NONBLOCK** flag is enabled in the associated open file description, the userfaultfd file descriptor can be monitored with **poll**(2), **select**(2), and **epoll**(7). When events are available, the file descriptor indicates as readable. If the **O_NONBLOCK** flag is not enabled, then **poll**(2) (always) indicates the file as having a **POLLERR** condition, and **select**(2) indicates the file descriptor as both readable and writable.

RETURN VALUE

On success, **userfaultfd**() returns a new file descriptor that refers to the userfaultfd object. On error, -1 is returned, and *errno* is set to indicate the error.

ERRORS

EINVAL

An unsupported value was specified in fla gs.

EMFILE

The per-process limit on the number of open file descriptors has been reached

ENFILE

The system-wide limit on the total number of open files has been reached.

ENOMEM

Insufficient kernel memory was available.

EPERM (since Linux 5.2)

The caller is not privileged (does not have the **CAP_SYS_PTRACE** capability in the initial user namespace), and /proc/sys/vm/unprivileged_userfaultfd has the value 0.

VERSIONS

The **userfaultfd()** system call first appeared in Linux 4.3.

The support for hugetlbfs and shared memory areas and non-page-fault events was added in Linux 4.11

STANDARDS

userfaultfd() is Linux-specific and should not be used in programs intended to be portable.

NOTES

The userfaultfd mechanism can be used as an alternative to traditional user-space paging techniques based on the use of the **SIGSEGV** signal and **mmap**(2). It can also be used to implement lazy restore for check-point/restore mechanisms, as well as post-copy migration to allow (nearly) uninterrupted execution when transferring virtual machines and Linux containers from one host to another.

BUGS

If the **UFFD_FEATURE_EVENT_FORK** is enabled and a system call from the **fork**(2) family is interrupted by a signal or failed, a stale userfaultfd descriptor might be created. In this case, a spurious **UFFD EVENT FORK** will be delivered to the userfaultfd monitor.

EXAMPLES

The program below demonstrates the use of the userfaultfd mechanism. The program creates two threads, one of which acts as the page-fault handler for the process, for the pages in a demand-page zero region created using **mmap**(2).

The program takes one command-line argument, which is the number of pages that will be created in a mapping whose page faults will be handled via userfaultfd. After creating a userfaultfd object, the program then creates an anonymous private mapping of the specified size and registers the address range of that mapping using the **UFFDIO_REGISTER ioctl(2)** operation. The program then creates a second thread that will perform the task of handling page faults.

The main thread then walks through the pages of the mapping fetching bytes from successive pages. Because the pages have not yet been accessed, the first access of a byte in each page will trigger a page-fault event on the userfaultfd file descriptor.

Each of the page-fault events is handled by the second thread, which sits in a loop processing input from the userfaultfd file descriptor. In each loop iteration, the second thread first calls**poll**(2) to check the state of the file descriptor, and then reads an event from the file descriptor. All such events should be **UFFD_EVENT_PAGEFAULT** events, which the thread handles by copying a page of data into the faulting region using the **UFFDIO_COPY ioctl**(2) operation.

The following is an example of what we see when running the program:

```
$ ./userfaultfd_demo 3
Address returned by mmap() = 0x7fd30106c000

fault_handler_thread():
    poll() returns: nready = 1; POLLIN = 1; POLLERR = 0
```

```
UFFD_EVENT_PAGEFAULT event: flags = 0; address = 7fd30106c00f
               (uffdio_copy.copy returned 4096)
      Read address 0x7fd30106c00f in main(): A
      Read address 0x7fd30106c40f in main(): A
      Read address 0x7fd30106c80f in main(): A
      Read address 0x7fd30106cc0f in main(): A
      fault_handler_thread():
          poll() returns: nready = 1; POLLIN = 1; POLLERR = 0
          UFFD_EVENT_PAGEFAULT event: flags = 0; address = 7fd30106d00f
               (uffdio_copy.copy returned 4096)
      Read address 0x7fd30106d00f in main(): B
      Read address 0x7fd30106d40f in main(): B
      Read address 0x7fd30106d80f in main(): B
      Read address 0x7fd30106dc0f in main(): B
      fault_handler_thread():
          poll() returns: nready = 1; POLLIN = 1; POLLERR = 0
          UFFD_EVENT_PAGEFAULT event: flags = 0; address = 7fd30106e00f
               (uffdio_copy.copy returned 4096)
      Read address 0x7fd30106e00f in main(): C
      Read address 0x7fd30106e40f in main(): C
      Read address 0x7fd30106e80f in main(): C
      Read address 0x7fd30106ec0f in main(): C
Program source
   /* userfaultfd_demo.c
      Licensed under the GNU General Public License version 2 or later.
   * /
   #define _GNU_SOURCE
   #include <err.h>
   #include <errno.h>
   #include <fcntl.h>
   #include <inttypes.h>
   #include <linux/userfaultfd.h>
   #include <poll.h>
   #include <pthread.h>
   #include <stdio.h>
   #include <stdlib.h>
   #include <string.h>
   #include <sys/ioctl.h>
   #include <sys/mman.h>
   #include <sys/syscall.h>
   #include <unistd.h>
   static int page_size;
   static void *
   fault_handler_thread(void *arg)
       int
                           nready;
                                   /* userfaultfd file descriptor */
       long
                           uffd;
       ssize_t
                           nread;
```

```
struct pollfd
              pollfd;
struct uffdio_copy uffdio_copy;
               fault_cnt = 0; /* Number of faults so far handled */
static int
static char
               *page = NULL;
static struct uffd_msg msg; /* Data read from userfaultfd */
uffd = (long) arg;
/* Create a page that will be copied into the faulting region. */
if (page == NULL) {
    page = mmap(NULL, page_size, PROT_READ | PROT_WRITE,
              MAP_PRIVATE | MAP_ANONYMOUS, -1, 0);
    if (page == MAP_FAILED)
       err(EXIT_FAILURE, "mmap");
}
/* Loop, handling incoming events on the userfaultfd
   file descriptor. */
for (;;) {
    /* See what poll() tells us about the userfaultfd. */
    pollfd.fd = uffd;
    pollfd.events = POLLIN;
    nready = poll(&pollfd, 1, -1);
    if (nready == -1)
        err(EXIT_FAILURE, "poll");
    printf("\nfault_handler_thread():\n");
    printf(" poll() returns: nready = %d; "
           "POLLIN = %d; POLLERR = %d\n", nready,
           (pollfd.revents & POLLIN) != 0,
           (pollfd.revents & POLLERR) != 0);
    /* Read an event from the userfaultfd. */
    nread = read(uffd, &msg, sizeof(msg));
    if (nread == 0) {
       printf("EOF on userfaultfd!\n");
        exit(EXIT_FAILURE);
    }
    if (nread == -1)
        err(EXIT_FAILURE, "read");
    /* We expect only one kind of event; verify that assumption. */
    if (msg.event != UFFD_EVENT_PAGEFAULT) {
       fprintf(stderr, "Unexpected event on userfaultfd\n");
        exit(EXIT_FAILURE);
    }
```

```
/* Display info about the page-fault event. */
        printf(" UFFD EVENT PAGEFAULT event: ");
        printf("flags = %"PRIx64"; ", msg.arg.pagefault.flags);
        printf("address = %"PRIx64"\n", msg.arg.pagefault.address);
        /* Copy the page pointed to by 'page' into the faulting
           region. Vary the contents that are copied in, so that it
           is more obvious that each fault is handled separately. */
        memset(page, 'A' + fault_cnt % 20, page_size);
        fault_cnt++;
        uffdio_copy.src = (unsigned long) page;
        /* We need to handle page faults in units of pages(!).
           So, round faulting address down to page boundary. */
        uffdio_copy.dst = (unsigned long) msg.arg.pagefault.address &
                                           ~(page_size - 1);
        uffdio_copy.len = page_size;
        uffdio_copy.mode = 0;
        uffdio_copy.copy = 0;
        if (ioctl(uffd, UFFDIO COPY, &uffdio copy) == -1)
            err(EXIT_FAILURE, "ioctl-UFFDIO_COPY");
        printf("
                       (uffdio_copy.copy returned %"PRId64")\n",
              uffdio_copy.copy);
   }
}
main(int argc, char *argv[])
    int
              s;
             c;
    char
    char
              *addr; /* Start of region handled by userfaultfd */
             uffd;
                       /* userfaultfd file descriptor */
   pthread_t thr; /* ID of thread that handles page faults */
struct uffdio_api uffdio api;
            len, l; /* Length of region handled by userfaultfd */
    struct uffdio_register uffdio_register;
    if (argc != 2) {
        fprintf(stderr, "Usage: %s num-pages\n", argv[0]);
        exit(EXIT FAILURE);
    }
    page_size = sysconf(_SC_PAGE_SIZE);
    len = strtoull(argv[1], NULL, 0) * page_size;
    /* Create and enable userfaultfd object. */
    uffd = syscall(SYS_userfaultfd, O_CLOEXEC | O_NONBLOCK);
```

```
if (uffd == -1)
   err(EXIT_FAILURE, "userfaultfd");
uffdio api.api = UFFD API;
uffdio api.features = 0;
if (ioctl(uffd, UFFDIO_API, &uffdio_api) == -1)
    err(EXIT_FAILURE, "ioctl-UFFDIO_API");
/* Create a private anonymous mapping. The memory will be
  demand-zero paged--that is, not yet allocated. When we
   actually touch the memory, it will be allocated via
   the userfaultfd. */
addr = mmap(NULL, len, PROT_READ | PROT_WRITE,
           MAP_PRIVATE | MAP_ANONYMOUS, -1, 0);
if (addr == MAP FAILED)
   err(EXIT_FAILURE, "mmap");
printf("Address returned by mmap() = %p\n", addr);
/* Register the memory range of the mapping we just created for
  handling by the userfaultfd object. In mode, we request to track
  missing pages (i.e., pages that have not yet been faulted in). */
uffdio_register.range.start = (unsigned long) addr;
uffdio_register.range.len = len;
uffdio_register.mode = UFFDIO_REGISTER_MODE_MISSING;
if (ioctl(uffd, UFFDIO_REGISTER, &uffdio_register) == -1)
    err(EXIT_FAILURE, "ioctl-UFFDIO_REGISTER");
/* Create a thread that will process the userfaultfd events. */
s = pthread_create(&thr, NULL, fault_handler_thread, (void *) uffd);
if (s != 0) {
    errc(EXIT_FAILURE, s, "pthread_create");
/* Main thread now touches memory in the mapping, touching
  locations 1024 bytes apart. This will trigger userfaultfd
   events for all pages in the region. */
            /* Ensure that faulting address is not on a page
              boundary, in order to test that we correctly
              handle that case in fault_handling_thread(). */
while (1 < len) {
   c = addr[1];
   printf("Read address %p in %s(): ", addr + 1, __func__);
   printf("%c\n", c);
   1 += 1024;
   usleep(100000); /* Slow things down a little */
}
exit(EXIT_SUCCESS);
```

}

SEE ALSO

 $fcntl(2), ioctl(2), ioctl_userfaultfd(2), madvise(2), mmap(2)\\$

Documentation/admin-guide/mm/userfaultfd.rst in the Linux kernel source tree