## **NAME**

XtOpenApplication, XtVaOpenApplication - initialize, open, or close a display

#### **SYNTAX**

#include <X11/Intrinsic.h>

Widget XtOpenApplication(XtAppContext \*app\_context\_return, const char \*application\_class, XrmOptionDescRec \*options, Cardinal num\_options, int \*argc\_in\_out, char \*\*argv\_in\_out, String \*fall-back\_resources, WidgetClass widget\_class, ArgList args, Cardinal num\_args);

Widget XtVaOpenApplication(XtAppContext \*app\_context\_return, const char \*application\_class, XrmOptionDescRec \*options, Cardinal num\_options, int \*argc\_in\_out, char \*\*argv\_in\_out, String \*fall-back\_resources, WidgetClass widget\_class, ...);

# **ARGUMENTS**

app\_context\_return

Specifies the application context.

application\_class

Specifies the class name of this application, which usually is the generic name for all in-

stances of this application.

options Specifies how to parse the command line for any application-specific resources. The op-

tions argument is passed as a parameter to XrmParseCommand. For further informa-

tion, see Xlib - C Language X Interface.

*num\_options* Specifies the number of entries in the options list.

argc\_in\_out Specifies a pointer to the number of command line parameters.

*argv\_in\_out* Specifies the command line parameters.

fallback\_resources

Specifies resource values to be used if the application class resource file cannot be opened

or read, or NULL.

widget\_class Specifies the widget class of the shell to be created.

args Specifies the argument list to override any other resource specification for the created

shell widget.

*num\_args* Specifies the number of entries in the argument list.

... Specifies the variable argument list to override any other resource specification for the

created shell widget.

## DESCRIPTION

The **XtOpenApplication** function calls **XtToolkitInitialize** followed by **XtCreateApplicationContext**, then calls **XtOpenDisplay** with *display\_string* NULL and *application\_name* NULL, and finally calls **XtAppCreateShell** with *application\_name* NULL, the specified *widget\_class*, and the specified *args* and *num\_args* and returns the created shell. The modified *argc* and *argv* returned by **XtDisplayInitialize** are returned in *argc\_in\_out* and *argv\_in\_out*. If *app\_context\_return* is not NULL, the created application context is also returned. If the display specified by the command line cannot be opened, an error message is issued and **XtOpenApplication** terminates the application. If *fallback\_resources* is non-NULL, **XtAppSet-FallbackResources** is called with the value prior to calling **XtOpenDisplay**.

XtAppInitialize and XtVaAppInitialize have been superceded by **XtOpenApplication** and **XtVaOpenApplication** respectively.

## **SEE ALSO**

XtAppInitialize(3), XtVaAppInitialize(3) X Toolkit Intrinsics — C Language Interface Xlib — C Language X Interface