NAME

cmake-qt - CMake Qt Features Reference

INTRODUCTION

CMake can find and use Qt 4 and Qt 5 libraries. The Qt 4 libraries are found by the **FindQt4** find—module shipped with CMake, whereas the Qt 5 libraries are found using "Config—file Packages" shipped with Qt 5. See **cmake—packages(7)** for more information about CMake packages, and see *the Qt cmake manual* for your Qt version.

Qt 4 and Qt 5 may be used together in the same **CMake buildsystem**:

```
cmake_minimum_required(VERSION 3.8.0 FATAL_ERROR)
project(Qt4And5)

set(CMAKE_AUTOMOC ON)

find_package(Qt5 COMPONENTS Widgets DBus REQUIRED)
add_executable(publisher publisher.cpp)
target_link_libraries(publisher Qt5::Widgets Qt5::DBus)

find_package(Qt4 REQUIRED)
add_executable(subscriber subscriber.cpp)
target_link_libraries(subscriber Qt4::QtGui Qt4::QtDBus)
```

A CMake target may not link to both Qt 4 and Qt 5. A diagnostic is issued if this is attempted or results from transitive target dependency evaluation.

QT BUILD TOOLS

Qt relies on some bundled tools for code generation, such as **moc** for meta-object code generation, **uic** for widget layout and population, and **rcc** for virtual file system content generation. These tools may be automatically invoked by **cmake(1)** if the appropriate conditions are met. The automatic tool invocation may be used with both Qt 4 and Qt 5.

AUTOMOC

The **AUTOMOC** target property controls whether **cmake(1)** inspects the C++ files in the target to determine if they require **moc** to be run, and to create rules to execute **moc** at the appropriate time.

If a macro from **AUTOMOC_MACRO_NAMES** is found in a header file, **moc** will be run on the file. The result will be put into a file named according to **moc_<basename>.cpp**. If the macro is found in a C++ implementation file, the moc output will be put into a file named according to **<basename>.moc**, following the Qt conventions. The **<basename>.moc** must be included by the user in the C++ implementation file with a preprocessor **#include**.

Included **moc_*.cpp** and ***.moc** files will be generated in the **<AUTOGEN_BUILD_DIR>/include** directory which is automatically added to the target's **INCLUDE_DIRECTORIES**.

- This differs from CMake 3.7 and below; see their documentation for details.
- For **multi configuration generators**, the include directory is **<AUTOGEN_BUILD_DIR>/include_<CONFIG>**.
- See AUTOGEN_BUILD_DIR.

Not included **moc_<basename>.cpp** files will be generated in custom folders to avoid name collisions and included in a separate file which is compiled into the target, named either **<AUTO-GEN_BUILD_DIR>/mocs_compilation.cpp** or **<AUTOGEN_BUILD_DIR>/mocs_compilation_\$<CONFIG>.cpp**.

• See AUTOGEN_BUILD_DIR.

The **moc** command line will consume the **COMPILE_DEFINITIONS** and **INCLUDE_DIRECTORIES** target properties from the target it is being invoked for, and for the appropriate build configuration.

The AUTOMOC target property may be pre–set for all following targets by setting the CMAKE_AUTO-MOC variable. The AUTOMOC_MOC_OPTIONS target property may be populated to set options to pass to moc. The CMAKE_AUTOMOC_MOC_OPTIONS variable may be populated to pre–set the options for all following targets.

Additional macro names to search for can be added to AUTOMOC_MACRO_NAMES.

Additional **moc** dependency file names can be extracted from source code by using **AUTOMOC_DE-PEND FILTERS**.

Source C++ files can be excluded from **AUTOMOC** processing by enabling **SKIP_AUTOMOC** or the broader **SKIP AUTOGEN**.

AUTOUIC

The **AUTOUIC** target property controls whether **cmake(1)** inspects the C++ files in the target to determine if they require **uic** to be run, and to create rules to execute **uic** at the appropriate time.

If a preprocessor **#include** directive is found which matches **<path>ui_<base>basename>.h**, and a **<base-name>.ui** file exists, then **uic** will be executed to generate the appropriate file. The **<basename>.ui** file is searched for in the following places

- 1. <source_dir>/<basename>.ui
- 2. <source_dir>/<path><basename>.ui
- 3. <AUTOUIC SEARCH PATHS>/<basename>.ui
- 4. <AUTOUIC_SEARCH_PATHS>/<path><basename>.ui

where **<source_dir>** is the directory of the C++ file and **AUTOUIC_SEARCH_PATHS** is a list of additional search paths.

The generated generated ui_*.h files are placed in the <AUTOGEN_BUILD_DIR>/include directory which is automatically added to the target's INCLUDE DIRECTORIES.

- This differs from CMake 3.7 and below; see their documentation for details.
- For **multi configuration generators**, the include directory is **<AUTOGEN_BUILD_DIR>/include_<CONFIG>**.
- See AUTOGEN_BUILD_DIR.

The **AUTOUIC** target property may be pre–set for all following targets by setting the **CMAKE_AUTOUIC** variable. The **AUTOUIC_OPTIONS** target property may be populated to set options to pass to **uic**. The **CMAKE_AUTOUIC_OPTIONS** variable may be populated to pre–set the options for all following targets. The **AUTOUIC_OPTIONS** source file property may be set on the **
base-name>.ui** file to set particular options for the file. This overrides options from the **AUTOUIC_OPTIONS** target property.

A target may populate the **INTERFACE_AUTOUIC_OPTIONS** target property with options that should be used when invoking **uic**. This must be consistent with the **AUTOUIC_OPTIONS** target property content of the depender target. The **CMAKE_DEB UG_TARGET_PROPERTIES** variable may be used to track the origin target of such **INTERFACE_AUTOUIC_OPTIONS**. This means that a library which provides an alternative translation system for Qt may specify options which should be used when running

uic:

```
add_library(KI18n klocalizedstring.cpp)
target_link_libraries(KI18n Qt5::Core)

# KI18n uses the tr2i18n() function instead of tr(). That function is
# declared in the klocalizedstring.h header.
set(autouic_options
    -tr tr2i18n
    -include klocalizedstring.h
)

set_property(TARGET KI18n APPEND PROPERTY
    INTERFACE_AUTOUIC_OPTIONS ${autouic_options}}
)
```

A consuming project linking to the target exported from upstream automatically uses appropriate options when **uic** is run by **AUTOUIC**, as a result of linking with the **IMPORTED** target:

```
set(CMAKE_AUTOUIC ON)
# Uses a libwidget.ui file:
add_library(LibWidget libwidget.cpp)
target_link_libraries(LibWidget
   KF5::KI18n
   Qt5::Widgets
)
```

Source files can be excluded from AUTOUIC processing by enabling SKIP_AUTOUIC or the broader SKIP_AUTOGEN.

AUTORCC

The AUTORCC target property controls whether cmake(1) creates rules to execute rcc at the appropriate time on source files which have the suffix .qrc.

```
add_executable(myexe main.cpp resource_file.qrc)
```

The AUTORCC target property may be pre–set for all following targets by setting the CMAKE_AUTORCC variable. The AUTORCC_OPTIONS target property may be populated to set options to pass to rcc. The CMAKE_A UTORCC_OPTIONS variable may be populated to pre–set the options for all following targets. The AUTORCC_OPTIONS source file property may be set on the <name>.qrc file to set particular options for the file. This overrides options from the AUTORCC_OPTIONS target property.

Source files can be excluded from AUTORCC processing by enabling SKIP_AUTORCC or the broader SKIP_AUTOGEN.

THE <ORIGIN> AUTOGEN TARGET

The **moc** and **uic** tools are executed as part of a synthesized **<ORIGIN>_autogen custom target** generated by CMake. By default that **<ORIGIN>_autogen** target inherits the dependencies of the **<ORIGIN>_autogen** (see **AUTOGEN_ORIGIN_DEPENDS**). Target dependencies may be added to the **<ORIGIN>_autogen** target by adding them to the **AUTOGEN_TARGET_DEPENDS** target property.

VISUAL STUDIO GENERATORS

When using the **Visual Studio generators**, CMake generates a **PRE_BUILD custom command** instead of the **<ORIGIN>_autogen custom target** (for **AUTOMOC** and **AUTOUIC**). This isn't always possible though and an **<ORIGIN>_autogen custom target** is used, when either

- the <ORIGIN> target depends on GENERATED files which aren't excluded from AUTOMOC and AUTOUIC by SKIP_AUTOMOC, SKIP_AUTOUIC, SKIP_AUTOGEN or CMP0071
- AUTOGEN_TARGET_DEPENDS lists a source file
- CMAKE_GLOBAL_AUTOGEN_TARGET is enabled

QTMAIN.LIB ON WINDOWS

The Qt 4 and 5 **IMPORTED** targets for the QtGui libraries specify that the qtmain.lib static library shipped with Qt will be linked by all dependent executables which have the **WIN32_EXECUTABLE** enabled.

To disable this behavior, enable the Qt5_NO_LINK_QTMAIN target property for Qt 5 based targets or QT4_NO_LINK_QTMAIN target property for Qt 4 based targets.

```
add_executable(myexe WIN32 main.cpp)
target_link_libraries(myexe Qt4::QtGui)

add_executable(myexe_no_qtmain WIN32 main_no_qtmain.cpp)
set_property(TARGET main_no_qtmain PROPERTY QT4_NO_LINK_QTMAIN ON)
target_link_libraries(main_no_qtmain Qt4::QtGui)
```

COPYRIGHT

2000-2022 Kitware, Inc. and Contributors