### **NAME**

atanh, atanhf, atanhl - inverse hyperbolic tangent function

#### **LIBRARY**

Math library (libm, -lm)

### **SYNOPSIS**

```
#include <math.h>
```

**double atanh(double** *x***)**;

float atanhf(float x);

long double atanhl(long double x);

Feature Test Macro Requirements for glibc (see **feature\_test\_macros**(7)):

```
atanh():
```

```
_ISOC99_SOURCE || _POSIX_C_SOURCE >= 200112L || _XOPEN_SOURCE >= 500 || /* Since glibc 2.19: */_DEFAULT_SOURCE || /* glibc <= 2.19: */_BSD_SOURCE || _SVID_SOURCE |

atanhf(), atanhl(): _ISOC99_SOURCE || _POSIX_C_SOURCE >= 200112L || /* Since glibc 2.19: */_DEFAULT_SOURCE || _/* glibc <= 2.19: */_BSD_SOURCE || _SVID_SOURCE || _/* glibc <= 2.19: */_BSD_SOURCE || _/* glibc <= 2.19: */_B
```

#### **DESCRIPTION**

These functions calculate the inverse hyperbolic tangent of x; that is the value whose hyperbolic tangent is x.

### **RETURN VALUE**

On success, these functions return the inverse hyperbolic tangent of x.

If x is a NaN, a NaN is returned.

If x is +0 (-0), +0 (-0) is returned.

If x is +1 or -1, a pole error occurs, and the functions return **HUGE\_VAL**, **HUGE\_VALF**, or **HUGE\_VALL**, respectively, with the mathematically correct sign.

If the absolute value of x is greater than 1, a domain error occurs, and a NaN is returned.

### **ERRORS**

See **math\_error**(7) for information on how to determine whether an error has occurred when calling these functions.

The following errors can occur:

Domain error: x less than -1 or greater than +1

errno is set to EDOM. An invalid floating-point exception (FE\_INVALID) is raised.

Pole error: x is +1 or -1

*errno* is set to **ERANGE** (but see BUGS). A divide-by-zero floating-point exception (**FE\_DI-VBYZERO**) is raised.

## **ATTRIBUTES**

For an explanation of the terms used in this section, see **attributes**(7).

Interface	Attribute	Value
atanh(), atanhl()	Thread safety	MT-Safe

### **STANDARDS**

C99, POSIX.1-2001, POSIX.1-2008.

The variant returning double also conforms to SVr4, 4.3BSD.

# **BUGS**

In glibc 2.9 and earlier, when a pole error occurs, *errno* is set to **EDOM** instead of the POSIX-mandated **ERANGE**. Since glibc 2.10, glibc does the right thing.

# **SEE ALSO**

acosh(3), asinh(3), catanh(3), cosh(3), sinh(3), tanh(3)