NAME

fido2-cred — make/verify a FIDO2 credential

SYNOPSIS

DESCRIPTION

fido2-cred makes or verifies a FIDO2 credential.

A credential *type* may be *es256* (denoting ECDSA over NIST P-256 with SHA-256), *rs256* (denoting 2048-bit RSA with PKCS#1.5 padding and SHA-256), or *eddsa* (denoting EDDSA over Curve25519 with SHA-512). If *type* is not specified, *es256* is assumed.

When making a credential, the authenticator may require the user to authenticate with a PIN. If the **-q** option is not specified, **fido2-cred** will prompt the user for the PIN. If a *tty* is available, **fido2-cred** will use it to obtain the PIN. Otherwise, *stdin* is used.

The input of **fido2-cred** is defined by the parameters of the credential to be made/verified. See the **INPUT FORMAT** section for details.

The output of **fido2-cred** is defined by the result of the selected operation. See the **OUTPUT FORMAT** section for details.

If a credential is successfully created or verified, **fido2-cred** exits 0. Otherwise, **fido2-cred** exits 1.

The options are as follows:

- -M Tells **fido2-cred** to make a new credential on *device*.
- **-V** Tells **fido2-cred** to verify a credential.
- **-b** Request the credential's "largeBlobKey", a 32-byte symmetric key associated with the generated credential.
- -c cred_protect

If making a credential, set the credential's protection level to <code>cred_protect</code>, where <code>cred_protect</code> is the credential's protection level in decimal notation. Please refer to <code><fido/param.h></code> for the set of possible values. If verifying a credential, check whether the credential's protection level was signed by the authenticator as <code>cred_protect</code>.

- -d Causes **fido2-cred** to emit debugging output on *stderr*.
- **-h** If making a credential, enable the FIDO2 hmac-secret extension. If verifying a credential, check whether the extension data bit was signed by the authenticator.
- -i input file

Tells **fido2-cred** to read the parameters of the credential from *input_file* instead of *stdin*.

-o output_file

Tells **fido2-cred** to write output on output_file instead of stdout.

- -q Tells **fido2-cred** to be quiet. If a PIN is required and -q is specified, **fido2-cred** will fail.
- -r Create a resident credential. Resident credentials are called "discoverable credentials" in CTAP 2.1.

- Create a U2F credential. By default, **fido2-cred** will use FIDO2 if supported by the authentica--11 tor, and fallback to U2F otherwise.
- $-\mathbf{v}$ If making a credential, request user verification. If verifying a credential, check whether the user verification bit was signed by the authenticator.

INPUT FORMAT

The input of fido2-cred consists of base64 blobs and UTF-8 strings separated by newline characters ('\n').

When making a credential, **fido2-cred** expects its input to consist of:

- client data hash (base64 blob);
- 2. relying party id (UTF-8 string);
- 3. user name (UTF-8 string);
- 4. user id (base64 blob).

When verifying a credential, **fido2-cred** expects its input to consist of:

- 1. client data hash (base64 blob);
- 2. relying party id (UTF-8 string);
- 3. credential format (UTF-8 string);
- 4. authenticator data (base64 blob);
- 5. credential id (base64 blob);
- 6. attestation signature (base64 blob);
- 7. attestation certificate (optional, base64 blob).

UTF-8 strings passed to **fido2-cred** must not contain embedded newline or NUL characters.

OUTPUT FORMAT

The output of fido2-cred consists of base64 blobs, UTF-8 strings, and PEM-encoded public keys separated by newline characters ('\n').

Upon the successful generation of a credential, **fido2-cred** outputs:

- 1. client data hash (base64 blob);
- 2. relying party id (UTF-8 string);
- 3. credential format (UTF-8 string);
- 4. authenticator data (base64 blob);
- 5. credential id (base64 blob);
- 6. attestation signature (base64 blob);
- 7. attestation certificate, if present (base64 blob).
- the credential's associated 32-byte symmetric key ("largeBlobKey"), if present (base64 blob).

Upon the successful verification of a credential, **fido2-cred** outputs:

- 1. credential id (base64 blob);
- 2. PEM-encoded credential key.

EXAMPLES

Create a new es256 credential on /dev/hidraw5, verify it, and save the id and the public key of the credential in cred:

```
$ echo credential challenge | openssl sha256 -binary | base64 >
cred_param
```

```
$ echo relying party >> cred_param
```

\$ echo user name >> cred param

```
$ dd if=/dev/urandom bs=1 count=32 | base64 >> cred_param
$ fido2-cred -M -i cred_param /dev/hidraw5 | fido2-cred -V -o cred
```

SEE ALSO

fido2-assert(1), fido2-token(1)

CAVEATS

Please note that **fido2-cred** handles Basic Attestation and Self Attestation transparently. In the case of Basic Attestation, the validity of the authenticator's attestation certificate is *not* verified.