



Hands-on session Day 3 Density Functional Perturbation Theory: calculation of phonons

Andrea Urru

SISSA – Scuola Internazionale Superiore di Studi Avanzati, Trieste, Italy

aurru@sissa.it

Summer School on Advanced Materials and Molecular Modelling with QUANTUM ESPRESSO

Jozef Stefan Institute (Ljubljana, Slovenia), September 16th-20th, 2019

Outline

- 1. Introduction
- 2. Exercise 1a: Phonons at Gamma in non-polar materials
- 3. Exercise 1b: Phonon dispersion in non-polar materials
- 4. Exercise 2a: Phonons at Gamma in polar materials
- 5. Exercise 2b: Phonon dispersion in polar materials
- 6. Exercise 3: Phonon dispersion of 2D materials (optional)


Outline


1. Introduction


- 2. Exercise 1a: Phonons at Gamma in non-polar materials
- 3. Exercise 1b: Phonon dispersion in non-polar materials
- 4. Exercise 2a: Phonons at Gamma in polar materials
- 5. Exercise 2b: Phonon dispersion in polar materials
- 6. Exercise 3: Phonon dispersion of 2D materials (optional)

Let us consider a unit cell with N_{at} atoms.

 $s = 1...N_{at}$ index of an atom in the unit cell $\alpha = x, y, z$ is the cartesian index







 $3 \times N_{at}$ variables

Interatomic Force Constants:

$$C_{s\alpha,s'\beta}(\mathsf{R},\mathsf{R}') = C_{s\alpha,s'\beta}(\mathsf{R}-\mathsf{R}') = \frac{\partial^2 E_{tot}}{\partial \mathsf{u}_{s\alpha}(\mathsf{R})\partial \mathsf{u}_{s'\beta}(\mathsf{R}')} \longrightarrow \mathcal{N}_\mathsf{R}^2$$

Fourier transformation:

$$\tilde{\mathsf{u}}_{slpha}(\mathsf{q}) = \sum_{\mathsf{R}} \mathsf{u}_{slpha}(\mathsf{R}) \, e^{-i\mathsf{q}\cdot\mathsf{R}}$$

Essence of the Bloch theorem:

$$\frac{\partial^2 E_{tot}}{\partial \tilde{\mathbf{u}}_{s\alpha}^*(\mathbf{q})\partial \tilde{\mathbf{u}}_{s'\beta}(\mathbf{q}')} = \delta_{\mathbf{q},\mathbf{q}'} \frac{\partial^2 E_{tot}}{\partial \tilde{\mathbf{u}}_{s\alpha}^*(\mathbf{q})\partial \tilde{\mathbf{u}}_{s'\beta}(\mathbf{q})}$$



Important concept: We can perform calculations of Interatomic Force Constants for each **q** independently!

Important concept: Instead of $N_{\mathbf{R}}^2$ Interatomic Force Constants we need only $N_{\mathbf{R}}$!

Sampling theorem

The number of \mathbf{q} points is equal to the number of \mathbf{R} points at which Interatomic Force Constants are computed.

Normal mode frequencies, ω , and eigenvectors, $\mathbf{U}_{s\alpha}$ are determined by the secular equation:

$$\sum_{s',\beta} \tilde{D}_{s\alpha,s'\beta}(\mathbf{q}) \, \tilde{\mathbf{u}}_{s'\beta}(\mathbf{q}) = \omega_{\mathbf{q}}^2 \, \tilde{\mathbf{u}}_{s\alpha}(\mathbf{q})$$

where

$$\tilde{D}_{s\alpha,s'\beta}(\mathbf{q}) = \frac{1}{\sqrt{M_s M_{s'}}} \sum_{\mathbf{R},\mathbf{R}'} \frac{\partial^2 E_{tot}}{\partial \mathbf{u}_{s\alpha}(\mathbf{R}) \partial \mathbf{u}_{s'\beta}(\mathbf{R}')} e^{i\mathbf{q}(\mathbf{R}'-\mathbf{R})}$$

is the *dynamical matrix*.

Interatomic Force Constants (IFC)

Diagonalization of the dynamical matrix gives phonon modes at q.

Outline

- 1. Introduction
- 2. Exercise 1a: Phonons at Gamma in non-polar materials
- 3. Exercise 1b: Phonon dispersion in non-polar materials
- 4. Exercise 2a: Phonons at Gamma in polar materials
- 5. Exercise 2b: Phonon dispersion in polar materials
- 6. Exercise 3: Phonon dispersion of 2D materials (optional)

Go to the directory with the input files:

In this directory you will find:

- README.md File describing how to do the exercise
- Scf.Si.in Input file for the SCF ground-state calculation
- ph.Si.in Input file for the phonon calculation at Γ
- dynmat.Si.in Input file to impose the acoustic sum rule
- reference Directory with the reference results

Step 1. Perform a Self-Consistent Field ground-state calculation for silicon <u>at the equilibrium structure</u> using the <u>pw.x</u> program.

scf.Si.in

Input file for the SCF calculation

```
&control
    calculation='scf'
    restart mode='from scratch',
    pseudo dir='../../pseudo'
    outdir='./out'
    prefix='Si',
 &system
    ibrav = 2.
    celldm(1) = 10.20.
    nat = 2,
   ntyp = 1,
    ecutwfc = 16
&electrons
   diagonalization = 'davidson'
   mixing mode = 'plain',
   conv thr = 1.0d-8
   mixing beta = 0.7
ATOMIC SPECIES
 Si 28.0855 Si.vbc.UPF
ATOMIC POSITIONS
 Si 0.00 0.00 0.00
Si 0.25 0.25 0.25
K POINTS
   10
 0.1250000 0.1250000 0.1250000
                                   1.00
 0.1250000 0.1250000 0.3750000
                                   3.00
 0.1250000 0.1250000 0.6250000
                                   3.00
 0.1250000 0.1250000 0.8750000
                                   3.00
                                   3.00
 0.1250000 0.3750000 0.3750000
 0.1250000 0.3750000 0.6250000
                                   6.00
 0.1250000 0.3750000 0.8750000
                                   6.00
 0.1250000 0.6250000 0.6250000
                                   3.00
 0.3750000
          0.3750000
                       0.3750000
                                   1.00
 0.3750000 0.3750000 0.6250000
                                   3.00
```

Step 2. Perform a phonon calculation at Γ using the ph.x program.

ph.Si.in

Input file for the phonon calculation

```
Phonons at Gamma &inputph prefix = 'Si', tr2_ph = 1.0d-14, amass(1) = 28.0855, outdir = './out' fildyn = 'Si.dyn', /

0.0 0.0 0.0 0.0 The same prefix as in the SCF calculation Threshold for self-consistency Atomic mass Directory for temporary files File containing the dynamical matrix Coordinates of the q point in units of 2*pi/a in Cartesian framework
```

ph.x < ph.Si.in > ph.Si.out

Step 2. Perform a phonon calculation at Γ using the ph.x program.


ph.Si.in

Input file for the phonon calculation

```
Phonons at Gamma
&inputph
   prefix = 'Si',
   tr2_ph = 1.0d-14,
   amass(1) = 28.0855,
   outdir = './out'
   fildyn = 'Si.dyn',
   /
   0.0   0.0   0.0
```

We consider only the Γ point:

 $\mathbf{q} = 2*pi/a (0.0, 0.0, 0.0)$



Brillouin Zone

Dynamical matrix file Si.dyn:

```
(0.069949) [THz] =
          1) =
                                          2.333248 [cm-1]
 freq (
                            0.000000 -0.699311
                                               0.000000)
0.006270
          0.000000
0.006270
          0.000000
                   0.104520 0.000000 -0.699311
                                               0.000000)
                     0.069949 [THz] =
 freq (
          2) =
                                          2.333248 [cm-1]
                   0.286121
                            0.000000 0.048545
                                               0.000000)
0.644809
          0.000000
0.644809
                                               0.000000)
          0.000000
                   0.286121 0.000000
                                      0.048545
                     0.069949 [THz] =
 freq (
          3) =
                                          2.333248 [cm-1]
0.290142
          0.000000 -0.638130
                            0.000000 -0.092775
                                               0.000000)
0.290142
          0.000000 -0.638130
                            0.000000 -0.092775
                                               0.000000
                    15.474501 [THz] =
                                        516.173789 [cm-1]
 freq (
-0.534305
          0.000000 -0.463023
                            0.000000 -0.011325
                                               0.000000)
0.534305
          0.000000 0.463023
                                               0.000000)
                            0.000000
                                      0.011325
 freq (
          5) =
               15.474501 [THz] =
                                        516.173789 [cm-1]
-0.202506
          0.000000 0.217991
                            0.000000
                                      0.641460
                                               0.000000)
0.202506
          0.000000 -0.217991
                            0.000000 -0.641460
                                               0.000000)
 freq (
         6) =
                    15.474501 [THz] =
                                        516.173789 [cm-1]
0.416545
          0.000000 -0.487944
                            0.000000
                                      0.297322
                                               0.000000)
-0.416545
          0.000000
                   0.487944
                            0.000000 -0.297322
                                               0.000000)
```

Acoustic modes



Optical modes



Acoustic sum rule at Γ

Because of the numerical inaccuracies the interatomic force constants do not strictly satisfy the acoustic sum rule (ASR).

ASR comes directly from the continous translational invariance of the crystal. If we translate the whole solid by a uniform displacement, the forces acting on the atoms must be zero.

As a consequence:

For each
$$\alpha$$
, β and i :
$$\sum_{\mathbf{L},j} C_{\alpha i,\beta j}(\mathbf{R_L}) = 0$$

As a consequence, the frequencies of the acoustic modes must be zero.

Acoustic sum rule at Γ

Because of the numerical inaccuracies the interatomic force constants do not strictly satisfy the acoustic sum rule (ASR) => acoustic frequencies are not exactly zero.

However, the ASR can be imposed using the **dynmat.x** program.

The input file is **dynmat.Si.in**:

```
&input
fildyn = 'Si.dyn',
asr = 'simple'
/ A way to impose the acoustic sum rule
(simple, crystal, one-dim, zero-dim)
```

dynmat.x < dynmat.Si.in > dynmat.Si.out

The program dynmat.x produces the file dynmat.out which contains the new acoustic frequencies, which are *exactly* equal to zero.

diagonalizing the dynamical matrix ...

```
0.0000
                     0.0000
                                  0.0000
                        0.000000)[THz] =
  freq (
                                                0.000000 [cm-1]
                          0.707107
0.000000
            0.000000
                                      0.000000
                                                   0.000000
                                                               0.000000
0.000000
            0.000000
                          <del>0.707</del>107
                                      0.000000
                                                   0.000000
                                                               0.000000
                        0.000000)[THz] =
            2) =
                                                0.000000 [cm-1]
 freq (
-0.707107
            0.000000
                          0.000000
                                      0.000000
                                                   0.000000
                                                               0.000000
-0.707107
            0.000000
                          0.000000
                                      0.000000
                                                   0.000000
                                                               0.000000
 freq (
            3) =
                        0.000000)[THz] =
                                                0.000000 [cm-1]
                          0.000000
0.000000
            0.000000
                                      0.000000
                                                   -0.707107
                                                               0.000000
0.000000
            0.000000
                          0.000000
                                      0.000000
                                                   -0.707107
                                                               0.000000
 freq (
            4) =
                       15.474329 [THz]
                                              516.168042 [cm-1]
0.000000
            0.000000
                          0.707107
                                      0.000000
                                                   0.000000
                                                               0.000000
0.000000
            0.000000
                         -0.707107
                                                   0.000000
                                      0.000000
                                                               0.000000
                       15.474329 [THz] =
                                              516.168042 [cm-1]
 freq (
            5) =
0.000000
                                                   -0.707107
            0.000000
                          0.000000
                                      0.000000
                                                               0.000000
0.000000
            0.000000
                          0.000000
                                      0.000000
                                                   0.707107
                                                               0.000000
  freq (
            6) =
                       15.474329 [THz] =
                                              516.168042 [cm-1]
-0.707107
            0.000000
                          0.000000
                                      0.000000
                                                   0.000000
                                                               0.000000
            0.000000
 0.707107
                          0.000000
                                      0.000000
                                                    0.000000
                                                               0.000000
```

Outline

- 1. Introduction
- 2. Exercise 1a: Phonons at Gamma in non-polar materials
- 3. Exercise 1b: Phonon dispersion in non-polar materials
- 4. Exercise 2a: Phonons at Gamma in polar materials
- 5. Exercise 2b: Phonon dispersion in polar materials
- 6. Exercise 3: Phonon dispersion of 2D materials (optional)

Go to the directory with the input files:


```
cd QE-2019/Day-3/example1b
```

In this directory you will find:

- README.md File describing how to do the exercise
- scf.Si.in Input file for the SCF ground-state calculation
- ph.Si.in Input file for the phonon calculation on a uniform q-grid
- q2r.Si.in Input file for calculation of Interatomic Force Constants
- matdyn.Si.in Input file for Fourier Interpolation for various q points
- plotband.Si.in Input file for plotting a phonon dispersion
- reference Directory with the reference results

Step 1. Perform a SCF calculation for silicon at the equilibrium structure using the pw.x program.

Step 2. Perform a phonon calculation on a uniform grid of **q** points using the **ph.x** program.




Step 1. Perform a SCF calculation for silicon at the equilibrium structure using the pw.x program.

```
pw.x < Si.scf.in > Si.scf.out
```

Step 2. Perform a phonon calculation.

```
Phonons on a uniform q-grid &inputph prefix='Si', tr2_ph = 1.0d-14, amass(1) = 28.0855, ldisp = .true., nq1 = 4, nq2 = 4, nq3 = 4, outdir='./out' fildyn='Si.dyn', /
```

We sample the Brillouin zone with a uniform grid of 4x4x4 **q** points.



4x4x4 = 64 q-points => Use of symmetry => 8 non-equivalent q points
 The file Si.dyn0 contains a list of the non-equivalent q points (8, in this case).

```
(q-grid)
                   (number of non-equivalent q-points)
                             0.00000000000000E+00
      0.00000000000000E+00
                                                     0.00000000000000E+00
     -0.25000000000000E+00
                             0.25000000000000E+00
                                                    -0.25000000000000E+00
q3
      0.50000000000000E+00
                             -0.50000000000000E+00
                                                     0.50000000000000E+00
     0.00000000000000E+00
                             0.50000000000000E+00
                                                     0.00000000000000E+00
q5 =
     0.75000000000000E+00
                             -0.25000000000000E+00
                                                     0.75000000000000E+00
      0.50000000000000E+00
                             0.00000000000000E+00
                                                     0.50000000000000E+00
      0.00000000000000E+00
                             -0.10000000000000E+01
                                                     0.00000000000000E+00
     -0.50000000000000E+00
                                                     0.00000000000000E+00
                             -0.10000000000000E+01
```

• The phonon program **ph.x** generates files for every non-equivalent **q** point **Si.dyn1**, **Si.dyn2**, ..., **Si.dyn8**, which contain information about dynamical matrices, phonon frequencies and atomic displacements.

Step 3. Calculation of the Interatomic Force Constants (IFC) using the q2r.x program.

Fourier transforms of IFC's:

$$\tilde{C}_{s\alpha,s'\beta}(\mathbf{q}_{ijk}) = \frac{\partial^2 E_{tot}}{\partial \tilde{\mathbf{u}}_{s\alpha}^*(\mathbf{q}_{ijk})\partial \tilde{\mathbf{u}}_{s'\beta}(\mathbf{q}_{ijk})}$$

 α, β are Cartesian components, and \mathbf{S}, \mathbf{S}' are atomic indices.

$$\tilde{C}_{s\alpha,s'\beta}(\mathbf{R}_{lmn}) = \frac{1}{N_{\mathbf{q}}} \sum_{i,j,k} \tilde{C}_{s\alpha,s'\beta}(\mathbf{q}_{ijk}) e^{i\mathbf{q}_{ijk} \cdot \mathbf{R}_{lmn}} \\ \tilde{C}_{s\alpha,s'\beta}(\mathbf{q}_{ijk}) - \hspace{1.5cm} C_{s\alpha,s'\beta}(\mathbf{R}_{lmn})$$

Fourier transforms of IFC's on a grid of **q** points nq1 x nq2 x nq3 in reciprocal space

IFC's in a supercell nq1 x nq2 x nq3 in real space

Input file q2r.Si.in:


```
&input
fildyn='Si.dyn',
zasr='simple',
flfrc='Si444.fc'

Output file of the interatomic force constants
```


The denser the grid of **q** points, the larger the vectors **R** for which the Interatomic Force Constants are calculated!

To perform the calculation:

Step 4. Calculate phonons at generic q' points using IFC by means of the code matdyn.x




Input file Si.matdyn.in:



matdyn.x < matdyn.Si.in > matdyn.Si.out

Step 5. Plot the phonon dispersion using the plotband.x program and gnuplot.

Input file plotband.Si.in:





plotband.x < Si.plotband.in > Si.plotband.out

Use **gnuplot** and the file **plot_dispersion**. **gp** in order to plot the phonon dispersion of silicon (**experimental_data.dat**).


You will obtain a postscript file **phonon_dispersion.eps** which you can visualize.

Phonon dispersion of silicon along some high-symmetry directions in the Brillouin zone (file phonon_dispersion.eps):







How to determine whether the quality of the Fourier interpolation is satisfactory? — Compare with the direct calculation (no interpolation)!



Comparison of the phonon dispersion computed using the Fourier interpolation with the direct calculation at several $\bf q$ points. The $\bf q$ -grid 4x4x4 is very satisfactory for the Fourier interpolation for silicon!




Comparison of the phonon dispersion computed using the Fourier interpolation with the direct calculation at several \mathbf{q} points. The \mathbf{q} -grid 4x4x4 is very satisfactory for the Fourier interpolation for silicon!




Perform a direct phonon calculation (no interpolation) at several **q'** points and make a comparison with the phonon frequencies obtained from the interpolation.

Use **exercise1a** as an example. Some **q'** points along the Gamma-X high symmetry line are listed in the file reference/q_points_direct_calc.txt



The agreement of *ab initio* calculation of the phonon dispersion using the Fourier interpolation on a **q**-grid 4x4x4 is excellent with the experimental data!



The Fourier interpolation works well if the Interatomic Force Constants (IFC's) are known on a sufficiently large supercell, i.e. on a large enough grid of **q** points in the phonon calculation.

There are cases when the IFC's are long range and the Fourier interpolation does not work properly:

- When there are Kohn anomalies in metals. In this case the dynamical matrices are not a smooth function of **q** and the IFC's are long range.
- In polar insulators where the atomic displacements generate long range electrostatic interactions and the dynamical matrix is not analitical for q→0. However, this case can be dealt with by calculating the Born effective charges and the dielectric tensor of the material.

Outline

- 1. Introduction
- 2. Exercise 1a: Phonons at Gamma in non-polar materials
- 3. Exercise 1b: Phonon dispersion in non-polar materials
- 4. Exercise 2a: Phonons at Gamma in polar materials
- 5. Exercise 2b: Phonon dispersion in polar materials
- 6. Exercise 3: Phonon dispersion of 2D materials (optional)

Polar materials in the $\mathbf{q} = \mathbf{0}$ limit: a macroscopic electric field appears as a consequence of the long-range character of the Coulomb interaction (incompatible with Periodic Boundary Conditions).

A non-analytic term must be added to Interatomic Force Constants at $\mathbf{q} = \mathbf{0}$:

$$ilde{C}_{slpha,s'eta}(\mathbf{q}) = ilde{C}_{slpha,s'eta}^{\mathrm{analytic}}(\mathbf{q}) + rac{4\pi}{\Omega} rac{(\mathbf{q}\cdotoldsymbol{Z}_s^{\star})_{lpha}(\mathbf{q}\cdotoldsymbol{Z}_{s'}^{\star})_{eta}}{\mathbf{q}\cdotoldsymbol{\epsilon}_{\infty}\cdot\mathbf{q}}$$

Effective charges Z_s^* are related to polarization **P** induced by a lattice distortion:

$$Z_{s,\alpha\beta}^{\star} = \Omega \frac{\partial \mathrm{P}_{lpha}}{\partial \mathit{u}_{seta}}$$

Dielectric tensor $\epsilon_{\infty}^{\alpha\beta}$ is related to polarization **P** induced by an electric field **E**:

$$\epsilon_{\infty}^{lphaeta} = \delta_{lphaeta} + 4\pi \left. rac{\partial \mathrm{P}_{lpha}}{\partial \mathrm{E}_{eta}} \right|_{u_{s}(q=0)=0}$$

All of the above can be calculated from (mixed) second order derivatives of the total energy.

Go to the directory with the input files:

Step 1. Perform a Self-Consistent Field ground-state calculation for a polar semiconductor AIAs.

Step 2. Perform a phonon calculation at Gamma for AlAs.

```
Phonons at Gamma &inputph prefix='AlAs', tr2_ph = 1.0d-14, amass(1) = 26.98, amass(2) = 74.92, outdir='./out' fildyn='AlAs.dyn', epsil = .true. /
0.0 0.0 0.0
```

If .true. will calculate and store the dielectric tensor and effective charges

In the file **ph.Alas.out** you will find an information about the dielectric tensor and effective charges:

```
Dielectric constant in cartesian axis
            13.743494475
                               -0.000000000
                                                   0.0000000000)
            -0.000000000
                               13.743494475
                                                   0.000000000 )
             0.000000000
                                0.000000000
                                                  13.743494475 )
     Effective charges (d Force / dE) in cartesian axis
                    Αl
      atom
               1.88274
                              0.00000
                                              0.00000)
 Ex
                                            -0.00000 )
 Ey
              0.00000
                              1.88274
 Ez
              0.00000
                             -0.00000
                                             1.88274 )
      atom
                2 As
             -3.23377
 Ex
                             -0.00000
                                              0.00000)
 Εy
             -0.00000
                             -3.23377
                                             0.00000)
                                            -3.23377 )
 Ez
             -0.00000
                              0.00000
Diagonalizing the dynamical matrix
q = (
         0.000000000
                        0.000000000
                                      0.0000000000)
freq (
                                             4.931268 [cm-1]
          1) =
                      0.147836 [THz] =
frea (
          2) =
                      0.147836 [THz] =
                                             4.931268 [cm-1]
freq (
                      0.147836 [THz] =
                                             4.931268 [cm-1]
          3) =
freq (
          4) =
                     11.258207
                                           375.533365 [cm-1]
                               THz] =
freq (
                     11.258207 THz] =
          5) =
                                           375.533365 [cm-1]
frea (
          6) =
                     11.258207 [THz] =
                                            375.533365 [cm-1]
```

No LO-TO splitting

Step 3. Impose Acoustic Sum Rule and <u>add the non-analytic LO-TO splitting</u> using the <u>dynmat.x</u> program.

Input file dynmat.AlAs.in:

```
&input
    fildyn = 'AlAs.dyn',
    asr='simple',
    amass(1)=26.98,
    amass(2)=74.92
    q(1) = 1.0,
    q(2) = 0.0,
    q(3) = 0.0
/
```



Direction for the LO-TO splitting

Output file dynmat.out:

```
-0.000000 [THz] =
   frea (
  0.538473
              0.000000
                           -0.458309
                                       0.000000
  0.538473
              0.000000
                           -0.458309
                                       0.000000
   freq (
                         -0.000000 [THz] =
              2) =
  0.000000
              0.000000
                            0.000000
                                       0.000000
  0.000000
              0.000000
                            0.000000
                                       0.000000
   freq (
                         0.000000 [THz] =
              3) =
(-0.458309)
                           -0.538473
              0.000000
                                       0.000000
(-0.458309)
              0.000000
                                       0.000000
                            0.538473
                         1.257454 THz] =
   frea (
              4) =
  0.000000
                            0.940852
              0.000000
                                       0.000000
( -0.000000
              0.000000
                           -0.338817
                                       0.000000
   freq (
              5) =
                        11.257454 THzl =
              0.000000
                            0.000000
  0.000000
                                       0.000000
  0.000000
              0.000000
                           0.000000
                                       0.000000
   freq (
                        12.307908 THzl
              6) =
  0.940852
              0.000000
                           -0.000000
                                       0.000000
 -0.338817
              0.000000
                            0.000000
                                       0.000000
```

LO-TO splitting

Outline

- 1. Introduction
- 2. Exercise 1a: Phonons at Gamma in non-polar materials
- 3. Exercise 1b: Phonon dispersion in non-polar materials
- 4. Exercise 2a: Phonons at Gamma in polar materials
- 5. Exercise 2b: Phonon dispersion in polar materials
- 6. Exercise 3: Phonon dispersion of 2D materials (optional)

Go to the directory with the input files:

• Calculate phonon dispersion in AlAs following the same steps as in **exercise 1b**.


Where necessary insert the missing information in the input files.

- Step 1. Perform a SCF ground-state calculation for AlAs using pw.x
- Step 2. Perform a phonon calculation on a 4x4x4 **q**-grid using **ph.x** (dielectric tensor and effective charges will be calculated)
- Step 3. Perform Fourier Transformations (FT) of $\tilde{C}_{s\alpha,s'\beta}(\mathbf{q})$ in order to obtain Interatomic Force Constants in real space $C_{s\alpha,s'\beta}(\mathbf{R})$ using $\mathbf{q2r.x}$.

A term having the same behaviour for $\mathbf{q} \to \mathbf{0}$ as the non-analytic term is subtracted from $\tilde{C}_{s\alpha,s'\beta}(\mathbf{q})$ before the FT and re-added to $C_{s\alpha,s'\beta}(\mathbf{R})$, so that no problem related to non-analytic behaviour and related long-rangeness arises in the FT.

- Step 4. Calculate phonons at generic q' points using Interatomic Force Constants (including the non-analytic term) using the code matdyn.x
- Step 5. Plot the phonon dispersion of AlAs using plotband.x and gnuplot.

The phonon dispersion of AlAs:



Outline

- 1. Introduction
- 2. Exercise 1a: Phonons at Gamma in non-polar materials
- 3. Exercise 1b: Phonon dispersion in non-polar materials
- 4. Exercise 2a: Phonons at Gamma in polar materials
- 5. Exercise 2b: Phonon dispersion in polar materials
- 6. Exercise 3: Phonon dispersion in 2D materials (optional)

Exercise 3: Phonon dispersion in 2D materials

Go to the directory with the input files:


- Calculate phonon dispersion in 2D hexagonal BN following the same steps as in exercise 1b and exercise 2b.
- Notice that the options assume_isolated='2D' in scf.bn.in and loto_2d=.true. in q2r.bn.in and matdyn.bn.in have been set to properly deal with 2D materials.

Exercise 3: Phonon dispersion in 2D materials

- Step 1. Perform a SCF ground-state calculation for 2D h-BN using pw.x
- Step 2. Perform a phonon calculation on a 6x6x1 **q**-grid using **ph.x**
- Step 3. Perform Fourier Transformations (FT) of $\tilde{C}_{s\alpha,s'\beta}(\mathbf{q})$ in order to obtain Interatomic Force Constants in real space $C_{s\alpha,s'\beta}(\mathbf{R})$ using $\mathbf{q2r}.\mathbf{x}$.
- Step 4. Calculate phonons at generic q' points using Interatomic Force Constants using the code matdyn.x
- Step 5. Plot the phonon dispersion of 2D h-BN using plotband.x and gnuplot.

Exercise 3: Phonon dispersion in 2D materials

The phonon dispersion of 2D hexagonal BN:



Bibliography

Books

- 1. N. W. Ashcroft, N. D. Mermin, Solid State Physics (for general discussion)
- 2. M. Fox, Optical properties of solids (for LO-TO splitting)

Papers

- **1**. S. Baroni, P. Giannozzi, and A. Testa, *Green's-function approach to linear response in solids*, Phys. Rev. Lett. **58**, 1861 (1987).
- **2**. P. Giannozzi, S. de Gironcoli, P. Pavone, and S. Baroni, *Ab initio calculation of phonon dispersions in semiconductors*, Phys. Rev. B **43**, 7231 (1991).
- **3**. S. Baroni, S. de Gironcoli, A. Dal Corso, and P. Giannozzi, *Phonons and related crystal properties from density-functional perturbation theory*, Rev. Mod. Phys. **73**, 515 (2001).
- **4**. T. Sohier, M. Gibertini, M. Calandra, F. Mauri, and N. Marzari, *Breakdown of Optical Phonons' splitting in Two-Dimensional Materials*, Nano Lett. 2017, **17**, 6, 3758-3763.

