
Docker Bind Mounts

Overview of File Trees and Mount Points in Linux

In Linux, all storage is consolidated into a single tree structure, unlike other operating systems. This structure organizes storage devices such as disk partitions or USB drives by attaching them to specific locations within the tree, known as mount points. Mount points define the location in the tree, access properties, and the source of the mounted data.



Mount points enable seamless usage of the file tree in a Linux environment without requiring detailed knowledge of storage device mappings. This is particularly advantageous in container environments where each container has its own unique file tree root and set of mount points.

Bind mounts are a powerful feature that allows mapping directories or files on the host system into a Docker container, enabling *direct interaction* between the containerized application and the host filesystem.

What are Bind Mounts?:


Bind mounts allow you to attach specific files or directories from the host system to locations within a container's filesystem. Essentially, they remount parts of the host filesystem tree onto the container.

With bind mounts, the files and directories are directly accessible from both the host and the container, facilitating seamless sharing of data between them.

How Bind Mounts Work:

When you create a bind mount, you specify a source location on the host system and a target location within the container. The target location within the container effectively becomes a mirror of the source location on the host.

Any changes made to files or directories within the bind mount from either the host or the container are immediately reflected in both environments.



Example Scenario

Consider a scenario where you have an NGINX web server running inside a Docker container. The NGINX server requires access to a configuration file stored on the host system and needs to write access logs to a file on the host.

Solution

We can do this by using bind mounts, we can map these host files into the container, enabling seamless interaction between the containerized NGINX server and the host filesystem. To demonstrate the usage of bind mounts, we can follow these steps:

Step 1: Create Placeholder Files

First, we need to create the files that the NGINX container will use for its configuration and logging.

Create an empty log file:

```
touch ~/example.log
```

This command creates an empty file named example.log in the home directory. This file will be used by NGINX to write access logs.

Create a custom NGINX configuration file:

```
cat > ~/example.conf <<EOF
server {
    listen 80;
    server_name localhost;
    access_log /var/log/nginx/custom.host.access.log main;
    location / {
        root /usr/share/nginx/html;
        index index.html index.htm;
    }
}</pre>
```

This command creates a file named example.conf in the home directory with the provided NGINX server configuration. The configuration sets up an NGINX server to:

- Listen on port 80.
- Serve content from /usr/share/nginx/html.
- Write access logs to /var/log/nginx/custom.host.access.log.

```
root@09f4476223564cb1:~# touch ~/example.log
root@09f4476223564cb1:~# ls
example.log install-prerequisites-k3s.sh install.sh
root@09f4476223564cb1:~# cat > ~/example.conf <<EOF
> server {
> listen 80;
> server_name localhost;
> access_log /var/log/nginx/custom.host.access.log main;
> location / {
> root /usr/share/nginx/html;
> index index.html index.htm;
> }
> }
> EOF
root@09f4476223564cb1:~#
```

Step 2: Run NGINX Container with Bind Mounts

Now, we'll run an NGINX container and use bind mounts to map the host files into the container.

Define variables for source and destination paths:

```
CONF_SRC=~/example.conf

CONF_DST=/etc/nginx/conf.d/default.conf

LOG_SRC=~/example.log

LOG_DST=/var/log/nginx/custom.host.access.log
```

CONF_SRC is the path to our custom NGINX configuration file on the host.

CONF_DST is the path where the configuration file will be mounted inside the container.

LOG_SRC is the path to our log file on the host.

LOG_DST is the path where the log file will be mounted inside the container.

Run the container with bind mounts:

```
docker run -d --name diaweb \
    --mount type=bind,src=${CONF_SRC},dst=${CONF_DST} \
    --mount type=bind,src=${LOG_SRC},dst=${LOG_DST} \
    -p 8000:80 \
    nginx:latest
```

Here,

- **docker run -d** starts the container in detached mode (running in the background).
- --name diaweb names the container diaweb.
- --mount type=bind,src=\${CONF_SRC},dst=\${CONF_DST} mounts the host's example.conf to the container's /etc/nginx/conf.d/default.conf.
- --mount type=bind,src=\${LOG_SRC},dst=\${LOG_DST} mounts the host's example.log to the container's /var/log/nginx/custom.host.access.log.
- -p 80:80 maps port 80 of the host to port 80 of the container, making the web server accessible via http://localhost.
- nginx:latest specifies the Docker image to use.

Expected Output:

```
root@f7ae7407a93669fb:~#
root@f7ae7407a93669fb:∼# docker run -d --name diaweb \ ←
   --mount type=bind,src=${CONF SRC},dst=${CONF DST} \
   --mount type=bind,src=${LOG_SRC},dst=${LOG_DST} \
   -p 8000:80 \
  nginx:latest
c1d4fdc2272c32f33bfbabae8fa018d4548be409f1494d6668ab4ed632e07ffe
root@f7ae7407a93669fb:~# docker ps
CONTAINER ID IMAGE
                            COMMAND
                                                     CREATED
                                                                     STATUS
c1d4fdc2272c nginx:latest "/docker-entrypoint..."
                                                   3 seconds ago
                                                                     Up 2 seconds
                                                                                   0.0.0.0:8000->80/tcp, :::8000->80/tcp
                                                                                                                          diaweb
root@f7ae7407a93669fb:~#
```

Step 3: Access the Web Server and Logs

After running the container, we can verify the setup.

Access the NGINX web server:

To verify if nginx is running we can run this command to check it from the terminal:

curl http://localhost:8000

we should get this response from nginx server:

```
root@f7ae7407a93669fb:~# curl http://localhost:8000
<!DOCTYPE html>
<html>
<head>
<title>Welcome to nginx!</title>
<style>
html { color-scheme: light dark; }
body { width: 35em; margin: 0 auto;
font-family: Tahoma, Verdana, Arial, sans-serif; }
</style>
</head>
<body>
<h1>Welcome to nginx!</h1>
If you see this page, the nginx web server is successfully installed and
 working. Further configuration is required.
For online documentation and support please refer to
<a href="http://nginx.org/">nginx.org</a>.<br/>
Commercial support is available at
<a href="http://nginx.com/">nginx.com</a>.
<em>Thank you for using nginx.</em>
</html>
 oot@f7ae7407a93669fb:~#
```

Check the logs:

Run the command on the host to see the access logs generated by NGINX. These logs are written to the example.log file on the host due to the bind mount.

cat ~/example.log

```
root@491b09600433b96d:~# cat ~/example.log
172.17.0.1 - - [31/May/2024:20:21:20 +0000] "GET / HTTP/1.1" 200 615 "-" "curl/7.68.0" "-"
root@491b09600433b96d:~#
```

Step 4: Make Configuration File Read-Only

To enhance security, we can make the configuration file read-only so that the container cannot modify it.

Remove the existing container:

docker stop diaweb

docker rm -f diaweb

This command forcefully removes the diaweb container.

```
root@f7ae7407a93669fb:~#
root@f7ae7407a93669fb:~#
docker stop diaweb
diaweb
root@f7ae7407a93669fb:~#
docker rm -f diaweb
diaweb
root@f7ae7407a93669fb:~# docker ps
CONTAINER ID IMAGE COMMAND CREATED STATUS PORTS NAMES
root@f7ae7407a93669fb:~#
```

Run the container with a read-only bind mount:

```
docker run -d --name diaweb \
--mount type=bind,src=${CONF_SRC},dst=${CONF_DST},readonly=true \
--mount type=bind,src=${LOG_SRC},dst=${LOG_DST} \
-p 8000:80 \
nginx:latest
```

Adding readonly=true to the bind mount for CONF_DST ensures that the configuration file cannot be modified by processes inside the container.

```
root@f7ae7407a93669fb:~# docker run -d --name diaweb \
   -mount type=bind,src=${CONF_SRC},dst=${CONF_DST},readonly=true \
  --mount type=bind,src=${LOG_SRC},dst=${LOG_DST} \
 -p 8000:80 \
 nginx:latest
a97d58da9675e35645ebf3aa7d7a39627e2fb085f3261c35fed96a90d9a75c97
root@f7ae7407a93669fb:~# docker ps
CONTAINER ID IMAGE
                                                                       STATUS
             nginx:latest
a97d58da9675
                             "/docker-entrypoint..." 3 seconds ago
                                                                      Up 2 seconds
                                                                                      0.0.0.0:8000->80/tcp, :::8000->80/tcp
                                                                                                                              diaweb
oot@f7ae7407a93669fb:~#
```

Step 5: Attempt to Modify Read-Only File

Finally, we can test the read-only restriction by attempting to modify the configuration file inside the container.

Try to modify the nginx configuration file:

docker exec diaweb \

sed -i "s/listen 8000/listen 8001/" /etc/nginx/conf.d/default.conf

This command atteps to modify the NGINX configuration file

(/etc/nginx/conf.d/default.conf) inside the container using sed to change the port in the NGINX configuration file from 8080 to 8081. Because the file is mounted as read-only, this command will fail due to the file being mounted as read-only.

The output confirms that the container has been started with the readonly=true flag applied to the bind mount for the configuration file. The failed attempt to modify the configuration file verifies that the mount is indeed read-only, preventing modifications to the file inside the container.

Considerations

Portability: Bind mounts tie the container to specific paths on the host filesystem, which can reduce portability across different hosts.

Conflicts: If multiple containers use the same bind mount for data storage, they can interfere with each other, leading to data corruption.

Conclusion

Bind mounts are a powerful tool for sharing files and directories between Docker containers and the host filesystem. By understanding their usage and the associated considerations, you can effectively manage data and configurations for your containerized applications.