Trust

What it is and how to get it

Dr. Perry Alexander

Information and Telecommunication Technology Center
Electrical Engineering and Computer Science
The University of Kansas
palexand@ku.edu



Defining Trust

Trust

"An entity can be trusted if it always behaves in the expected manner for the intended purpose [1]"



Defining Trust

Properties

- ► Unambiguous identification
- ► Unimpeded operation
- ► First-hand observation of good behavior *or* indirect experience of good behavior by a trusted third party



Necessary Capabilities for Trust

- ► Strong Identification An unambiguous, immutable identifier associated with the platform. The identifier is a protected encryption key in the TXT implementation.
- ► Reporting Configuration An unambiguous identification mechanism for software and hardware running on the platform. The mechanism is hashing in the TXT implementation



Tools for Trust

- ▶ #X Hash function such as MD-5
 - ▶ #X is unique for each X
 - ► Guessing *X* from #*X* is impossible
- ▶ $\{X\}_Y$ Encrypting X with Y
 - ➤ X cannot be obtained from {X}_Y without Y
 - Y cannot be guessed



We would like to start A and B while gathering evidence of trust

► Start with a root measurer and store that are trusted *a priori*




Trusted Measurer

Α




Measurer

- Start with a root measurer and store that are trusted a priori
- Measure the new software to be launched






- Start with a root measurer and store that are trusted a priori
- Measure the new software to be launched
- Store the measurement of the new software






Measurer

- Start with a root measurer and store that are trusted a priori
- Measure the new software to be launched
- Store the measurement of the new software
- ► Launch the new software





- Start with a root measurer and store that are trusted a priori
- Measure the new software to be launched
- Store the measurement of the new software
- ► Launch the new software
- Repeat for each system software component






Trusted

Measurer

- Start with a root measurer and store that are trusted a priori
- Measure the new software to be launched
- Store the measurement of the new software
- Launch the new software
- Repeat for each system software component





Appraisal — What Do We Know?

Measurement \neq trust — Measurements must be appraised

- ► Determine if 0 | #A | #B is correct
 - ► Calculate a *golden hash* from A and B
 - ► Compare golden hash with 0 | #A | #B from trusted store
 - ► Correct 0 | #A | #B implies trusted boot
- ► Correct 0 | #A | #B implies A and B must be correct
 - ► Correct 0 | #A | #B implies #A and #B are the correct hashes
 - ► Correct #A and #B implies A and B are the correct binaries
 - A includes hash and launch functions
- ► Correct 0 | #A | #B implies measurement occurred in the right order
 - $\blacktriangleright \#(XY) \neq \#(YX)$
 - Trusted store started with 0



Appraisal — But Why Trust B?

A chain exists from the Trusted Measurer and Trusted Store to B

- ► Trusted Measurer and Trusted Store are trusted a priori
- ► A is trusted to be A because its measurement is:
 - ▶ Correct
 - ► Taken by a trusted party (Trusted Measurer)
 - Stored by a trusted party (Trusted Store)
- ▶ B is trusted to be B because its measurement is:
 - ▶ Correct
 - Taken by a trusted party (A)
 - Stored by a trusted party (Trusted Store)
 - If A's ability to measure B were compromised, #A would be wrong
- ▶ and so on and so on...



Trust is a Preorder

 $T^{x}[y]$ is an homogeneous relation over actors that is true when x trusts y. $T^{x}[y]$ is a preorer:

- ► Reflexive $\forall x \cdot T^x[x]$
- ► Transitive $\forall x, y, z \cdot T^{x}[y] \wedge T^{y}[z] \Rightarrow T^{x}[z]$

Measured Boot gathers evidence of these chains



Trusted Platform Module

The *Trusted Platform Module (TPM)* is a cryptographic coprocessor for trust.

- ► Endorsement Key (EK) factory generated asymmetric key that uniquely identifies the TPM
- ► Attestation Instance Key (AIK) TPM_CreateIdentity generated asymmetric key alias for the EK
- Storage Root Key (SRK) TPM_TakeOwnership generated asymmetric key that encrypts data associated with the TPM
- Platform Configuration Registers (PCRs) protected registers for storing and extending hashes
- ► NVRAM Non-volatile storage associated with the TPM



Endorsement Key

- Asymmetric key generated at TPM fabrication
- $ightharpoonup EK^{-1}$ is protected by the TPM
- ► EK by convention is managed by a Certificate Authority
 - ▶ Binds *EK* with a platform
 - Classic trusted third party
- ► Only used for encryption
- Attestation Instance Keys (AIK) are aliases for the EK
 - Used for signing
 - Authorized by the EK



Storage Root Key

- ► Asymmetric key generated by TPM_TakeOwnership
- ► SRK⁻¹ is protected by the TPM
- ► SRK is available for encryption
- Used as the root for chaining keys by wrapping
 - A wrapped key is an asymmetric key pair with it's private key sealed
 - Safe to share the entire key
 - Only usable in the presence of the wrapping key with expected PCRs



Platform Configuration Registers

Operations on PCRs

- Extension Hash a new value juxtaposed with the existing PCR value
- ► Reset Set to 0
- Set Set to a known value

Operations using PCRs

- Sealing data PCR state dependent encryption
- Wrapping keys PCR state dependent encryption of a private key
- Quote Reporting PCR values to a third party

► Properties

- ► Locality Access control
- ▶ Resettable Can a PCR be reset
- Many others that we don't need yet



Roots of Trust

A *root of trust* provides a basis for transitively building trust. Roots of trust are trusted implicitly.

There are three important Roots of Trust:

- ► Root of Trust for Measurement (RTM)
- ► Root of Trust for Reporting (RTR)
- Root of Trust for Storage (RTS)



Root of Trust for Measurement

A *Root of Trust for Measurement* is trusted to take the base system measurement.

- ► A hash function called on an initial code base from a protected execution environment
- Starts the measurement process during boot
- ► In the Intel TXT process the RTM is SENTER implemented on the processor



Root of Trust for Reporting

A *Root of Trust for Reporting* is trusted to guarantee the integrity of the base system report or quote

- ► A protected key used for authenticating reports
- In the Intel TXT processes this is the TPM's Endorsement Key (EK)
- Created and bound to its platform by the TPM foundry
- ► EK⁻¹ is stored in the TPM and cannot be accessed by any entity other than the TPM
- ► EK is available for encrypting data for the TPM
- $ightharpoonup EK^{-1}$ is used for decrypting data inside the TPM
- ► Linking *EK* to its platform is done by a trusted Certificate Authority (CA)



Root of Trust for Storage


A Root of Trust for Storage is trusted to protect stored data


- ► A key stored in a protected location
- ► In the Intel TXT boot process this is the TPM's Storage Root Key (SRK)
- Created by TPM_TakeOwnership
- ► SRK⁻¹ is stored in the TPM and cannot be accessed by any entity other than the TPM
- SRK is available for encrypting data for the TPM
- SRK is used for protecting other keys



Roots of trust are used to build a trusted system from boot.

► Power-on reset









Roots of trust are used to build a trusted system from boot.

- ► Power-on reset
- ▶ Resettable PCRs set to -1









Roots of trust are used to build a trusted system from boot.

- ► Power-on reset
- Resettable PCRs set to -1
- SENTER called, resets resettable PCRs to 0








Roots of trust are used to build a trusted system from boot.

- ▶ Power-on reset
- Resettable PCRs set to -1
- SENTER called, resets resettable PCRs to 0
- ► SENTER measures SINIT policy into PCR 18





What We Know From Good PCR 18

A good value in PCR 18 tells us:

- ► SENTER was called Resetting PCR 18 starts measurements at 0 rather than -1
- ► SINIT was measured by SENTER Only SENTER can extend PCR 18
- SINIT uses the correct policy PCR 18 is extended with SINIT measurement policy
- ▶ SENTER ran before SINIT was measured $A \mid B \neq B \mid A$


Measurement \neq Trust

Measurements must be appraised to determine trust.



Two Steps from Roots of Trust


- SINIT measures the Measured Launch Environment (MLE) using measured policy
- ► SINIT returns control to SENTER





Two Steps from Roots of Trust

- SINIT measures the Measured Launch Environment (MLE) using measured policy
- ► SINIT returns control to SENTER
- ► SENTER invokes the MLE





What We Know From Good PCRs

- ► SENTER was called Resetting PCR 18 starts measurement sequence at 0 rather than -1
- ► SINIT policy was measured by SENTER Only SENTER can extend PCR 18
- SINIT uses the correct policy PCR 18 is extended with SINIT measurement policy
- ▶ SENTER ran before SINIT $0 \mid SINIT \neq -1 \mid SINIT$
- ► MLE is good Measured by good SINIT into PCR
- ► Initial OS is good Measured by good MLE into PCR



► SENTER starts the MLE


- ► SENTER starts the hypervisor
- SENTER passes dom0 to hypervisor
- ► hypervisor starts dom0



Armored VP


vTPM appraiser attester measurer application

TPM





- ► SENTER starts the MLE
 - ► SENTER starts the hypervisor
 - SENTER passes dom0 to hypervisor
 - hypervisor starts dom0
- dom0 constructs the Armored VP
 - Measures the vTPM into the TPM
 - Starts the vTPM






► SENTER starts the MLE

- ► SENTER starts the hypervisor
- SENTER passes dom0 to hypervisor
- hypervisor starts dom0

dom0 constructs the Armored VP

- Measures the vTPM into the TPM
- Starts the vTPM
- Measures remaining Armored VMs into the vTPM
- Starts remaining Armored VMs
- Measures Armored application into the vTPM
- Starts the Armored application





► SENTER starts the MLE

- ► SENTER starts the hypervisor
- SENTER passes dom0 to hypervisor
- hypervisor starts dom0

dom0 constructs the Armored VP

- Measures the vTPM into the TPM
- Starts the vTPM
- Measures remaining Armored VMs into the vTPM
- Starts remaining Armored VMs
- Measures Armored application into the vTPM
- Starts the Armored application





What we know from good PCRs

- ► The right hypervisor and dom0 started PCR 17 measurement and we trust SENTER, SINIT and SINIT Policy
- ► The right vTPM started PCR 19 measurement and we trust SENTER, SINIT, and dom01
- ► The right ArmoredSoftware components started vTPM PCRs and we trust dom0 and the vTPM
- ► The right application started vTPM PCRs and we trust dom0 and the vTPM



¹More work for vTPM startup remains

Chaining Trust (Reprise)

▶ Trust is transitive

- $ightharpoonup T^{x}[y] \wedge T^{y}[z] \Rightarrow T^{x}[z]$
- Construct evidence trust chains
- Remember "directly observed or indirectly observed by a trusted third party"
- Roots of Trust define the "root" for trust
 - Use Roots of Trust to establish base for chain
 - ▶ RTM is the Trusted Measurer
 - ▶ RTS is the Trusted Store
 - ► RTR is the Trusted Reporter (coming soon...)
- Extend chains of trust by measuring before executing



Getting a Quote

A *quote* is a signed data package generated by a TPM used to establish trust

- $\blacktriangleright q = \{|\langle n, pcr \rangle|\}_{AIK^{-1}}$
 - ▶ *n* A nonce or other data
 - pcr A PCR composite generated from TPM PCRs
 - ► AIK⁻¹ An alias for EK⁻¹ used for signing
- AIK is a wrapped TPM key usable only in the TPM that generated it
 - $wrap(AIK, \{pcr\}) = \langle AIK, seal(AIK^{-1}, \{pcr\}) \rangle$
 - ► seal(AIK⁻¹, {pcr}) = {AIK⁻¹}_{SRK} and decrypts only when pcr matches the TPMs PCRs at decryption time
- ► Generated by the TPM with command TPM_Quote



Checking a Quote

Assume that the appraiser is given *q* of the form:

$$q = \{|\langle n, pcr \rangle|\}_{AIK^{-1}}$$


- Signature check using AIK Signature was generated by a TPM with AIK installed
- pcr check using regenerated composite from desired PCR values — TPM PCRs matched desired PCR values at quote generation time
- ▶ n check by knowing nonce or data values Nonce provides replay prevention. Other data serves other purposes.

The binding of AIK to the target is missing



Assume a trusted Certificate Authority (CA) that maintains links from ID to *EK*

► Target *ID_n* requests AIK certification from CA




Appraiser



Assume a trusted Certificate Authority (CA) that maintains links from ID to *EK*

- ► Target ID_n requests AIK certification from CA
- ► CA signs AIK




Attestation

Appraiser




- ► Target *ID_n* requests AIK certification from CA
- ► CA signs AIK
- CA encrypts signed AIK with requester's EK






- ► Target *ID_n* requests AIK certification from CA
- ► CA signs AIK
- CA encrypts signed AIK with requester's EK
- CA sends encrypted AIK to requester






- ► Target ID_n requests AIK certification from CA
- ► CA signs AIK
- CA encrypts signed AIK with requester's EK
- CA sends encrypted AIK to requester
- Requester decrypts encrypted AIK





- Target ID_n requests AIK certification from CA
- ► CA signs AIK
- CA encrypts signed AIK with requester's EK
- CA sends encrypted AIK to requester
- Requester decrypts encrypted AIK
- Requester sends signed AIK to appraiser





Why Believe AIK Belongs to ID_n ?

Cryptographic evidence ensures AIK is an alias for the right EK

- ► Only the CA can generate {|AIK|}_{CA-1}
- ► CA is trusted to know $ID_n > EK_n$
- ► CA is trusted to generate $\{\{|AIK|\}_{CA^{-1}}\}_{EK_n}$
- ► Only ID_n can decrypt $\{\{|AIK|\}_{CA^{-1}}\}_{EK_n}$
- ► Appraiser can check {|AIK|}_{CA-1} to ensure use of trusted CA
- ▶ If Appraiser can use AIK then it was decrypted by ID_n

AIK is an alias for EK used for signing



[1] A. Martin et al. The ten page introduction to trusted computing. Technical Report CS-RR-08-11, Oxford University Computing Labratory, Oxford, UK, 2008.

