

# **Active IQ Digital Advisor documentation**

Active IQ Digital Advisor

NetApp February 03, 2022

This PDF was generated from https://docs.netapp.com/us-en/active-iq/index.html on February 03, 2022. Always check docs.netapp.com for the latest.

# **Table of Contents**

Active IQ Digital Advisor documentation	1
Release notes	2
What's new in Active IQ Digital Advisor	2
Known limitations	. 14
Get started	. 15
Quick start for Active IQ Digital Advisor	. 15
Understand Active IQ features	. 16
Key concepts	. 17
AutoSupport	. 19
Log in to Active IQ Digital Advisor	. 20
Manage your clusters in Cloud Manager	. 20
Provision watchlist	. 21
Understand watchlist	. 21
Create a watchlist	. 21
Manage a watchlist	. 21
Analyze wellness attributes	. 22
Understand wellness	. 22
View the risk and manually take corrective actions	. 23
Increase protection against hackers and Ransomware attacks	. 24
Protect systems against ransomware risks	. 25
View and acknowledge the risk	. 25
View wellness history	. 26
View risks that can be automatically mitigated using Unified Manager or Ansible Playbook	. 26
Avoid the downtime and possible data loss	. 27
Subscribe to wellness review email	. 29
Renew the software and hardware of your storage system	. 30
Analyze the wellness of clusters and nodes	. 30
View system details	. 32
View inventory details.	. 32
View valuable insights	. 32
View capacity utilization with NetApp Keystone Flex Subscription	. 33
Identify system requirements proactively	. 35
Understand planning	. 35
Identify systems reaching capacity limits	. 35
Avoid a volume filling up to prevent an outage	. 36
Renew the software and hardware of your storage system	. 36
Identify configuration deviations	. 38
Understand configuration deviation	. 38
Add a config drift template	. 38
Compare a config drift template	. 39
Generate a drift timeline report	. 39
Manage a template	. 40
Improve the efficiency and performance of your storage system.	. 41

Analyze capacity and storage efficiency savings	41
Analyze performance graphs	42
Monitor and tier inactive data with FabricPool Advisor	44
Analyze the health of your storage system	45
Understand Health Check Dashboard	45
Get started with Health Check Dashboard	45
Renew your support contracts	46
Upgrade to optimize your install base	47
Upgrade the ONTAP version by generating an upgrade plan	47
Upgrade the support offering	47
Update your AFF and FAS firmware using Ansible Playbook	48
Integrate data using APIs	59
Understand API Services	59
Generate tokens to use APIs	60
Use the API Catalog to execute APIs	61
Generate custom reports	62
Types of reports	62
Generate reports	63
Get more information	64
Legal notices	65
Copyright	65
Trademarks	65
Patents	65
Privacy policy	65

# **Active IQ Digital Advisor documentation**

# Release notes

# What's new in Active IQ Digital Advisor

The following features and enhancements have been introduced in NetApp Active IQ Digital Advisor:

## 12 January 2021

## **Config Drift**

- · You can clone a template to make a copy of the original template.
- You can share golden templates with other entitled users with read-only or full access to these templates. Learn how.

#### 15 December 2021

#### **Reports**

- Cluster Viewer Report: This report provides information about a single cluster or multiple clusters at a customer and watchlist level. You can use the ClusterViewer Report to download all the information in a single file. You can generate this report only for watchlist with up to 100 nodes.
- **Performance Report**: This report provides information, at a watchlist level, about the performance of a cluster, node, local tier (aggregate), and volume in a single zip file. Each zip file contains performance data for a single clusters, which helps the user analyze data of each cluster. You can generate this report only for watchlist with up to 100 nodes.

#### Integration with E-Series systems

You can view the capacity details and performance graph of a selected E-series system in Active IQ.

#### **18 November 2021**

#### **Storage Efficiency**

You can view the storage efficiency details for nodes that are maintained and monitored by NetApp Cloud Insights.

#### 11 November 2021

#### **Health Check Dashboard**

- Added icons on those Health Check tiles which are only applicable for systems with the SupportEdge
  Advisor and SupportEdge Expert support offerings. The enhancements have been made to Recommended
  Software–Software Currency and Firmware Currency sections, Recommended Configuration, and Best
  Practices.
- Added a Confidential Data banner for Internal and External (Customers and Partners) users on the Active IQ Digital Advisor—Reports screen.

#### **Wellness and Upgrade Widgets**

Enhanced the dashboard with E-Series upgrade recommendations and risk triggered date added to column in the Wellness Action History.

#### ClusterViewer

The ClusterViewer Stack Visualization module has been enhanced to include the Zoom in/Zoom out and Save Image feature.

#### Storage Efficiency

You can view the storage efficiency details for systems that are maintained and monitored by NetApp Cloud Insights.

#### 14 October 2021

#### **Ansible Inventory**

You can now generate Ansible inventory files in .yml and .ini file formats at the region and site level. Learn how.

#### **Inactive Data Reporting (IDR)**

From the FabricPool Advisor screen, you can activate inactive data reporting (IDR) to monitor aggregates and generate an Ansible Playbook. Learn more

#### **Drift Timeline Report**

You can compare the AutoSupport data of the last 90 days and generate a drift timeline report. Learn how.

#### **Compliant Systems Toggle**

The Health Check dashboard has been enhanced with a toggle for the Minimum OS and Latest OS tabs so that you can view the systems, which are compliant and not compliant with the minimum requirements of the recommended and latest version.

#### **Key Recommendations Summary**

On the Health Check dashboard, you can view a summary of the top 5 overall key recommendations.

#### Tabs for NetApp Cloud Volumes ONTAP and E-Series Platforms

The Health Check dashboard has been enhanced with Cloud Volumes ONTAP \*\* and E-Series tabs so that you can view the Health Check KPIs and details for those platforms.

A tab for 'ONTAP' has also been added along with the other platforms, which are now enabled.

#### Capacity

You can view the capacity details about the NetApp Cloud Volumes ONTAP systems in Active IQ.

#### Reports

The reporting timeline has been extended to 12 months. You will also receive a notification when the schedule report is about to expire.

## 30 September 2021

#### **Customer Qualified Version**

Customer Qualified Version helps a Support Account Manager (SAM) manage a portion of their customer's install base, which hosts applications requiring:

- · An earlier and sometimes unsupported version of ONTAP
- Or a customer's install base tested and certified to use a certain OS version.

#### **Technical Case Workflow**

In both the dashboard and drill down screen, graphical enhancements have been made to the data chart and line graph. You have an option to view that data in a bar graph as well.

In the line-graph window, you can view, select, and deselect graphs for Open, Closed, and Total cases in both these user interfaces.

#### **Performance Graphs**

You can now download the performance graphs in PNG and JPG format, in addition to the CSV format.

#### **End of Support (EOS) Controllers Beyond 12 Months**

The Health Check Dashboard has been enhanced with a tab displaying controllers with an EOS exceeding 12 months.

## 16 September 2021

#### Wellness

- The Ransomware Defense widget is now part of Wellness workflow instead of a standalone widget.
- In the Wellness Review email, you'll find information about the Ransomware Defense instead of Renewals.

#### Capacity

You can view the capacity details about the NetApp ONTAP® Select systems in Active IQ.

#### ClusterViewer

You can view the cabling faults and other errors in the Visualization tab of ClusterViewer.

## 06 September 2021

#### **StorageGRID**

- View AutoSupport: View the AutoSupport logs for the StorageGRID and the underlying nodes.
- StorageGRID Appliance details: View StorageGRID appliance details such as the node type, appliance

model, drive size, drive type, RAID mode, and so on in the GRID Viewer - GRID Inventory section.

- · Renewals: View the list of GRIDs and the underlying nodes that are due for renewal.
- E-series SANtricity risks: View E-series SANtricity risks for the underlying nodes in the GRID Dashboard Wellness section.

#### **Capacity Forecast**

The Capacity Forecast widget has been updated with an improved algorithm that better accounts for system reconfigurations. Learn more.

## 26 August 2021

#### **Active IQ Digital Advisor Mobile Application**

You can now enable biometric authentication on the Active IQ Digital Advisor mobile application. The options available for authentication vary, depending on the features supported by your mobile phone.

#### Download the application to learn more:

Active IQ Digital Advisor Mobile Application (Android) Active IQ Digital Advisor Mobile Application (iOS)

#### Wellness

Wellness widget has been enhanced with Ransomware Defense attribute. You can now view risks and corrective actions associated with ransomware detection, prevention, and recovery.

## 16 August 2021

#### **Wellness Review**

You can now generate the on-demand report. In addition, you can download the last scheduled report from the Wellness Review Subscription screen.

#### Inventory

In the Grid Inventory tab, you can now view the node details based on site level in an expandable and collapsible format.

#### **Mixed-Model Cluster Flag**

Where clusters have mixed-hardware models, the OS version applied across the cluster is the one which all nodes can use. As a result, the OS version of some nodes of more recent hardware models might be downrev from where they should be. To make these mixed-model clusters more visible, we have applied a "mixed model" icon.

#### Recommended Configuration / Storage Virtual Machine (SVM) Health: Volume-level Summary

Upon clicking the blue 'Volume Summary' box in the SVM table, a "pop-out" displays detailed information about the volumes which are hosted or attached to the specific serial number or physical node.

## 12 July 2021

#### **System Firmware**

You can now view information about the system firmware that is shipped along with the major and patch versions of ONTAP. You can access this feature from the Quick Links menu.

#### **Health Check Dashboard**

- The Health Check Dashboard has been enhanced to include a blue banner notifying users that the systems that are not supported by SupportEdge Advisor and SupportEdge Expert will not be factored in while calculating the health score.
- The Recommended Configuration widget has been enhanced to provide an in-depth analysis of the failed checks for your storage VM (SVM) and lets you take the recommended corrective actions for each risk.
- The recommended target ONTAP version is now the same for all nodes in a cluster configured with different hardware models. The target version is supported on all the nodes.
- You can now extend the EOS timeline for controllers, disks, and shelves through the purchase of a PVR.
   PVR dates and extension details, when purchased, are viewable in the end-of-support widget. The PVR details are also provided as part of the EOSL report.

#### Inventory

You can view the end dates of the support contracts for your hardware, software, and non-returnable disks on the detailed inventory page.

#### **Support Offering Upgrade**

- The user interface has been enhanced to display the specific support offering that you are subscribed to in Active IQ.
- You can now raise a request to upgrade your support offering subscription from the system dashboard to access more features. Learn how.

#### 25 June 2021

#### Flex Subscription widget

- If you have opted for ONTAP Collector to obtain data on your capacity usage, you can view the details of
  your file shares and disks in the Shares and Disks tabs. You can save storage space by identifying those
  nearing committed capacity.
- The capacity usage, shown on the Keystone Capacity Utilization dashboard and used for billing, is now based on the logical capacity.

#### 17 June 2021

#### Reports

You can now generate aggregate volume performance reports for all volumes in a storage VM for any day, week, or month.

#### Wellness review email

The wellness review email has been enhanced to include information about the support and entitlements from the health check and upgrade actions.

#### Upgrade workflow

- The user interface has been enhanced to provide you with a table view of the information.
- You can now view information about the end of support of the ONTAP version in the Upgrade Details screen.

#### **Config Drift**

- Config Drift now supports over 200 AutoSupport sections for creating golden templates and generating drift reports across customer, site, group, watchlist, cluster, and host.
- Config drift allows you to mitigate deviations using Ansible playbooks which are included in the config drift report payload.

#### **Health Check Assessment Dashboard**

This feature has been enhanced to compare your storage VM (SVM) against a predefined catalog of risks to assess gaps and recommend the associated corrective actions.

## 09 June 2021

#### **Health Check Assessment Dashboard**

You can now view the number of systems based on which the health score is calculated. This enhancement is applicable for all the attributes in the Health Check Assessment Dashboard.

## 20 May 2021

#### **Drift Chat for capacity addition requests**

For real-time assistance on your capacity addition requests, chat with a salesperson directly from your dashboard. Learn how.

## 29 April 2021

- · Here's how to protect your systems against hackers and Ransomware attacks. Learn how.
- You can avoid the downtime and possible data loss. Learn how.
- Learn how to avoid a volume filling up to prevent an outage. Learn how.

#### 07 April 2021

#### Watchlist

When you access Active IQ Digital Advisor for the first time, you should now create a watchlist instead of a dashboard. You can also view the dashboard for different watchlists, edit the details of an existing watchlist, and delete a watchlist.

## **24 February 2021**

#### **Config Drift**

This release provides the following functionality:

- Ability to edit attributes during template creation.
- · Grouping of AutoSupport sections.
- Generate or schedule a config drift report across customer, site, group, watchlist, cluster, and hostname. Learn how.

#### Reports

You can generate or schedule Capacity and Efficiency reports to view detailed information on the capacity and storage efficiency savings of your system.

## **10 February 2021**

#### **StorageGRID**

StorageGRID Dashboard is enabled using the NextGen API framework.

You can use the StorageGRID Dashboard for viewing information at the Watchlist, Customer, Group, and Site level.

This release provides the following functionality:

- Inventory widget: View inventory of StorageGRID systems available under the selected level.
- **Wellness widget:** View all the Risks and Actions, including the ones related to StorageGRID if they are applicable based on existing ARS rules for the available systems.
- · Planning widget:
  - Capacity Addition: For any GRID sites that are exceeding the threshold of 70% of existing capacity, you'll be notified. You have the option to add capacity for the StorageGRIDs in the site, for the next 1, 3, & 6 months if the capacity threshold is likely to exceed 70%.
  - Renewals: For any StorageGRID systems for which the license contract has expired or is nearing
    expiration in the next 6 months, you'll be notified. You can select one or more systems to raise a
    request to the NetApp support team for renewal.
- GRID dashboard: The GRID dashboard provides wellness, planning, and configuration details for the selected GRID.
- Configuration widget: Provides basic details of the selected StorageGRID in the widget, such as GRID Name, Host Name, Serial Number, Model, OS Version, Customer Name, Shipped Location, and Contact Details.
- **GRID Viewer:** From the **Configuration** widget, you can view the GRID configuration in detail by clicking the **GRID Viewer** link. From the **Configuration** widget, you can download the Site Details and Capacity Details for the selected StorageGRID by clicking the **Download** button in the **Grid Viewer** screen.
- Site details: This tab provides the Grid Summary and Storage Nodes available for each site.
- **GRID summary:** Contains basic information, such as License Type, License Capacity, number of installed nodes, Support Term (Date of termination of license contract), Primary Admin Node, and Primary Site of the Primary Admin Node. This tab also provides the Site name and the number of storage nodes tagged

under the corresponding site. In this release, you can view the list of node names upon clicking the hyperlink available for viewing storage nodes for the corresponding site.

Capacity Details tab: Provides the Grid Level and Site capacity details configured for the GRID. The
Capacity details, such as Installed Storage Capacity, Available Storage Capacity, Total Used Storage
Capacity, and Capacity used for Data and Metadata. These details are available at both the Grid and Site
levels.

#### **FabricPool Advisor**

The Tier Data button has been added to the FabricPool dashboard, and it lets you tier data to low-cost object storage tiers using NetApp Cloud Manager.

#### Cloud ready workloads

You can view the different types of workloads that are available within your storage system and identify the workloads that are cloud-ready.

#### 21 December 2020

#### **Health Check Assessment Dashboard**

The following widgets have been added to the dashboard:

- Recommended Software: This widget provides a consolidated list of all the software and firmware upgrades and currency recommendations.
- Loss of Signal: This widget provides scores and information about the systems, which have stopped sending AutoSupport data for some reason. It provides information if no AutoSupport data has been received from a hostname within a 7-day period.

#### **12 November 2020**

#### Integrating data using APIs

You can use Active IQ APIs to pull data of interest and integrate it directly into your company's workflow. Learn more.

#### Wellness - Upgrades widget

The enhanced Risk Advisor and Upgrade Advisor tabs enable you to view all the system risks and help you plan for an upgrade for mitigating all the risks.

#### **Health Check Assessment Dashboard**

The Recommended Configuration widget has been added to the dashboard, and it provides a summary on the number of systems that are monitored for remote management risks, spares and failed drives risks, and HA pair risks.

#### FabricPool Advisor

You can reduce your storage footprint and associated costs by monitoring your clusters, which have been classified into four categories: inactive local tier (aggregate) data, inactive volume data, tiered data, and those that are not IDR enabled.

#### **Localization in Simplified Chinese and Japanese**

Active IQ Digital Advisor is now available in three languages - Chinese, English, and Japanese.

#### Reports

You can generate or schedule ClusterViewer reports to view detailed information on the physical and logical configuration of your systems. Learn how.

#### 15 October 2020

#### **Health Check Assessment Dashboard**

The Active IQ Health Check Assessment (HCA) Dashboard provides a point-in-time review of your overall environment. Based on the health check score, you can align your storage systems to the recommended NetApp best practices to facilitate longer-term planning and improve the health of your installed base. Learn more.

#### **Config Drift**

This feature enables you compare the system and cluster configurations and the detect configuration deviations in near real time. Learn how to add a config drift template.

#### **AutoSupport**

You can view your AutoSupport data and review the details.

#### **Wellness Review Subscription**

You can subscribe to receiving monthly email notifications that summarize wellness status of systems—that are nearing their renewal dates and require an upgrade for the NetApp products in your installed base. Subscribe now.

#### **Reports**

You can use the reports feature to generate reports immediately or schedule a report to be generated on a weekly or monthly basis. Learn how.

#### Manual AutoSupport Upload

Manual AutoSupport Upload has been enhanced to improve the user experience. An additional column has been provided for remarks on the upload status.

#### Flex Subscription widget

You can monitor the committed, consumed, and burst storage capacity for your NetApp Keystone Flex Subscription Service.

## 30 September 2020

#### AFF and FAS firmware using Ansible Playbook

The documentation has been enhanced to include information about downloading, installing, and executing the AFF and FAS firmware ansible automation package.

Learn how to update AFF and FAS firmware using Ansible Playbook.

## 18 August 2020

#### **Performance**

Performance graphs have been enhanced to enable you to assess the performance of the volume. You can navigate and toggle between the node tab, cluster tab, the local tier tab, and the volume tab on the same screen. Learn how.

#### AFF and FAS firmware using Ansible Playbook

The AFF and FAS firmware screen has been enhanced to provide a better user experience.

## 17 July 2020

#### **Performance**

Performance graphs have been enhanced to enable you to assess the performance of the local tier. You can navigate and toggle between the node tab, cluster tab, and the local tier tab on the same screen.

#### Wellness

The wellness attributes have been enhanced to view all the affected systems without having to drill-down to the actions and risks.

#### 19 June 2020

#### Generate report for inventory

You can now generate report of the selected watchlist and emails the report to a maximum of 5 recipients. Learn how.

#### **Performance**

Performance graphs have been enhanced to enable you to assess the cluster performance of your storage system. You can navigate and toggle between the node tab and the cluster tab on the same screen.

#### Storage efficiency

The storage efficiency widget has been enhanced to enable you to view the storage efficiency ratio and savings at a cluster level. You can navigate and toggle between the node tab and the cluster tab on the same screen.

#### Update the default home page

You can now provide your feedback and let us know the reason you are updating the default home page screen for Active IQ.

#### Update to the inventory widget

The inventory widget has been enhanced to improve the user experience, by providing user-friendly date formats, additional columns for end of platform support and end of version support.

## 19 May 2020

#### Set the default home page

You can now set the default home page screen for Active IQ. You can either set it to Active IQ Digital Advisor or Active IQ Classic.

#### Storage efficiency

You can view the storage efficiency ratio and savings of your storage system with and without Snapshot backups for AFF systems, non-AFF systems, or both. You can view the storage efficiency information at a node level. Learn how.

#### **Performance**

Performance graphs enable you to assess the performance of your storage devices in different significant areas.

#### AFF and FAS firmware upgrades using Ansible Playbook

Update the AFF and FAS firmware using Ansible on your storage system to mitigate the identified risks and to keep your storage system up to date.

#### Disabling the wellness score feature

The wellness score feature is being temporarily disabled to improve the scoring algorithm and simplify the overall experience.

## 02 April 2020

#### Onboarding overview video

The onboarding video helps users to quickly get familiar with the options and features of Active IQ Digital Advisor.

#### Wellness score

Wellness score provides customers with a consolidated score of their installed base based on the number of high risks and the expired contracts. Score can be good, average, or poor.

#### **Risk summary**

The risk summary provides detailed information about the risk, the impact of the risk, the corrective actions.

#### Support for acknowledging and disregarding risks

Provides the option to acknowledge a risk if you do want to mitigate or are unable to mitigate the risk.

#### 19 March 2020

#### Upgrade workflow

You can use the upgrade workflow to view upgrade recommendations and a summary of new features available in your target ONTAP release. Learn how.

#### Valuable insights

You can view the summary of the benefits that you received through Active IQ and your support contract. For selected systems, the value report consolidates the benefits from last one year. View now.

#### **Drill into details**

Provides deeper information, which is a powerful way to dig deeper into the data and gain immediate insights into the make-up of aggregated information as required.

#### **Capacity additions**

You can proactively identify systems that have exceeded capacity or are nearing 90% capacity and send a request to increase capacity.

## **29 February 2020**

#### **Enhanced user interfaces**

The latest Active IQ Digital Advisor Dashboards offer a personalized experience. It allows smooth and seamless navigation, with its intuitiveness, throughout different dashboards, widgets, and screens. It provides an all-in-one experience. It communicates comparisons, relationships, and trends. It provides insights that help you detect and validate important relationships and meaningful differences based on the data that is presented by different dashboards.

#### Customizable dashboards

Helps you monitor your systems at a glance by providing key insights and analysis about your data on one or more pages or screens. You can also create up to 10 dashboards and make effective business decisions.

#### Learn more.

#### Mitigate risks using Active IQ Unified Manager

You can view the risks and rectify them by using Active IQ Unified Manager. Learn how.

#### Wellness

Provides detailed information about the status of your storage system that is classified into the following 6 widgets:

- · Performance & Efficiency
- Availability & Protection
- Capacity
- Configuration
- Security
- Renewals

See Analyze wellness attributes for more details.

#### Smarter and faster search

Allows you to search parameters, such as serial number, system ID, host name, site name, group name, and cluster name using the single-system view. You can also search for group of systems, in addition, you can search by a customer name, site name, or group name by group of systems.

## **Known limitations**

Known limitations identify platforms, devices, or functions that are not supported by this release of the product, or that do not interoperate correctly with it. Review these limitations carefully.

The following limitations exist:

- For Data ONTAP storage systems operating in 7-Mode only (Data ONTAP storage systems operating in 7-Mode is nearing End of Support Life)
  - Performance charts
  - Storage efficiency
- Upgrade Advisor will not support upgrade plans for clustered ONTAP earlier than 9.0.

#### Editing a watchlist may take 60 minutes to reflect in Active IQ Digital Advisor

Editing a watchlist does not update the information in Active IQ Digital Advisor immediately. It may take up to 60 minutes for the changes to reflect in Active IQ Digital Advisor.

#### A blank report is displayed while scheduling reports


Scheduled reports are available only with a SupportEdge Advisor or a SupportEdge Expert support contract. If your systems are not under SupportEdge Advisor or a SupportEdge Expert support contract, you may get a blank report while scheduling reports.

# **Get started**


# **Quick start for Active IQ Digital Advisor**

Active IQ Digital Advisor has been enhanced and redesigned to help you perform tasks more effectively. The user interface has been developed to guide you to perform your desired goals.

You can look at the following diagram to understand the workflows of Active IQ Digital Advisor.



You can view the following video to get started with Active IQ Digital Advisor:



All Active IQ Digital Advisor widgets are not supported on all platforms. Active IQ Digital Advisor identifies the platform of your storage system and displays only the set of tasks that can be performed on your storage

system.

Read the following information to be aware of the widgets that are supported on your storage system.

Widge t	Customer	Cluster	Node
Wellne ss	Supported on all platforms	Supported on all platforms	Supported on all platforms
Renew als	Supported on all platforms	Supported on all platforms	Supported on all platforms
Capaci ty Additio ns	platforms (Data ONTAP	Supported only on ONTAP platforms (Data ONTAP operating in 7-Mode and clustered Data ONTAP)	Supported only on ONTAP platforms (Data ONTAP operating in 7-Mode and clustered Data ONTAP)
Invent ory	Supported on all platforms	Supported only on clustered Data ONTAP	Supported only on clustered Data ONTAP
Upgra des	Supported only on clustered Data ONTAP	Supported only on clustered Data ONTAP	Supported only on clustered Data ONTAP

## **Understand Active IQ features**

You can view the overall status of your storage system, high-level information about the wellness of the system, inventory, planning, upgrades, and valuable insights at a watchlist level using Active IQ Digital Advisor.

When you access Active IQ Digital Advisor for the first time, you can either create a watchlist or search for a customer name, site name, group name, StorageGRID, hostname, cluster, serial number, or system ID.

You should also be aware of the colors applied to the cards, which indicate the severity and type of risks.

The following are some of the features of Active IQ Digital Advisor:

- View multiple watchlists, actionable and useful at-a-glance views of information
- Gain insights regarding all the risks to your storage system and the actions to mitigate the risks
- Mitigate risks using Active IQ Unified Manager
- Upgrade your storage system
- View storage efficiency ratio, the logical space used, the physical space used, and the total data saved for storage systems running ONTAP 9.1 and later
- Analyze the performance of your storage devices by viewing the graphical format of performance data
- Get information about the hardware and software that have expired or are near-expiration within the next 6
  months
- Update your ONTAP firmware using Ansible
- Get details about systems that have exceeded 90% capacity or are nearing 90% capacity
- View detailed physical and logical configuration information, including a summary of the cluster and node configuration, the local tier and volume information, the network interface and port information, a stack diagram detailing information about the disks and shelves, and a few cable visualizations

- Provide cross-stack information and insights that are beneficial for troubleshooting, upgrade assessments, solution validation, and migration
- Check the compatibility of hosts, and provide upgrade recommendations for host operating systems, drivers, and firmware
- · Arrive at exactly what you want to find in a smarter and faster manner



You can upgrade the support offering from the **Configuration** widget on the system dashboard to gain insights on your install base and receive personalized support.

# **Key concepts**

As you start using Active IQ Digital Advisor, it is important that you understand some of the basic terms that you can expect to see throughout the Active IQ Digital Advisor.

- **Watchlist:** Provides you the flexibility to access systems inside Active IQ Digital Advisor that have already been selected. You can use watchlists to add systems from either one or more customers.
  - · Wellness Dashboard: Provides an overall status of the systems in the watchlist.
  - Widgets: Displays small applications on the Dashboard that provide you a quick summary of the status of the systems.
  - Risks: Displays a list of systems with their respective issues. It has different severity levels:
    - High risks
    - Medium risks
    - No risks
  - Unique Risks: Displays the risk names and number of systems for a specific risk category.
  - Actions: Displays the number of unique actions that you can take to fix the issues.
  - Color-coded risk status: Displays risk levels and their color codes that are classified into 3 levels on the basis of their severity levels. The use of colors allows a faster assessment of the levels of risk involved.

Color	Severity
	High
	Medium
	No risks

- Wellness widget: Displays information about the performance, efficiency, capacity, configuration settings, security vulnerabilities, and others. It proactively determines the systems that have either exceeded the capacity or are near exceeding 90% capacity. In addition, it provides information about software and hardware that have either expired or set to expire in the next 6 months.
  - Performance & Efficiency: Displays information about the performance and efficiency of the storage system.

- Availability & Protection: Displays information about the availability and protection of the storage system.
- Capacity: Consists of risks with a capacity attribute for impact area values.
- **Configuration:** Consists of risks with a configuration attribute for impact area values sorted with the highest impact on the top.
- Security vulnerabilities: Consists of risks with a security attribute for impact area values.
- **Wellness History:** Displays information about system risks occurring in the past three months, so that you can learn how they are faring overtime.
- **Ransomware Defense:** Provides information about risks and corrective actions associated with ransomware detection, prevention, and recovery.
- Acknowledge Risks (Ack): Allows you to acknowledge the risks and systems that have been
  impacted. You can acknowledge these risks and familiarize yourself with the actions that you can
  perform to mitigate these risks.
- Unacknowledge Risks (un-ack): Allows you to unacknowledge the risks and systems that have been acknowledged.
- **Fix It:** Fixes the risks to the system using Active IQ United Manager (UM) 9.7 or higher. Click this button to launch UM and perform the steps to mitigate the risks.
- **Inventory widget:** Displays a rollup of total systems you own. This includes both Active IQ enabled and non-enabled products.
  - **Generate a report:** Generates the report of the selected watchlist and emails the report to a maximum of 5 recipients.
- **Planning widget:** Displays information about the capacity addition, software, and hardware that needs to be renewed.
  - Capacity Additions: Identifies systems that have exceeded or are nearing 90% capacity and GRID sites that have exceeded or are nearing 70% capacity. You can raise a request to increase the capacity of your storage system.
  - **Renewals:** Provides information about the software and hardware that has expired or are near expiration in the next 6 months.
- **Upgrades widget:** Provides the number of upgrades that are available.
- **Storage Efficiency:** Identifies the storage efficiency ratio and savings of your storage system with and without Snapshot backups for AFF systems, non-AFF systems, or both.
- **Performance graph:** Enables you to analyze the performance of your storage devices by viewing the graphical format of performance data. You can view detailed performance graphs of the ONTAP cluster for the selected node.
- Valuable Insights widget: Provides information about the number of support cases, pending software upgrades, storage efficiency savings, risks mitigated, and others. It also proactively lists the risk notifications from the Wellness attribute.
- **AutoSupport:** Enables you to view AutoSupport instances at a high level or in detail. The details include system details, possible reasons for the issue, and suggested actions.

To access the AutoSupport feature, log in to Active IQ Digital Advisor and search for a cluster or hostname. The AutoSupport option is available on the left pane.

• Cloud ready workloads: Provides information about the different types of workloads available within your storage system and identify the workloads that are cloud-ready. Moving workloads to the cloud result in cost savings and provide cloud disaster recovery. You can move workloads and volumes that are running

on Oracle, SAP, SAP HANA, File Share, SQL, and SharePoint. NetApp® Cloud Volumes helps in moving workloads and volumes to the cloud by delivering extreme performance and advanced data management capabilities to satisfy even your most demanding applications in the cloud. For more information about using NetApp® Cloud Volumes, see the Cloud Manager documentation.

- Quick Links: Provides the list of applications that can be launched using Active IQ Digital Advisor.
  - ClusterViewer: Enables you to see detailed physical and logical configuration information. The details
    are presented in several easy-to-view tables across multiple tabs that include a summary of the cluster
    and node configuration, the local tier and volume information, the network interface and port
    information, a stack diagram detailing information about the disks and shelves, and a few cable
    visualizations. You can also download the cable visualizations graphics in the SVG format.

The ClusterViewer feature is not supported on E-Series systems.

- API Services: Allows you to pull data of interest and integrate it directly into your company's workflow.
- AutoSupport Upload: Enables you to analyze the defects or issues in ONTAP and E-Series systems. The defects or issues are reviewed and fixed manually by Support Site personnel.
- **System Firmware:** Enables you to view information about the system firmware that is shipped along with each major and patch version of ONTAP.
  - Search: Allows you to search for systems based on various categories, such as customer name, serial number, cluster, site name, group name, hostname, and others.
- **Customer:** Allows you to view and manage a customer's installed base. Customer Dashboard is the central portal in Active IQ.
- **Cluster:** Provides information about ONTAP clusters. The Dashboard also consolidates health, capacity, storage efficiency, and performance insights.
- Serial Number: Provides information about the serial number that is assigned to the customer.

## **AutoSupport**

AutoSupport is a telemetry mechanism that proactively monitors the health of your system and automatically sends configuration, status, performance, and system events data to NetApp.

This data is used by NetApp Technical Support to speed the diagnosis and resolution of issues, and by Active IQ to proactively detect and avoid potential issues. It can also be sent to your internal support organization and a support partner.



AutoSupport data does not contain any user data.

For ONTAP systems, AutoSupport is enabled by default when you configure your storage system for the first time. You should set up AutoSupport on ONTAP systems to control how the AutoSupport information is sent to technical support and your internal support organization.

If you do not want to enable AutoSupport, you can use the AutoSupport Upload feature to manually upload AutoSupport data to receive recommendations and insights into your storage ecosystem.

For more information about AutoSupport, refer to the appropriate documentation:

ONTAP (FAS and AFF)

- StorageGRID
- SANtricity (E-Series and EF-Series)
- Element (NetApp HCl and SolidFire)
- Technical Report ONTAP AutoSupport and AutoSupport On Demand
- Technical Report Security and Privacy of NetApp Telemetry Data

# Log in to Active IQ Digital Advisor

You must have a valid NetApp Support site credential to log in to Active IQ Digital Advisor. If you do not have an account and are getting started, click here.

#### **Steps**

1. Click here to access Active IQ Digital Advisor.

Active IQ Digital Advisor shows systems with a valid support contract. If contracts expire, a grace period of 90 days is given in which systems continue to be visible. Thereafter, systems are not searchable or visible within Active IQ Digital Advisor.

2. Provide your username and password and click Sign In.

# Manage your clusters in Cloud Manager

Active IQ Digital Advisor is integrated into Cloud Manager. You can now manage your clusters and access all the features of Active IQ from the Cloud Manager user interface (UI). Using Cloud Manager, IT experts and cloud architects can centrally manage their hybrid multi-cloud infrastructure.

All you need is an NSS account in Cloud Manager to integrate and access Active IQ in Cloud Manager. For information about integrating and accessing Active IQ in Cloud Manager, see How Active IQ Digital Advisor works with Cloud Manager.

# **Provision watchlist**

## **Understand watchlist**

Watchlists are used to access preselected systems inside Active IQ Digital Advisor quickly and easily. If you view a certain customer or a set of systems frequently, we recommend you create watchlists. You can create up to 50 watchlists and each watchlist can contain up to 15,000 systems by category or 500 systems by serial numbers.

When you access Active IQ Digital Advisor for the first time, you can either create a watchlist or search for a customer name, site name, group name, StorageGRID, hostname, cluster, serial number, or system ID.

You should also be aware of the colors applied to the cards, which indicate the severity and type of risks.

## Create a watchlist

You can create a watchlist to access a set of systems quickly and easily. You can combine the set of systems based on the category or location.

#### **Steps**

1. From the left pane, click Watchlists

The Manage Watchlist screen is displayed.

- 2. Click Create Watchlist.
- 3. Provide a name for the watchlist.
- 4. Provide the details of the systems that you want to add to the watchlist.

You can add a maximum of 15,000 systems under a category and 500 systems under a serial number.

5. Click Create Watchlist.

The watchlist dashboard is displayed.

# Manage a watchlist

You can view the dashboard for different watchlists, edit the details of an existing watchlist, and delete a watchlist.

#### **Steps**

1. From the left pane, click Watchlists.


The Manage Watchlist screen is displayed.

- Click the name of the watchlist to view the dashboard details of the watchlist.
- 3. Click **Edit** to update the details of the watchlist.
- 4. Click **Delete** to delete the watchlist.

# **Analyze wellness attributes**

## **Understand wellness**

Wellness widget provides detailed information about your storage system. It provides information about different attributes of your storage system, such as performance and efficiency, capacity, configuration settings, security vulnerabilities, renewals, and others.



The wellness widget also provides information about the risks and the actions that should be taken to mitigate the risk for each wellness attribute. The following are the types of risks and the associated consequence for each risk:

Risk Type	Consequence
Critical	Data loss, data corruption, cluster data outage, personal safety issue, or potential legal compliance issue.
High	Short-term loss of data access or prolonged loss of node redundancy.
Medium	Performance degradation or short-term loss of node redundancy.

Risk Type	Consequence
Low	Low impact scenarios
Best Practice	Deviations from documented best practices

You can view the following video to understand the importance of the wellness attributes:



# View the risk and manually take corrective actions

You can analyze the wellness attributes of your storage system by viewing the actions and risks associated with them. You should view the associated corrective actions and manually mitigate the risk.

#### Steps

- 1. Click the **Wellness** widget on the dashboard or click **View All Actions** to view the list of all the actions and risks.
- View the Actions and Risks associated with the wellness attribute.
- 3. Click **Actions** to view the risks associated with the actions, click **Risks** to view all the risks, or click **Affected Systems** to view the systems that require attention.
- 4. Click the risk name to view information about the risk.
- 5. Click the associated corrective actions and follow the information to resolve the risk.

The steps to mitigate the risks are same for all wellness attributes. You can view the following video to monitor and fix security related issues:



# **Increase protection against hackers and Ransomware attacks**

When you log in to the Active IQ Digital Advisor and notice the red badge on the **Security Vulnerabilities** widget, you can take actions to fix critical risks.

#### **Steps**

- 1. Log in to Active IQ Digital Advisor.
- 2. Click Actions in the Security Vulnerabilities widget.



For the high-impact security risks, follow the recommended action that is to upgrade the operating system.

3. Click the Unique Risks tab, and then click the link in the Corrective Action column.



https://mysupport.netapp.com/site/products/all/details/ontap9/downloads-tab/download/62286/9.7P8

4. The most important step is to plan OS upgrade in the **Upgrade Advisor** in Active IQ Digital Advisor.

# Protect systems against ransomware risks

When you log in to the Active IQ Digital Advisor, you can view the **Actions** highlighted on the **Ransomware Defense** widget, which shows the risk counts.

You can view the Snapshot creation, retention, and ONTAP FPolicy risks, and then take actions to fix them.

#### **Steps**

- 1. Log in to Active IQ Digital Advisor.
- Click Actions on the Ransomware Defense widget.
- 3. For the risks that are displayed, check the impact level and follow the recommended actions.
- 4. Click the Unique Risks tab and link in the Corrective Action column.
- Click the Affected Systems tab to view systems with risks.
- 6. Follow remediation actions that are recommended to protect the systems.

# View and acknowledge the risk

You can analyze the wellness attributes of your storage system by viewing the actions and risks associated with them. You should view the corrective actions and manually mitigate the risk.

#### **Steps**

- Click the wellness attribute widget on the dashboard or click View All Actions to view the list of all the actions and risks.
- View the Actions and Risks associated with the wellness attribute.
- 3. Click **Actions** to view the risks associated with the actions, click **Risks** to view all the risks, or click **Affected Systems** to view the systems that require attention.
- 4. Click the risk to view the risk summary.
- 5. Click **Ack** to acknowledge the risk.

The detailed risk summary information is provided along with corrective actions that should be manually performed to mitigate the risk.

6. If you do not want to or are unable to mitigate the risk at this time, provide the values for the fields and click **Acknowledge**.

The risk will be added to acknowledged risks.



If you no longer want a risk to be acknowledged, you can disregard the risk by clicking **Un-Ack** and following the same steps.

# View wellness history

You can view system risks occurring in the past three months, so that you can learn how they are faring overtime.

These risks are classified under four types of risks— **Unresolved**, **New**, **Resolved**, and **Acknowledged**. They are represented by different colors. The summary of these risks is represented through a **Risk History** graph.

#### **Steps**

- 1. On the dashboard, in the Wellness pane, click View All Actions.
- 2. Click Wellness History.
- 3. In the **Risk History** graph, click the category for which you want to view the risk history.

When you hover over the colored bars, they display information on the number of risks in each category. Upon clicking the respective risk category, the information gets displayed in the **Risk Information** table.

You can also download risk summary in an Excel sheet.

# View risks that can be automatically mitigated using Unified Manager or Ansible Playbook

You can analyze your storage system by viewing the actions and risks, and mitigate them using Active IQ Unified Manager or Ansible Playbook.



#### Steps

- 1. Click View All Actions on the dashboard.
- 2. Click **Actions** to view the risks associated with the actions, click **Risks** to view all the risks, or click **Affected Systems** to view the systems that require attention.

If the risk can be mitigated using Active IQ Unified Manager, the icon is highlighted and if the risk can be mitigated using Ansible Playbook, the icon is highlighted.

To mitigate the risk using Unified Manager	To mitigate the risk using Ansible Playbook
1. Click the icon.	1. Click the A icon.
2. Click <b>Fix It</b> to launch Active IQ Unified Manager.	2. Click <b>Download</b> to download the AFF and FAS
<ol><li>Click Install to install Active IQ Unified Manager</li><li>or later to use the Fix It option.</li></ol>	firmware Ansible Automation package.
<ol> <li>Click <b>Upgrade</b> to upgrade to Active IQ Unified Manager 9.7 or later to use the <b>Fix It</b> option.</li> </ol>	



A SupportEdge Advisor or SupportEdge Expert contract is required to use the **Fix It** option and the Ansible Playbook features.

# Avoid the downtime and possible data loss

When you log in to the Active IQ Digital Advisor and notice the red badge on the

**Availability and Protection** widget, you can take actions to fix critical risks. Without the firmware fix, these drives are vulnerable to become inoperable after a certain number of hours of being powered on. Fixing this would avoid both the downtime and possible data loss.


#### **Steps**

- 1. Log in to the Active IQ Digital Advisor.
- 2. Click Actions in the Availability & Protection widget.



For the high-impact security risks, follow the recommended action that is to update disk firmware.

Click the Risk Name link for viewing risk summary.




Click the Unique Risks tab, and then click the link in the Corrective Action column.



Active IQ Digital Advisor generates custom Ansible scripts or playbooks to update the required disk firmware, including the disk firmware files.

5. Click the **Ansible "A"** icon to generate and download the scripts.



## Subscribe to wellness review email

You can subscribe to the wellness review email to receive a monthly email that summarizes wellness status, systems that are nearing their renewal dates, systems that require an upgrade for the NetApp products in your installed base.

You will receive a wellness review email so that you can view a monthly summary and take action for your systems.

You also have options to view, edit, share, and delete your subscriptions. At any time, if you decide to not receive the email, you can unsubscribe from getting email as well.

After the subscription is enabled, you should select a start date when adding a subscription. The monthly email summary provides a view of outstanding wellness, renewal, upgrade, and health check actions. You can confirm the email address and the email is sent to the specified email address. You also have the option to delete subscriptions.



This feature is available only through NetApp SupportEdge Advisor and SupportEdge Expert service offerings.

#### Steps

- 1. On the Health Check Assessment Dashboard, click Wellness Review Subscription.
- 2. Click Add Subscription.
- 3. Provide the required information in the Name the Subscription, Choose Category, Search Customer, and Email fields in the Add New Subscription dialog box.
- 4. Click Subscribe.

Upon successful subscription, you will receive a Subscription was added message.

# Renew the software and hardware of your storage system

You can proactively identify the software and hardware that have expired or are near expiration in the next 6 months, and send a request to renew the hardware and software.

#### **Steps**

- 1. Click Renewals from the Planning widget.
- 2. Select the systems that you want to renew and click **Renew**.
- 3. Optionally, provide additional comments.
- 4. Click Send.

# Analyze the wellness of clusters and nodes

You can analyze the wellness of your clusters and nodes using ClusterViewer, a one-stop source for information on the physical and logical configuration of your clusters and nodes.

ClusterViewer provides information, such as stack diagrams of your nodes, storage usage and efficiency, headroom in hardware capacity, and so on, that helps you take informed decisions to improve the wellness of your clusters and nodes.

You can view visualizations or graphical representations of the physical configuration of your nodes at cable, stack, and RAID Disk levels. You can also download the visualizations in SVG format.



#### **Steps**

1. In the **Inventory** widget, select the cluster or node (host) that you want.

2. At the cluster or node level, click <b>ClusterViewer</b> next to the <b>Configuration</b> widget.
3. Click the <b>Visualization</b> tab to view a graphical representation of the cluster.

# View system details

# View inventory details

The **Inventory** widget provides you with a rollup of the total systems that you own. This includes both Active IQ enabled and non-enabled products.

You can also generate the report of the selected watchlist and email the report to a maximum of 5 recipients.



#### Steps

- 1. In the **Inventory** widget, click **Systems** to view the system information of all platforms or click the platform type and then click **Systems** to view systems specific to that platform.
- 2. Click the node or cluster to view detailed information about the system.
- 3. Download the **Inventory** report to view the system details in .xls format.
- 4. Download the **Ansible Inventory** report to view the system details in the .yml and .ini formats at the region or site level.

The Ansible Inventory files can be used with customized Ansible Playbook files to make infrastructure configuration changes.

## View valuable insights

The **Valuable Insights** widget provides information about the number of support cases, pending software upgrades, storage efficiency savings, risks mitigated, and others. It also proactively lists the risk notifications from the **Wellness** attribute.



#### **Steps**

- 1. In the **Inventory** widget, click **Systems** to view the system information of all platforms or click the platform type and then click **Systems** to view systems specific to that platform.
- 2. Click the node or cluster to view detailed information about the system.

The Valuable Insights widget is available on the dashboard.

Review the information in the widget to understand the business and technical value received from your support contract.

# View capacity utilization with NetApp Keystone Flex Subscription

If you are subscribed to Keystone Flex Subscription Service, you can view the Flex Subscription widget on the Active IQ Digital Advisor Dashboard.

The Flex Subscription widget provides you a summary of the capacity usage for your account. It consists of capacity utilization charts with respect to the logical capacity, the snapshot being rounded up to the last five minutes. The utilization over and above the committed capacity (the burst capacity) is marked in red.

You can view the **Keystone - Capacity Utilization** dashboard, which analyzes the data in the widget and graphically represents the utilization trend of the capacity and usage for all the subscribed storage services tiers, such as premium, extreme, and standard, associated with your NetApp Keystone Flex Subscription account.

You can view the Flex Subscription service capacity and usage of each subscribed service for your block, file services, or object storage on the dashboard.



As an Active IQ user, you can choose between ONTAP Collector and AutoSupport to obtain data on your capacity usage.

### **Steps**

- 1. Click View Details to view the utilization trend in the detailed Keystone Capacity Utilization dashboard.
- 2. Select either 30 days, 7 days, or 1 day to view the recent average usage trend.
- 3. Optionally, if you have opted for ONTAP Collector to obtain data on your capacity usage, you can click through the tabs on the dashboard to view more details about your file shares and disks.

Click **Shares** or **Disks** to identify the file shares or disks nearing the committed capacity and make informed decisions to save storage capacity.

## Identify system requirements proactively

## **Understand planning**

The **Planning** widget helps customers identify capacity requirements that have exceeded 90% capacity or are nearing 90% capacity and identify the software and hardware that have expired or are near expiration in the next 6 months. You can send a request to increase the capacity of your storage system and to renew the hardware and software.



## **Identify systems reaching capacity limits**

Proactively identify systems reaching capacity limits and send a request through live chat to increase the capacity of your storage system.

You can view systems that have exceeded 90% capacity or are to exceed 90% capacity in 1, 3, and 6 months. Chat with a salesperson to raise capacity addition requests easily and get real-time assistance.

#### **Steps**

1. In the **Planning** widget, click **Capacity Additions** to view the systems that have exceeded 90% capacity or are nearing 90% capacity.

You can view the number of systems that have exceeded 90% capacity or are to exceed 90% capacity in the next 1, 3, and 6 months.

- 2. Select a card to view the systems.
- 3. Select the systems for which you want to increase capacity and click **Contact Sales**.

- 4. Verify your contact details.
- 5. Copy and paste up to five hostnames into the chat to raise capacity addition requests.

## Avoid a volume filling up to prevent an outage


When you log in to Active IQ Digital Advisor and notice the red badge on the **Configuration** widget. Upon clicking the widget, you see that the volume is 98% full and this might cause an outage. Fixing this issue would avoid a volume filling up, which would make it go read-only resulting in applications accessing it crash and fail.

### **Steps**

- 1. Log in to Active IQ Digital Advisor.
- Click Actions in the Configuration widget.



3. Click the **Unique Risks** tab. Upon clicking the **Corrective Action** link, you can either change the warning thresholds or allocate more space to the volume.



### Renew the software and hardware of your storage system

You can proactively identify the software and hardware that have expired or are near expiration in the next 6 months, and send a request to renew the hardware and software.

- 1. Click Renewals from the Planning widget.
- 2. Select the systems that you want to renew and click **Renew**.
- 3. Optionally, provide additional comments.

4. Click Send.

## Identify configuration deviations

## **Understand configuration deviation**

The Config Drift feature identifies configuration deviations by comparing a system template to a "golden" or base system template. You can schedule weekly or monthly drift reports or generate them on-demand. You can mitigate some deviations by using the Ansible Playbooks, which are provided in the config drift report.

This feature is available to systems with Advisor and Expert Support contracts only.

You can look at the following diagram to understand the workflow to identify configuration deviations and generate the report.



You can view the following video to generate and run an Ansible Playbook to fix the configuration deviations:



### Add a config drift template

You should add a template to compare the system and cluster configurations and detect the configuration deviations in near real time. The config drift templates are added using systems running AutoSupport data.

- 1. From the left pane, click Config Drift.
- 2. Click Add Template.
- 3. Provide the requested values.
- 4. Optional: Click Edit to edit the template.
- 5. Click Add Template.

## Compare a config drift template

You can compare the system and cluster configurations and detect the configuration deviations in near real time.

### **Steps**

- 1. From the left pane, click Config Drift.
- 2. Select one of the existing templates or click **Add Template** to add a new template.
- 3. Generate a config drift report

You can generate a report immediately or you can schedule the report to be generated on a weekly or monthly basis.

To generate a report immediately	To schedule the report to be generated on a weekly or monthly basis	
<ol> <li>Select a category and provide the requested values for the report.</li> </ol>	Click the <b>Schedule Report</b> tab.	
<ol> <li>Select Include only drifts option to download only the configuration deviation changes.</li> </ol>	<ol><li>Select a category and provide the requested values for the report.</li></ol>	
	3. Select <b>Include only drifts</b> option to download	
3. Click <b>Submit</b> .	only the configuration deviation changes.	
4. Download and view the config drift report.	4. Select the frequency of the report.	
<ol> <li>Run Ansible Playbook (included as part of the config drift report) to mitigate the drifts.</li> </ol>	5. Select the start date and end date for the report.	
	6. Click <b>Submit</b> .	
	7. Download and view the config drift report.	
	Run Ansible Playbook (included as part of the config drift report) to mitigate the drifts.	

An email is sent with the details of the configuration deviation between the selected systems.

## Generate a drift timeline report

You can compare the AutoSupport data of the last 90 days and generate a report that provides information about the events and the configuration deviations that have occurred.

### Steps

1. From the left pane, click Config Drift.

- 2. Select the **Drift Timeline** report type.
- 3. Generate a drift timeline report

You can generate a report immediately or you can schedule the report to be generated on a weekly or monthly basis.

To generate a report immediately	To schedule the report to be generated on a weekly or monthly basis	
<ol> <li>Select a category and provide the requested values for the report.</li> <li>Select Include only drifts option to download only the configuration deviation changes.</li> <li>Click Submit.</li> </ol>	1. Click the <b>Schedule Report</b> tab.	
	2. Select a category and provide the requested	
	values for the report.	
	<ol><li>Select Include only drifts option to download only the configuration deviation changes.</li></ol>	
5. Select the start date and end date for the report.		
6. Click <b>Submit</b> .		
	7. Download and view the drift timeline report.	

## Manage a template

You can clone a template, share a template, edit the details of an existing template, and delete a template.

Sharing a template saves the time and effort required to create and customize a template that has already been created by a user. Shared templates can be mutually changed by shared users, allowing several users to make modifications to a single golden template.

#### About this task

- · Access to shared templates can be revoked at any time.
- Shared users can delete this template from their account at any time.

- 1. From the left pane, click Config Drift.
- 2. Click to make a copy of the template.
- 3. Click sand enter the usernames with whom you want to share the template.
  - If you enter the email address of the user instead of the username, the template will not be shared.
- 4. Click to update the details of the template.
- 5. Click to delete the template.

# Improve the efficiency and performance of your storage system

## Analyze capacity and storage efficiency savings

You can view the capacity details and the storage efficiency savings of your system and take appropriate actions. The capacity and storage efficiency information can be viewed either at a cluster level or a node level.



This feature is not supported on E-Series systems.

The capacity dashboard displays the capacity details and the capacity forecast of your system. Capacity forecast uses historical capacity information to identify the utilization of each system. Based on the historical data (a year's data, if available) of utilized and allocated capacity, the algorithm considers the current utilization of each system and generates a forecast for the system's utilization over the next 1 through 6 months.

The storage efficiency dashboard displays the storage efficiency ratio, the logical space used, the physical space used, and the total data saved for storage systems running ONTAP 9.1 and later. The efficiency ratio and savings can be seen with and without Snapshot backups for AFF systems, non-AFF systems, or both. The total savings across customer storage can be seen per efficiency feature such as volume deduplication, volume compression, compaction, FlexClone volumes, and Snapshot backups. You can also view the top 5 storage systems with the best efficiency ratio.



#### **Steps**

1. From the left pane, click Capacity and Efficiency.

By default, the **Capacity** tab is selected.

- 2. View the capacity details at the cluster and node level.
  - a. View the capacity forecast at the node level.

For ONTAP systems, information about RAW capacity is available in ClusterViewer.

- b. Click Add Capacity to send a notification to NetApp or your partner to add capacity.
- 3. View the storage efficiency and the data savings of your storage system.
  - a. If the storage efficiency ratio of your storage system is higher than the average storage efficiency ratio, click **Share Your Success Story** to let us know the best practices followed.
  - b. If the storage efficiency ratio of your storage system is less than the average storage efficiency ratio, click **Contact Us** to let us know the configurations of your storage system.

## **Analyze performance graphs**

Performance graphs enable you to analyze the performance of your storage devices. You can view detailed performance graphs for an ONTAP cluster or multiple nodes of an ONTAP cluster. It displays cluster nodes for systems running ONTAP 8.3.1 and later. These graphs provide historical performance data, which can be used for understanding performance trend and pattern analysis. You can select a date from the calendar to view performance graphs for a day, week, month, and two months. You can select multiple nodes to view a particular graph at the same time.

You have an option to set preferences, for example, you can view either one graph for three nodes or two graphs for three nodes.

When the graph is first displayed, a 1-week tab is preselected and it presents data for a 1 week in a graphical format to make it easier to understand large quantities of data and its relationship between different series of data. If you want to reset the date range, for example, you can click 1-month tab and select dates in the calendar.

You also have an option to zoom in performance graph; the individual data points are displayed.



### Steps

1. On the Dashboard, click **Performance**.

By default, the cluster performance is displayed. You can click the **Node** tab to view the performance of a single node of an ONTAP cluster, click the **Local Tier** tab to view the performance of the local tier, or click the **Volume** tab to view the performance of the volume.

2. Select either 1 day, 1 week, 1 month, or 2 months, in the calendar, for viewing performance data in a graphical format. Confirm that you want to perform the operation.

For example, select 2-months tab to view data for 2 months. This enables you to view specific data for a duration based on your performance requirements.

3. View performance graphs with required metrics, including:

For Cluster	For Node	For Local Tier	For Volume
IOPS	CPU Utilization - Peak Performance (Headroom)	Average Throughput	IOPS
Network Throughput	Latency	Average Utilization	Latency
	IOPS		
	Protocol IOPS		
	Network Throughput		



Node latency performance graphs and volume performance graphs are supported only on systems that are running ONTAP 9.2 and later.

# Monitor and tier inactive data with FabricPool Advisor

You can reduce your storage footprint and associated costs by monitoring and tiering your cold or inactive data to low-cost object storage tiers.

The FabricPool Advisor dashboard in Active IQ Digital Advisor displays details of your inactive local tier (aggregate) data, inactive volume data, tiered data, and unmonitored data.



You can enable Inactive Data Reporting (IDR) to generate a zip file with an Ansible Playbook file. This information is available at customer, site, group, watchlist, cluster, and node levels.

If there is more than 50% inactive data in a volume, you can tier the data using NetApp® Cloud Manager. For more information on cloud tiering, refer to Learn about Cloud Tiering.

### **Steps**

- 1. Select **FabricPool Advisor** from the left navigation pane.
- 2. Click **Tier Data** to tier the data using Cloud Manager.

To learn more about FabricPool, refer to FabricPool Best Practices.

## Analyze the health of your storage system

### **Understand Health Check Dashboard**

The Active IQ Health Check Dashboard provides a point-in-time review of your overall environment.

Based on the health check score, you can align your storage systems to the recommended NetApp best practices to facilitate long-term planning. It helps you monitor all the systems running on software and hardware through a centralized user interface. Health Check scores enable you to quickly gain insights about system risks. The key recommendations and best practices help you take actions to improve the health of your installed base.



You can access the Health Check Dashboard only through NetApp SupportEdge Advisor and SupportEdge Expert service offerings.

### Get started with Health Check Dashboard

This dashboard provides an at-a-glance summary of your installed base through the following widgets:

- AutoSupport Adoption: Displays the number and percentage of systems with AutoSupport enabled. You
  can also view systems marked as 'Declined', those with HTTPS and AutoSupport on Demand enabled,
  as well as Loss of Signal for those systems that have stopped sending AutoSupport data in the last 7
  days.
  - To view your health check score and information about the systems in your install base, click the **AutoSupport Adoption** widget.
- Recommended Configuration: Displays systems that are compliant and non-compliant as per the
  Recommended Configuration widget. It helps you take actions to ensure that your systems are well
  configured across your installed base. You can view the score provided on the dashboard and take actions
  based on the key recommendations which are provided in order of priority.
- Recommended Software: Displays a consolidated list of all the software and firmware upgrades and currency recommendations. You can view the systems with AutoSupport enabled that should be at either the minimum or latest software or firmware versions.
- Support & Entitlements: Displays support contracts that have expired and those that are nearing
  expiration within 6 to 12 months. It displays end of support platforms, disks, shelves, entitlement
  compliance, pending expirations, and end of support for platform and hardware is not applicable.
  You can view the health check score provided on the dashboard and take actions based on the key
  recommendations, which are provided in order of priority.
  - To view detailed information about support contracts, click the **Support & Entitlements** widget. You can also renew your support contracts using this widget.
- **Best Practices**: Displays the health check score by assessing the best practices attributes of your storage system performance & efficiency, availability & protection, capacity, configuration, and security vulnerabilities. NetApp best practices help sustain system health, which optimizes the performance of your installed base.
- **Technical Cases**: Provides you with a detailed view of your technical case history, by case type and open or closed status, over selectable time ranges. You can drill into case groups as well as view case details through NetApp Support Site or other case portals.

## Renew your support contracts

You can view the score and summary of all the active support contracts on the dashboard. You can take actions based on the key recommendations which are provided in order of priority.

- 1. On the Health Check Assessment Dashboard, click the Support & Entitlements widget.
- 2. If any of your system support contracts have expired or are nearing expiration, then click the **Active Support Contracts** widget.
- 3. Select the checkboxes and click **Renew** for initiating the renewal process for the selected systems.

## Upgrade to optimize your install base

## Upgrade the ONTAP version by generating an upgrade plan

You can view the pending upgrades of your storage system and upgrade to a later version of ONTAP by generating an upgrade plan. You should also view the list of risks in the **Risk Advisor** tab which would be mitigate because of the upgrade.

### Steps

- 1. On the dashboard, view pending upgrades in the **Upgrades** widget.
- 2. Click the number of **Actions** to view the pending upgrades.
- 3. Select the required upgrade option.
- 4. Click the number of systems displayed on the widget to view the Upgrade Advisor tab.

You can also check the Release Notes to view detailed information about the release.

- 5. View the list of risks in the **Risk Advisor** tab, along with their severity level, which would be mitigated because of the upgrade.
- 6. Click Generate Upgrade Plan to navigate to Upgrade Advisor.

## Upgrade the support offering


You can purchase an upgrade to the support offering to access more features and functionalities in Active IQ Digital Advisor.

You can upgrade your current support offering to optimize your install base with the help of recommended practices and fixes, upgrade automation with Ansible playbooks, actionable reports and reviews, personalized support, and so on. The upgrade can be purchased when you renew your support contracts or at any other time from the system (node) dashboard.



You can opt for AIQ Upgrade only if you currently use the SupportEdge Premium or SupportEdge Secure support offerings.

- 1. Click View All Systems next to the Inventory widget.
- 2. On the Inventory Dashboard, select the node (host) that you want to upgrade. You are redirected to the system or node dashboard.
- 3. Click **Upgrade** in the **Configuration** widget.



4. Optionally, click **Compare Support Offerings** to view the comparison chart and pick the support offering that fits your requirements.

Alternatively, you can click **Support Offerings** on the left navigation menu to view the comparison chart.

- 5. Select the type of upgrade that you want.
  - a. Add AIQ Upgrade to your SupportEdge Premium or SupportEdge Secure support offerings
  - b. Any other upgrade request
- Add any comments that you have and click **Send**.
   A request to purchase the support offering upgrade is sent to the NetApp Renewals team.

## Update your AFF and FAS firmware using Ansible Playbook

### Download the AFF and FAS firmware Ansible Automation package

You should update the AFF and FAS firmware using Ansible to mitigate the identified risks and keep your storage system up to date.

### Before you begin

Before updating AFF and FAS firmware using Ansible, you should:

- Install and set up Ansible on your storage system
- Install Ansible 2.9 with collections on your storage system
- Upgrade your storage system to ONTAP 9.1 or later
- Configure your account with an administrator role

- Click any wellness widget on the dashboard or click View All Actions to view a list of all the actions and risks.
- 2. Click Firmware Upgrade to view all firmware upgrade risks.
- 3. Click **Update AFF and FAS Firmware** to view all available update packages or click **A** next to each risk

to update the package specific to that risk.

4. Click **Download** to download the zip files and update your storage system.

The zip file contains the following:

- Ansible Playbook A YAML file containing the Ansible script to perform the disk, shelf, and service processor firmware updates.
- Inventory A YAML file containing the details of the systems that are applicable for firmware updates.
- Disk, Shelf, and Service Processor/BMC Firmware packages are named as all.zip, all\_shelf\_fw.zip, and <SP/BMC>\_<version\_number>\_fw.zip respectively.



Manual addition of clusters and controllers to the inventory file is not supported.

## Install and execute AFF and FAS firmware Ansible automation package (Experienced Users)

Experienced users can install and execute the AFF and FAS firmware ansible automation package quickly.

### Firmware update with Ansible using NetApp Docker Image

### Steps

1. Pull the Ansible Docker image to the Linux host:

```
$ docker pull schmots1/netapp-ansible
Using default tag: latest
latest: Pulling from schmots1/netapp-ansible
docker.io/schmots1/netapp-ansible:latest
```

2. Run the docker image as a container on the Linux host:

```
$ docker run -v <downloaded_playbook_path>:/<container_path> -it
schmots1/netapp-ansible:latest /bin/bash
```



The Ansible Playbook and the inventory file should be in the same path.

Execute the Ansible Playbook on the Linux host. Firmware updates run in the background for a few hours.



If the URLs for disk firmware, shelf firmware, and service processor firmware are <a href="http://<web-server>/path/all\_shelf\_fw.zip">http://<web-server>/path/all\_shelf\_fw.zip</a>, <a href="http://<web-server>/path/sP/BMC>\_<version\_number>\_fw.zip</a>, provide <a href="http://<web-server>/path/">http://<web-server>/path/<a href="http://<web-server>/path/">http://<a href="http://<a href="http://<a

4. Log in to the cluster as the cluster administrator and verify that the new drive firmware has been installed:

### Firmware update if Ansible is already used

### **Steps**

1. Install Python and Ansible and then download the Python packages using PIP:

```
$ pip install netapp-lib requests paramiko
Installing collected packages: netapp-lib, requests, paramiko
Successfully installed netapp-lib-2020.3.12 requests-2.23.0 paramiko-
2.7.2
```

2. Install the NetApp Ansible Collection:

```
To install the collection only for the current user:

$ ansible-galaxy collection install netapp.ontap

For universal installation:

$ ansible-galaxy collection install netapp.ontap -p
/usr/share/ansible/collections

$ chmod -R +rw /usr/share/ansible/collections
```

3. Ensure that the Ansible Playbook and the inventory file are in the same path and then execute the Ansible Playbook. Firmware updates run in the background for a few hours.



If the URLs for disk firmware, shelf firmware, and service processor firmware are <a href="http://<web-server>/path/all\_shelf\_fw.zip">http://<web-server>/path/all\_shelf\_fw.zip</a>, <a href="http://<web-server>/path/<SP/BMC>\_<version\_number>\_fw.zip</a>, provide <a href="http://<web-server>/path/">http://<web-server>/path/<a href="http://<web-server>/path/">http://<a href="http://<a href="http://<

4. Log in to the cluster as the cluster administrator and verify that the new drive firmware has been installed:

## Install and execute the AFF and FAS firmware Ansible Automation package (Beginners)

### Host firmware files using web server

After you download the automation package, the firmware files should be hosted on a web server.

The web server can be set up in multiple ways. For instructions to set up a simple web server using Python, refer to Webserver using Python.

#### Step

 Save the base URL of the web server. If the URLs for disk firmware, shelf firmware, and service processor firmware are http://<web-server>/path/all\_shelf\_fw.zip, http://<web-server>/path/all.zip, and http://<web-server>/path/<SP/BMC>\_<version\_number>\_fw.zip, save http://<web-server>/path/ as the base URL.

The filename is automatically detected by the Ansible Playbook.

### Work with inventory file

The inventory file consists of the cluster management LIFs of the systems that are eligible for firmware updates. It contains the list of clusters with disk and shelf firmware filename information wherever applicable.

For service processor firmware update, node hostnames and SP/BMC IP is included in the inventory file.

### Inventory file format

The following is a sample inventory file format with both disk and shelf firmware updates:

```
clusters:
 - clustername: <cluster management LIF-1>
   disk fw file: all.zip
   shelf fw file: all shelf fw.zip
 - clustername: <cluster management LIF-2>
   disk fw file: all.zip
   sp nodes:
   - hostname: <node hostname 1>
     sp fw file: SP FW 308-03990 11.5.zip
     sp fw type: bmc
     sp fw ver: '11.5'
     sp ip: <BMC IP>
    - hostname: <node hostname 2>
      sp fw file: SP FW 308-03991 5.8.zip
     sp fw type: sp
     sp fw ver: '5.8'
      sp ip: <SP IP>
```

In the example, both shelf and disk firmware updates are applicable on cluster-1 and disk and SP/BMC firmware updates are applicable on cluster-2.

### Delete a cluster from the inventory file

In case you do not want to apply firmware updates on a particular cluster, you can remove the cluster from the inventory file.

For example, if you do not want to apply disk firmware updates on cluster-2, you can remove it from the inventory file using the following command:

```
clusters:
  - clustername: <cluster management LIF-1>
    disk_fw_file: all.zip
    shelf_fw_file: all_shelf_fw.zip
```

You can observe that all the data for cluster-2 has been deleted.

If you want to apply only disk firmware updates on cluster-1 and not shelf firmware updates, you can do so using the following command:

```
clusters:
  - clustername: <cluster management LIF-1>
    disk_fw_file: all.zip
```

You can see that the shelf fw file key and value have been removed from cluster-1.



Manual addition of clusters or controllers is not supported.

### **Execute Ansible Playbook using NetApp Docker image**

Before you execute the Ansible Playbook, ensure that the **NetApp\_Ansible\_\*.zip** file has been extracted and the web server with disk or shelf firmware files is ready.

### Before you begin

Before executing Ansible Playbook using NetApp docker, you should:

- Download the AFF and FAS firmware Ansible Automation package
- · Host the Firmware files using the web server
- · Work with the inventory file
- Ensure that NetApp Docker is installed.

### **Steps**

- 1. Set up Docker.
- 2. Pull the NetApp Docker image from DockerHub by executing the following command:

```
$ docker pull schmots1/netapp-ansible

Using default tag: latest
latest: Pulling from schmots1/netapp-ansible
docker.io/schmots1/netapp-ansible:lates
```

For more information about the docker pull command, refer to the Docker Pull Documentation.

- 3. Run the Docker image as a container and log in to the container to execute the Ansible Playbook.
- 4. Copy the path of the folder which contains the extracted Ansible Playbook and inventory files, for example, downloaded\_playbook\_path. The Ansible Playbook and inventory files should be in the same folder for successful execution.
- 5. Mount the folder as a volume on the Docker container. For example, to mount the folder **container\_path**, you should execute the following command:

```
$ docker run -v <downloaded_playbook_path>:/<container_path> -it
schmots1/netapp-ansible:latest /bin/bash
```

The container starts and the console is now at bash shell of the container. For more information about the Docker Run command, refer to the Docker Run Documentation.

Execute the Ansible Playbook inside the container using the ansible-playbook command:



If there are a set of clusters with different login credentials, the Ansible Playbook must be run on each cluster. There are no changes required to the inventory file as the Ansible Playbook skips the clusters for which the login has failed.

For more information about the **ansible-playbook** command, refer to the Ansible Playbook Documentation and to execute the Ansible playbook in check mode (dry run), refer to Ansible: Check mode.

After executing the Ansible Playbook, refer to the Firmware Installation Validations for post-execution instructions.

### **Execute Ansible Playbook without NetApp Docker image**

### **Steps**

- 1. Install Python and Ansible.
- 2. Install the required Python packages using **pip**:

```
$ pip install netapp-lib requests paramiko
Installing collected packages: netapp-lib, requests, paramiko
Successfully installed netapp-lib-2020.3.12 requests-2.23.0 paramiko-
2.7.2
```

3. Install NetApp Ansible collection using the ansible-galaxy command:

```
To install the collection only for the current user $ ansible-galaxy collection install netapp.ontap

To do a more universal installation,
$ ansible-galaxy collection install netapp.ontap -p
/usr/share/ansible/collections

$ chmod -R +rw /usr/share/ansible/collections
```

For more information about the ansible-galaxy command, refer to Ansible Galaxy Documentation and for

more information about the NetApp Ansible Collection, refer to the NetApp Ansible Collection page.

4. Execute the Ansible Playbook using ansible-playbook command:



If there are a set of clusters with different login credentials, the Ansible Playbook must be run on each cluster. There are no changes required to the inventory file as the Ansible Playbook skips the clusters for which the login has failed.

For more information about the **ansible-playbook** command, refer to the Ansible Playbook Documentation and to execute the Ansible Playbook in check mode (dry run), refer to Ansible: Check mode.

After executing the playbook, refer to the Firmware Installation Validations for post-execution instructions.

### Validate firmware installation

After the execution of the playbook, log in to the cluster as the cluster administrator.

#### Validate disk firmware installation

### **Steps**

1. Verify that the drive firmware is installed:

For more information about the command, refer to storage disk show.

2. Verify that the new NVMe Flash Cache firmware is installed:

```
::*> system controller flash-cache show
```

For more information about the command, refer to system controller flash-cache show.

#### Validate shelf firmware installation

### **Steps**

1. Verify that the new shelf firmware is updated:

```
::*> system node run -node * -command sysconfig -v
```

In the output, verify that each shelf's firmware is updated to the desired level. For example:

```
Shelf 1: IOM6 Firmware rev. IOM6 A: 0191 IOM3 B: 0191
```

For more information about the command, refer to system node run.

2. Verify that the new ACP firmware is updated:

```
::*> storage shelf acp module show -instance
```

For more information about the command, refer to storage shelf acp module show.

3. Verify that the desired ACP mode is configured:

```
::*> storage shelf acp show
```

For more information about the command, refer to storage shelf acp show.

4. Change the ACP mode (channel):

```
::*> storage shelf acp configure -channel [in-band | out-of-band]
```

For more information about the command, refer to storage shelf acp configure.

### Validating SP/BMC Firmware installation

The Ansible Playbook for Service Processor/BMC firmware updates is enabled with an option to verify the installation of latest SP/BMC firmware on the controller. After the verification is complete (the updates could take a maximum time of two hours), the Ansible Playbook applies internal switch firmware updates by connecting to the SP/BMC console.

The failure and success information for SP/BMC firmware and the internal switch firmware installations will be

notified at the end of Ansible Playbook execution. Follow the steps mentioned in the Ansible Playbook in case the SP/BMC firmware/internal switch firmware installation fails.

### Get more information

You can get help and find more information through various resources.

- Troubleshooting information
- Slack workspace
- Email
- Support button in Active IQ Digital Advisor for support and feedback.

## Integrate data using APIs

### **Understand API Services**

Active IQ API Services uses automation to add efficiency to your workflows. Inside API Services resides the **API Catalog**, which describes over 100 different API endpoints that are grouped into 20+ different service areas. These APIs are available to you as a NetApp customer and they span different areas of interest, such as system information, storage efficiency, performance, health, and upgrades.

APIs are interfaces that enable you to write simple code that can contact Active IQ Digital Advisor programmatically and bring back data into your compute environment. You can write code in such a way that it contacts Active IQ Digital Advisor every day and brings back the latest data in the areas that are of interest to you. You can then use this data to populate your ticketing system or to create your own dashboards, webpages, or reports. The Active IQ API Catalog has both code samples and a facility for you to try out the APIs in the browser.

Automation with APIs is a great way to add efficiency and accuracy to daily or weekly tasks. It frees up your resources to perform more complex activities or to automate new workflows. For example, if you have system health risks that need to be fixed, you can automate at least the pullout of those items from Active IQ Digital Advisor and the push into your ticketing system.

### **API Catalog**

The toggle at the top of the page allows the user to switch between the two modes to view the Catalog. The Code view focuses on the input parameters needed, the content and format of the return data, and code samples to get the user started with putting code in place. The Experiment view offers the user a chance to "try out" the API in the browser using a generated token obtained from the main API Services page.

Either view allows the user to browse through available items using the navigation pane on the left. The items are organized by service in alphabetical order. Within a given service, you can expand the heading to show the individual API Endpoints. Clicking on the service heading or an API Endpoint will take you to that section of the Catalog in the middle pane.

### **Using the APIs**

Once you are authorized and can generate tokens, you can leverage the tokens to make programmatic queries and retrieve data. You can also test out an API from within the API Catalog to see first-hand how the query works and the type of data that is returned. This is a great way to make sure you understand how an API will work prior to building out the code framework in your system.



### Generate tokens to use APIs

It is easy to register for API Services and generate tokens.

### Steps

- 1. From the Quick Links menu, click API Services.
- 2. Click Register.
- 3. Complete the request for authorization form and click Submit.

Activation is automatic and should be instantaneous. Once you have been authorized to use the Active IQ APIs, you can generate tokens to use when making programmatic API calls. You can also use these tokens to execute "try it out" from within the API Catalog. When obtained programmatically, tokens always come in sets of two: An Access Token and a Refresh Token. The Access Token must be passed to successfully use all APIs (except for one - the Refresh Token is used to programmatically obtain a new set of tokens).

4. On the Main API Services page, click **Generate Token** to view and download the access token and refresh token to invoke APIs.

The portal gives you multiple ways to save one or both tokens in the set. You can copy them to clipboard, download them as a text file, or view them as plain text.



You should download and save the access token and refresh token for later use. Access tokens expire one hour after generation and refresh tokens expire after seven days. The refresh token used in this API call will be invalidated after a new refresh token is generated.

## **Use the API Catalog to execute APIs**

The API Catalog allows you to browse through categories and the available APIs within each of those categories.

Using a valid Access Token and correct inputs for the required fields, you can make a test call for an API.

### **Steps**

- 1. From the Quick Links menu, click API Services.
- 2. Click Browse under the API Catalog icon.

The API Catalog is displayed.

- 3. Select any API
- 4. At the top of the page, slide the toggle to "Experiment".
- 5. From the left navigation, expand the categories and select any API to view detailed information.
- 6. Expand the API.
- 7. Click the **Try it out** button on the right.
- 8. Provide the required parameters and click **Execute** to view the results.

You can also examine the **Responses** section of the API to understand the data that will be returned better. You can click on **Example Value** to see the format of the data or click on **Model** and click on the carets to expand the sections to see the definition of each element.

By sliding the toggle to the Code view, you can view code samples in various languages.

## **Generate custom reports**

## Types of reports

Active IQ provides a variety of reporting options that enable you to monitor and manage your system health and operation success.

The following are the types of reports that are available in Active IQ:

Report Name	Description	
Wellness	Provides information about the outstanding and acknowledged risks, risk details, corrective actions, and affected systems.	
Wellness – Aggregated	Provides a summary of the outstanding risks and the count of systems affected in an excel format.	
7-Mode Upgrade Advisor Plans	Provides a report about the upgrade advisor plan for 7-mode systems. This report includes information about the HA partner in a PDF format.	
Ansible Inventory	Provides an Ansible inventory file which lists all system inventory details by region or site. This file can be used for automation.	
FabricPool	Provides information about inactive, cold, active, hot, tiered, and unmonitored data. This report also includes Ansible playbook for enabling Inactive Data Reporting on disabled aggregates.	
Inventory	Provides information about the install base for a selected watchlist, customer, site, group levels.  This report can be generated either as a direct download from Inventory details page or can be generated from Reports page.	
End of Support Life	Provides information about the list the controllers, shelves, and disks, that have reached end-of-support (EOS).	
Recommended Configuration	Provides information about the various recommended configuration gaps for Remote Management Configuration, spares and drives, HA Pair, and SVM Health.	
Technical Case Details	Provides a yearly report about all the technical cases and their status.	
Upgrade Recommendations (SW & FW)	Multi-tabbed report about the software and firmware currency and recommended versions for each controller or serial in the search criteria.	
ClusterViewer Report	Provides information about a single or multiple clusters at a customer and watchlist level. You can use the ClusterViewer Report to download all the information in a single file.  You can generate this report only for watchlist with up to 100 nodes.	
Capacity & Efficiency	Provides information about the Capacity and Efficiency details at cluster, customer, site, group, watchlist and node level.	
Volume Performance Report	Provides information about the performance details of the volumes at the cluster level.	

Report Name	Description	
Performance Report	Provides information, at a watchlist level, about the performance of a cluster, node, local tier (aggregate), and volume in a single zip file.	
	You can generate this report only for watchlist with up to 100 nodes.	

## **Generate reports**

You can generate reports immediately or schedule a report to be generated on a weekly or monthly basis. You can generate reports for areas like inventory, wellness, and configuration (ClusterViewer).

### About this task

• You cannot edit the reports in Active IQ. You should delete the existing report and create a new report.

### **Steps**

- 1. From the left pane, click **Reports**.
- 2. Click Create Report to generate a new report.

You can generate a report immediately or you can schedule the report to be generated on a weekly or monthly basis.

To generate a report immediately		To schedule the report to be generated on a weekly or monthly basis	
<ol> <li>Select the type of report and provide the requested values for the report.</li> <li>Click Submit.</li> <li>The report is saved in Active IQ for 3 days.</li> </ol>		<ol> <li>Click the Schedule Report tab.</li> <li>Select the type of report and provide the requested values for the report.</li> <li>Select the frequency of the report.</li> <li>Select the start date and end date for the report.</li> </ol>	
		5. Click	Submit.  The existing scheduled reports will be replaced when the new reports are generated.

## **Get more information**

You can get help and find more information through various resources.

- NetApp Community
- Documentation resources
- Security and Privacy of NetApp Telemetry Data
- ONTAP AutoSupport and AutoSupport On Demand

## Legal notices

Legal notices provide access to copyright statements, trademarks, patents, and more.

## Copyright

http://www.netapp.com/us/legal/copyright.aspx

### **Trademarks**

NETAPP, the NETAPP logo, and the marks listed on the NetApp Trademarks page are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.

http://www.netapp.com/us/legal/netapptmlist.aspx

### **Patents**

A current list of NetApp owned patents can be found at:

https://www.netapp.com/us/media/patents-page.pdf

## **Privacy policy**

https://www.netapp.com/us/legal/privacypolicy/index.aspx

### **Copyright Information**

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

#### **Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at <a href="http://www.netapp.com/TM">http://www.netapp.com/TM</a> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.