

Requirements for installing Unified Manager

Active IQ Unified Manager 9.11

NetApp July 19, 2022

This PDF was generated from https://docs.netapp.com/us-en/active-iq-unified-manager/install-windows/concept_virtual_infrastructure_or_hardware_system_requirements.html on July 19, 2022. Always check docs.netapp.com for the latest.

Table of Contents

| Re | quirements for installing Unified Manager | . 1 |
|----|---|-----|
| , | Virtual infrastructure and hardware system requirements | . 1 |
| 1 | Windows software and installation requirements | . 2 |
| ; | Supported browsers | . 4 |
| | Protocol and port requirements | . 4 |
| | Completing the worksheet | . 6 |

Requirements for installing Unified Manager

Before you begin the installation process, ensure that the server on which you want to install Unified Manager meets the specific software, hardware, CPU, and memory requirements.

NetApp does not support any modification of the Unified Manager application code. If you need to apply any security measures to the Unified Manager server, you should make those changes to the operating system on which Unified Manager is installed.

For more details about applying security measures to the Unified Manager server, see the Knowledge Base article

Supportability for Security Measures applied to Active IQ Unified Manager for Clustered Data ONTAP

Related information

NetApp Interoperability Matrix Tool

Virtual infrastructure and hardware system requirements

Installing Unified Manager on virtual infrastructure or a physical system should meet the minimum requirements for memory, CPU, and disk space.

The following table displays the values that are recommended for memory, CPU, and disk space resources. These values have been qualified so that Unified Manager meets acceptable performance levels.

| Hardware configuration | Recommended settings |
|------------------------|--|
| RAM | 12 GB (minimum requirement 8 GB) |
| Processors | 4 CPUs |
| CPU cycle capacity | 9572 MHz total (minimum requirement 9572 MHz) |
| Free disk space | 150 GB, where the capacity is allocated as follows: 100 GB of disk space for the installation directory 50 GB of disk space for the MySQL data directory |

Unified Manager can be installed on systems with a small amount of memory, but the recommended 12 GB of RAM ensures that enough memory is available for optimal performance, and so that the system can accommodate additional clusters and storage objects as your configuration grows. You should not set any memory limits on the VM where Unified Manager is deployed, and should not enable any features (for example, ballooning) that hinder the software from utilizing the allocated memory on the system.

Additionally, there is a limit to the number of nodes that a single instance of Unified Manager can monitor before you install a second instance of Unified Manager. For more information, see the *Best Practices Guide*.

Technical Report 4621: Unified Manager Best Practices Guide

Memory-page swapping negatively impacts the performance of the system and the management application. Competing for CPU resources that are unavailable because of overall host utilization can degrade performance.

Requirement for dedicated use

The physical or virtual system on which you install Unified Manager should be used exclusively for Unified Manager and should not be shared with other applications. Other applications might consume system resources and can drastically reduce the performance of Unified Manager.

Space requirements for backups

If you plan to use the Unified Manager backup and restore feature, allocate additional capacity so that the "data" directory or disk has 150 GB of space. A backup can be written to a local destination or to a remote destination. The best practice is to identify a remote location that is external to the Unified Manager host system that has a minimum of 150 GB of space.

Requirements for host connectivity

The physical system or virtual system on which you install Unified Manager should be configured in such a way that you can successfully ping the host name from the host itself. In case of IPv6 configuration, you should verify that ping6 to the host name is successful to ensure that the Unified Manager installation succeeds.

You can use the host name (or the host IP address) to access the product web UI. If you configured a static IP address for your network during deployment, then you designated a name for the network host. If you configured the network using DHCP, you should obtain the host name from the DNS.

If you plan to allow users to access Unified Manager by using the short name instead of using the fully qualified domain name (FQDN) or IP address, then your network configuration has to resolve this short name to a valid FQDN.

Windows software and installation requirements

For the successful installation of Unified Manager on Windows, you should ensure that the system on which Unified Manager is being installed meets the software requirements.

Operating system software

You can install Unified Manager on the following Windows editions:

- Microsoft Windows Server 2019 Standard and Datacenter Edition
- Microsoft Windows Server 2022 Standard and Datacenter Edition

Unified Manager is supported on 64 bits Windows operating system for the following languages:

- English
- Japanese
- Simplified Chinese

See the Interoperability Matrix for the complete and most current list of supported Windows versions.



NetApp does not support installation of Unified Manager by using third-party tools, such as Microsoft System Center Configuration Manager (SCCM).

The server should be dedicated to running Unified Manager. No other applications should be installed on the server.

Third-party software

The following third-party packages are bundled with Unified Manager. If these third-party packages are not installed on your system, Unified Manager installs them as a part of the installation.

- Microsoft Visual C++ 2015 Redistributable package version 14.26.28720.3
- Microsoft Visual C++ Redistributable Packages for Visual Studio 2013 version 12.0.40660.0
- MySQL Community Edition version 8.0.28
- Python 3.9.2
- OpenJDK version 11.0.13
- p7zip version 18.05 or later



Starting with Unified Manager 9.5, OpenJDK is provided in the Unified Manager installation package and installed automatically. Oracle Java is not supported starting with Unified Manager 9.5.

If MySQL is pre-installed, you should ensure that:

- It is using the default port.
- The sample databases are not installed.
- The service name is "MYSQL8".

Unified Manager is deployed on a WildFly web server. WildFly 19.0.0 is bundled and configured with Unified Manager.



You should shut down a running instance of Unified Manager before upgrading any third-party software. After the third-party software installation is complete, you can restart Unified Manager.

Installation requirements

- Microsoft .NET 4.5.2, or greater, should be installed.
- The temp directory should be configured with 2 GB of disk space for extracting the installation files. To verify whether the directory is created, run the following command on the command-line interface: echo %temp%
- You should reserve 2 GB of disk space in the Windows drive for caching the Unified Manager MSI files.
- The Microsoft Windows Server on which you want to install Unified Manager should be configured with a fully qualified domain name (FQDN) such that ping responses to the host name and FQDN are successful.
- You should disable Microsoft IIS worldwide web publishing service and ensure that ports 80 and 443 are

free.

- You should make sure that the Remote Desktop Session Host setting for "Windows Installer RDS Compatibility" is disabled during the installation.
- UDP port 514 should be free, and should not be used by any other service.
- If you have an active anti-virus software installed on your Windows system, Unified Manager installation might fail. You should disable all virus scan software on your system before installing Unified Manager.

 After your installation is complete, make sure to manually exclude the following paths from anti-virus scan:
 - Unified Manager data directory
 - Unified Manager installation directory
 - MySQL data directory

Supported browsers

To access the Unified Manager web UI, use a supported browser.

The Interoperability Matrix has the list of supported browser versions.

mysupport.netapp.com/matrix

For all browsers, disabling pop-up blockers ensures that software features are displayed properly.

If you plan to configure Unified Manager for SAML authentication, so that an identity provider (IdP) can authenticate users, you should check the list of browsers supported by the IdP as well.

Protocol and port requirements

The required ports and protocols enable communication between the Unified Manager server and the managed storage systems, servers, and other components.

Connections to the Unified Manager server

In typical installations you do not have to specify port numbers when connecting to the Unified Manager web UI, because default ports are always used. For example, because Unified Manager always attempts to run on its default port, you can enter https://<host>instead of https://<host>:443.

The Unified Manager server uses specific protocols to access the following interfaces:

| Interface | Protocol | Port | Description |
|------------------------|----------|------|--|
| Unified Manager web UI | HTTP | 80 | Used to access the Unified Manager web UI; automatically redirects to the secure port 443. |

| Interface | Protocol | Port | Description |
|--|----------|------|--|
| Unified Manager web UI and programs using APIs | HTTPS | 443 | Used to securely access the Unified Manager web UI or to make API calls; API calls can only be made using HTTPS. |
| Maintenance console | SSH/SFTP | 22 | Used to access the maintenance console and retrieve support bundles. |
| Linux command line | SSH/SFTP | 22 | Used to access the Red Hat Enterprise Linux or CentOS command line and retrieve support bundles. |
| Syslog | UDP | 514 | Used to access subscription-based EMS messages from ONTAP systems and to create events based on the messages. |
| REST | HTTPS | 9443 | Used to access realtime REST API-based EMS events from authenticated ONTAP systems. |
| MySQL database | MySQL | 3306 | Used to enable OnCommand Workflow Automation and OnCommand API Services access to Unified Manager. |



The ports used for HTTP and HTTPS communication (ports 80 and 443) can be changed using the Unified Manager maintenance console. For more information, see the *Active IQ Unified Manager System Configuration Guide*.

Active IQ Unified Manager System Configuration Guide

Connections from the Unified Manager server

You should configure your firewall to open ports that enable communication between the Unified Manager server and managed storage systems, servers, and other components. If a port is not open, communication fails.

Depending on your environment, you can choose to modify the ports and protocols used by the Unified Manager server to connect to specific destinations.

The Unified Manager server connects using the following protocols and ports to the managed storage systems, servers, and other components:

| Destination | Protocol | Port | Description |
|-------------------------------|------------------|-----------|--|
| Storage system | HTTPS | 443/TCP | Used to monitor and manage storage systems. |
| Storage system | NDMP | 10000/TCP | Used for certain Snapshot restore operations. |
| AutoSupport server | HTTPS | 443 | Used to send AutoSupport information. Requires Internet access to perform this function. |
| Authentication server | LDAP | 389 | Used to make authentication requests, and user and group lookup requests. |
| | LDAPS | 636 | Used for secure LDAP communication. |
| Mail server | SMTP | 25 | Used to send alert notification emails. |
| SNMP trap sender | SNMPv1 or SNMPv3 | 162/UDP | Used to send alert notification SNMP traps. |
| External data provider server | TCP | 2003 | Used to send performance data to an external data provider, such as Graphite. |
| NTP server | NTP | 123/UDP | Used to synchronize the time on the Unified Manager server with an external NTP time server. (VMware systems only) |

Completing the worksheet

Before you install and configure Unified Manager, you should have specific information about your environment readily available. You can record the information in the worksheet.

Unified Manager installation information

The details required to install Unified Manager.

| System on which software is deployed | Your value |
|--------------------------------------|------------|
| Host fully qualified domain name | |
| Host IP address | |
| Network mask | |
| Gateway IP address | |
| Primary DNS address | |
| Secondary DNS address | |
| Search domains | |
| Maintenance user name | |
| Maintenance user password | |

Unified Manager configuration information

The details to configure Unified Manager after installation. Some values are optional depending on your configuration.

| Setting | Your value |
|---|--------------------|
| Maintenance user email address | |
| SMTP server host name or IP address | |
| SMTP user name | |
| SMTP password | |
| SMTP port | 25 (Default value) |
| Email from which alert notifications are sent | |
| Authentication server host name or IP address | |

| Setting | Your value |
|---|------------|
| Active Directory administrator name or LDAP bind distinguished name | |
| Active Directory password or LDAP bind password | |
| Authentication server base distinguished name | |
| Identity provider (IdP) URL | |
| Identity provider (IdP) metadata | |
| SNMP trap destination host IP addresses | |
| SNMP port | |

Cluster information

The details for the storage systems that you manage using Unified Manager.

| Cluster 1 | of N | Your value |
|--|---|------------|
| Host name or cluster-management IP address | | |
| ONTAP administrator user name | | |
| (i) | The administrator must have been assigned the "admin" role. | |
| ONTAP administrator password | | |
| Protocol | | HTTPS |

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.