### Export as PDF


### Lua Wireshark

- 1 Lua in Wireshark
  - 1.1 Setup
  - 1.2 Setting up the boilerplate code
  - 1.3 Adding fields
  - 1.4 Debugging
  - 1.5 Extending the iLinkRT protocol dissector

# Lua in Wireshark

### Setup

If you go to Help -> About Wireshark -> Folders, you'll find all the folders Wireshark reads Lua scripts from. Choose either the Personal Lua Plugins, Global Lua Plugins or Personal configuration folder. E.g. C:\Program Files\Wireshark\plugins\<version> on Windows. The script will be active when Wireshark is started. You have to restart Wireshark after you do changes to the script, or reload all the Lua scripts with Ctrl+Shift+L.



# Setting up the boilerplate code 1-

Let's start by setting up some of the boilerplate code that's needed in all dissectors::

```
-- iLinkRT_Proto.lua
-- Uses V3.0 of the ILinkRT specification
--
iLinkRT_protocol = Proto("iLinkRT", "iLinkRT Protocol")

iLinkRT_protocol.fields = {}

function iLinkRT_protocol.dissector(buffer, pinfo, tree)

length = buffer:len()

if length == 0 then return end

pinfo.cols.protocol = iLinkRT_protocol.name

local subtree = tree:add(iLinkRT_protocol, buffer(), "iLinkRT Protocol
Data")
end

local udp_port = DissectorTable.get("udp.port")
udp_port:add(8090, iLinkRT_protocol)
```

We start my creating a Proto (protocol) object and call it iLinkRT\_protocol. The table constructor takes two arguments: name and description. The protocol requires a fields table and a dissector function. We haven't added any fields yet, so the fields table is empty. The dissector function is called once for every packet of our type.

The dissector function has three parameters: buffer, pinfo and tree. buffer contains the packet's buffer and is a Tvb object. It contains the data we want to dissect. pinfo contains the columns of the packet list and is a Pinfo object. Finally, tree is the tree root and is a Treeltem object.

```
Datei Bearbeiten Ansicht Navigation Aufzeichnen Analyse Statistiken Telephonie Wireless Tools Hilfe
Anzeigefilter anwenden ... <Ctrl-/>
          Time
                      Source
                                          Destination
                                                              Protocol Length Info
     3307 87.010236 192.168.0.107
                                          192.168.0.110
                                                             LIDP
                                                                       89 54726 → 64674 Len=47
     3308 87.016072 192.168.0.110
                                          192.168.0.107
                                                             UDP
                                                                        58 64674 → 54726 Len=16
                                                                        66 64674 → 54726 Len=24
     3309 87 016203
                      192 168 0 110
                                          192 168 0 107
                                                             LIDP
 _ 3310 87.017678 192.168.0.107 192.168.0.110 ILINKRT 70 8089 → 8090 Len=28
     3311 87 018250
                      192 168 0 110
                                          192 168 0 107
                                                              LIDP
                                                                        85 64674 → 54726 Len=43
     3312 87.019103
                      192.168.0.107
                                          192.168.0.110
                                                             UDP
                                                                       66 54726 → 64674 Len=24
     3313 87.051878
                      192.168.0.107
                                          192.168.0.110
                                                             UDP
                                                                      118 54726 → 64674 Len=76
     3314 87.053983
                      192.168.0.107
                                          192.168.0.110
                                                             UDP
                                                                      773 54726 → 64674 Len=731
     3315 87.054414
                      192.168.0.107
                                         192.168.0.110
                                                             UDP
                                                                       173 54726 → 64674 Len=131
                                                            A IDP
                       192 168 0 107
                                          192 168 0 110
                                                                      1066 54726 → 64674 Len=1024
> Frame 3310: 70 bytes on wire (560 bits), 70 bytes captured (560 bits) on interface \Device\NPF_{BF7E6F20-DC25-4567-9AFA-07DDACFA8A23}, id 0
 >> Ethernet II, Src: Dell_95:9c:0e (64:00:6a:95:9c:0e), Dst: Microsof_b9:2e:dd (28:18:78:b9:2e:dd)
 > Internet Protocol Version 4, Src: 192.168.0.107, Dst: 192.168.0.110
 > User Datagram Protocol, Src Port: 8089, Dst Port: 8090
  iLinkRT Protocol Data tree
```

```
0000 28 18 78 b9 2e dd 64 00 6a 95 9c 0e 08 00 45 00 (·x·.·d·j····E·
0010 00 38 45 14 00 00 80 11 73 77 c0 a8 00 6b c0 a8 ·8E···· sw··k·
0020 00 6e 1f 99 1f 9a 00 24 26 46 12 00 02 00 00 00 ·n···$ &F····
0030 00 00 02 01 01 00 00 01 00 00 01 00 00 10 00 01 .....$
```

Inside the dissector function, we start by checking the length of the buffer and then returning if it's empty. As mentioned before, the pinfo object contains the columns in the packet list. We can use it to set the protocol name when we receive a packet of iLinkRT type. On the script's first line we set the name of the protocol to be "iLinkRT" (by passing the name to the constructor). We set the protocol column name here.

```
pinfo.cols.protocol = mongodb_protocol.name
```

and the protocol column name changes from TCP to ILINKRT:

We must then create a sub tree in the tree structure found in the Packet Details pane. It done by adding an additional tree item to the tree object that was passed as an argument to the dissector function.

```
local subtree = tree:add(iLinkRT_protocol, buffer(), "iLinkRT Protocol
Data")
```

Finally, we must assign the protocol to a port. In my case, I'll use port 8090, because that's the port I use to connect to the Mongo database.

```
local udp_port = DissectorTable.get("udp.port")
udp_port:add(8090, iLinkRT_protocol)
```

# **Adding fields**

he script already runs at this stage, but it isn't doing anything useful. For the script to do something useful we have to add the fields that we want to parse. Fields are made by creating ProtoField objects. We can start off simple by adding only the first field. The first field in the iLinkRT protocol specification is the message length, which is an int16.

```
-- iLinkRT Proto.lua
-- Uses V3.0 of the ILinkRT specification
iLinkRT_protocol = Proto("iLinkRT", "iLinkRT Protocol")
message_length = ProtoField.int16("ilinkrt.message_length", "messageLength",
base.DEC)
iLinkRT_protocol.fields = {message_length}
function iLinkRT_protocol.dissector(buffer, pinfo, tree)
 length = buffer:len()
 if length == 0 then return end
 pinfo.cols.protocol = iLinkRT_protocol.name
 local subtree = tree:add(iLinkRT_protocol, buffer(), "iLinkRT Protocol
 Data")
 subtree:add_le(message_length, buffer(0,2))
end
local udp_port = DissectorTable.get("udp.port")
udp_port:add(8090, iLinkRT_protocol)
```

We add the following above the dissector function:

The first argument is used as a label in the filter settings, second is used as a label in the sub tree and the last is used to decide how the variable's value should be displayed. In this case I want to show the value in decimal, but I could also use hase HEX to show it in hexadecimal format. Hexadecimal format doesn't work for int32 though

ProtoField has several types of functions we can use: uint8(), uint16(), string() and so on. We have to use the one that matches the specification. A list of all the functions can be found <a href="https://example.com/here">here</a>. We then add the field to the fields table of the protocol:

```
iLinkRT_protocol.fields = {message_length}
```


and finally add the field to the sub tree:

```
subtree:add_le(message_length, buffer(0,2))
```


I use add\_le rather than add, because we are working with a little-endian protocol. If the protocol was big endian we would have to use add. The function takes two arguments: the field we made further up, and a buffer range. We can get a range of the buffer by using the range function that is a part of the buffer object. buffer(offset,length) is the short form for the range function. buffer(0,2) means we want to start at the first byte, and then take 2 bytes. The reason we want to start at 0 is because we're dealing with the first field in the header. We take 2 bytes because that is the size of an int16.

# **Debugging**

When I'm talking about debugging I am not really thinking of debugging the normal way, where you use a symbolic debugger to step through code. You won't do that here. I am rather thinking about the process of finding and fixing errors in the code. There are generally three ways to debug dissectors written in Lua. The first is to check if you get any error messages during startup of the script. This happens either when you start Wireshark or when you reload the script with Ctrl+Shift+L. Syntax errors in the script will be caught this way. Here is what an error message looks like when an end statement is missing:




Runtime errors are often shown in the sub tree for the dissector. For example, if a function is called with the wrong name is wrong then the error message will look like this.



Finally, Wireshark has a Lua console built in that you can print error messages to. It's found in the Tools # Lua menu. Wireshark has a function called print() that can be used for logging. So the following code:

```
print ("Number of messages: " .. num_of_msg)
```


will end up looking like this when printed to the console:



where .. is used for string concatenation.

# Extending the iLinkRT protocol dissector

In the previous post we made a dissector that ended up looking like this in the packet details pane:



The Command code is only a number. It would be nicer if we showed the opcode name too. According to the iLinkRT wire protocol, the Command code have the following names:

Command HEX	Command DEC	Caommand Name
FFFF	65535	RT_GET_ALL_SERVER
0100	256	RT_GET_SERVER_STATE
0101	257	RT_GET_SERVER_TIME
0102	258	RT_SERVER_CONNECT
0103	259	RT_SERVER_DISCONNECT
0200	512	RT_GET_CALPAGE_INFO
0201	513	RT_GET_CHARACTERISTIC_ID_LI\$T
0202	514	RT_GET_CHARACTERISTIC_INFO
0203	515	RT_GET_DAQ_RESOLUTION_INFO
0204	516	RT_GET_DEVICE_INFO
0205	517	RT_GET_DEVICE_STATE
0206	518	RT_GET_MEASUREMENT_ID_LIST
0207	519	RT_GET_MEASUREMENT_INFO
0208	520	RT_GET_RASTER_OVERVIEW
0209	521	RT_GET_SELECTED_DEVICES
0300	768	RT_CHANGE_DESCRIPTION_FILE
0301	769	RT_CHANGE_HEX_FILE
0302	770	RT_CONFIGURE_SERVER
0303	771	RT_COPY_DATA_EXCHANGE_FILE_TO_DEVICE
0304	772	RT_DEVICE_CONNECT
0305	773	RT_DISTRIBUTE_EVENT
0306	774	RT_SAVE_HEX_FILE
0307	775	RT_SELECT_CHARACTERISTIC_ID
0308	776	RT_SELECT_DEVICE
0309	777	RT_SELECT_DEVICE_SET
030A	778	RT_SELECT_MEASUREMENT_ID
0400	1024	RT_CLEAR_MEASURING_LIST
0401	1025	RT_CONFIGURE_MEASURING
0402	1026	RT_GET_DAQ_EVENT_INFO
0403	1027	RT_GET_DAQ_MEASUREMENT_LIST
0404	1028	RT_GET_DEVICE_DAQ_LIST
0405	1029	RT_START_STOP_MEASURING
0500	1030	RT_GET_CALPAGE
0501	1031	RT_READ_CELL_VALUES
0502	1032	RT_READ_CHARACTERISTIC
0503	1033	RT_SET_CALPAGE
0504	1034	RT_WRITE_CELL_VALUES
0505	1035	RT_WRITE_CHARACTERISTIC
0600	1536	RT_ADD_KEY_VALUE_PAIR_TO_RECORDER_FILE
0601	1537	RT_CONFIGURE_RECORDER
0602	1538	RT_CONTROL_RECORDER

0603	1539	RT_GET_RETRIGGERING
0604	1540	RT_GET_TRIGGER
0605	1541	RT_SET_CLIENT_BOOKMARK
0606	1542	RT_SET_RETRIGGERING
0607	1543	RT_SET_TRIGGER
0700	1792	RT_EXECUTE_SERVICE
0701	1793	RT_ GET_AVAILABLE_CHARACTERISTICS
0702	1794	RT_ GET_AVAILABLE_DEVICE_SETS
0703	1795	RT_ GET_AVAILABLE_DEVICES
0704	1796	RT_ GET_AVAILABLE_MEASUREMENTS

To grab the command as an integer we can use

```
local cmd = buffer(8,2):le_uint()
```

le\_int() gets a little endian int from the buffer range. The variable cmd now contains an int representing the command in decimal. We can then make a function that returns the command name given the command number:

```
function get_cmd_name(cmd)
    local cmd_name = "Unknown"
    if cmd == 65535 then cmd_name = "RT_GET_ALL_SERVER"
                        then cmd_name = "RT_GET_SERVER_STATE"
    elseif cmd == 256
    elseif cmd == 257
                        then cmd_name = "RT_GET_SERVER_TIME"
    elseif cmd == 258
                        then cmd_name = "RT_SERVER_CONNECT"
    elseif cmd == 259
                        then cmd_name = "RT_SERVER_DISCONNECT"
    elseif cmd == 512
                        then cmd_name = "RT_GET_CALPAGE_INFO"
                        then cmd_name = "RT_GET_CHARACTERISTIC_ID_LIST"
    elseif cmd == 513
   elseif cmd == 514
                        then cmd_name = "RT_GET_CHARACTERISTIC_INFO"
    elseif cmd == 515
                        then cmd_name = "RT_GET_DAQ_RESOLUTION_INFO"
    elseif cmd == 516
                        then cmd_name = "RT_GET_DEVICE_INFO"
    elseif cmd == 517
                        then cmd_name = "RT_GET_DEVICE_STATE"
    elseif cmd == 518
                        then cmd_name = "RT_GET_MEASUREMENT_ID_LIST"
                        then cmd_name = "RT_GET_MEASUREMENT_INFO"
    elseif cmd == 519
                        then cmd_name = "RT_GET_RASTER_OVERVIEW"
    elseif cmd == 520
    elseif cmd == 521
                        then cmd_name = "RT_GET_SELECTED_DEVICES"
                        then cmd_name = "RT_CHANGE_DESCRIPTION_FILE"
    elseif cmd == 768
    elseif cmd == 769
                        then cmd_name = "RT_CHANGE_HEX_FILE"
    elseif cmd == 770
                        then cmd_name = "RT_CONFIGURE_SERVER"
    elseif cmd == 771
                        then cmd_name =
 "RT_COPY_DATA_EXCHANGE_FILE_TO_DEVICE"
    elseif cmd == 772
                        then cmd_name = "RT_DEVICE_CONNECT"
    elseif cmd == 773
                        then cmd_name = "RT_DISTRIBUTE_EVENT"
    elseif cmd == 774
                        then cmd_name = "RT_SAVE_HEX_FILE"
    elseif cmd == 775
                        then cmd_name = "RT_SELECT_CHARACTERISTIC_ID"
                        then cmd_name = "RT_SELECT_DEVICE"
    elseif cmd == 776
   elseif cmd == 777
                        then cmd_name g=_"RT_SELECT_DEVICE_SET"
                        then cmd_name = "RT_SELECT_MEASUREMENT_ID"
    elseif cmd == 778
                        then cmd_name = "RT_CLEAR_MEASURING_LIST"
    elseif cmd == 1024
    olderif and -- 100E then and name - HDE CONETCIDE MEACIDING
```

```
elseif cmd == 1029 then cmd name = "RT_START_STOP_MEASURING"
   elseif cmd == 1030 then cmd_name = "RT_GET_CALPAGE"
   elseif cmd == 1031
                       then cmd_name = "RT_READ_CELL_VALUES"
   elseif cmd == 1032 then cmd_name = "RT_READ_CHARACTERISTIC"
   elseif cmd == 1033 then cmd_name = "RT_SET_CALPAGE"
   elseif cmd == 1034 then cmd_name = "RT_WRITE_CELL_VALUES"
   elseif cmd == 1035 then cmd_name = "RT_WRITE_CHARACTERISTIC"
   elseif cmd == 1536 then cmd_name =
"RT_ADD_KEY_VALUE_PAIR_TO_RECORDER_FILE"
   elseif cmd == 1537
                       then cmd_name = "RT_CONFIGURE_RECORDER"
   elseif cmd == 1538
                       then cmd_name = "RT_CONTROL_RECORDER"
   elseif cmd == 1539
                       then cmd_name = "RT_GET_RETRIGGERING"
   elseif cmd == 1540 then cmd_name = "RT_GET_TRIGGER"
   elseif cmd == 1541
                       then cmd_name = "RT_SET_CLIENT_BOOKMARK"
   elseif cmd == 1542 then cmd_name = "RT_SET_RETRIGGERING"
   elseif cmd == 1543
                       then cmd_name = "RT_SET_TRIGGER"
   elseif cmd == 1792
                       then cmd_name = "RT_EXECUTE_SERVICE"
   elseif cmd == 1793 then cmd name = "RT GET AVAILABLE CHARACTERISTICS"
   elseif cmd == 1794 then cmd_name = "RT_ GET_AVAILABLE_DEVICE_SETS"
   elseif cmd == 1795 then cmd_name = "RT_ GET_AVAILABLE_DEVICES"
   elseif cmd == 1796 then cmd_name = "RT_ GET_AVAILABLE_MEASUREMENTS"
   end
return cmd_name
end
```

Finally, we have to replace the old addition to the sub tree with the following code:

```
local cmd_name = get_cmd_name(cmd)
subtree:add_le(command, buffer(8,2)):append_text(" (" .. cmd_name ..
")")
```

We append the name of the name of the command in parentheses to the original statement that only showed command number. The packet details pane in Wireshark will then end up looking like this:

```
Datei Bearbeiten Ansicht Navigation Aufzeichnen Analyse Statistiken Telephonie Wireless Tools Hilfe
\times
ilinkrt
         Time
                      Source
                                         Destination
                                                             Protocol Length Info
     3310 87.017678
                     192.168.0.107
                                         192.168.0.110
                                                            ILINKRT 70 8089 → 8090 Len=28
ILINKRT 70 8089 → 8090 Len=28
    14979 448.384576 192.168.0.107
                                         192.168.0.110
    35857 1064.936057 192.168.0.107
                                         192.168.0.110
                                                            ILINKRT
                                                                       70 8089 → 8090 Len=28
                                                          ILINKRT
    55037 1507.889590 192.168.0.107 192.168.0.110
                                                                       70 8089 → 8090 Len=28
    55422 1519.617404 192.168.0.107
                                         192.168.0.110
                                                             ILINKRT
                                                                       70 8089 → 8090 Len=28
 - 73972 1793.034386 192.168.0.107 192.168.0.110 ILINKRT 94 8089 → 8090 Len=52
> Frame 73972: 94 bytes on wire (752 bits), 94 bytes captured (752 bits) on interface \Device\NPF_{BF7E6F20-DC25-4567-9AFA-07DDACFA8A23}, id 0
> Ethernet II, Src: Dell_95:9c:0e (64:00:6a:95:9c:0e), Dst: Microsof_b9:2e:dd (28:18:78:b9:2e:dd)
 > Internet Protocol Version 4, Src: 192.168.0.107, Dst: 192.168.0.110
 > User Datagram Protocol, Src Port: 8089, Dst Port: 8090
iLinkRT Protocol Data
     messageLength: 42
    messageCounter: 9
    messageFirstControl: 0
    messagefillBytes: 0
     messageSecondControl: 0
    command: 258 (RT_SERVER_CONNECT)
(·x·.·<mark>d· j···</mark>··E
·Pz···· =····k·
                                                    ·Pz····· = · · · · · · ·
                                                    ···We4Da ta···IL·
0050 06 00 31 2e 31 2e 32 00 9e 1f 00 00 00 00
```

#### With the final code being:

```
-- iLinkRT_Proto.lua
-- Uses V3.0 of the ILinkRT specification
iLinkRT_protocol = Proto("iLinkRT", "iLinkRT Protocol")
message_length = ProtoField.int16("ilinkrt.message_length", "messageLength",
base.DEC)
message_ctr = ProtoField.int16("ilinkrt.message_ctr", "messageCounter",
message_cf1 = ProtoField.int16("ilinkrt.message_cf1", "messageFirstControl",
message_fill1 = ProtoField.int16("ilinkrt.message_fill1",
 "messagefillBytes", base.DEC)
message_cf2 = ProtoField.int16("ilinkrt.message_cf2",
 "messageSecondControl", base.DEC)
command = ProtoField.int16("ilinkrt.command", "command", base.DEC)
num_of_msg = 0
iLinkRT_protocol.fields = {message_length, message_ctr, message_cf1,
message_fill1, message_cf2, command }
function iLinkRT_protocol.dissector(buffer, pinfo, tree)
 length = buffer:len()
 if length == 0 then return end
                                    - 10 -
  --num_of_msg = num_of_msg +1
```

```
pinfo.cols.protocol = iLinkRT_protocol.name
 local subtree = tree:add(iLinkRT_protocol, buffer(), "iLinkRT Protocol
Data")
 subtree:add_le(message_length, buffer(0,2))
 subtree:add_le(message_ctr, buffer(2,2))
 subtree:add_le(message_cf1, buffer(4,2))
 subtree:add_le(message_fill1, buffer(6,2))
 subtree:add_le(message_cf2, buffer(length-2,2))
 local cmd = buffer(8,2):le_uint()
 local cmd_name = get_cmd_name(cmd)
 subtree:add_le(command, buffer(8,2)):append_text(" (" .. cmd_name .. ")")
end
function get cmd name(cmd)
   local cmd_name = "Unknown"
   if cmd == 65535 then cmd_name = "RT_GET_ALL_SERVER"
   elseif cmd == 256
                      then cmd_name = "RT_GET_SERVER_STATE"
   elseif cmd == 257 then cmd_name = "RT_GET_SERVER_TIME"
    elseif cmd == 258
                      then cmd_name = "RT_SERVER_CONNECT"
    elseif cmd == 259
                        then cmd_name = "RT_SERVER_DISCONNECT"
    elseif cmd == 512
                        then cmd_name = "RT_GET_CALPAGE_INFO"
                        then cmd_name = "RT_GET_CHARACTERISTIC_ID_LIST"
    elseif cmd == 513
   elseif cmd == 514
                        then cmd_name = "RT_GET_CHARACTERISTIC_INFO"
    elseif cmd == 515
                        then cmd_name = "RT_GET_DAQ_RESOLUTION_INFO"
    elseif cmd == 516
                        then cmd_name = "RT_GET_DEVICE_INFO"
    elseif cmd == 517
                        then cmd_name = "RT_GET_DEVICE_STATE"
    elseif cmd == 518
                        then cmd_name = "RT_GET_MEASUREMENT_ID_LIST"
    elseif cmd == 519
                        then cmd_name = "RT_GET_MEASUREMENT_INFO"
    elseif cmd == 520
                        then cmd_name = "RT_GET_RASTER_OVERVIEW"
    elseif cmd == 521
                        then cmd_name = "RT_GET_SELECTED_DEVICES"
    elseif cmd == 768
                        then cmd_name = "RT_CHANGE_DESCRIPTION_FILE"
    elseif cmd == 769
                        then cmd_name = "RT_CHANGE_HEX_FILE"
   elseif cmd == 770
                        then cmd_name = "RT_CONFIGURE_SERVER"
    elseif cmd == 771
                        then cmd_name =
 "RT_COPY_DATA_EXCHANGE_FILE_TO_DEVICE"
    elseif cmd == 772
                        then cmd_name = "RT_DEVICE_CONNECT"
    elseif cmd == 773
                      then cmd_name = "RT_DISTRIBUTE_EVENT"
    elseif cmd == 774
                        then cmd_name = "RT_SAVE_HEX_FILE"
    elseif cmd == 775
                        then cmd_name = "RT_SELECT_CHARACTERISTIC_ID"
    elseif cmd == 776
                        then cmd_name14 - "RT_SELECT_DEVICE"
    elseif cmd == 777
                        then cmd_name = "RT_SELECT_DEVICE_SET"
    elseif cmd == 778
                        then cmd_name = "RT_SELECT_MEASUREMENT_ID"
```

```
elseif cmd == 1035 then cmd_name = "RT_WRITE_CHARACTERISTIC"
    elseif cmd == 1536 then cmd_name =
 "RT_ADD_KEY_VALUE_PAIR_TO_RECORDER_FILE"
    elseif cmd == 1537 then cmd_name = "RT_CONFIGURE_RECORDER"
    elseif cmd == 1538 then cmd_name = "RT_CONTROL_RECORDER"
    elseif cmd == 1539 then cmd_name = "RT_GET_RETRIGGERING"
    elseif cmd == 1540 then cmd_name = "RT_GET_TRIGGER"
    elseif cmd == 1541 then cmd_name = "RT_SET_CLIENT_BOOKMARK"
    elseif cmd == 1542 then cmd_name = "RT_SET_RETRIGGERING"
    elseif cmd == 1543 then cmd_name = "RT_SET_TRIGGER"
    elseif cmd == 1792 then cmd_name = "RT_EXECUTE_SERVICE"
    elseif cmd == 1793 then cmd_name = "RT_ GET_AVAILABLE_CHARACTERISTICS"
    elseif cmd == 1794 then cmd_name = "RT_ GET_AVAILABLE_DEVICE_SETS"
    elseif cmd == 1795 then cmd_name = "RT_ GET_AVAILABLE_DEVICES"
    elseif cmd == 1796 then cmd_name = "RT_ GET_AVAILABLE_MEASUREMENTS"
return cmd_name
end
local udp_port = DissectorTable.get("udp.port")
udp_port:add(8090, iLinkRT_protocol)
```