## Reversing with Radare2

### **Starting Radare**

The basic usage is radare2 executable (on some systems you can use r2 instead of radare2); if you want to run radare2 without opening any file, you can use -- instead of an executable name.

Some command-line options are:

-d file|pid debug executable file or process pid
-A analyze all referenced code (aaa command)

-R profile.rr2 specifies rarun2 profile (same as

-e dbg.profile=profile.rr2)

-w open file in write mode

-p prj-p use project prj-p list projects

-h show help message (-hh the verbose one)

Example: r2 -dA /bin/ls

#### General information

The command? prints the help. Command names are hierarchically defined; for instance, all printing commands start with p. So, to understand what a command does, you can append? to a *prefix* of such a command; for instance, to learn what pdf does, you can first try pd?, then the more general p?.

Single-line comments can be entered using #; e.g. s # where R we?.

Command? can also be used to evaluate an expression and print its result in various format; e.g. ? 5 \* 8 + 2 (note the space between? and the expression). There are also some special \$-variables (list all of them with: ?\$?):

\$\$ current virtual seek

\$b block size

Where an address addx is expected, you can provide any expression that evaluates to an address, e.g. a function name or a register name. In this cheatsheet we sometimes use fn-name, instead of addx, to emphasize that the argument is supposed to be a function starting address. As default address is (usually?) used the current seek: \$\$.

All commands that:

- accept an optional size (e.g. pd), use the current block size by default (see: b)
- accept an optional address (e.g., pdf), use the current position by default (see: s)

#### Internal grep-like filtering

You can filter command output by appending ~[!]str, to display only rows [not] containing string str; e.g. pdf~rdx and pdf~!rdx. You can further filter by appending

:r to display row r  $(0 \le r < \#rows$  or, backwards with:  $-\#rows \le r \le -1)$  [c] to display column c  $(0 \le c < \#cols)$  :r[c] to display column c of row r

Examples: afl~[0], afl~malloc[0], pdf~:2 and pdf~mov:2

#### Shell interaction

Command output can be redirected to a file by appending *>filename* or piped to an external command with | progname [args]. Examples: afl > all\_functions and afl | wc -l.

External commands can be run with !!progname [args]. Note: if a command starts with a single!, the rest of the string is passed to currently loaded IO plugin (only if no plugin can handle the command, it is passed to the shell).

The output of external programs can be used as arguments for internal commands by using back-ticks to enclose the invocation of external commands; e.g. pdf 'echo 3' @ 'echo entry0'.

#### Python scripting

Assuming that Python extension has been installed (#! lists installed extensions) an, interactive Python interpreter can be spawned with #!python and a script can be run with #!python script-filename.

Inside the spawned interpreter r2 is an r2pipe object that can be used to interact with the same instance of Radare, by invoking method cmd; e.g. print(r2.cmd('pdf @ entry0')).

In a script the same behaviour can be obtained by importing r2pipe and inizializing r2 with r2pipe.open("#!pipe").

You can make most Radare2 commands output in JSON format by appending a j; e.g. pdfj (instead of pdf).

Method cmdj can de-serialize JSON output into Python objects; e.g. f = r2.cmdj('pdfj @ entry0')

print f['name'], f['addr'], f['ops'][0]['opcode']

#### Configuration

e??	list all variable names and descriptions
e?[?] var-name	show description of var-name
	1
e $var$ - $name$	show the value of var-name
e	show the value of all variables
$\verb"eco" theme-name"$	select theme; eg. eco solarized
eco	list available themes
b	display current block size
b $size$	set block size
<pre>env [name [=value]]</pre>	get/set environment variables

#### Some variables

asm.pseudo asm.bytes asm.cmtright asm.emu asm.demangle	enable pseudo-code syntax (in visual mode, toggle with: \$) display bytes of each instruction comments at right of disassembly if they fit run ESIL emulation analysis on disasm Show demangled symbols in disasm
bin.demangle	Import demangled symbols from RBin
cmd.stack	command to display the stack in visual debug mode (Eg: $px$ 32)
dbg.follow.child	continue tracing the child process on fork
io.cache	enable cache for IO changes

(AKA non-persistent write-mode)

show nice UTF-8 chars instead of ANSI

(Windows: switch code-page with chcp 65001)

## Example: my ~/.radare2rc

e asm.bytes=0 e scr.utf8=true e asm.cmtright=true e cmd.stack=px 32 eco solarized

scr.utf8

#### Searching: /

/ str search for string str
/x hstr search for hex-string hstr
/a asm-instr assemble instruction and search for its bytes
find ROP gadgets containing opcode;
see: http://radare.today/posts/ropnroll/

a lot of other commands... TODO!

Also: e??search for options

#### Seeking: s

s	print current position/address
$s\ addx$	seek to addx
s+ $n$	seek $n$ bytes forward
s++	seek block-size bytes forward
s-n	seek n bytes backward
s	seek block-size bytes backward
s-	undo seek
s+	redo seek
s=	list seek history
s*	list seek history as r2-commands

#### Analysis (functions and syscalls): a

aaa	analyze (aa) and auto-name all functions
afl	list functions
afll	list functions with details
afi $fn$ - $name$	show verbose info for fn-name
afn new-name addx	name function at address $addx$
afn new-name old-name	rename function
asl	list syscalls
asl $name$	display syscall-number for name
asl $n$	display name of syscall number $n$
afvd $var\text{-}name$	output r2 command for displaying the
	address and value of arg/local var-name
.afvd $var$ - $name$	display address and value of var-name
afvn name new-name	rename argument/local variable
afvt name type	change type for given argument/local
$axt \ addx$	find data/code references to $addx$
	,

#### Graphviz/graph code: ag

${\tt ag}\ addr$	output graphviz code (BB at addr and children)
	E.g. view the function graph with: ag \$\$   xdot -
$\mathtt{agc}\ addr$	callgraph of function at $addx$
agC	full program callgraph

#### Information: i

```
i show info of current file
ie entrypoint
iz strings in data sections
izz strings in the whole binary
ii imports
iS sections
```

#### Printing: p

$\begin{array}{l} \texttt{ps} \; [\texttt{@} \; addx] \\ \texttt{pxr} \; [n] \; [\texttt{@} \; addx] \end{array}$	print C-string at $addx$ (or current position) print $n$ bytes (or block-size), as words, with references to flags and code (telescoping) at $addx$ (or current position)
$\mathtt{px}\ [n]\ [\mathtt{0}\ addx]$	hexdump
pxh	hexdump half-words (16 bits)
pxw	hexdump words (32 bits)
pxq	hexdump quad-words (64 bits)
$\mathtt{pxl}\ [n]\ [\mathtt{0}\ addx]$	display $n$ rows of hexdump
<pre>px/fmt [@ addx]</pre>	gdb-style printing fmt (in gdb see: help x
	from r2: !!gdb -q -ex 'help x' -ex quit)
pd[n][@addx]	disassemble $n$ instructions
pD[n][@addx]	disassemble $n$ bytes
pd - n [@ addx]	disassemble $n$ instructions backwards
pdf [@ fn-name]	disassemble function $fn$ -name
pdc [@ fn-name]	pseudo-disassemble in C-like syntax

#### Debugging: d

?d opcode	description of opcode (eg. ?d jle)
	BUG (?): this doesn't work on Windows
dc	continue (or start) execution
$\mathtt{dcu}\ addx$	continue until $addx$ is reached
$ exttt{dcs} [name]$	continue until the next syscall (named name,
	if specified)
dcr	continue until ret (uses step over)
dr=	show general-purpose regs and their values
dro	show previous (old) values of registers
drr	show register references (telescoping)
dr reg-name = value	set register value
drt	list register types
$\mathtt{drt}\ type$	list registers of type type and their values
db	list breakpoints
$\mathtt{db}\ addx$	add breakpoint
$\mathtt{db}$ - $addx$	remove breakpoint
doo <i>args</i>	(re)start debugging
ood	synonym for doo
ds	step into
dso	step over
dbt	display backtrace
drx	hardware breakpoints
dm	list memory maps; the asterisk shows where
	the current offset is
dmp	change page permissions (see: dmp?)
m .	

# Types: t "td C-type-def"

t $t$ - $name$	show type t-name in pf syntax
.t $t$ -name $\mathbf{Q}$ $addx$	display the value (of type $t$ -name) at $addx$
t	list (base?) types
te	list enums
ts	list structs
tu	list unions
to $file$	parse type information from C header file
tl t-name	link t-name to current address
t1 t-name = addx	link $t$ -name to address $addx$
tl	list all links in readable format

define a new type

Visual mode: V			
Command V enters visual mode.			
q	exit visual-mode		
С	cursor-mode, tab switches among stack/regs/disassembly		
:	execute a normal-mode command; e.g. :dm		
p and P	rotate forward/backward print modes		
/str	highlight occurences of string str		
\$	toggle pseudo-syntax		
0	toggle ESIL-asm		
;	add/remove comments (to current offset)		
x	browse xrefs-to current offset		
X	browse xrefs-from current function		
_	browse flags		
d	define function, end-function, rename,		
V	enter block-graph viewer		

enter visual-assembler

#### Seeking (in Visual Mode)

•	seeks to program counter
Enter	on jump/call instructions, follow target address
u	undo
U	redo
0	go/seek to given offset
d (a digit)	jump to the target marked [d]
ml (a letter)	mark the spot with letter $l$
, l	jump to mark $l$
n	jump to next function
N	jump to previous function

#### Debugging (in Visual Mode)

b or F2	2 toggle breakpoin
F4	run to cursor
s or F7	step-into
S or F8	3 step-over
F9	continue

Flags: f

Comments: C

TODO

Writing: w

 $ext{wa} \ asm\text{-}instr$  assemble and write opcodes; for more instructions

the whole command must be quoted: "wa  $asm-instr_1$ ;  $asm-instr_2$ ; ..."

Projects: P

TODO

### Running in different environments: rarun2

rarun2 is used as a launcher for running programs with different environment, arguments, permissions, directories and overridden default file-descriptors. Usage:

rarun2 [-t|script-name.rr2] [directives] [--] [prog-name] [args] rarun2 -t shows the terminal name, say  $\alpha$ , and wait for a connection from another process. For instance, from another terminal, you can execute rarun2 stdio= $\alpha$  program=/bin/sh (use stdin/stdout to redirect one stream only).

rarun2 supports a lot of directives, see the man page.

Copyright ©2017 by zxgio

This cheat-sheet may be freely distributed under the terms of the GNU General Public License; the latest version can be found at:

https://github.com/zxgio/r2-cheatsheet/