Reversing with Radare2

Starting Radare

The basic usage is radare2 exe (on some systems you can use simply r2 instead of radare2). If there exists a script named exe.r2, then it gets executed after the others rc-files. If you want to run radare2 without opening any file, you can use -- instead of an executable name.

Some command-line options are:

-d file-d ebug executable file-d piddebug process pid

-A analyze all referenced code (aaa command)

-r profile.rr2 specifies rarun2 profile (same as

-e dbg.profile=profile.rr2) open file in write mode

-p [prj] list projects / use project prj

-h show help message (-hh the verbose one)

Example: r2 -dA /bin/ls

Running in different environments: rarun2

rarun2 runs programs with different environments, arguments, permissions, directories and overridden default file-descriptors. Usage: rarun2 [-t|script-name.rr2] [directives] [--] [prog-name] [args] rarun2 -t shows the terminal name, say α , and wait for a connection from another process. For instance, from another terminal, you can execute rarun2 stdio= α program=/bin/sh (use stdin/stdout to redirect one stream only). Run rarun2 -h to get a sample .rr2 file. rarun2 supports a lot of directives, see the man page for details.

General information

The command? prints the help. Command names are hierarchically defined; for instance, all printing commands start with p. So, to understand what a command does, you can append? to a prefix of such a command; e.g., to learn what pdf does, you can first try pd?, then the more general p?. You can get recursive help with ?*; e.g.: p?* Single-line comments can be entered using #; e.g. s # where R we?. Command? can also be used to evaluate an expression and print its result in various format; e.g.? 5 * 8+2 (note the space after?). Commands?v/?vi print result only in hex/decimal. There are also some special \$-variables (list them all with: ?\$?); e.g.:

\$\$ current virtual seek

\$b block size

Where an address addx is expected, you can provide any expression that evaluates to an address, e.g. a function name or a register name. In this cheatsheet we sometimes use fn-name, instead of addx, to emphasize that the argument is supposed to be a function starting address. As default address is (usually?) used the current seek: \$\$. All commands that:

- accept an optional size (e.g. pd), use the current block size by default (see: b)
- accept an optional address (e.g., pdf), use the current position by default (see: s)

Commands can be chained by using; as separator; e.g. s fun; pd 2 affect others.

Internal grep-like filtering

You can filter command output by appending ~[!]str, to display only rows [not] containing string str; e.g. pdf~rdx and pdf~!rdx. You can further filter by appending

 $\begin{array}{lll} :r & \text{to display row } r \ (0 \leq r < \#rows \ \text{or, backwards} \\ & \text{with: } -\#rows \leq r \leq -1) \\ [c_1[,c_2,\ldots]] & \text{to display columns } c_1,c_2,\ldots \ (0 \leq c_i < \#cols) \\ :\mathbf{r}[c_1,\ldots,c_n] & \text{to display columns } c_1,\ldots,c_n \ \text{of row } r \\ \ldots & \text{to pipe the output into less-like viewer} \\ \ldots & \text{to pipe the output into HUD viewer} \\ \text{Examples: afl-[0], afl-malloc[0], pdf-:2 and pdf-mov:2} \end{array}$

There is much more (sorting, counting, ...); see: ~?

Shell interaction

Command output can be redirected to a file by appending *>filename* or piped to an external command with | progname [args]. Examples: afl > all_functions and afl | wc -1.

External commands can be run with !!progname [args]. Note: if a command starts with a single !, the rest of the string is passed to currently loaded IO plugin (only if no plugin can handle the command, it is passed to the shell).

Moreover, backticks can be used to send the output of r2-commands as arguments; e.g. !!echo '? 42'. Vice versa output of external programs can be used as arguments for internal commands; e.g. pdf 'echo 3' @ 'echo entry0'.

Some common Unix-like commands are implemented as built-ins; e.g. 1s, cd, pwd, mkdir and rm.

Radare scripting

. filename interpret r2 script filename
.! command interpret output of command as r2 commands

Python scripting (via r2pipe)

You can script Radare2 with Python, by leveraging *r2pipe*, that can be easily installed (inside any Python 2 virtual environment) with: pip install r2pipe.

Then, you can spawn a Python interpreter, from inside r2, with: #!pipe python [python-file] or simply:

#. python-file

Once you are in Python-world, you can connect to r2 by importing r2pipe and inizializing some variable, say r2, with r2pipe.open("#!pipe"), or simply r2pipe.open().

Then you can interact with Radare by invoking method cmd; e.g. print(r2.cmd('pdf @ entry0')).

You can make most Radare2 commands output in JSON format by appending a j; e.g. pdfj (instead of pdf).

Method cmdj can de-serialize JSON output into Python objects; e.g. f = r2.cmdj('pdfj @ entry0')

print f['name'], f['addr'], f['ops'][0]['opcode']

r2pipe: connecting to other r2 instances

You can connect to any web-listening instance of r2 by passing r2pipe.open a string of the form 'http://host:port'. By using this approach you get your own seek-cursor: your seek commands won't affect others

To open a background web-service in r2 use command =h&. You may also want to take a look at configuration variable http.sandbox.

Configuration

list all variable names and descriptions e?[?] var-name show description of var-name show the value of var-name e var-name e var-name = ?[?]print valid values of var-name [with descript.] E.g. e asm.arch=?? show the value of all variables select theme; eg. eco solarized eco theme-name eco list available themes display current block size b size set block size get/set environment variables env [name [=value]]

enable pseudo-code syntax

Some variables

asm.pseudo

asm.bytes display bytes of each instruction asm.describe show opcode description comments at right of disassembly if they fit asm.cmtright asm.emu run ESIL emulation analysis on disasm Show demangled symbols in disasm asm.demangle bin.demangle Import demangled symbols from RBin command to display the stack in visual cmd.stack debug mode (Eg: px 32) continue tracing the child process on fork dbg.follow.child show stack and regs in visual mode, in a slow but dbg.slow verbose (e.g. telescoping) mode io.cache enable cache for IO changes (AKA non-persistent write-mode) show nice UTF-8 chars instead of ANSI scr.utf8 (Windows: switch code-page with chcp 65001) show curved UTF-8 corners (requires scr.utf8) scr.utf8.curvy scr.nkey select seek mode (fun, hit, flag); affects commands n and N during visual mode scr.wheel enables mouse-wheel in visual mode break lines in Visual instead of truncating them scr.breaklines

Searching: /

/ str search for string str
/x hstr search for hex-string hstr
/a asm-instr assemble instruction and search for its bytes
/R opcode find ROP gadgets containing opcode;
see: http://radare.today/posts/ropnroll/
/A type find instructions of type type (/A? for the listof types)
Also: e??search for options

Seeking: s

Writing: w

wa asm-instrassemble and write opcodes; for more instructions the whole command must be quoted: "wa $asm-instr_1$; $asm-instr_2$; ..." replace current instruction; see wao? for details wao ... w[z] strwrite string str [and append byte $\x00$] write hex-pairs wx hex-pairs list pending changes (see variable io.cache) list pending changes in Radare commands wc* wtf [file] [size] write to file

Analysis (functions and syscalls): a

analyze (aa) and auto-name functions list functions [with details] af1[1] afi fn-name show verbose info for fn-name (re)name function at address addx afn new-name addx asl list syscalls display syscall-number for nameasl namedisplay name of syscall number n $\mathtt{asl}\ n$ output r2 command for displaying the afvd var-name address and value of arg/local var-name display address and value of var-name .afvd var-name afvn name new-name rename argument/local variable change type for given argument/local afvt name type afv- name removes variable name axt addxfind data/code references to addx ahi $\{b|d|h|o|r|S|s\}$ @ addxdefine binary/decimal/hex/octal/IP/ syscall/string base for immediate

ESIL: ae

aeiminitialize ESIL VM stack change ESIL PC to addx (aeip sets PC to curseek) $aepc \ addr$ aer ... handle ESIL registers like dr does perform emulated debugger step [back|over] aes[b|o] step until given address $aesu \ addr$

Graphviz/graph code: ag

 $ag \ addr$ output graphviz code (BB at addr and children) E.g. view the function graph with: ag \$\$ | xdot $agc \ addr$ callgraph of function at addx agCfull program callgraph

Flags (AKA "bookmarks"): f

fs [name] display flagspaces [select/create fs name] push previous flagspace and set name fs+ name pop to the previous flagspace fsf list flags f name @ addx f name = addxassociate name name to address addxf- @ addxremove the association at address addxremove the association with name name f- name

Comments: C

CCu text [@ addx] set (update?) comment text at addx CC text [@ addx] append comment text at addx CC- [@ addx]remove comment at addx CC. $\begin{bmatrix} 0 & addx \end{bmatrix}$ show comment at addxCC! [@ addx] edit comment using cfg.editor (vim, ...)

Debugging: d

?d opcode description of opcode (eg. ?d jle) dc continue (or start) execution dcu addxcontinue until addx is reached continue until the next syscall (named name. dcs [name] if specified) continue until ret (uses step over) dcr dr= show general-purpose regs and their values show previous (old) values of registers dro show register references (telescoping) drr dr req-name = valueset register value list register types drt $\mathtt{drt}\ type$ list registers of type type and their values db list breakpoints add [remove] breakpoint db[-] addx (re)start debugging doo args synonym for doo ood step into [over] ds[o] display backtrace dbt hardware breakpoints drx dm list memory maps; the asterisk shows where the current offset is list library symbols dmi change page permissions (see: dmp?) dmp

Types: t

"td C-type-def" define a new type t t-name show type *t-name* in pf syntax display the value (of type t-name) at addx .t t-name @ addx list (base?) types te / ts / tu list enums/structs/unions to file parse type information from C header file tl t-name link t-name to current address t1 t-name = addxlink t-name to address addxt.1 list all links in readable format tp t-name = addxcast data at addx to type t-name, and prints it

Printing: p

ps [@ *addx*] print C-string at addx (or current position) pxr[n] [@ addx]print with references to flags/code (telescoping) px [n] [@ addx]hexdump — note: x is an alias for px hexdump in 16/32/64 bit words $px\{h|w|q\} \dots$ $px\{H|W|Q\}$... as the previous one, but one per line display n rows of hexdump pxl[n][@addx]px/fmt [@ addx] gdb-style printing fmt (in gdb see: help x from r2: !!gdb -q -ex 'help x' -ex quit) pd[n][@addx]disassemble n instructions p8 [n] [@ addx] print bytes disassemble n bytes pD [n] [@ addx] pd - n [@ addx]disassemble n instructions backwards disassemble function fn-name pdf [@ fn-name] pc[p][n][@addx]dumps in C [Python] format * addx [=value] shortcut for reading/writing at addx pf $fmt \ a_1[, a_2, \ldots]$ formatted print, see pf?? and pf???

Information: i (and S)

show info of current file iz[z] strings in data sections [whole binary] $i\{e|i|1|S\}$ entrypoint/imports/libraries/sections list segments (confusingly called sections?!?)

Visual mode: V (q exits) Command V enters visual mode. exit visual-mode q cursor-mode, tab switches among panels С +/- increment/decrement current byte execute a normal-mode command; e.g. :dm p and P rotate forward/backward print modes highlight occurrences of string str/str toggle pseudo-syntax \$ 0 toggle ESIL-asm add/remove comments (to current offset) х browse xrefs-to current offset browse xrefs-from current function Х browse flags define function, end-function, rename, ... $di\{b|o|d|h|s\}$ define immediate bin/oct/dec/hex or str enter block-graph viewer (space toggles visual/graph) enter visual-assembler (preview must be confirmed) Α n / Nseek next/previous function/flag/hit (see scr.nkey) i enter insert mode configures internal variables

toggle the column mode

Seeking (in Visual Mode)

seeks to program counter Enteron jump/call instructions, follow target address u / U undo / redo go/seek to given offset seek to beginning of current function 0 (*zero*) jump to the target marked [d] d (a non-zero digit) mark the spot with letter lml (a letter) , 1 iump to mark ln / N jump to next/previous function

Debugging (in Visual Mode)

b or F2 toggle breakpoint F4 run to cursor s or F7 step-into S or F8 step-over continue

Projects: P [unstable feature]

list all projects $P\{o|s|d\}$ [prj-name] open/save/delete project prj-name Pc prj-name show project script to console

Copyright ©2017 by zxgio; cheat-sheet built on October 29, 2017 This cheat-sheet may be freely distributed under the terms of the GNU General Public License: the latest version can be found at: https://github.com/zxgio/r2-cheatsheet/