Reversing with Radare2

Starting Radare

The basic usage is radare2 exe (on some systems you can use simply r2 instead of radare2). If there exists a script named exe.r2, then it gets executed after the others rc-files. If you want to run radare2 without opening any file, you can use -- instead of an executable

Some command-line options are:

-d file debug executable file -d piddebug process pid

-A analyze all referenced code (aaa command)

-r profile.rr2 specifies rarun2 profile (same as -e dbg.profile=profile.rr2)

open file in write mode list projects / use project pri -p [*prj*]

show help message (-hh the verbose one)

Example: r2 -dA /bin/ls

Running in different environments: rarun2

rarun2 runs programs with different environments, arguments, permissions, directories and overridden default file-descriptors. Usage: rarun2 [-t|script-name.rr2] [directives] [--] [prog-name] [args] rarun2 -t shows the terminal name, say α , and wait for a connection from another process. For instance, from another terminal, you can execute rarun2 stdio=\alpha program=/bin/sh (use stdin/stdout to redirect one stream only). Run rarun2 -h to get a sample .rr2 file. rarun2 supports a lot of directives, see the man page for details.

General information

The command? prints the help. Command names are hierarchically defined; for instance, all printing commands start with p. So, to understand what a command does, you can append? to a prefix of such a command; e.g., to learn what pdf does, you can first try pd?, then the more general p?. You can get recursive help with ?*; e.g.: p?* Single-line comments can be entered using #; e.g. s # where R we?. Command? can also be used to evaluate an expression and print its result in various format; e.g. ? 5 * 8+2 (note the space after ?). Commands ?v/?vi print result only in hex/decimal. There are also some special \$-variables (list them all with: ?\$?); e.g.:

\$\$ current virtual seek

\$b block size

Where an address addx is expected, you can provide any expression that evaluates to an address, e.g. a function name or a register name. In this cheatsheet we sometimes use fn-name, instead of addx, to emphasize that the argument is supposed to be a function starting address. As default address is (usually?) used the current seek: \$\$. All commands that:

- accept an optional size (e.g. pd), use the current block size by default (see: b)
- accept an optional address (e.g., pdf), use the current position by default (see: s)

Commands can be chained by using :: e.g. s fun: pd 2.

A single command can be applied to each element of a sequence by using 00; e.g. axt 00 str.*, see 00?.

Internal grep-like filtering

You can filter command output by appending $\sim [!] str$, to display only rows [not] containing string str; e.g. pdf~rdx and pdf~!rdx. You can further filter by appending

display row r (0 < r < #rows or, backwards with: -#rows < r < -1) display columns $c_1, c_2, \dots (0 \le c_i \le \#cols)$ $[c_1[,c_2,\ldots]]$ $:r[c_1,\ldots,c_n]$ display columns c_1, \ldots, c_n of row rpipe output into less-like viewer

pipe into HUD, which filters space separated strings

Examples: afl~[0], afl~malloc[0], pdf~:2 and pdf~mov:2 There is much more (sorting, counting, ...); see: ~?

Shell interaction

Command output can be redirected to a file by appending >filename or piped to an external command with | progname [args]. Examples: afl > all functions and afl | wc -1.

External commands can be run with !!progname [args]. Note: if a command starts with a single!, the rest of the string is passed to currently loaded IO plugin (only if no plugin can handle the command, it is passed to the shell).

Moreover, backticks can be used to send the output of r2-commands as arguments; e.g. !!echo '? 42'. Vice versa output of external programs can be used as arguments for internal commands; e.g. pdf 'echo 3' @ 'echo entry0'.

Some common Unix-like commands are implemented as built-ins; e.g. ls, cd, pwd, mkdir and rm.

Radare scripting

. filename interpret r2 script filename .! command interpret output of command as r2 commands

Python scripting (via r2pipe)

You can script Radare2 with Python, by leveraging r2pipe, that can be easily installed (inside any Python 2 virtual environment) with: pip install r2pipe.

Then, you can spawn a Python interpreter, from inside r2, with: #!pipe python [python-file] or simply:

#. python-file

Once you are in Python-world, you can connect to r2 by importing r2pipe and inizializing some variable, say r2, with r2pipe.open("#!pipe"), or simply r2pipe.open().

Then you can interact with Radare by invoking method cmd; e.g. print(r2.cmd('pdf @ entry0')).

You can make most Radare2 commands output in JSON format by appending a j; e.g. pdfj (instead of pdf).

Method cmdj can de-serialize JSON output into Python objects; e.g. f = r2.cmdj('pdfj @ entry0')

print f['name'], f['addr'], f['ops'][0]['opcode']

r2pipe: connecting to other r2 instances

You can connect to any web-listening instance of r2 by passing r2pipe.open a string of the form 'http://host:port'. By using this approach you get your own seek-cursor: your seek commands won't affect others.

To open a background web-service in r2 use command =h&. You may also want to take a look at configuration variable http.sandbox.

Configuration

e?? list all variable names and descriptions e?[?] var-name show description of var-name e [var-name] show the value of all variables [var-name only] print valid values of var-name [with descript.] e var-name = ?[?]E.g. e asm.arch=?? select theme; eg. eco solarized eco theme-name list available themes eco b [size] display [set] current block size env [name [=value]] get/set environment variables

Some variables asm.pseudo enable pseudo-code syntax asm.bvtes display bytes of each instruction asm.describe show opcode description comments at right of disassembly if they fit asm.cmt.right asm.emu run ESIL emulation analysis on disasm Show demangled symbols in disasm asm.demangle bin.demangle Import demangled symbols from RBin command to run when a breakpoint is hit: cmd.bp e.g. cmd.bp=!!program command to display the stack in visual cmd.stack debug mode (Eg: px 32) continue tracing the child process on fork dbg.follow.child display func. arguments in visual mode [experimental] dbg.funcarg show stack and regs in visual mode, in a slow but dbg.slow verbose (e.g. telescoping) mode; check column mode trace program execution (check also asm.trace) dbg.trace enable cache for IO (=non-persistent write-mode) io.cache scr.utf8 show nice UTF-8 chars instead of ANSI (Windows: switch code-page with chcp 65001) show curved UTF-8 corners (requires scr.utf8) scr.utf8.curvy select seek mode; affects n/N in visual mode scr.nkey scr.breaklines break lines in Visual instead of truncating them scr.html disassembly outputs in HTML syntax

Searching: /

/ str search for string str/x hstr search for hex-string hstr assemble instruction and search for its bytes /a asm-instr /R[/] opcode find ROP gadgets [with r.e.] containing opcode; see: http://radare.today/posts/ropnroll/ find instructions of type type (/A? for the listof types) /A type

Also: e search.in=?? and e??search for options

Seeking: s

print current position/address s addxseek to addx s.. hex changes least-significant part of current address to hex seek n bytes forward/backward s+ n and s- ns++ and s-seek block-size bytes forward/backward undo seek redo seek list seek history list seek history as r2-commands s*

Writing: w

wa $asm\text{-}instr$	assemble+write opcodes; quote the whole command
	for more instructions: "wa $instr_1$; $instr_2$;"
wao	replace current instruction; see wao? for details
$w[z] \ str$	write string str [and append byte $\x00$]
wx hex-pairs	write hex-pairs
WC	list pending changes (see variable io.cache)
wtf [file] [size]	write to file
${\tt wop0}\ v$	print offset of v inside De Bruijn pattern; equiv. to
	ragg2 -q v ; to produce a pattern: ragg2 -r -P $size$

Analysis (functions and syscalls): a

aaa	analyze (aa) and auto-name functions
af1[1]	list functions [with details]
afi fn-name	show verbose info for fn-name
afn new-name addx	(re)name function at address addx
asl	list syscalls
asl $name$	display syscall-number for name
asl n	display name of syscall number n
afvd var - $name$	output r2 command for displaying the
	address and value of arg/local var-nam
.afvd var - $name$	display address and value of var-name
afvn name new-name	rename argument/local variable
afvt $name\ type$	change type for given argument/local
afv- $name$	removes variable name
$\mathtt{axt}\ addx$	find data/code references to addx
$ahi \{b d h o r S s\}$ @ $addx$	define binary/decimal/hex/octal/IP/
	syscall/string base for immediate

ESIL: ae

aeiminitialize ESIL VM stack change ESIL PC to addx (aeip sets PC to curseek) $aepc \ addr$ aer ... handle ESIL registers like dr does perform emulated debugger step [back|over] aes[b|o] $aesu \ addr$ step until given address

Graphviz/graph code: ag

 $ag \ addr$ output graphviz code (BB at addr and children) E.g. view the function graph with: ag \$\$ | xdot $agc \ addr$ callgraph of function at addx

agCfull program callgraph

Flags (AKA "bookmarks"): f

fs [name] display flagspaces [select/create fs name] push previous flagspace and set name fs+ name pop to the previous flagspace fsf list flags ${\tt f}$ name @ addxf name = addxassociate name name to address addxf- @ addxremove the association at address addxf- name remove the association with name name

Comments: C

CCu text [@ addx] set (update?) comment text at addx CC text [@ addx] append comment text at addx CC- [@ addx]remove comment at addx CC. $\begin{bmatrix} 0 & addx \end{bmatrix}$ show comment at addxCC! [@ addx] edit comment using cfg.editor (vim, ...)

Debugging: d

00 0	
?d opcode	description of opcode (eg. ?d jle)
dc	continue (or start) execution
$\mathtt{dcu}\ addx$	continue until $addx$ is reached
$\mathtt{dcs}\ [name]$	continue until the next syscall [name]
dcr	continue until ret (uses step over)
dr=	show general-purpose regs and their values
dro	show previous (old) values of registers
drr	show register references (telescoping)
dr reg-name = value	set register value
drt	list register types
$\mathtt{drt}\ type$	list registers of type type and their values
db	list breakpoints
db[-] $addx$	add [remove] breakpoint
doo $[args]$	(re)start debugging
ood	synonym for doo
ds[o]	step into [over]
dbt	display backtrace (check dbg.btdepth/btalgo)
drx	hardware breakpoints
dm	list memory maps; the asterisk shows where
	the current offset is
dmh	show heap allocation (see: dmh?)
dmm	list modules (libraries, loaded binaries)
$\mathtt{dmi}\;[addr lib]\;[sym]$	list symbols of target lib
dmp	change page permissions (see: dmp?)
dt[d]	list all traces [disassembled]
.	

Types: t

"td C-type-def" t t-name .t t-name @ addx te / ts / tu to filetl t-name t1 t-name = addxtl tp t-name = addx

define a new type show type t-name in pf syntax display the value (of type t-name) at addxlist (base?) types list enums/structs/unions parse type information from C header file link t-name to current address link t-name to address addx list all links in readable format cast data at addx to type t-name, and prints it

Printing: p

ps [@ *addx*] pxr[n] [@ addx]px [n] [@ addx] $px\{h|w|q\} \dots$ $px\{H|W|Q\}$... pxl[n][@addx]px/fmt [@ addx] pd[n][@addx]p8 [n] [@ addx] pD [n] [@ addx] pd - n [@ addx]pdf [@ fn-name] pc[p][n][@addx]* addx [=value]pf $fmt \ a_1[, a_2, \ldots]$

print C-string at addx (or current position) print with references to flags/code (telescoping) hexdump — note: x is an alias for px hexdump in 16/32/64 bit words as the previous one, but one per line display n rows of hexdump gdb-style printing fmt (in gdb see: help x from r2: !!gdb -q -ex 'help x' -ex quit) disassemble n instructions print bytes disassemble n bytes disassemble n instructions backwards disassemble function fn-name dumps in C [Python] format shortcut for reading/writing at addx formatted print, see pf?? and pf???

Information: i (and S)

i $iz[z]$	show info of current file strings in data sections [whole binary]
i{e i 1 S}	entrypoint/imports/libraries/sections
S	list segments (confusingly called sections?!?)

Visual mode: V (q exits)

Command V enters visual mode. exit visual-mode cursor-mode, tab switches among panels С +/- increment/decrement current byte execute a normal-mode command; e.g. :dm rotate forward/backward print modes p and P highlight occurrences of string str/str \$ toggle pseudo-syntax toggle ESIL-asm add/remove comments (to current offset) browse xrefs-to current offset X browse xrefs-from current function browse flags define function, end-function, rename, ... $di\{b|o|d|h|s\}$ define immediate bin/oct/dec/hex or str enter block-graph viewer (space toggles visual/graph) Α enter visual-assembler (preview must be confirmed) n / Nseek next/previous function/flag/hit (see scr.nkey) i enter insert mode configures internal variables toggle the column mode

Seeking (in Visual Mode)

•	seeks to program counter
Enter	on jump/call instructions, follow target address
u / U	undo / redo
0	go/seek to given offset
0 (zero)	seek to beginning of current function
d (a non-zero digit)	jump to the target marked [d]
ml (a letter)	mark the spot with letter l
,1	jump to mark l
n / N	jump to next/previous function

Debugging (in Visual Mode)

B (b in older versions) or F2 toggle breakpoint F4 run to cursor s or F7 step-into S or F8 step-over continue

Projects: P [unstable feature]

Pl	list all projects
$P\{o s d\}$ [prj-name]	open/save/delete project prj-name
Pc prj - $name$	show project script to console

Copyright ©2017 by zxgio; cheat-sheet built on April 3, 2018 This cheat-sheet may be freely distributed under the terms of the GNU General Public License: the latest version can be found at: https://github.com/zxgio/r2-cheatsheet/