Reversing with Radare2

Starting Radare

The basic usage is radare2 exe (on some systems you can use simply r2 instead of radare2). If there exists a script named exe.r2, then it gets executed after the others rc-files. If you want to run radare2 without opening any file, you can use -- instead of an executable

Some command-line options are:

-d file debug executable file -d piddebug process pid

-A analyze all referenced code (aaa command)

-r profile.rr2 specifies rarun2 profile (same as -e dbg.profile=profile.rr2)

open file in write mode list projects / use project pri -p [*prj*]

show help message (-hh the verbose one)

Example: r2 -dA /bin/ls

Running in different environments: rarun2

rarun2 runs programs with different environments, arguments, permissions, directories and overridden default file-descriptors. Usage: rarun2 [-t|script-name.rr2] [directives] [--] [prog-name] [args] rarun2 -t shows the terminal name, say α , and wait for a connection from another process. For instance, from another terminal, you can execute rarun2 stdio=\alpha program=/bin/sh (use stdin/stdout to redirect one stream only). Run rarun2 -h to get a sample .rr2 file. rarun2 supports a lot of directives, see the man page for details.

General information

The command? prints the help. Command names are hierarchically defined; for instance, all printing commands start with p. So, to understand what a command does, you can append? to a prefix of such a command; e.g., to learn what pdf does, you can first try pd?, then the more general p?. You can get recursive help with ?*; e.g.: p?* Single-line comments can be entered using #; e.g. s # where R we?. Command? can also be used to evaluate an expression and print its result in various format; e.g. ? 5 * 8+2 (note the space after ?). Commands ?v/?vi print result only in hex/decimal. There are also some special \$-variables (list them all with: ?\$?); e.g.:

\$\$ current virtual seek

\$b block size

Where an address addx is expected, you can provide any expression that evaluates to an address, e.g. a function name or a register name. In this cheatsheet we sometimes use fn-name, instead of addx, to emphasize that the argument is supposed to be a function starting address. As default address is (usually?) used the current seek: \$\$. All commands that:

- accept an optional size (e.g. pd), use the current block size by default (see: b)
- accept an optional address (e.g., pdf), use the current position by default (see: s)

Commands can be chained by using :: e.g. s fun: pd 2.

A single command can be applied to each element of a sequence by using 00; e.g. axt 00 str.*, see 00?.

Internal grep-like filtering

You can filter command output by appending $\sim [!] str$, to display only rows [not] containing string str; e.g. pdf~rdx and pdf~!rdx. You can further filter by appending

display row r (0 < r < #rows or, backwards with: -#rows < r < -1)

display columns $c_1, c_2, \dots (0 \le c_i \le \#cols)$ $[c_1[,c_2,\ldots]]$ display columns c_1, \ldots, c_n of row r

 $:r[c_1,\ldots,c_n]$ pipe output into less-like viewer

pipe into HUD, which filters space separated strings

Examples: afl~[0], afl~malloc[0], pdf~:2 and pdf~mov:2

There is much more (sorting, counting, ...); see: ~?

Shell interaction

Command output can be redirected to a file by appending >filename or piped to an external command with | progname [args]. Examples: afl > all functions and afl | wc -1.

External commands can be run with !!progname [args]. Note: if a command starts with a single!, the rest of the string is passed to currently loaded IO plugin (only if no plugin can handle the command, it is passed to the shell).

Moreover, backticks can be used to send the output of r2-commands as arguments; e.g. !!echo '? 42'. Vice versa output of external programs can be used as arguments for internal commands; e.g. pdf 'echo 3' @ 'echo entry0'.

Some common Unix-like commands are implemented as built-ins; e.g. ls, cd, pwd, mkdir and rm.

Radare scripting

. filename interpret r2 script filename

.! command interpret output of command as r2 commands

Python scripting (via r2pipe)

You can script Radare2 with Python, by leveraging r2pipe, that can be easily installed (inside any Python 2 virtual environment) with: pip install r2pipe.

Then, you can spawn a Python interpreter, from inside r2, with: #!pipe python [python-file]

or simply:

#. python-file

Once you are in Python-world, you can connect to r2 by importing r2pipe and inizializing some variable, say r2, with r2pipe.open("#!pipe"), or simply r2pipe.open().

Then you can interact with Radare by invoking method cmd; e.g. print(r2.cmd('pdf @ entry0')).

You can make most Radare2 commands output in JSON format by appending a j; e.g. pdfj (instead of pdf).

Method cmdj can de-serialize JSON output into Python objects; e.g. f = r2.cmdj('pdfj @ entry0')

print f['name'], f['addr'], f['ops'][0]['opcode']

r2pipe: connecting to other r2 instances

You can connect to any web-listening instance of r2 by passing r2pipe.open a string of the form 'http://host:port'. By using this approach you get your own seek-cursor: your seek commands won't affect others.

To open a background web-service in r2 use command =h&. You may also want to take a look at configuration variable http.sandbox.

Configuration

list all variable names and descriptions e?[?] var-name show description of var-name e var-name show the value of var-name e var-name = ?[?]print valid values of var-name [with descript.] E.g. e asm.arch=?? show the value of all variables select theme; eg. eco solarized eco theme-name 900 list available themes b [size] display [set] current block size

env [name [=value]] get/set environment variables Some variables asm.pseudo enable pseudo-code syntax asm.bytes display bytes of each instruction show opcode description asm.describe asm.cmtright comments at right of disassembly if they fit run ESIL emulation analysis on disasm asm.demangle Show demangled symbols in disasm bin.demangle Import demangled symbols from RBin command to run when a breakpoint is hit; cmd.bp e.g. cmd.bp=!!program command to display the stack in visual cmd.stack debug mode (Eg: px 32) dbg.follow.child continue tracing the child process on fork show stack and regs in visual mode, in a slow but dbg.slow verbose (e.g. telescoping) mode enable cache for IO (=non-persistent write-mode) io.cache show nice UTF-8 chars instead of ANSI scr.utf8 (Windows: switch code-page with chcp 65001) show curved UTF-8 corners (requires scr.utf8) scr.utf8.curvy scr.nkey select seek mode (fun, hit, flag); affects commands n and N during visual mode scr.wheel enables mouse-wheel in visual mode break lines in Visual instead of truncating them scr.breaklines

Searching: /

/ str search for string str/x hstr search for hex-string hstr assemble instruction and search for its bytes /a asm-instr /R[/] opcode find ROP gadgets [with r.e.] containing opcode; see: http://radare.today/posts/ropnroll/ find instructions of type type (/A? for the listof types) /A type

Also: e??search for options

Seeking: s

print current position/address s addxseek to addx s.. hex changes least-significant part of current address to hex seek n bytes forward/backward s+ n and s- ns++ and s-seek block-size bytes forward/backward undo seek redo seek list seek history list seek history as r2-commands s*

Writing: w

Analysis (functions and syscalls): a

analyze (aa) and auto-name functions af1[1] list functions [with details] afi fn-name show verbose info for fn-name (re)name function at address addx afn new-name addx asl list syscalls display syscall-number for nameasl name display name of syscall number n $\mathtt{asl}\ n$ output r2 command for displaying the afvd var-name address and value of arg/local var-name display address and value of var-name .afvd var-name afvn name new-name rename argument/local variable change type for given argument/local afvt name type afv- name removes variable name axt addxfind data/code references to addx ahi $\{b|d|h|o|r|S|s\}$ @ addxdefine binary/decimal/hex/octal/IP/ syscall/string base for immediate

ESIL: ae

aeim initialize ESIL VM stack
aepc addr change ESIL PC to addx (aeip sets PC to curseek)
aer ... handle ESIL registers like dr does
aes[b|o] perform emulated debugger step [back|over]aesu addr step until given address

Graphviz/graph code: ag

 $\begin{array}{lll} \text{ag } addr & \text{output graphviz code (BB at } addr \text{ and children)} \\ & \text{E.g. view the function graph with: ag $\$ \mid xdot - \\ \text{agc } addr & \text{callgraph of function at } addx \\ \text{agC} & \text{full program callgraph} \end{array}$

Flags (AKA "bookmarks"): f

fs [name] display flagspaces [select/create fs name]
fs+ name push previous flagspace and set name
fs- pop to the previous flagspace
f list flags
f name @ addx or
f name = addx
f- @ addx
f- name
display flagspaces [select/create fs name]
push previous flagspace and set name
flagspace
f list flags
or
associate name name to address addx
remove the association at address addx
f- name
frame

Comments: C

CCu $text \ [@ \ addx]$ set (update?) comment text at addx append comment text at addx ccc- $[@ \ addx]$ remove comment at addx ccc. $[@ \ addx]$ show comment at addx ccc! $[@ \ addx]$ edit comment using cfg.editor (vim, ...)

Debugging: d

?d opcode description of opcode (eg. ?d jle) dc continue (or start) execution dcu addxcontinue until addx is reached continue until the next syscall [name] dcs [name] continue until ret (uses step over) show general-purpose regs and their values dr= show previous (old) values of registers dro show register references (telescoping) drr set register value dr reg-name = value list register types drt list registers of type type and their values drt type list breakpoints db add [remove] breakpoint db[-] addx (re)start debugging doo [arqs] synonym for doo ood step into [over] ds[o] display backtrace (check dbg.btdepth/btalgo) dbt hardware breakpoints drx list memory maps; the asterisk shows where dmthe current offset is list modules (libraries, loaded binaries) dmi [addr|lib] [sym]list symbols of target lib change page permissions (see: dmp?)

Types: t

"td C-type-def" define a new type t t-name show type *t-name* in pf syntax display the value (of type t-name) at addx.t t-name @ addx list (base?) types te / ts / tu list enums/structs/unions to file parse type information from C header file tl t-name link t-name to current address t1 t-name = addxlink t-name to address addxt.1 list all links in readable format tp t-name = addxcast data at addx to type t-name, and prints it

Printing: p

ps [@ *addx*] print C-string at addx (or current position) pxr[n] [@ addx]print with references to flags/code (telescoping) px [n] [@ addx]hexdump — note: x is an alias for px hexdump in 16/32/64 bit words $px\{h|w|q\} \dots$ $px\{H|W|Q\}$... as the previous one, but one per line display n rows of hexdump pxl[n][@addx]px/fmt [@ addx] gdb-style printing fmt (in gdb see: help x from r2: !!gdb -q -ex 'help x' -ex quit) pd[n][@addx]disassemble n instructions p8 [n] [@ addx] print bytes disassemble n bytes pD [n] [@ addx] pd - n [@ addx]disassemble n instructions backwards disassemble function fn-name pdf [@ fn-name] pc[p][n][@addx]dumps in C [Python] format * addx [=value] shortcut for reading/writing at addx pf $fmt \ a_1[, a_2, \ldots]$ formatted print, see pf?? and pf???

Information: i (and S)

 $\begin{array}{ll} \textbf{i} & \text{show info of current file} \\ \textbf{iz[z]} & \text{strings in data sections [whole binary]} \\ \textbf{i}\{\textbf{e}|\textbf{i}|\textbf{1}|\textbf{S}\} & \text{entrypoint/imports/libraries/sections} \\ \textbf{S} & \text{list segments (confusingly called sections?!?)} \\ \end{array}$

Visual mode: V (q exits) Command V enters visual mode. exit visual-mode cursor-mode, tab switches among panels С +/- increment/decrement current byte execute a normal-mode command; e.g. :dm rotate forward/backward print modes p and P highlight occurrences of string str/str toggle pseudo-syntax \$ 0 toggle ESIL-asm add/remove comments (to current offset) browse xrefs-to current offset browse xrefs-from current function browse flags define function, end-function, rename, ... $di\{b|o|d|h|s\}$ define immediate bin/oct/dec/hex or str enter block-graph viewer (space toggles visual/graph) enter visual-assembler (preview must be confirmed) seek next/previous function/flag/hit (see scr.nkey) n / Ni enter insert mode configures internal variables toggle the column mode

Seeking (in Visual Mode)

seeks to program counter Enteron jump/call instructions, follow target address u / U undo / redo go/seek to given offset seek to beginning of current function 0 (*zero*) jump to the target marked [d] d (a non-zero digit) mark the spot with letter lml (a letter) , 1 iump to mark ln / N jump to next/previous function

Debugging (in Visual Mode)

 $\begin{array}{lll} b \ or \ F2 & toggle \ breakpoint \\ F4 & run \ to \ cursor \\ s \ or \ F7 & step-into \\ S \ or \ F8 & step-over \\ F9 & continue \end{array}$

Projects: P [unstable feature]

 $\begin{array}{ll} \texttt{P1} & \text{list all projects} \\ \texttt{P\{o|s|d\}} \; [\textit{prj-name}] & \text{open/save/delete project } \textit{prj-name} \\ \texttt{Pc} \; \textit{prj-name} & \text{show project script to console} \end{array}$

Copyright ©2017 by zxgio; cheat-sheet built on November 2, 2017 This cheat-sheet may be freely distributed under the terms of the GNU General Public License; the latest version can be found at: https://github.com/zxgio/r2-cheatsheet/