Be Careful Using Chars

Ashwin Menon

December 15, 2024

You might think that the *char* would be the perfect data type to represent byte sized variables, especially in an embedded system where storage space is at a premium. However, there are serious pitfalls with this, not least of which is the fact that it is implementation defined whether a *char* is a signed or an unsigned value. Consider this:

```
char c = 255; // Is c signed or unsigned?
int i = c; // Is i -1 or 255?
```

The moment you try to store the *char* in a larger numeric value, then the larger value becomes implementation defined. You might think you could get around this by using *unsigned char* or *signed char* variables to make the signedness explicit, and therefore under your control. But that has pitfalls as well. Consider this:

```
char ch;
signed char schar;
unsigned char uchar;

char *p_char = &uchar;
signed char *p_schar = p_char; // error
unsigned char *p_uchar = p_char; // error
p_schar = p_uchar; // error
// error
```

All four pointer assignments are illegal in C++ and will be flagged as invalid conversions. This makes it a problem when you try to pass a *signed char* or an *unsigned char* pointer to any of the standard library string functions, all of which take *char** arguments. Consider:

```
const char *str = "hello";
const signed char *s_str = "goodbye"; // error
const unsigned char *u_str = "ringo"; // error

int i = strlen(str);
int j = strlen(s_str); // error
int k = strlen(u_str); // error
```

The second and third string assignments are errors, because you can't convert a $char^*$ to a $signed\ char^*$ or an $unsigned\ char^*$. For the same reason (working in reverse), the second and third calls to strlen are errors, since strlen only accepts $char^*$ arguments.

You can avoid all this bother by simply using char everywhere instead of the signed or unsigned variant, and by also making sure that you never store negative or too large values in these char's. This makes it perfectly fine to use char's to store ASCII strings, since ASCII characters use only the lower 127 values, and therefore can never be sign extended to negative values.

If you want to store 8-bit numeric values that don't represent ASCII characters (i.e. they really are numbers) then use one of the standard integer types, like $uint8_t$ or $int8_t$.