

PI JDBC 2012 Administrator Guide

OSIsoft, LLC

777 Davis St., Suite 250 San Leandro, CA 94577 USA

Tel: (01) 510-297-5800 Fax: (01) 510-357-8136 Web: http://www.osisoft.com

OSIsoft Australia • Perth, Australia

OSIsoft Europe GmbH • Frankfurt, Germany

OSIsoft Asia Pte Ltd. • Singapore

OSIsoft Canada ULC • Montreal & Calgary, Canada

OSIsoft, LLC Representative Office • Shanghai, People's Republic of China

OSIsoft Japan KK • Tokyo, Japan

OSIsoft Mexico S. De R.L. De C.V. • Mexico City, Mexico

OSIsoft do Brasil Sistemas Ltda. • Sao Paulo, Brazil

OSIsoft France EURL • Paris, France

PI JDBC 2012 Administrator Guide

Copyright: © 2009-2013 OSIsoft, LLC. All rights reserved.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, mechanical, photocopying, recording, or otherwise, without the prior written permission of OSIsoft, LLC.

OSIsoft, the OSIsoft logo and logotype, PI Analytics, PI ProcessBook, PI DataLink, ProcessPoint, PI Asset Framework (PI AF), IT Monitor, MCN Health Monitor, PI System, PI ActiveView, PI ACE, PI AlarmView, PI BatchView, PI Coresight, PI Data Services, PI Event Frames, PI Manual Logger, PI ProfileView, PI WebParts, ProTRAQ, RLINK, RtAnalytics, RtBaseline, RtPortal, RtPM, RtReports and RtWebParts are all trademarks of OSIsoft, LLC. All other trademarks or trade names used herein are the property of their respective owners.

U.S. GOVERNMENT RIGHTS

Use, duplication or disclosure by the U.S. Government is subject to restrictions set forth in the OSIsoft, LLC license agreement and as provided in DFARS 227.7202, DFARS 252.227-7013, FAR 12.212, FAR 52.227, as applicable. OSIsoft, LLC.

Version: 1.3.0.0251 Published: 2/27/2013

Table of Contents

Chapte	er 1 Introduction	1
	In this Guide	1
	About the OSIsoft PI Data Access Suite	2
	Architecture	2
	Deployment Options	3
Chapte	er 2 Installation	5
	Installation Components	5
	System Requirements	5
	Install PI SQL Data Access Server	6
	Install PI JDBC Driver on Windows	11
	Install PI JDBC Driver on Linux	15
Chapte	er 3 Using PI JDBC	19
	Configuration	19
	Functionality	22
	Use Cases	
	PI JDBC Driver Limitations	27
Chapte	er 4 Troubleshooting	29
	Run PI SQL DAS Interactively	29
	Connection Messages and Errors	29
	Verify Java Version	32
	OpenSSL Library	32
Appen	ndix A Tested PI JDBC Scenarios	37
Appen	ndix B Technical Support and Resources	39
Index .		41

Chapter 1

Introduction

PI JDBC Driver is a JDBC 4.0 compliant driver that provides robust data access to the PI System through SQL queries. PI JDBC Driver offers much of the same functionality as the PI OLEDB Enterprise Provider, and is also backward compatible with the behavior of the classic PI OLEDB Provider.

Java is a programming language that allows you to create platform independent software. This platform independence is made possible by the Java Runtime Environment (JRE), which handles Java code and makes it available to run on most operating systems. Typically, you would select a Java programming environment when there is a demand to run software in both Linux and Windows.

Java Database Connectivity (JDBC) is an API that is built into every JRE and defines how a client can access a database. For relational database access, Java applications should use JDBC.

This version of PI JDBC is intended for use with Java applications and middleware, but is not meant for installation on many end-user computers. PI OLEDB and PI OLEDB Enterprise, although multithreaded, were not designed as server back ends and will only perform with a limited amount of parallel connections.

Later versions of PI JDBC will allow for scaling up to many concurrent user connections. PI JDBC will then migrate to a type 3 JDBC driver. See *PI JDBC Driver Limitations* (page 27) for information about other limitations.

PI JDBC Driver is a member of the PI Data Access product suite (page 2).

In this Guide

This guide includes procedures to install and configure PI JDBC Driver and PI SQL Data Access Server on Windows and Linux operating systems. It also provides information about how to use and troubleshoot PI JDBC Driver.

Users of this guide should be familiar with:

- Java
- JDBC technologies
- PI OLEDB and PI OLEDB Enterprise

About the OSIsoft PI Data Access Suite

The OSIsoft PI Data Access product suite is designed to support implementation of custom applications on top of the PI System, as well as integration of PI System data with other applications and business systems such as Microsoft Office or SQL Server, Enterprise Resource Planning systems (ERPs), Web portals, and maintenance systems, just to name a few.

The PI Data Access suite of products covers a wide range of use cases in various environments, programming languages, operating systems and infrastructures. Products include:

- SQL-based data access (PI OLEDB Provider, PI OLEDB Enterprise, PI JDBC Driver)
- OPC specifications (PI OPC DA/HDA Server)
- Service-oriented architecture (PI Web Services)
- Programmatic access (PI SDK and AF SDK)

Licensing for the PI Data Access products is divided into development and runtime licenses. Developers and integrators obtain development licenses for most PI Data Access components through their individual membership to the OSIsoft Virtual Campus (*vCampus* (*http://vCampus.osisoft.com*)) program. For details, see the OSIsoft vCampus *Frequently Asked Questions http://vCampus.osisoft.com/content/FAQ.aspx*.

The PI System Access (PSA) license enables end users to access PI System data, including time-series data in PI Servers and asset metadata in AF Servers. PSA is a runtime license to access PI System data using any of the programmatic access methods licensed through the PSA, including PI Web Services. For more information, see the *OSIsoft Web site* (http://www.osisoft.com) or contact *OSIsoft Technical Support* (page 39).

Architecture


The PI JDBC driver is an implementation of the JDBC standard based on the JDBC 4.0 API (Java Platform SE 6). PI JDBC is a type 1 JDBC driver (bridge) that employs the PI OLEDB Enterprise and PI OLEDB query engines to connect to the PI System and execute queries.

Note: For more information, see *Types of JDBC technology drivers* (http://www.oracle.com/technetwork/java/overview-141217.html) on the Oracle Technology Network Web site.

Communication from PI JDBC to the PI System requires using the PI SQL Data Access Server (PI SQL DAS). PI SQL DAS serves as a gateway between PI JDBC and PI OLEDB Enterprise/PI OLEDB. It provides secure network communication through HTTPS to PI JDBC and executes queries as an OLE DB client, also known as the consumer.



PI OLEDB Enterprise/PI OLEDB and PI SQL DAS run on Windows whereas PI JDBC is supported on Windows and Linux operating systems.



Deployment Options


PI JDBC can be deployed in various combinations. PI JDBC and PI SQL DAS can run on different architectures (32-bit or 64-bit). In addition, PI JDBC can run on Linux or Windows. For combinations tested, see *Tested PI JDBC Scenarios* (page 37).

The resulting combinations can be categorized as *standalone* (page 4) and *middleware* (page 4) scenarios.

Note: For best performance, OSIsoft recommends that you use 64-bit operating systems whenever possible. The PI SQL DAS will especially benefit from running on a 64-bit Windows.

Multiple standalone and middleware configurations can be used as needed. This is useful if performance of one application should not be influenced by queries of another one.

Standalone Deployment



Notes

- All products installed on one machine
- Windows only
- Supports standalone Java applications

Use the standalone deployment if a single Java application needs to be supported with maximum performance.

Middleware Deployment



Notes

- PLIDBC on clients, other products on server
- Windows or Linux
- Support for Java server applications, limited number of clients

Middleware deployment takes advantage cross-platform support, for example, when supporting Java applications on Linux.



Chapter 2

Installation

Installation Components

The PI JDBC setup kits are distributed as four self-extracting executables and one compressed tar archive. PI JDBC consists of these components:

- PI SQL Data Access Server is the gateway between PI JDBC driver and PI OLEDB Enterprise/PI OLEDB providers.
- PI JDBC driver on Windows is the JDBC client for Windows operating systems.
- PI JDBC driver on Linux is the JDBC client for Linux operating systems.

Note: The setup kits for each of these components include both 32- and 64-bit versions.

System Requirements

PI SQL DAS requires:

- Windows XP or later
- .NET 4.0
- PI OLEDB
- PI OLEDB Enterprise

PI JDBC driver on Windows requires:

- Windows XP or later
- Java Runtime (JRE) 1.6.0.0 or higher

PI JDBC driver on Linux requires:

- Java Runtime (JRE) 1.6.0.0 or higher
- OpenSSL 0.9.8 or OpenSSL 1.0.0

Further dependencies are based on the OpenSSL version being used:

- OpenSSL 0.9.8
 - o libstdc++ 4.2, including GLIBCXX_3.4.9 (standard GNU C++ shared library)
 - o glibc 2.4 (standard GNU C shared library)
 - o libgcc 4.1.2 (standard GNU C Compiler runtime library)

- OpenSSL 1.0.0
 - o glibc 2.11

Note: The required Linux libraries are optional components and may need to be enabled or updated depending on the Linux distribution you are using. For additional information, see *OpenSSL Library* (page 32).

For further details about the PI JDBC release you are using, see the PI JDBC 2012 Release Notes.

Install PI SQL Data Access Server

To install PI SQL Data Access Server:


- 1. Select either the *standalone* (page 4) or *middleware* (page 4) deployment option.
- 2. Verify whether the computer you will use meets the *System Requirements* (page 5).
- 3. Install the *OSIsoft Prerequisites Kit* (http://techsupport.osisoft.com/Products/Prerequisite+Kits/Prerequisite+Kits+Overview. htm), available at the OSIsoft Technical Support Web site.
- 4. Run the PI SQL DAS setup kit (page 6).

Run the PI SQL DAS Setup Kit

Note: The installation must be run from an account that has administrative privileges.

Run the setup kit: pisqldas_1.3.0.xxxx.exe where

• xxxx is the build number






Note: The installation of 32-bit and 64-bit versions of PI SQL DAS on the same machine is not supported. When you run the installation on a 64-bit Windows operating system, the 64-bit version of PI SQL DAS is automatically selected.

Files

The list of files installed is provided in the release notes document PI JDBC 2012 Release Notes.pdf.

Installation Result

Files are installed in the [PIHOME]\SQLDAS directory. The Windows Service **PI SQL Data Access Server** gets registered with startup type **Automatic**, and is started.



The PI SQL Data Access Server is automatically configured to use a SELF-SIGNED certificate, bound to port **5461**. If your IT policies allow working with SELF-SIGNED certificates then the installation procedure is complete and you can skip the optional *configuration of PI SQL Data Access Server* (page 7).

Configure PI SQL Data Access Server (optional)

PI SQL Data Access Server is a self-hosted Windows Communication Foundation (WCF) service that uses HTTP transport and SSL security. As a result, a port is bound with an X.509 certificate.

Secure Sockets Layer (SSL) uses certificates on the client and server to store encryption keys. The server provides its SSL certificate when a connection is made so that the client can verify the identity of the server. The server can also request a certificate from the client to provide

mutual authentication of both sides of the connection, but this mechanism is currently not used for PI SQL DAS.

Certificates are stored in a centralized store according to the IP address and port number of the connection. The special IP address **0.0.0.0** matches any IP address for the local machine. You must have administrative privileges to modify the certificates stored on the computer.


If you are required to use enterprise-type security certificates, use the information here to configure an enterprise certificate for PI SQL DAS and bind it to the port used by PI SQL DAS.

Configuration Tool

Use the **pisqldasAutoConfig.exe** configuration tool for all basic configurations of PI SQL DAS. The tool is located in the [PIHOME]\SQLDAS directory, where [PIHOME] is your PIPC installation directory.

If your IT policies require that you use enterprise type certificates, you can use the tool to configure an enterprise certificate for PI SQL DAS and bind it to the port used by PI SQL DAS.

- In a command prompt, run the tool with parameter -e. For example:
 C:\PIPC\SQLDAS>pisqldasAutoConfig.exe -e
- 2. Optionally, select a certificate from the Certificates dialog. The **Intended Purposes** column must include at least **Client Authentication and Server Authentication**:



Note: Enterprise certificates are typically already installed on your computer if it is part of a domain. You should see your organization's name in the **Issued by** column. The certificate named PISQLDAS is the SELF-SIGNED certificate used by default.

3. Click OK.



4. This output indicates that the selected certificate has been bound to the SSL port:

```
C:\PIPC\SQLDAS>pisqldasAutoConfig.exe -e Found existing binding .....deleted Create new SSL binding .....OK
Updating config file .....OK
```

In this example, the tool has configured the selected certificate to be used by PI SQL DAS and bound this certificate to IP address/port **0.0.0.0:5461**.

5. Restart the PI SQL Data Access Server service to use the new configuration.

SSL Port

The port used for PI SQL Data Access Server HTTPS communication is 5461.

The *configuration tool* (page 8) allows communication from any IP address. To further restrict the port you can use operating system tools for this purpose. For details, see the Microsoft Windows documentation on *HttpCfg.exe http://msdn.microsoft.com/en-us/library/bb736546(VS.85).aspx*, *Netsh.exe http://msdn.microsoft.com/en-us/library/bb736546(VS.85).aspx*, or Windows integrated firewall.

You may also have 3rd party Firewall or Virus Scanner tools that can restrict communication through port **5461**.

PI Server Login through PI SQL DAS

For the PI Server login, OSIsoft recommends that you use Integrated Security (SSPI) configuration. The PI SQL Data Access Server will log into the PI Server with the user credentials of its client, that is, the PI JDBC driver connection.


The Windows user of the PI SQL DAS login must have a trust configured on the PI Server or have a PI Server identity mapping configured on the PI Server (available in PI Server 3.4.380 or later). See *Configuring PI Server Security* for details about how to configure trusts.

For example, use these properties to configure a trust for Windows user MyDomain\User1:

Trust Name: PISQLDAS **Network Path:** pisqldas64

Domain: MyDomain

Account: User1




To map a PI Server Identity for Windows user MyDomain\User1:

Name: User1Map

Windows Account: MyDomain\User1

Identity: piadmin



In PI JDBC, the authentication information is configured in the JDBC connection string. For details, see *Using PI JDBC* (page 19). The **getSnap** test application is configured to use the trust mechanism.



Remove PI SQL DAS

To remove the PI SQL Data Access Server, use Windows Control Panel or re-run the setup kit. The **Remove** option automatically stops and deletes the PI SQL DAS service and uninstalls all files:



The SELF-SIGNED certificate and the SSL port binding are removed when PI SQL DAS is uninstalled.

Install PI JDBC Driver on Windows

- 1. Run the PI JDBC driver setup kit (page 11).
- 2. To validate the installation results, review the *files installed* (page 11) and the *system environment variables* (page 11).
- 3. Verify the installation (page 12) using sample the Java application getSnap.

Run the PI JDBC Driver Setup Kit

To start the PI JDBC Installation Wizard, run PI JDBC_2012_.exe.

Files Installed

After you run the *PI JDBC Driver setup kit* (page 11), you can view the files installed in the [PIHOME]\JDBC directory. The complete list of files is provided in the PI JDBC 2012 Release Notes.

Installation Results

- 1. *Files* (page 11) are installed into the [PIHOME]\JDBC directory.
- 2. The following system environment variables are automatically added/updated:

```
PI_RDSA_LIB=[PIHOME]\JDBC\RDSAWrapper.dll
PI_RDSA_LIB64=[PIHOME]\JDBC\RDSAWrapper64.dll(64-bit only)
CLASSPATH=[PIHOME]\JDBC\PIJDBCDriver.jar;.
```

[PIHOME] is replaced by the value of the PIHOME directory.

Note: The CLASSPATH environment variable is a standard mechanism in Java to easily launch an application without having to specify the path separately. If the CLASSPATH already existed, the PI JDBC installation appends the name and location of the PI JDBC driver plus a dot (.) which denotes the *current directory*.

Verify the PI JDBC Installation

PI JDBC ships with a sample command line application called **getSnap** to validate successful installation and communication with a PI Server. There is also a sample command line application called **getEASnap** to validate successful communication with the PI Asset Framework (AF).

Refer to the information here to run these applications.

getSnap

The **getSnap** test application is located in the Samples directory of the PI JDBC installation. To open it, use a command prompt window:

- 1. Change to the directory <PIHOME>\PIPC\JDBC\Samples\getSnap\bin
- 2. Enter these three parameters:
- PI SQL DAS name
- PI Server name
- PI tag name or tag name wildcard (SQL Syntax)

For example, if you enter:

```
<PIHOME>\JDBC\Samples\getSnap\bin>java getSnap PISQLDAS01 PIServer01 sin%
```

You should see results in the form of PI data values such as:

```
SINUSOID 79.11583
SINUSOID.Fast 95.47511
SINUSOID_Alert 18.164595
SINUSOID_Fast 95.47511
SINUSOIDU 29.995642
```



Note: On first use you will see the security login (page 14) dialog.

getEASnap

The **getEASnap** test application is located in a Samples directory where PI JDBC is installed.

1. To open **getEASnap**, use a command prompt window and change to the directory:

```
<PIHOME>\PIPC\JDBC\Samples\getEASnap\bin
```

2. Enter these four parameters:

```
PI SQL DAS name
AF Server name
AF Database name
Element name
```

Note: This example assumes that the NuGreen test database, which is shipped with PI OLEDB Enterprise, is loaded.

For example, if you enter:

```
C:\PIPC\JDBC\Samples\getEASnap\bin>java getEASnap PISQLDAS01 AFServer01 NuGreen B-210
```

You should see output such as shown here:

```
Administrator: C:\Windows\system32\cmd.exe
                                                                               _ | _ | × |
C:\Program Files\PIPC\JDBC\Samples\getEASnap\bin>ja∪a getEASnap FRADEU-T3-DAS1
RADEV-T2-AF25 NuGreen B-210
com.osisoft.jdbc.Driver 1.3.0.0251
PI SQL DataAccessServer using PIOLEDBENT
PIOLEDBENT: 1.3.1.5
          Asset Name
                      High Pressure
              Burner
                      TZ-14
        Feedrate Tag
                      SINUSOID
                Fueī
                      1000
       Fuel Gas Flow
                      89.49614715576172
  Fuel Gas Flow Tag
Fuel Savings
                      SINUSOID
                      48.95354772843288
          Fuel(2007)
                      1959
          FuelTarget
                      1919.82
                      16-May-1985 06:00:00
   Installation Date
   Make-Up Water Tag
                      SINUSOID
        Manufacturer
                      Borne Engineering
               Model
                      BX-414
               Plant
                      Houston
             Process
                      Cracking Plant
    Process Feedrate
                      89.49614715576172
               Water
                      1000
                      89.49614715576172
          Water Flow
                      -1920.20202020202
       Water Savings
                      49.5
         Water(2007)
         WaterTarget
                      48.51
:\Program Files\PIPC\JDBC\Samples\getEASnap\bin>_
```

Note: On first use you will see the security login (page 14) dialog.

Security

Two logins are required to connect to the PI Server through PI SQL DAS:

- A login (page 14) to the PI SQL Data Access Server
- A *login* (page 14) to the PI Server

Connect with PI SQL Data Access Server

The JDBC login mechanism is used to connect with the PI SQL Data Access Server.

After you install PI JDBC and attempt the first connection with PI SQL Data Access Server, use the login dialog to:

1. Provide valid Windows user login information for the machine that runs PI SQL DAS:



- 2. To store the login credentials, select **Save and Reuse Authentication**. Login information is stored in an encrypted file in your home directory (%USERPROFILE%). The filename consists of your PI SQL DAS server name suffixed by .dca. For example, win2008test1.dca. Subsequent logins of the same user automatically refer to that file until it is manually deleted.
- 3. Click **OK**.

PI Server Login

For the PI Server login, OSIsoft recommends that you use Integrated Security (SSPI) configuration. For complete details, see *Configuring PI Server Security*, available at the *OSIsoft Technical Support Web site* (http://techsupport.osisoft.com).

In PI JDBC, the authentication information is configured in the JDBC connection string. For details, see *Using PI JDBC* (page 19). The getSnap test application is configured to use the trust mechanism.



Remove PI JDBC

To remove PI JDBC on Windows, use Windows Control Panel or re-run the setup kit.

Install PI JDBC Driver on Linux

To install PI JDBC driver on Linux operating systems:

- 1. Select either the *standalone* (page 4) or *middleware* (page 4) deployment option.
- 2. Verify whether the computer you will use meets the *System Requirements* (page 5).
- 3. Remove any previous version of PI JDBC.
- 4. Extract and run the PI JDBC driver setup kit (page 15).
- 5. Add PI JDBC driver location to *Java* CLASSPATH [optional] (page 18).

Note: The process to install PI JDBC Driver on Linux are very similar to the *procedures* (page 11) used for Windows operating systems.

Set up PI JDBC Driver on Linux

Extract contents of PI JDBC_2012-x86-x64_.tar.gz.

Note: The same setup file is used for 32-bit and 64-bit Linux versions.

OSIsoft recommends that the installation files be installed into the /opt directory, but you can choose any other directory as needed.


The different Linux distributions have different tools to execute this task. Below is an example performed on **SLES10**.

1. To launch File Roller with root privileges, enter in a command prompt:


```
administrator@SLES10-32:~> su
```

Password:

SLES10-32:/home/administrator # "/opt/gnome/bin/file-roller"



2. Click **Extract** to extract the files:



Note: If you cannot gain root privileges, OSIsoft recommends that you instead extract the files to your home directory.

Files Installed


After you run the *PI JDBC Driver setup kit* (page 11), you can view the files installed in the [PIHOME]\JDBC directory. The complete list of files is provided in the PI JDBC 2012 Release Notes.



System Variable PI_RDSA_LIB

PI JDBC requires properly defined system variables. There are various mechanisms you can use to complete this task.

OSIsoft recommends that variables be defined in the user profile or system profile. In this example, the system variables are defined in the user profile:



• For OpenSSL 0.9.8 use:

```
export PI_RDSA_LIB=/opt/pipc/jdbc/lib/libRdsaWrapper-1.3.0a.so
export PI_RDSA_LIB64=/opt/pipc/jdbc/lib/libRdsaWrapper64-1.3.0a.so
```

• For OpenSSL 1.0.0 use

```
export PI_RDSA_LIB=/opt/pipc/jdbc/lib/libRdsaWrapper-1.3.0b.so export PI_RDSA_LIB64=/opt/pipc/jdbc/lib/libRdsaWrapper64-1.3.0b.so
```

Note: On 32-bit Linux, the 64-bit PI JDBC driver cannot be called, therefore you do not need to define **PI_RDSA_LIB64**.

Validating Installation

PI JDBC ships with a sample application called **getSnap** to validate successful installation. To use **getSnap**:

- 1. Add the driver to the CLASSPATH Variable (page 18).
- 2. Enter these three parameters:

```
PI SQL DAS name
PI Server name
PI tag name or tag name wildcard (SQL Syntax)
```

For example, if you enter:

```
$java getSnap PISQLDAS01 PIServer01 sin%
```

You should see results in the form of PI data values such as:

```
SINUSOID 79.11583
SINUSOID.Fast 95.47511
SINUSOID_Alert 18.164595
SINUSOID_Fast 95.47511
SINUSOIDU 29.995642
```

Note: On first use you will see the security login (page 14) dialog.

Add the Driver to the CLASSPATH Variable

In order to easily launch a PI JDBC command line application we recommend you add the PI JDBC driver to the CLASSPATH environment variable.

In Linux this is done with an export command as shown for PI_RDSA_LIB:

```
export CLASSPATH=$CLASSPATH:/opt/pipc/jdbc/PIJDBCDriver.jar:.
```

getEASnap

To use the **getEASnap** test application to verify your installation, see *getEASnap* (page 12).

Remove PI JDBC (Linux)

- 1. Remove your PI_RDSA_LIB, PI_RDSA_LIB64 and CLASSPATH modification.
- 2. Delete all files in the /pipc/jdbc directory.



Using PI JDBC

Configuration

Driver Class

Before a JDBC driver can make a connection it needs to be registered with the Driver Manager. Applications typically either prompt you for the location of the driver and then auto discover the JDBC driver name, or directly prompt you to configure the driver name (class name).

The driver name for PI JDBC is:

```
com.osisoft.jdbc.Driver
```

URL Format

To connect to a database, JDBC uses database URLs. The URL for PI JDBC needs to provide the name of the PI SQL DAS machine and the PI OLEDB Enterprise/PI OLEDB connection string.

• To use PI OLEDB Enterprise table set and connect to the PI Asset Framework (AF):

```
jdbc:pi//pisqldas_server/pioledbent_connectionstring
```

o For example:

```
jdbc:pi//mySQLDAS/Data Source=myAFServer; Integrated
Security=SSPI;
```

• To use PI OLEDB Provider and connect to the PI Archive:

```
jdbc:pisql://pisqldas_server/pioledb_connectionstring
```

• For example:

```
jdbc:pisql://mySQLDAS/Data Source=myPIServer; Integrated
Security=SSPI;
```

Time Zone


In this version Time Zone/DST settings have to be the same for the PI SQL DAS computer and the PI JDBC client computer.

PI JDBC automatically uses "Time Zone=Local;".

Driver Properties

Driver properties are used to specify details for making a connection to the underlying database. In general driver properties can be required or optional. PI JDBC has only optional properties. Even username and password are optional because there is an alternative way to specify authentication information (see DCA property in the table below).

Optional driver properties can be specified in addition to the URL string and typically control additional driver features such as logging capabilities and connection timeouts. These driver properties can only be specified if exposed by the JDBC client or from a development environment. For example, here driver properties are exposed by DBVisualizer:





Driver Property	Description	Examples
DASNode Name of PI SQL DAS node. Is automatically populated from URL.		
	DO NOT EDIT	
DCA	Options to ignore or reuse persisted authentication (filename.dca) for PI SQL DAS The DCA file is specific to a certain user and a certain PI SQL DAS Values: INIT – clears persisted authentication information REUSE – reuses persisted authentication file name – use specific authentication file SAVE – persists a DCA file from values specified in user and password properties Note: The value SAVE can be used to create a DCA file in an environment without graphical user interface	DCA=C:\PIPC\JDBC\myAu thentication.dca DCA=INIT DCA=REUSE (default)
LogConsole	Print log messages to Console.	LogConsole=True
LogFile	Full log file path/name.	LogFile = C:\Temp\Log\PIJDBC.log
LogLevel	Specifies granularity of messages to be logged. Values: 0-5	LogLevel=3
password	Password for PI SQL DAS login. Automatically filled from Logon screen or persisted authentication file.	
ProviderString	PI OLEDB or PI OLEDB Enterprise provider string. Automatically filled from URL. DO NOT EDIT	
user	Username for PI SQL DAS login. Automatically filled from Login dialog or persisted authentication file.	

Functionality

SQL

PI JDBC delegates all SQL commands via PI SQL DAS to the underlying query engine.

When connected to Asset Framework (AF) Server, the built-in query engine of PI OLEDB Enterprise is used. Please refer to the *PI OLEDB Enterprise User Guide* for supported SQL syntax. When connected to a PI Server, the built-in query engine of PI OLEDB is used. Refer to the *PI OLEDB Provider User Manual* for supported SQL syntax.

PI OLEDB documentation is available at the *OSIsoft Technical Support Web site* (http://techsupport.osisoft.com).

Advanced JDBC

Multithreading

PI JDBC supports query execution from multiple threads. We recommend reusing connection objects as much as possible because connection open and close operations are expensive.

For example, connection objects can be passed as parameter to a new thread and when that thread is finished, it gives that connection to a connection pool.

Batch Processing

It is possible to assign a series of SQL statements to a JDBC statement to be submitted for execution by PI SQL DAS. This mechanism can be used to:

- aggregate multiple executions of a parameterized query, such as INSERT statements
- execute multiple independent queries at once (these queries cannot have parameters)

JDBC Driver Extensions

PI JDBC supports JDBC extensions, also known as JDBC 2.0 Optional Package, or javax.sql, that allow configuring connections in a directory service through JNDI. It also allows using JNDI connection pooling.

Note: The connection pooling is a dummy implementation to support environments that demand that interface. However, there is no performance gain when using this interface. OSIsoft therefore recommends reuse of connections in the application itself. PI Server and AF Server connections are pooled within PI SQL DAS.



Message Logging

PI SQL DAS

PI SQL DAS puts errors and other messages into the local PI SDK log. This local log is where PI SQL DAS runs, not where PI JDBC runs.

The messages are retrievable via the PI JDBC driver by querying the new pilog..pisdklog table, introduced in PI OLEDB 3.3.0.1.

Note: If the PI JDBC driver has connection problems and you cannot execute a pilog..pisdklog query, then use PI OLEDB to get to this same information.

PI JDBC

The PI JDBC driver offers two logging mechanisms:

• Remote configuration of PI OLEDB logging to get details about query execution. PI OLEDB logging is configurable via the connection string part of the URL.

Note: For security reasons the **Log File** keyword is disabled for remote use. Use the **Server Log** keyword instead.

Local PI JDBC log file.

Use Cases

Source Code Example

The source code for the **getSnap** test application is located in the Samples directory of the Windows version.


For example, you can execute getSnap in the Eclipse IDE development platform to step through the code as shown below.

```
| Live - getSuppercycletonypuro - Ectipes Parison
| File Edit Source Relactor Navegets Seage Project Bon Window Help
| Project Seage | Project
```



DBVisualizer


If you want to explore the PI JDBC functionality without using a programming environment, you might consider using **DBVisualizer** http://www.dbvis.com (http://www.dbvis.com/products/dbvis/):



DbVisualizer Free 7.1.3 - Untitled _ | U × Scripts <u>SQL</u> <u>Tools</u> <u>W</u>indow <u>H</u>elp Databases Scripts Object View SQL Commander Connections
P 1.08C (afserver)
P 1.08C (ofserver)
MSGLOG_WP
ASGLOG_WP
TABLE
VIEW
TOS 🍶 Info 📗 Columns 🔛 Data 🔯 Row Count 🔑 Primary Key | 🤪 Indexes | 🔊 Grants | 🔑 Row Id | 🖷 References | 🔞 🌚 🤌 🔊 🔊 tag time value sinusoid 03-Dec-2010 00:02:09.0684 50.9385567 0 null • 2 0 null sinusoid 03-Dec-2010 00:02:14.17785 50.9757042 TodaysSinusoid sinusoid 03-Dec-2010 00:04:26.7733 sinusoid 03-Dec-2010 00:04:31.86711 0 null sinusoid 03-Dec-2010 00:06:44.47817 52.9397507 sinusoid 03-Dec-2010 00:06:49.572 52.9767265 pibatch pibatchproperty sinusoid 03-Dec-2010 00:09:07.27688 sinusoid 03-Dec-2010 00:09:12.37069 picampaign 0 null 54.0126305 9 10 0 null sinusoid 03-Dec-2010 00:11:30 07559 55 0099449 sinusoid 03-Dec-2010 00:11:35.1694 55.0468025 sinusoid 03-Dec-2010 00:13:52.87429 56.0420265 pitransfer 0 null 11 pitransferoroperty 12 sinusoid 03-Dec-2010 00:13:57.9681 56.0787964 piunitbatch 12 13 14 15 16 17 sinusoid 03-Dec-2010 00:16:15.673 sinusoid 03-Dec-2010 00:16:20.76681 57 0714989 pids
pids
pifunction
piheading
pilog
pimodule 0 null sinusoid 03-Dec-2010 00:18:38.47169 58.0979233 sinusoid 03-Dec-2010 00:18:43 56552 58 1344757 sinusoid 03-Dec-2010 00:21:01.2704 18 0 null sinusoid 03-Dec-2010 00:21:06.36421 59.1572723 0 null sinusoid 03-Dec-2010 00:23:24.0691 60 1398468 sinusoid 03-Dec-2010 00:23:29.17854 60.1762314 sinusoid 03-Dec-2010 00:25:46.86781 61.1544685 pialias pimodule pimoduleh piproperty pisubmodule 20 21 0 null 0 null sinusoid 03-Dec-2010 00:25:51.97724 61.1906891 sinusoid 03-Dec-2010 00:28:09.6665 sinusoid 03-Dec-2010 00:28:14.77595 piversion 0 null sinusoid 03-Dec-2010 00:30:32 46521 63.1688461 sinusoid 03-Dec-2010 00:30:37:57466 63:2046852 sinusoid 03-Dec-2010 00:33:00:37335 64:2033615 ■ VIEW
 Procedures pipoint 0.020/0.063 sec | 524/6 | 1-27 Max Rows: 1000 Max Chars: 0

This figure illustrates how you can open a PI SQL View using DBVisualizer:

This figure illustrates how you can insert data into a PI SQL View using DBVisualizer:





PI JDBC Driver Limitations

Time Zone

In this version Time Zone/DST settings have to be the same for the PI SQL DAS computer and the PI JDBC client computer.

Moreover, the PI OLEDB-specific connection property **Time Zone** cannot be used. If specified, the setting has no effect.

Data Types

The following data types are unsupported:

- .NET (AF) Object
- COM Object, etc.
- VARIANT containing GUID or
- VARIANT containing Timestamp

Multiple Connections

Multiple connections from one PI JDBC application to different PI SQL DAS (installed on multiple nodes) are supported.

Transactions

Manual transactions are not supported. Queries always have to be executed in auto-commit mode.

PI Initialization Properties

The following Initialization Properties are preconfigured and cannot be changed (their use in the connection string part of the URL has no effect):

Connection String Keyword	PI OLEDB Enterprise/PI OLEDB Description	Value
Always Return Rowset	If set, all SQL commands return rowsets containing number of rows affected by the execution.	Always Return Rowset = False;
Time Zone	Time zone used for parsing of timestamp literals and for rendering of timestamp column values.	Time Zone = Local;
Log File	Full log file path/name.	Log File =;

The following Initialization Properties have different default values:

Connection String Keyword	PI OLEDB Description	Value
Session ID	Can be a positive integer value or -1. Only applies to consumer processes that work with multiple session objects. Allows for grouping of server connections. All sessions with the same positive Session ID belong to the same group. Server calls within the same group are serialized.	Session ID = -1; sessions in the same process have own server connections and own cache



Chapter 4

Troubleshooting

To identify solutions when PI JDBC driver does not connect or does not get data, OSIsoft recommends that you troubleshoot from the ground up, and test components in the order they are used:

- PI SDK, check connectivity using **About PI-SDK**
- PI OLEDB Enterprise, verify functionality using PI SQL Commander
- PI OLEDB, verify functionality using PI OLEDB Tester
- PI SQL Data Access Server, run PI SQL DAS interactively to verify functionality or use a PI OLEDB query in the pilog..pisdklog table to check for PI SQL DAS error messages
- PI JDBC, start with installation on same computer as PI SQL DAS

Refer to Connection Messages and Errors (page 29) for more troubleshooting information.

Run PI SQL DAS Interactively

To run PI SQL DAS in interactive mode, enter into a command prompt:

```
C:\PIPC\SQLDAS>pisqldas.exe -x
BaseAddress = http://localhost:5460/DataAccessServer
BaseAddress = net.tcp://localhost:5462/DataAccessServer
EndPoints provided :
    net.tcp://localhost:5462/DataAccessServer/Query
    https://localhost:5461/DataAccessServer/Query
http://localhost:5460/DataAccessServer
```

Connection Messages and Errors

This topic contains common connection messages, including messages that indicate connection problems and the corresponding error messages.

These messages are visible as output of the getSnap sample application. Other JDBC applications might display messages in a message box or log file, depending on how those applications handle exceptions.

For example, *DBVisualizer* (page 24) displays messages in the **Connection Message** text box of its **Database Connection** dialog.

Successful Connection

```
com.osisoft.jdbc.Driver 1.3.0.0251 (Release)
PI SQL DataAccessServer using PIOLEDB
PIOLEDB: 3.3.0.1
or
com.osisoft.jdbc.Driver 1.3.0.0251 (Release)
PI SQL DataAccessServer using PIOLEDBENT
PIOLEDBENT: 1.3.1.5
```

Incorrect Username/Password for Connection to PI SQL DAS

```
An error occurred while establishing the connection:
   Type: java.sql.SQLException   Error Code: 0

Message:
   [PI SQL DAS gSOAP Channel] HTTP Error

Details: HTTP/1.1 403 Forbidden
```

No SSPI Configuration or Incorrect Username/Password

```
An error occurred while establishing the connection:
   Type: java.sql.SQLException   Error Code: 0

Message:
   [PISQLDAS] [PIOLEDB]

[PI SDK] Unable to open a session on a server. The user name and password may be incorrect. mypiserver
```

Incorrect Data Source (Server) Name

```
An error occurred while establishing the connection:
   Type: java.sql.SQLException   Error Code: 0

Message:
[PISQLDAS] [PIOLEDB]
[PI SDK] The requested server was not found in the known servers table. Unable to resolve name to IP address. mypi3

or,

An error occurred while establishing the connection:
   Type: java.sql.SQLException   Error Code: 0

Message:
[PI SQL DAS] [PIOLEDBENT] PI System 'pisqldas63' is not registered.
```



Incorrect PI SQL DAS

```
An error occurred while establishing the connection:
   Type: java.sql.SQLException   Error Code: 0
Message:
   [PI SQL DAS gSOAP Channel] Host not found
Details: get host by name failed in tcp_connect()
```

PI SQL DAS Not Running or Port 5461 Blocked by Access Rule

Note: This error message occurs when the PI SQL DAS port is linked by rules, such as those implemented by McAfee software.

```
An error occurred while establishing the connection:
   Type: java.sql.SQLException   Error Code: 0

Message:
   [PI SQL DAS gSOAP Channel] No connection could be made because the target machine actively refused it.
```

Firewall Does Not Allow Inbound Connection on PI SQL DAS Side

SSL not configured (error appears after short timeout)

```
An error occurred while establishing the connection:
   Type: java.sql.SQLException   Error Code: 0

Message:
   [PI SQL DAS gSOAP Channel] EOF was observed that violates the protocol. The client probably provided invalid authentication information.

Details: SSL connect failed in tcp_connect()
```

Certificate Not Suitable Error Appears Immediately

```
An error occurred while establishing the connection:
   Type: java.sql.SQLException   Error Code: 0

Message:
   [PI SQL DAS gSOAP Channel] EOF was observed that violates the protocol. The client probably provided invalid authentication information.

Details: SSL connect failed in tcp_connect()
```

Verify Java Version

In Java, older versions remain installed for compatibility. Programs can explicitly reference an older version or use the general path that should, but do not always, give you the latest version installed. Therefore, depending on the Linux version used, even if you updated the Java version to 1.6 or later, you may still be referencing an older version of Java.

To verify the version and architecture before using it from PI JDBC, enter into a command prompt:

```
administrator@SLES10-32:~> java -version
```

You should see output such as:

```
java version "1.6.0_21"
Java(TM) SE Runtime Environment (build 1.6.0_21-b06)
Java HotSpot(TM) 64-Bit Server VM (build 17.0-b16, mixed mode)
```

If the version does not meet the requirements you may need to redefine the Java link, for example, /usr/bin/java, to point to the latest JRE version installed.

OpenSSL Library

Linux

PI JDBC requires an OpenSSL library referenced as libcrypto.so.and libssl.so. These references are typically links to the real library files that represent a subversion. Depending on the Linux version, these links may not be defined yet.


1. Verify that these links exist. They are typically located in /lib or /lib64 or /usr/lib or /usr/lib64.

PI JDBC supports Linux systems that have or can be updated to OpenSSL 0.9.8 and Linux Systems that come with OpenSSL 1.0.0.




The following table lists examples of Linux systems and what OpenSSL version they are supporting:


Linux	OpenSSL version	Comment
OpenSuse 11.1	0.9.8	
RHEL 5	0.9.8	Needs update for libstdc++
Ubuntu 9	0.9.8	
SLES 10	0.9.8	Needs update for libstdc++
OpenSuse 11.4	1.0.0	
SLES 11	0.9.8	
RHEL 6	1.0.0	




Note: You may need to install the libraries if they are not installed on the system.

The OpenSSL library is dependent on the libc library and requires a certain revision. On some older Linux distributions, such as RHEL5 and SLES10, the libraries must be updated.









2. To verify that glibc contains libc.so.6(GLIBC_2.4):

Note: RPM packages that contain the necessary files typically use the naming convention libstdc++...4.2.1...rpm. For example, libstdc++42-4.2.1_20070604-1.x86_64.rpm, which can be used for RHEL5 (x64).


Windows

The OpenSSL library is included in the PI JDBC driver.

OpenSSL License

On Linux, PI JDBC dynamically links the OpenSSL library files that are installed as part of the Linux distribution. The related license information is part of the Linux distribution.

For example, in SLES10, the license information is found in the **File List**:



On Windows, PI JDBC includes the OpenSSL libraries. Please see the PI JDBC Release Notes for the location of the license and copyright information document.



Appendix A

Tested PI JDBC Scenarios

PI JDBC Linux (x86) and PI SQL DAS (x86)
PI JDBC Linux (x86) and PI SQL DAS (x64)
PI JDBC Linux (x64) and PI SQL DAS (x86)
PI JDBC Linux (x64) and PI SQL DAS (x64)
PI JDBC Windows (x86) and PI SQL DAS (x86)
PI JDBC Windows (x86) and PI SQL DAS (x64)
PI JDBC Windows (x64) and PI SQL DAS (x86)
PI JDBC Windows (x64) and PI SQL DAS (x64)
eclipse Indigo Service Release 1
DBVisualizer 7.1.3 and 8.0.1 (Free and Personal editions)
Java SE Runtime Environment from 1.6.0_02-b06 to 1.6.0_21-b06
Java SE Runtime Environment 1.7.0-b147
SQL Developer 2.3.0
SQuirreL SQL Client Version 3.4.0
Tomcat 6.0

Appendix B

Technical Support and Resources

For technical assistance, contact OSIsoft Technical Support at +1 510-297-5828 or techsupport@osisoft.com. The *OSIsoft Technical Support* (http://techsupport.osisoft.com) website offers additional contact options

(http://techsupport.osisoft.com/Contact+Us/Contact+Methods/Contact+Methods.htm) for customers outside of the United States.

When you contact OSIsoft Technical Support, be prepared to provide this information:

- Product name, version, and build numbers
- Computer platform (CPU type, operating system, and version number)
- Time that the difficulty started
- Log files at that time
- Details of any environment changes prior to the start of the issue
- Summary of the issue, including any relevant log files during the time the issue occurred

The OSIsoft Virtual Campus (vCampus) (http://vCampus.osisoft.com) website has subscription-based resources to help you with the programming and integration of OSIsoft products.

Index

About the OSIsoft PI Data Access Suite • 2 Add the Driver to the CLASSPATH Variable • 18 Advanced JDBC • 22 Architecture • 2	Install PI JDBC Driver on Windows • 11 Install PI SQL Data Access Server • 6 Installation • 5 Installation Components • 5 Installation Result • 7 Installation Results • 12 Introduction • 1
В	J
Batch Processing • 22	JDBC Driver Extensions • 22
С	L
Certificate Not Suitable Error Appears Immediately • 32	Linux • 32
Configuration • 19	М
Configuration Tool • 8 Configure PI SQL Data Access Server (optional) • 7 Connect with PI SQL Data Access Server • 14 Connection Messages and Errors • 29	Message Logging • 23 Middleware Deployment • 4 Multiple Connections • 27 Multithreading • 22
D	N
Data Types • 27 DBVisualizer • 25 Deployment Options • 3 Driver Class • 19	No SSPI Configuration or Incorrect Username/Password • 30
Driver Properties • 20	0
F	OpenSSL Library • 32 OpenSSL License • 36
Files • 7	D
Files Installed • 11, 16 Firewall Does Not Allow Inbound Connection on PI SQL DAS Side • 31	PI Initialization Properties • 27 PI JDBC • 23
Functionality • 22	PI JDBC Driver Limitations • 27
G	PI Server Login • 14 PI Server Login through PI SQL DAS • 9
getEASnap • 13, 18 getSnap • 12	PI SQL DAS • 23 PI SQL DAS Not Running or Port 5461 Blocked by Access Rule • 31
I	Access Rule • 31
In this Guide • 1	R
Incorrect Data Source (Server) Name • 30	Remove PI JDBC • 15
Incorrect PI SQL DAS • 31	Remove PI JDBC (Linux) • 18
Incorrect Username/Password for Connection to PI SQL DAS • 30	Remove PI SQL DAS • 11 Run PI SQL DAS Interactively • 29
Install PI JDBC Driver on Linux • 15	Run the PI JDBC Driver Setup Kit • 11

Run the PI SQL DAS Setup Kit • 6

S

Security • 14
Set up PI JDBC Driver on Linux • 15
Source Code Example • 24
SQL • 22
SSL not configured (error appears after short timeout) • 31
SSL Port • 9
Standalone Deployment • 4
Successful Connection • 30
System Requirements • 5
System Variable PI_RDSA_LIB • 17

Т

Technical Support and Resources • 39 Tested PI JDBC Scenarios • 37 Time Zone • 19, 27 Transactions • 27 Troubleshooting • 29

U

URL Format • 19 Use Cases • 24 Using PI JDBC • 19

V

Validating Installation • 18 Verify Java Version • 32 Verify the PI JDBC Installation • 12

W

Windows • 35

