Advanced radiation and remote sensing

Lukas Kluft, Manfred Brath, Stefan Bühler January 9, 2020

Exercise No. 6 – Inversion theory: Optimal Estimation Method (OEM)

In this exercise you will work with "realistic" data measured by a water vapor radiometer. The data is not real but has been simulated for a well-known atmospheric state using ARTS. Simulated measurements allow to compare retrieval results to the true atmospheric state. The radiometer (Fig. 1) measures thermal radiation in a frequency range around the 22 GHz water vapor absorption line. As the pressure broadening of absorption lines varies with height the measurement contains information about the vertical water vapor profile. This information can be retrieved using the "Optimal Estimation Method" (OEM). The radiometer is placed in 10 km height, which resembles an upward looking airborne measurement. The scarce concentration of water vapor in the stratosphere allows to perform a linear retrieval approach. Retrievals that cover the whole atmosphere, including the highly absorbent lower troposphere, need more advanced retrieval approaches like an iterative OEM.

- 1. Run the Python script oem.py and plot the observed brightness temperature spectrum y_measurement as function of frequency f_grid.
- 2. Uncomment the line with the function call forward_model() and rerun the script to simulate the brightness temperature spectrum y and the water vapor Jacobian K for the *a priori* state.
 - (a) Add the simulated brightness temperature spectrum to the plot of the observed brightness temperature spectrum.
 - (b) Plot the Jacobians K in a suitable way. Explain the plot.
- 3. Plot the measurement covariance matrix S_y and the *a priori* covariance matrix S_x in a suitable way. What do the covariance matrices mean?
- 4. Implement the function retrieve() according to the OEM solution:

$$\hat{\mathbf{x}} = \mathbf{x}_a + \left(\mathbf{K}^T \mathbf{S}_y^{-1} \mathbf{K} + \mathbf{S}_{xa}^{-1} \right) \mathbf{K}^T \mathbf{S}_y^{-1} \left(\mathbf{y}_{measure} - \mathbf{y}_a \right)$$
(1)



Figure 1: Onsala water vapor radiometer (photo: Peter Forkman)

with \mathbf{x}_a the a priori profile, \mathbf{K} the Jacobian, \mathbf{S}_y the measurement covariance matrix, \mathbf{S}_{xa} the a priori covariance matrix, $\mathbf{y}_{measure}$ the observed brightness temperature spectrum and \mathbf{y}_a the simulated brightness temperature spectrum of profile \mathbf{x}_a .

In Python, a matrix M can be transposed using M.T and inversed using inv(M)¹. Two matrices M1 and M2 can be multiplied using M1 @ M2.

- 5. Use the function retrieve() to retrieve the water vapor profile.
- 6. Plot the retrieved water vapor x_oem and the a priori water vapor profile as function of height z.
- 7. Load the true water vapor retrieval (input/x_true.xml) and add it to the previous plot. Dicuss the results.
- 8. Implement the function averaging_kernel_matrix() to calculate the same-named matrix:

$$\mathbf{A} = \left(\mathbf{K}^T \mathbf{S}_u^{-1} \mathbf{K} + \mathbf{S}_{xa}^{-1}\right) \mathbf{K}^T \mathbf{S}_u^{-1} \mathbf{K}$$
 (2)

- 9. Plot the kernels (columns) of **A** as function of height **z** and interpret the results.
- 10. The measurement response is defined as the sum over all averaging kernels in a given height (row). The measurement response indicates in which heights the measurement actually adds information to the retrieval result.
 - (a) Calculate the measurement response and plot it together with the averaging kernels.
 - (b) In which heights does the measurement provide useful information?
 - (c) Is it possible to estimate the vertical resolution?

¹We are using the inverse function scipy.linalg.inv() provided by the SciPy package.