

# **OpenShift Container Platform 4.16**

# Scalability and performance

Scaling your OpenShift Container Platform cluster and tuning performance in production environments

Last Updated: 2024-09-03

## OpenShift Container Platform 4.16 Scalability and performance

Scaling your OpenShift Container Platform cluster and tuning performance in production environments

## **Legal Notice**

Copyright © 2024 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java <sup>®</sup> is a registered trademark of Oracle and/or its affiliates.

XFS <sup>®</sup> is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL <sup>®</sup> is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack <sup>®</sup> Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

## **Abstract**

This document provides instructions for scaling your cluster and optimizing the performance of your OpenShift Container Platform environment.

## **Table of Contents**

CHAPTER 1. RECOMMENDED PERFORMANCE AND SCALABILITY PRACTICES	. 9
1.1. RECOMMENDED CONTROL PLANE PRACTICES	9
1.1.1. Recommended practices for scaling the cluster	9
1.1.2. Control plane node sizing	9
1.1.2.1. Selecting a larger Amazon Web Services instance type for control plane machines	12
1.1.2.1.1. Changing the Amazon Web Services instance type by using a control plane machine set	12
1.1.2.1.2. Changing the Amazon Web Services instance type by using the AWS console	13
1.2. RECOMMENDED INFRASTRUCTURE PRACTICES	14
1.2.1. Infrastructure node sizing	14
1.2.2. Scaling the Cluster Monitoring Operator	15
1.2.3. Prometheus database storage requirements	15
1.2.4. Configuring cluster monitoring	16
1.2.5. Additional resources	17
1.3. RECOMMENDED ETCD PRACTICES	17
1.3.1. Recommended etcd practices	17
1.3.2. Moving etcd to a different disk	19
1.3.3. Defragmenting etcd data	23
1.3.3.1. Automatic defragmentation	23
1.3.3.2. Manual defragmentation	24
1.3.4. Setting tuning parameters for etcd	27
1.3.4.1. Changing hardware speed tolerance	27
1.3.5. Increasing the database size for etcd	29
1.3.5.1. Changing the etcd database size	29
1.3.5.2. Troubleshooting	31
1.3.5.2.1. Value is too small	31
1.3.5.2.2. Value is too large	31
1.3.5.2.3. Value is decreasing	31
CHAPTER 2. REFERENCE DESIGN SPECIFICATIONS	33
2.1. TELCO CORE AND RAN DU REFERENCE DESIGN SPECIFICATIONS	33
2.1.1. Reference design specifications for telco 5G deployments	33
2.1.2. Reference design scope	33
2.1.3. Deviations from the reference design	33
2.2. TELCO RAN DU REFERENCE DESIGN SPECIFICATION	34
2.2.1. {rds-caps} 4.16 reference design overview	34
2.2.1.1. Deployment architecture overview	34
2.2.2. Telco RAN DU use model overview	35
2.2.2.1. Telco RAN DU application workloads	35
2.2.2.2. Telco RAN DU representative reference application workload characteristics	36
2.2.2.3. Telco RAN DU worker node cluster resource utilization	36
2.2.2.4. Hub cluster management characteristics	37
2.2.2.5. Telco RAN DU RDS components	38
2.2.3. Telco RAN DU 4.16 reference design components	39
2.2.3.1. Host firmware tuning	39
2.2.3.2. Node Tuning Operator	39
2.2.3.3. PTP Operator	41
2.2.3.4. SR-IOV Operator	42
2.2.3.5. Logging	43
2.2.3.6. SRIOV-FEC Operator	44
2.2.3.7. Local Storage Operator	44
2.2.3.8. LVMS Operator	44

2.2.3.9. Workload partitioning	45
2.2.3.10. Cluster tuning	46
2.2.3.11. Machine configuration	47
2.2.3.12. Lifecycle Agent	48
2.2.3.13. Reference design deployment components	49
2.2.3.13.1. Red Hat Advanced Cluster Management (RHACM)	49
2.2.3.13.2. Topology Aware Lifecycle Manager (TALM)	50
2.2.3.13.3. GitOps and GitOps ZTP plugins	51
2.2.3.13.4. Agent-based installer	52
2.2.4. Telco RAN distributed unit (DU) reference configuration CRs	53
2.2.4.1. Day 2 Operators reference CRs	53
2.2.4.2. Cluster tuning reference CRs	56
2.2.4.3. Machine configuration reference CRs	56
2.2.4.4. YAML reference	57
2.2.4.4.1. Day 2 Operators reference YAML	57
2.2.4.4.2. Cluster tuning reference YAML	99
2.2.4.4.3. Machine configuration reference YAML	104
2.2.5. Telco RAN DU reference configuration software specifications	116
2.2.5.1. Telco RAN DU 4.16 validated software components	116
2.3. TELCO CORE REFERENCE DESIGN SPECIFICATION	117
2.3.1. Telco RAN DU 4.16 reference design overview	117
2.3.2. Telco core 4.16 use model overview	117
2.3.2.1. Common baseline model	118
2.3.2.1.1. Engineering Considerations common use model	119
2.3.2.1.2. Application workloads	120
2.3.3. Telco core reference design components	121
2.3.3.1. CPU partitioning and performance tuning	121
2.3.3.2. Service Mesh	122
2.3.3.3. Networking	123
2.3.3.3.1. Cluster Network Operator (CNO)	123
2.3.3.3.2. Load Balancer	123
2.3.3.3. SR-IOV	124
2.3.3.3.4. NMState Operator	125
2.3.3.4. Logging	126
2.3.3.5. Power Management	126
2.3.3.6. Storage	127
2.3.3.6.1. OpenShift Data Foundation	127
2.3.3.6.2. Other Storage	127
2.3.3.7. Monitoring	128
2.3.3.8. Scheduling	128
2.3.3.9. Installation	129
2.3.3.10. Security	130
2.3.3.11. Scalability	131
2.3.3.12. Additional configuration	131
2.3.3.12.1. Disconnected environment	131
2.3.3.12.2. Kernel	132
2.3.4. Telco core 4.16 reference configuration CRs	133
2.3.4.1. Extracting the telco core reference design configuration CRs	133
2.3.4.2. Resource Tuning reference CRs	134
2.3.4.3. Storage reference CRs	134
2.3.4.4. Networking reference CRs	134
2.3.4.5. Scheduling reference CRs	136
2.3.4.6. Other reference CRs	136

2.3.4.7. YAML reference	137
2.3.4.7.1. Resource Tuning reference YAML	137
2.3.4.7.2. Storage reference YAML	138
2.3.4.7.3. Networking reference YAML	140
2.3.4.7.4. Scheduling reference YAML	147
2.3.4.7.5. Other reference YAML	148
2.3.5. Telco core reference configuration software specifications	154
2.3.5.1. Software stack	154
CHAPTER 3. PLANNING YOUR ENVIRONMENT ACCORDING TO OBJECT MAXIMUMS	<b>155</b>
3.1.1. Example scenario	155
3.2. OPENSHIFT CONTAINER PLATFORM ENVIRONMENT AND CONFIGURATION ON WHICH THE CLUST	
MAXIMUMS ARE TESTED	158
3.2.1. AWS cloud platform	158
3.2.2. IBM Power platform	159
3.2.3. IBM Z platform	159
3.3. HOW TO PLAN YOUR ENVIRONMENT ACCORDING TO TESTED CLUSTER MAXIMUMS	160
3.4. HOW TO PLAN YOUR ENVIRONMENT ACCORDING TO APPLICATION REQUIREMENTS	161
CHAPTER 4. RECOMMENDED HOST PRACTICES FOR IBM Z & IBM LINUXONE ENVIRONMENTS	164
4.1. MANAGING CPU OVERCOMMITMENT	164
4.2. DISABLE TRANSPARENT HUGE PAGES	164
4.3. BOOST NETWORKING PERFORMANCE WITH RECEIVE FLOW STEERING	165
4.3.1. Use the Machine Config Operator (MCO) to activate RFS	165
4.4. CHOOSE YOUR NETWORKING SETUP	166
4.5. ENSURE HIGH DISK PERFORMANCE WITH HYPERPAV ON Z/VM	166
4.5.1. Use the Machine Config Operator (MCO) to activate HyperPAV aliases in nodes using z/VM full-pack minidisks	167
4.6. RHEL KVM ON IBM Z HOST RECOMMENDATIONS	168
4.6.1. Use I/O threads for your virtual block devices	168
4.6.2. Avoid virtual SCSI devices	169
4.6.3. Configure guest caching for disk	169
4.6.4. Exclude the memory balloon device	169
4.6.5. Tune the CPU migration algorithm of the host scheduler	169
4.6.6. Disable the cpuset cgroup controller	170
4.6.7. Tune the polling period for idle virtual CPUs	170
CHAPTER 5. USING THE NODE TUNING OPERATOR	172
5.1. ABOUT THE NODE TUNING OPERATOR	172
5.2. ACCESSING AN EXAMPLE NODE TUNING OPERATOR SPECIFICATION	172
5.3. DEFAULT PROFILES SET ON A CLUSTER	173
5.4. VERIFYING THAT THE TUNED PROFILES ARE APPLIED	173
5.5. CUSTOM TUNING SPECIFICATION	174
5.6. CUSTOM TUNING EXAMPLES	179
5.7. SUPPORTED TUNED DAEMON PLUGINS	181
5.8. CONFIGURING NODE TUNING IN A HOSTED CLUSTER	182
5.9. ADVANCED NODE TUNING FOR HOSTED CLUSTERS BY SETTING KERNEL BOOT PARAMETERS	185
CHAPTER 6. USING CPU MANAGER AND TOPOLOGY MANAGER	188
6.1. SETTING UP CPU MANAGER	188
6.2. TOPOLOGY MANAGER POLICIES	193
6.3. SETTING UP TOPOLOGY MANAGER	194
6.4 POD INTERACTIONS WITH TOPOLOGY MANAGER POLICIES	10/

CHAPTER 7. SCHEDULING NUMA-AWARE WORKLOADS	196
7.1. ABOUT NUMA-AWARE SCHEDULING	196
Introduction to NUMA	196
Performance considerations	196
NUMA-aware scheduling	196
Integration with Node Tuning Operator	196
Default scheduling logic	196
NUMA-aware pod scheduling diagram	196
7.2. INSTALLING THE NUMA RESOURCES OPERATOR	198
7.2.1. Installing the NUMA Resources Operator using the CLI	198
7.2.2. Installing the NUMA Resources Operator using the web console	199
7.3. SCHEDULING NUMA-AWARE WORKLOADS	200
7.3.1. Creating the NUMAResourcesOperator custom resource	200
7.3.2. Deploying the NUMA-aware secondary pod scheduler	201
7.3.3. Configuring a single NUMA node policy	202
7.3.4. Sample performance profile	203
7.3.5. Creating a KubeletConfig CRD	203
7.3.6. Scheduling workloads with the NUMA-aware scheduler	204
7.4. OPTIONAL: CONFIGURING POLLING OPERATIONS FOR NUMA RESOURCES UPDATES	208
7.5. TROUBLESHOOTING NUMA-AWARE SCHEDULING	209
7.5.1. Reporting more exact resource availability	213
7.5.2. Checking the NUMA-aware scheduler logs	215
7.5.3. Troubleshooting the resource topology exporter	217
7.5.4. Correcting a missing resource topology exporter config map	219
7.5.5. Collecting NUMA Resources Operator data	220
CHAPTER 8. SCALABILITY AND PERFORMANCE OPTIMIZATION	222
8.1. OPTIMIZING STORAGE	222
8.1.1. Available persistent storage options	222
8.1.2. Recommended configurable storage technology	223
8.1.2.1. Specific application storage recommendations	224
8.1.2.1.1. Registry	224
8.1.2.1.2. Scaled registry	224
8.1.2.1.3. Metrics	225
8.1.2.1.4. Logging	225
8.1.2.1.5. Applications	225
8.1.2.2. Other specific application storage recommendations	225
8.1.3. Data storage management	226
8.1.4. Optimizing storage performance for Microsoft Azure	227
8.1.5. Additional resources	227
8.2. OPTIMIZING ROUTING	227
8.2.1. Baseline Ingress Controller (router) performance	227
8.2.2. Configuring Ingress Controller liveness, readiness, and startup probes	229
8.2.3. Configuring HAProxy reload interval	230
8.3. OPTIMIZING NETWORKING	231
8.3.1. Optimizing the MTU for your network	231
8.3.2. Recommended practices for installing large scale clusters	232
8.3.3. Impact of IPsec	232
8.3.4. Additional resources	232
8.4. OPTIMIZING CPU USAGE WITH MOUNT NAMESPACE ENCAPSULATION	232
8.4.1. Encapsulating mount namespaces	233
8.4.2. Configuring mount namespace encapsulation	235
8.4.3. Inspecting encapsulated namespaces	238
o. no. mopeeting eneapositated namespaces	200

8.4.4. Running additional services in the encapsulated namespace 8.4.5. Additional resources	239 239
CHAPTER 9. MANAGING BARE METAL HOSTS	240
9.1. ABOUT BARE METAL HOSTS AND NODES	240
9.2. MAINTAINING BARE METAL HOSTS	240
9.2.1. Adding a bare metal host to the cluster using the web console	240
9.2.2. Adding a bare metal host to the cluster using YAML in the web console	241
9.2.3. Automatically scaling machines to the number of available bare metal hosts	242
9.2.4. Removing bare metal hosts from the provisioner node	243
CHAPTER 10. MONITORING BARE-METAL EVENTS WITH THE BARE METAL EVENT RELAY	245
10.1. ABOUT BARE-METAL EVENTS	245
10.2. HOW BARE-METAL EVENTS WORK	245
10.2.1. Bare Metal Event Relay data flow	246
10.2.1.1. Operator-managed pod	246
10.2.1.2. Bare Metal Event Relay	246
10.2.1.3. Cloud native event	246
10.2.1.4. CNCF CloudEvents	246
10.2.1.5. HTTP transport or AMQP dispatch router	246
10.2.1.6. Cloud event proxy sidecar	247
10.2.2. Redfish message parsing service	247
10.2.3. Installing the Bare Metal Event Relay using the CLI	247
10.2.4. Installing the Bare Metal Event Relay using the web console	248
10.3. INSTALLING THE AMQ MESSAGING BUS	249
10.4. SUBSCRIBING TO REDFISH BMC BARE-METAL EVENTS FOR A CLUSTER NODE	250
10.4.1. Subscribing to bare-metal events	250
10.4.2. Querying Redfish bare-metal event subscriptions with curl	253
10.4.3. Creating the bare-metal event and Secret CRs	254
10.5. SUBSCRIBING APPLICATIONS TO BARE-METAL EVENTS REST API REFERENCE	256
api/ocloudNotifications/v1/subscriptions	256
HTTP method	256
Description	257
HTTP method	257
Description	257
api/ocloudNotifications/v1/subscriptions/ <subscription_id> HTTP method</subscription_id>	257
	257
Description api/ocloudNotifications/v1/health/	257 258
HTTP method	258
Description	258
10.6. MIGRATING CONSUMER APPLICATIONS TO USE HTTP TRANSPORT FOR PTP OR BARE-METAL	230
EVENTS	258
CHAPTER 11. WHAT HUGE PAGES DO AND HOW THEY ARE CONSUMED BY APPLICATIONS	260
11.1. WHAT HUGE PAGES DO	260
11.2. HOW HUGE PAGES ARE CONSUMED BY APPS	260
11.3. CONSUMING HUGE PAGES RESOURCES USING THE DOWNWARD API	261
11.4. CONFIGURING HUGE PAGES AT BOOT TIME	263
11.5. DISABLING TRANSPARENT HUGE PAGES	265
CHAPTER 12. LOW LATENCY TUNING	266
12.1. UNDERSTANDING LOW LATENCY TUNING FOR CLUSTER NODES	266
12.1.1. About low latency	266

12.1.2. About Hyper-Threading for low latency and real-time applications	267
12.2. TUNING NODES FOR LOW LATENCY WITH THE PERFORMANCE PROFILE	267
12.2.1. Creating a performance profile	267
12.2.1.1. About the Performance Profile Creator	268
12.2.1.2. Gathering data about your cluster using the must-gather command	268
12.2.1.3. Running the Performance Profile Creator using Podman	269
12.2.1.3.1. How to run podman to create a performance profile	272
12.2.1.3.2. Running the Performance Profile Creator wrapper script	273
12.2.1.3.3. Performance Profile Creator arguments	278
12.2.1.4. Reference performance profiles	281
12.2.1.4.1. Performance profile template for clusters that use OVS-DPDK on OpenStack	281
12.2.1.4.2. Telco RAN DU reference design performance profile template	282
12.2.1.4.3. Telco core reference design performance profile template	283
12.2.2. Supported performance profile API versions	284
Upgrading the performance profile to use device interrupt processing	284
Upgrading Node Tuning Operator API from v1alpha1 to v1	284
Upgrading Node Tuning Operator API from v1alpha1 or v1 to v2	284
12.2.3. Configuring node power consumption and realtime processing with workload hints	284
12.2.4. Configuring power saving for nodes that run colocated high and low priority workloads	286
12.2.5. Restricting CPUs for infra and application containers	287
12.2.6. Configuring Hyper-Threading for a cluster	289
12.2.6.1. Disabling Hyper-Threading for low latency applications	291
12.2.7. Managing device interrupt processing for guaranteed pod isolated CPUs	292
12.2.7.1. Finding the effective IRQ affinity setting for a node	292
12.2.7.2. Configuring node interrupt affinity	293
12.2.8. Configuring huge pages	294
12.2.8.1. Allocating multiple huge page sizes	295
12.2.9. Reducing NIC queues using the Node Tuning Operator	295
12.2.9.1. Adjusting the NIC queues with the performance profile	295
12.2.9.2. Verifying the queue status	299
12.2.9.3. Logging associated with adjusting NIC queues	302
12.3. PROVISIONING REAL-TIME AND LOW LATENCY WORKLOADS	302
12.3.1. Scheduling a low latency workload onto a worker with real-time capabilities	303
12.3.2. Creating a pod with a guaranteed QoS class	306
12.3.3. Disabling CPU load balancing in a Pod	307
12.3.4. Disabling power saving mode for high priority pods	308
12.3.5. Disabling CPU CFS quota	309
12.3.6. Disabling interrupt processing for CPUs where pinned containers are running	309
12.4. DEBUGGING LOW LATENCY NODE TUNING STATUS	310
12.4.1. Debugging low latency CNF tuning status	310
12.4.1.1. Machine config pools	311
12.4.2. Collecting low latency tuning debugging data for Red Hat Support	312
12.4.2.1. About the must-gather tool	313
12.4.2.2. Gathering low latency tuning data	313
12.5. PERFORMING LATENCY TESTS FOR PLATFORM VERIFICATION	315
12.5.1. Prerequisites for running latency tests	315
12.5.2. Measuring latency	315
12.5.3. Running the latency tests	316
12.5.3.1. Running hwlatdetect	317
Example hwlatdetect test results	320
12.5.3.2. Running cyclictest	321
Example cyclictest results	322
12.5.3.3. Running oslat	324

12.5.4. Generating a latency test failure report	325
12.5.5. Generating a JUnit latency test report	325
12.5.6. Running latency tests on a single-node OpenShift cluster	326
12.5.7. Running latency tests in a disconnected cluster	327
Mirroring the images to a custom registry accessible from the cluster	327
Configuring the tests to consume images from a custom registry	327
Mirroring images to the cluster OpenShift image registry	328
Mirroring a different set of test images	329
12.5.8. Troubleshooting errors with the cnf-tests container	329
CHAPTER 13. IMPROVING CLUSTER STABILITY IN HIGH LATENCY ENVIRONMENTS USING WORKER	
LATENCY PROFILES	331
13.1. UNDERSTANDING WORKER LATENCY PROFILES	331
13.2. IMPLEMENTING WORKER LATENCY PROFILES AT CLUSTER CREATION	334
13.3. USING AND CHANGING WORKER LATENCY PROFILES	335
13.4. EXAMPLE STEPS FOR DISPLAYING RESULTING VALUES OF WORKERLATENCYPROFILE	337
CHAPTER 14. WORKLOAD PARTITIONING	339
14.1. ENABLING WORKLOAD PARTITIONING	339
14.2. PERFORMANCE PROFILES AND WORKLOAD PARTITIONING	340
14.3. SAMPLE PERFORMANCE PROFILE CONFIGURATION	340
CHAPTER 15. USING THE NODE OBSERVABILITY OPERATOR	343
15.1. WORKFLOW OF THE NODE OBSERVABILITY OPERATOR	343
15.2. INSTALLING THE NODE OBSERVABILITY OPERATOR	343
15.2.1. Installing the Node Observability Operator using the CLI	343
15.2.2. Installing the Node Observability Operator using the web console	345
15.3. REQUESTING CRI-O AND KUBELET PROFILING DATA USING THE NODE OBSERVABILITY OPERAT	
	346
15.3.1. Creating the Node Observability custom resource	346
15.3.2. Running the profiling query	347
15.4. NODE OBSERVABILITY OPERATOR SCRIPTING	349
15.4.1. Creating the Node Observability custom resource for scripting	349
15.4.2. Configuring Node Observability Operator scripting	350
15.5. ADDITIONAL RESOURCES	352

# CHAPTER 1. RECOMMENDED PERFORMANCE AND SCALABILITY PRACTICES

## 1.1. RECOMMENDED CONTROL PLANE PRACTICES

This topic provides recommended performance and scalability practices for control planes in OpenShift Container Platform.

## 1.1.1. Recommended practices for scaling the cluster

The guidance in this section is only relevant for installations with cloud provider integration.

Apply the following best practices to scale the number of worker machines in your OpenShift Container Platform cluster. You scale the worker machines by increasing or decreasing the number of replicas that are defined in the worker machine set.

When scaling up the cluster to higher node counts:

- Spread nodes across all of the available zones for higher availability.
- Scale up by no more than 25 to 50 machines at once.
- Consider creating new compute machine sets in each available zone with alternative instance types of similar size to help mitigate any periodic provider capacity constraints. For example, on AWS, use m5.large and m5d.large.



#### NOTE

Cloud providers might implement a quota for API services. Therefore, gradually scale the cluster.

The controller might not be able to create the machines if the replicas in the compute machine sets are set to higher numbers all at one time. The number of requests the cloud platform, which OpenShift Container Platform is deployed on top of, is able to handle impacts the process. The controller will start to query more while trying to create, check, and update the machines with the status. The cloud platform on which OpenShift Container Platform is deployed has API request limits; excessive queries might lead to machine creation failures due to cloud platform limitations.

Enable machine health checks when scaling to large node counts. In case of failures, the health checks monitor the condition and automatically repair unhealthy machines.



#### NOTE

When scaling large and dense clusters to lower node counts, it might take large amounts of time because the process involves draining or evicting the objects running on the nodes being terminated in parallel. Also, the client might start to throttle the requests if there are too many objects to evict. The default client queries per second (QPS) and burst rates are currently set to **50** and **100** respectively. These values cannot be modified in OpenShift Container Platform.

## 1.1.2. Control plane node sizing

The control plane node resource requirements depend on the number and type of nodes and objects in

the cluster. The following control plane node size recommendations are based on the results of a control plane density focused testing, or *Cluster-density*. This test creates the following objects across a given number of namespaces:

- 1 image stream
- 1build
- 5 deployments, with 2 pod replicas in a **sleep** state, mounting 4 secrets, 4 config maps, and 1 downward API volume each
- 5 services, each one pointing to the TCP/8080 and TCP/8443 ports of one of the previous deployments
- 1 route pointing to the first of the previous services
- 10 secrets containing 2048 random string characters
- 10 config maps containing 2048 random string characters

Number of worker nodes	Cluster-density (namespaces)	CPU cores	Memory (GB)
24	500	4	16
120	1000	8	32
252	4000	16, but 24 if using the OVN-Kubernetes network plug-in	64, but 128 if using the OVN-Kubernetes network plug-in
501, but untested with the OVN-Kubernetes network plug-in	4000	16	96

The data from the table above is based on an OpenShift Container Platform running on top of AWS, using r5.4xlarge instances as control-plane nodes and m5.2xlarge instances as worker nodes.

On a large and dense cluster with three control plane nodes, the CPU and memory usage will spike up when one of the nodes is stopped, rebooted, or fails. The failures can be due to unexpected issues with power, network, underlying infrastructure, or intentional cases where the cluster is restarted after shutting it down to save costs. The remaining two control plane nodes must handle the load in order to be highly available, which leads to increase in the resource usage. This is also expected during upgrades because the control plane nodes are cordoned, drained, and rebooted serially to apply the operating system updates, as well as the control plane Operators update. To avoid cascading failures, keep the overall CPU and memory resource usage on the control plane nodes to at most 60% of all available capacity to handle the resource usage spikes. Increase the CPU and memory on the control plane nodes accordingly to avoid potential downtime due to lack of resources.



#### **IMPORTANT**

The node sizing varies depending on the number of nodes and object counts in the cluster. It also depends on whether the objects are actively being created on the cluster. During object creation, the control plane is more active in terms of resource usage compared to when the objects are in the **running** phase.

Operator Lifecycle Manager (OLM) runs on the control plane nodes and its memory footprint depends on the number of namespaces and user installed operators that OLM needs to manage on the cluster. Control plane nodes need to be sized accordingly to avoid OOM kills. Following data points are based on the results from cluster maximums testing.

Number of namespaces	OLM memory at idle state (GB)	OLM memory with 5 user operators installed (GB)
500	0.823	1.7
1000	1.2	2.5
1500	1.7	3.2
2000	2	4.4
3000	2.7	5.6
4000	3.8	7.6
5000	4.2	9.02
6000	5.8	11.3
7000	6.6	12.9
8000	6.9	14.8
9000	8	17.7
10,000	9.9	21.6



## **IMPORTANT**

You can modify the control plane node size in a running OpenShift Container Platform 4.16 cluster for the following configurations only:

- Clusters installed with a user-provisioned installation method.
- AWS clusters installed with an installer-provisioned infrastructure installation method.
- Clusters that use a control plane machine set to manage control plane machines.

For all other configurations, you must estimate your total node count and use the suggested control plane node size during installation.



#### **IMPORTANT**

The recommendations are based on the data points captured on OpenShift Container Platform clusters with OpenShift SDN as the network plugin.



#### **NOTE**

In OpenShift Container Platform 4.16, half of a CPU core (500 millicore) is now reserved by the system by default compared to OpenShift Container Platform 3.11 and previous versions. The sizes are determined taking that into consideration.

## 1.1.2.1. Selecting a larger Amazon Web Services instance type for control plane machines

If the control plane machines in an Amazon Web Services (AWS) cluster require more resources, you can select a larger AWS instance type for the control plane machines to use.



#### NOTE

The procedure for clusters that use a control plane machine set is different from the procedure for clusters that do not use a control plane machine set.

If you are uncertain about the state of the **ControlPlaneMachineSet** CR in your cluster, you can verify the CR status.

#### 1.1.2.1.1. Changing the Amazon Web Services instance type by using a control plane machine set

You can change the Amazon Web Services (AWS) instance type that your control plane machines use by updating the specification in the control plane machine set custom resource (CR).

## **Prerequisites**

• Your AWS cluster uses a control plane machine set.

#### Procedure

1. Edit your control plane machine set CR by running the following command:

\$ oc --namespace openshift-machine-api edit controlplanemachineset.machine.openshift.io cluster

2. Edit the following line under the **providerSpec** field:

providerSpec:
value:
...
instanceType: <compatible\_aws\_instance\_type> 1

- Specify a larger AWS instance type with the same base as the previous selection. For example, you can change **m6i.xlarge** to **m6i.2xlarge** or **m6i.4xlarge**.
- 3. Save your changes.
  - For clusters that use the default **RollingUpdate** update strategy, the Operator automatically propagates the changes to your control plane configuration.
  - For clusters that are configured to use the **OnDelete** update strategy, you must replace your control plane machines manually.

#### Additional resources

• Managing control plane machines with control plane machine sets

#### 1.1.2.1.2. Changing the Amazon Web Services instance type by using the AWS console

You can change the Amazon Web Services (AWS) instance type that your control plane machines use by updating the instance type in the AWS console.

#### **Prerequisites**

- You have access to the AWS console with the permissions required to modify the EC2 Instance for your cluster.
- You have access to the OpenShift Container Platform cluster as a user with the **cluster-admin** role.

#### Procedure

- 1. Open the AWS console and fetch the instances for the control plane machines.
- 2. Choose one control plane machine instance.
  - a. For the selected control plane machine, back up the etcd data by creating an etcd snapshot. For more information, see "Backing up etcd".
  - b. In the AWS console, stop the control plane machine instance.
  - c. Select the stopped instance, and click **Actions** → **Instance Settings** → **Change instance type**.
  - d. Change the instance to a larger type, ensuring that the type is the same base as the previous selection, and apply changes. For example, you can change **m6i.xlarge** to **m6i.2xlarge** or **m6i.4xlarge**.
  - e. Start the instance.

- f. If your OpenShift Container Platform cluster has a corresponding **Machine** object for the instance, update the instance type of the object to match the instance type set in the AWS console.
- 3. Repeat this process for each control plane machine.

#### Additional resources

- Backing up etcd
- AWS documentation about changing the instance type

## 1.2. RECOMMENDED INFRASTRUCTURE PRACTICES

This topic provides recommended performance and scalability practices for infrastructure in OpenShift Container Platform.

## 1.2.1. Infrastructure node sizing

Infrastructure nodes are nodes that are labeled to run pieces of the OpenShift Container Platform environment. The infrastructure node resource requirements depend on the cluster age, nodes, and objects in the cluster, as these factors can lead to an increase in the number of metrics or time series in Prometheus. The following infrastructure node size recommendations are based on the results observed in cluster-density testing detailed in the **Control plane node sizing**section, where the monitoring stack and the default ingress-controller were moved to these nodes.

Number of worker nodes	Cluster density, or number of namespaces	CPU cores	Memory (GB)
27	500	4	24
120	1000	8	48
252	4000	16	128
501	4000	32	128

In general, three infrastructure nodes are recommended per cluster.



#### **IMPORTANT**

These sizing recommendations should be used as a guideline. Prometheus is a highly memory intensive application; the resource usage depends on various factors including the number of nodes, objects, the Prometheus metrics scraping interval, metrics or time series, and the age of the cluster. In addition, the router resource usage can also be affected by the number of routes and the amount/type of inbound requests.

These recommendations apply only to infrastructure nodes hosting Monitoring, Ingress and Registry infrastructure components installed during cluster creation.



#### **NOTE**

In OpenShift Container Platform 4.16, half of a CPU core (500 millicore) is now reserved by the system by default compared to OpenShift Container Platform 3.11 and previous versions. This influences the stated sizing recommendations.

## 1.2.2. Scaling the Cluster Monitoring Operator

OpenShift Container Platform exposes metrics that the Cluster Monitoring Operator (CMO) collects and stores in the Prometheus-based monitoring stack. As an administrator, you can view dashboards for system resources, containers, and components metrics in the OpenShift Container Platform web console by navigating to **Observe**  $\rightarrow$  **Dashboards**.

## 1.2.3. Prometheus database storage requirements

Red Hat performed various tests for different scale sizes.



#### **NOTE**

- The following Prometheus storage requirements are not prescriptive and should be used as a reference. Higher resource consumption might be observed in your cluster depending on workload activity and resource density, including the number of pods, containers, routes, or other resources exposing metrics collected by Prometheus.
- You can configure the size-based data retention policy to suit your storage requirements.

Table 1.1. Prometheus Database storage requirements based on number of nodes/pods in the cluster

Number of nodes	Number of pods (2 containers per pod)	Prometheus storage growth per day	Prometheus storage growth per 15 days	Network (per tsdb chunk)
50	1800	6.3 GB	94 GB	16 MB
100	3600	13 GB	195 GB	26 MB
150	5400	19 GB	283 GB	36 MB
200	7200	25 GB	375 GB	46 MB

Approximately 20 percent of the expected size was added as overhead to ensure that the storage requirements do not exceed the calculated value.

The above calculation is for the default OpenShift Container Platform Cluster Monitoring Operator.



#### **NOTE**

CPU utilization has minor impact. The ratio is approximately 1 core out of 40 per 50 nodes and 1800 pods.

### **Recommendations for OpenShift Container Platform**

- Use at least two infrastructure (infra) nodes.
- Use at least three **openshift-container-storage** nodes with non-volatile memory express (SSD or NVMe) drives.

## 1.2.4. Configuring cluster monitoring

You can increase the storage capacity for the Prometheus component in the cluster monitoring stack.

#### **Procedure**

To increase the storage capacity for Prometheus:

1. Create a YAML configuration file, cluster-monitoring-config.yaml. For example:

```
apiVersion: v1
kind: ConfigMap
data:
 config.yaml: |
  prometheusK8s:
   retention: {{PROMETHEUS_RETENTION_PERIOD}}
   nodeSelector:
    node-role.kubernetes.io/infra: ""
   volumeClaimTemplate:
    spec:
     storageClassName: {{STORAGE CLASS}} 2
     resources:
      requests:
       storage: {{PROMETHEUS_STORAGE_SIZE}} 3
  alertmanagerMain:
   nodeSelector:
    node-role.kubernetes.io/infra: ""
   volumeClaimTemplate:
    spec:
     storageClassName: {{STORAGE_CLASS}} 4
     resources:
      requests:
       storage: {{ALERTMANAGER_STORAGE_SIZE}} 5
metadata:
 name: cluster-monitoring-config
 namespace: openshift-monitoring
```

- The default value of Prometheus retention is **PROMETHEUS\_RETENTION\_PERIOD=15d**. Units are measured in time using one of these suffixes: s, m, h, d.
- 2 4 The storage class for your cluster.
- A typical value is **PROMETHEUS\_STORAGE\_SIZE=2000Gi**. Storage values can be a plain integer or a fixed-point integer using one of these suffixes: E, P, T, G, M, K. You can also use the power-of-two equivalents: Ei, Pi, Ti, Gi, Mi, Ki.
- A typical value is **ALERTMANAGER\_STORAGE\_SIZE=20Gi**. Storage values can be a plain integer or a fixed-point integer using one of these suffixes: E, P, T, G, M, K. You can also

use the power-of-two equivalents: Ei, Pi, Ti, Gi, Mi, Ki.

- 2. Add values for the retention period, storage class, and storage sizes.
- 3. Save the file.
- 4. Apply the changes by running:

\$ oc create -f cluster-monitoring-config.yaml

## 1.2.5. Additional resources

- Infrastructure Nodes in OpenShift 4
- OpenShift Container Platform cluster maximums
- Creating infrastructure machine sets

## 1.3. RECOMMENDED ETCD PRACTICES

This topic provides recommended performance and scalability practices for etcd in OpenShift Container Platform.

## 1.3.1. Recommended etcd practices

Because etcd writes data to disk and persists proposals on disk, its performance depends on disk performance. Although etcd is not particularly I/O intensive, it requires a low latency block device for optimal performance and stability. Because etcd's consensus protocol depends on persistently storing metadata to a log (WAL), etcd is sensitive to disk-write latency. Slow disks and disk activity from other processes can cause long fsync latencies.

Those latencies can cause etcd to miss heartbeats, not commit new proposals to the disk on time, and ultimately experience request timeouts and temporary leader loss. High write latencies also lead to an OpenShift API slowness, which affects cluster performance. Because of these reasons, avoid colocating other workloads on the control-plane nodes that are I/O sensitive or intensive and share the same underlying I/O infrastructure.

In terms of latency, run etcd on top of a block device that can write at least 50 IOPS of 8000 bytes long sequentially. That is, with a latency of 10ms, keep in mind that uses fdatasync to synchronize each write in the WAL. For heavy loaded clusters, sequential 500 IOPS of 8000 bytes (2 ms) are recommended. To measure those numbers, you can use a benchmarking tool, such as fio.

To achieve such performance, run etcd on machines that are backed by SSD or NVMe disks with low latency and high throughput. Consider single-level cell (SLC) solid-state drives (SSDs), which provide 1 bit per memory cell, are durable and reliable, and are ideal for write-intensive workloads.



#### **NOTE**

The load on etcd arises from static factors, such as the number of nodes and pods, and dynamic factors, including changes in endpoints due to pod autoscaling, pod restarts, job executions, and other workload-related events. To accurately size your etcd setup, you must analyze the specific requirements of your workload. Consider the number of nodes, pods, and other relevant factors that impact the load on etcd.

The following hard drive practices provide optimal etcd performance:

- Use dedicated etcd drives. Avoid drives that communicate over the network, such as iSCSI. Do not place log files or other heavy workloads on etcd drives.
- Prefer drives with low latency to support fast read and write operations.
- Prefer high-bandwidth writes for faster compactions and defragmentation.
- Prefer high-bandwidth reads for faster recovery from failures.
- Use solid state drives as a minimum selection. Prefer NVMe drives for production environments.
- Use server-grade hardware for increased reliability.



#### NOTE

Avoid NAS or SAN setups and spinning drives. Ceph Rados Block Device (RBD) and other types of network-attached storage can result in unpredictable network latency. To provide fast storage to etcd nodes at scale, use PCI passthrough to pass NVM devices directly to the nodes.

Always benchmark by using utilities such as fio. You can use such utilities to continuously monitor the cluster performance as it increases.



#### **NOTE**

Avoid using the Network File System (NFS) protocol or other network based file systems.

Some key metrics to monitor on a deployed OpenShift Container Platform cluster are p99 of etcd disk write ahead log duration and the number of etcd leader changes. Use Prometheus to track these metrics.



## NOTE

The etcd member database sizes can vary in a cluster during normal operations. This difference does not affect cluster upgrades, even if the leader size is different from the other members.

To validate the hardware for etcd before or after you create the OpenShift Container Platform cluster, you can use fio.

## **Prerequisites**

- Container runtimes such as Podman or Docker are installed on the machine that you are testing.
- Data is written to the /var/lib/etcd path.

### **Procedure**

- Run fio and analyze the results:
  - If you use Podman, run this command:

\$ sudo podman run --volume /var/lib/etcd:/var/lib/etcd:Z quay.io/cloud-bulldozer/etcd-perf

• If you use Docker, run this command:

 $\$ \ sudo \ docker \ run \ --volume \ /var/lib/etcd: \ /var/lib/etcd: \ Z \ quay. io/cloud-bulldozer/etcd-performation \ for \ run \ --volume \ /var/lib/etcd: \ /var/lib/etcd:$ 

The output reports whether the disk is fast enough to host etcd by comparing the 99th percentile of the fsync metric captured from the run to see if it is less than 10 ms. A few of the most important etcd metrics that might affected by I/O performance are as follow:

- etcd\_disk\_wal\_fsync\_duration\_seconds\_bucket metric reports the etcd's WAL fsync duration
- etcd\_disk\_backend\_commit\_duration\_seconds\_bucket metric reports the etcd backend commit latency duration
- etcd\_server\_leader\_changes\_seen\_total metric reports the leader changes

Because etcd replicates the requests among all the members, its performance strongly depends on network input/output (I/O) latency. High network latencies result in etcd heartbeats taking longer than the election timeout, which results in leader elections that are disruptive to the cluster. A key metric to monitor on a deployed OpenShift Container Platform cluster is the 99th percentile of etcd network peer latency on each etcd cluster member. Use Prometheus to track the metric.

The histogram\_quantile(0.99, rate(etcd\_network\_peer\_round\_trip\_time\_seconds\_bucket[2m])) metric reports the round trip time for etcd to finish replicating the client requests between the members. Ensure that it is less than 50 ms.

#### Additional resources

- How to use fio to check etcd disk performance in OpenShift Container Platform
- etcd performance troubleshooting guide for OpenShift Container Platform

## 1.3.2. Moving etcd to a different disk

You can move etcd from a shared disk to a separate disk to prevent or resolve performance issues.

The Machine Config Operator (MCO) is responsible for mounting a secondary disk for OpenShift Container Platform 4.16 container storage.



#### NOTE

This encoded script only supports device names for the following device types:

SCSI or SATA

/dev/sd\*

Virtual device

/dev/vd\*

**NVMe** 

/dev/nvme\*[0-9]\*n\*

#### Limitations

• When the new disk is attached to the cluster, the etcd database is part of the root mount. It is not part of the secondary disk or the intended disk when the primary node is recreated. As a result, the primary node will not create a separate /var/lib/etcd mount.

## **Prerequisites**

- You have a backup of your cluster's etcd data.
- You have installed the OpenShift CLI (oc).
- You have access to the cluster with **cluster-admin** privileges.
- Add additional disks before uploading the machine configuration.
- The MachineConfigPool must match metadata.labels[machineconfiguration.openshift.io/role]. This applies to a controller, worker, or a custom pool.



#### NOTE

This procedure does not move parts of the root file system, such as /var/, to another disk or partition on an installed node.



#### **IMPORTANT**

This procedure is not supported when using control plane machine sets.

#### **Procedure**

1. Attach the new disk to the cluster and verify that the disk is detected in the node by running the **Isblk** command in a debug shell:

```
$ oc debug node/<node_name>
```

# Isblk

Note the device name of the new disk reported by the **Isblk** command.

2. Decode and replace the device name in the script according to your environment.

```
#!/bin/bash
set -uo pipefail

for device in <device_type_glob>; do 1
/usr/sbin/blkid $device &> /dev/null
if [ $? == 2 ]; then
echo "secondary device found $device"
echo "creating filesystem for etcd mount"
mkfs.xfs -L var-lib-etcd -f $device &> /dev/null
udevadm settle
touch /etc/var-lib-etcd-mount
exit
fi
```

done
echo "Couldn't find secondary block device!" >&2
exit 77

- Replace <device\_type\_glob> with a shell glob for your block device type. For SCSI or SATA drives, use /dev/sd\*; for virtual drives, use /dev/vd\*; for NVMe drives, use /dev/nvme\*[0-9]\*n\*.
- 3. Create a **MachineConfig** YAML file named **etcd-mc.yml** with contents such as the following:

```
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
 labels:
  machineconfiguration.openshift.io/role: master
 name: 98-var-lib-etcd
spec:
 config:
  ignition:
   version: 3.1.0
  storage:
   files:
     - path: /etc/find-secondary-device
      mode: 0755
      contents:
       source: data:text/plain;charset=utf-8;base64,
<encoded_etc_find_secondary_device_script> 11
  systemd:
   units:
     - name: find-secondary-device.service
      enabled: true
      contents: |
       [Unit]
       Description=Find secondary device
       DefaultDependencies=false
       After=systemd-udev-settle.service
       Before=local-fs-pre.target
       ConditionPathExists=!/etc/var-lib-etcd-mount
       [Service]
       RemainAfterExit=yes
       ExecStart=/etc/find-secondary-device
       RestartForceExitStatus=77
       [Install]
       WantedBy=multi-user.target
     - name: var-lib-etcd.mount
      enabled: true
      contents: |
       [Unit]
       Before=local-fs.target
       [Mount]
       What=/dev/disk/by-label/var-lib-etcd
```

```
Where=/var/lib/etcd
  Type=xfs
  TimeoutSec=120s
  [Install]
  RequiredBy=local-fs.target
- name: sync-var-lib-etcd-to-etcd.service
 enabled: true
 contents: |
  [Unit]
  Description=Sync etcd data if new mount is empty
  DefaultDependencies=no
  After=var-lib-etcd.mount var.mount
  Before=crio.service
  [Service]
  Type=oneshot
  RemainAfterExit=yes
  ExecCondition=/usr/bin/test!-d/var/lib/etcd/member
  ExecStart=/usr/sbin/setsebool -P rsync full access 1
  ExecStart=/bin/rsync -ar /sysroot/ostree/deploy/rhcos/var/lib/etcd/ /var/lib/etcd/
  ExecStart=/usr/sbin/semanage fcontext -a -t container_var_lib_t '/var/lib/etcd(/.*)?'
  ExecStart=/usr/sbin/setsebool -P rsync_full_access 0
  TimeoutSec=0
  [Install]
  WantedBy=multi-user.target graphical.target
- name: restorecon-var-lib-etcd.service
 enabled: true
 contents: |
  [Unit]
  Description=Restore recursive SELinux security contexts
  DefaultDependencies=no
  After=var-lib-etcd.mount
  Before=crio.service
  [Service]
  Type=oneshot
  RemainAfterExit=yes
  ExecStart=/sbin/restorecon -R /var/lib/etcd/
  TimeoutSec=0
  [Install]
  WantedBy=multi-user.target graphical.target
```

Use the encoded string that you previously created and replace it with the encoded script that you noted.

### **Verification steps**

• Run the **grep** /var/lib/etcd /proc/mounts command in a debug shell for the node to ensure that the disk is mounted:

\$ oc debug node/<node\_name>

# grep -w "/var/lib/etcd" /proc/mounts

## **Example output**

/dev/sdb /var/lib/etcd xfs rw,seclabel,relatime,attr2,inode64,logbufs=8,logbsize=32k,noquota 0 0

#### Additional resources

• Red Hat Enterprise Linux CoreOS (RHCOS)

## 1.3.3. Defragmenting etcd data

For large and dense clusters, etcd can suffer from poor performance if the keyspace grows too large and exceeds the space quota. Periodically maintain and defragment etcd to free up space in the data store. Monitor Prometheus for etcd metrics and defragment it when required; otherwise, etcd can raise a cluster-wide alarm that puts the cluster into a maintenance mode that accepts only key reads and deletes.

Monitor these key metrics:

- etcd\_server\_quota\_backend\_bytes, which is the current quota limit
- etcd\_mvcc\_db\_total\_size\_in\_use\_in\_bytes, which indicates the actual database usage after a history compaction
- **etcd\_mvcc\_db\_total\_size\_in\_bytes**, which shows the database size, including free space waiting for defragmentation

Defragment etcd data to reclaim disk space after events that cause disk fragmentation, such as etcd history compaction.

History compaction is performed automatically every five minutes and leaves gaps in the back-end database. This fragmented space is available for use by etcd, but is not available to the host file system. You must defragment etcd to make this space available to the host file system.

Defragmentation occurs automatically, but you can also trigger it manually.



#### **NOTE**

Automatic defragmentation is good for most cases, because the etcd operator uses cluster information to determine the most efficient operation for the user.

## 1.3.3.1. Automatic defragmentation

The etcd Operator automatically defragments disks. No manual intervention is needed.

Verify that the defragmentation process is successful by viewing one of these logs:

- etcd logs
- cluster-etcd-operator pod
- operator status error log



#### **WARNING**

Automatic defragmentation can cause leader election failure in various OpenShift core components, such as the Kubernetes controller manager, which triggers a restart of the failing component. The restart is harmless and either triggers failover to the next running instance or the component resumes work again after the restart.

## Example log output for successful defragmentation

etcd member has been defragmented: <member\_name>, memberID: <member\_id>

## Example log output for unsuccessful defragmentation

failed defrag on member: <member\_name>, memberID: <member\_id>: <error\_message>

## 1.3.3.2. Manual defragmentation

A Prometheus alert indicates when you need to use manual defragmentation. The alert is displayed in two cases:

- When etcd uses more than 50% of its available space for more than 10 minutes
- When etcd is actively using less than 50% of its total database size for more than 10 minutes

You can also determine whether defragmentation is needed by checking the etcd database size in MB that will be freed by defragmentation with the PromQL expression:

(etcd\_mvcc\_db\_total\_size\_in\_bytes - etcd\_mvcc\_db\_total\_size\_in\_use\_in\_bytes)/1024/1024



#### **WARNING**

Defragmenting etcd is a blocking action. The etcd member will not respond until defragmentation is complete. For this reason, wait at least one minute between defragmentation actions on each of the pods to allow the cluster to recover.

Follow this procedure to defragment etcd data on each etcd member.

## **Prerequisites**

• You have access to the cluster as a user with the **cluster-admin** role.

#### Procedure

1. Determine which etcd member is the leader, because the leader should be defragmented last.

a. Get the list of etcd pods:

\$ oc -n openshift-etcd get pods -l k8s-app=etcd -o wide

## **Example output**

```
etcd-ip-10-0-159-225.example.redhat.com 3/3
                                                              175m
                                              Running 0
10.0.159.225 ip-10-0-159-225.example.redhat.com <none>
                                                      <none>
etcd-ip-10-0-191-37.example.redhat.com
                                                             173m
                                   3/3
                                              Running
                                                       0
10.0.191.37 ip-10-0-191-37.example.redhat.com <none>
                                                     <none>
etcd-ip-10-0-199-170.example.redhat.com 3/3 Running 0
                                                              176m
10.0.199.170 ip-10-0-199-170.example.redhat.com <none>
                                                      <none>
```

b. Choose a pod and run the following command to determine which etcd member is the leader:

\$ oc rsh -n openshift-etcd etcd-ip-10-0-159-225.example.redhat.com etcdctl endpoint status --cluster -w table

#### **Example output**

Defaulting container name to etcdctl. Use 'oc describe pod/etcd-ip-10-0-159-225.example.redhat.com -n openshift-etcd' to see all of the containers in this pod. ENDPOINT | ID | VERSION | DB SIZE | IS LEADER | IS LEARNER | RAFT TERM | RAFT INDEX | RAFT APPLIED INDEX | ERRORS | +----+ | https://10.0.191.37:2379 | 251cd44483d811c3 | 3.5.9 | 104 MB | false | false | 7 | 91624 | 91624 | | https://10.0.159.225:2379 | 264c7c58ecbdabee | 3.5.9 | 104 MB | false | false | 7 | 91624 | 91624 | | | https://10.0.199.170:2379 | 9ac311f93915cc79 | 3.5.9 | 104 MB | true | false | 7 | 91624 | 91624 | | 

Based on the **IS LEADER** column of this output, the **https://10.0.199.170:2379** endpoint is the leader. Matching this endpoint with the output of the previous step, the pod name of the leader is **etcd-ip-10-0-199-170.example.redhat.com**.

- 2. Defragment an etcd member.
  - a. Connect to the running etcd container, passing in the name of a pod that is *not* the leader:
    - \$ oc rsh -n openshift-etcd etcd-ip-10-0-159-225.example.redhat.com
  - b. Unset the **ETCDCTL\_ENDPOINTS** environment variable:

sh-4.4# unset ETCDCTL\_ENDPOINTS

c. Defragment the etcd member:

sh-4.4# etcdctl --command-timeout=30s --endpoints=https://localhost:2379 defrag

## **Example output**

Finished defragmenting etcd member[https://localhost:2379]

If a timeout error occurs, increase the value for **--command-timeout** until the command succeeds.

d. Verify that the database size was reduced:

sh-4.4# etcdctl endpoint status -w table --cluster

## **Example output**

```
ENDPOINT
             | ID
                    | VERSION | DB SIZE | IS LEADER | IS LEARNER |
RAFT TERM | RAFT INDEX | RAFT APPLIED INDEX | ERRORS |
-----+
| https://10.0.191.37:2379 | 251cd44483d811c3 | 3.5.9 | 104 MB | false | false |
  91624 |
            91624 |
| https://10.0.159.225:2379 | 264c7c58ecbdabee | 3.5.9 | 41 MB | false | false |
7 | 91624 | 91624 |
                    | https://10.0.199.170:2379 | 9ac311f93915cc79 | 3.5.9 | 104 MB | true |
                                                false |
            91624 |
```

This example shows that the database size for this etcd member is now 41 MB as opposed to the starting size of 104 MB.

e. Repeat these steps to connect to each of the other etcd members and defragment them. Always defragment the leader last.

Wait at least one minute between defragmentation actions to allow the etcd pod to recover. Until the etcd pod recovers, the etcd member will not respond.

- 3. If any **NOSPACE** alarms were triggered due to the space quota being exceeded, clear them.
  - a. Check if there are any **NOSPACE** alarms:

sh-4.4# etcdctl alarm list

#### **Example output**

memberID:12345678912345678912 alarm:NOSPACE

b. Clear the alarms:

sh-4.4# etcdctl alarm disarm

## 1.3.4. Setting tuning parameters for etcd

You can set the control plane hardware speed to "Standard", "Slower", or the default, which is "".

The default setting allows the system to decide which speed to use. This value enables upgrades from versions where this feature does not exist, as the system can select values from previous versions.

By selecting one of the other values, you are overriding the default. If you see many leader elections due to timeouts or missed heartbeats and your system is set to "" or "Standard", set the hardware speed to "Slower" to make the system more tolerant to the increased latency.

## 1.3.4.1. Changing hardware speed tolerance

To change the hardware speed tolerance for etcd, complete the following steps.

#### **Procedure**

- 1. Check to see what the current value is by entering the following command:
  - \$ oc describe etcd/cluster | grep "Control Plane Hardware Speed"

## **Example output**

Control Plane Hardware Speed: <VALUE>



#### NOTE

If the output is empty, the field has not been set and should be considered as the default ("").

2. Change the value by entering the following command. Replace **<value>** with one of the valid values: "", "Standard", or "Slower":

 $\label{thm:controlPlaneHardwareSpeed": "<value>"}} 's oc patch etcd/cluster --type=merge -p '{"spec": {"controlPlaneHardwareSpeed": "<value>"}}'s oc patch etcd/cluster --type=merge -p '{"spec": {"controlPlaneHardwareSpeed": {"controlPlaneHardwareSpeed":$ 

The following table indicates the heartbeat interval and leader election timeout for each profile. These values are subject to change.

Profile	ETCD_HEARTBEAT_INTERVA	ETCD_LEADER_ELECTION_TI MEOUT
****	Varies depending on platform	Varies depending on platform
Standard	100	1000
Slower	500	2500

3. Review the output:

## **Example output**

etcd.operator.openshift.io/cluster patched

If you enter any value besides the valid values, error output is displayed. For example, if you entered **"Faster"** as the value, the output is as follows:

## **Example output**

The Etcd "cluster" is invalid: spec.controlPlaneHardwareSpeed: Unsupported value: "Faster": supported values: "", "Standard", "Slower"

- 4. Verify that the value was changed by entering the following command:
  - \$ oc describe etcd/cluster | grep "Control Plane Hardware Speed"

## **Example output**

- Control Plane Hardware Speed: ""
- 5. Wait for etcd pods to roll out:
  - \$ oc get pods -n openshift-etcd -w

The following output shows the expected entries for master-0. Before you continue, wait until all masters show a status of **4/4 Running**.

## Example output

installer-9-ci-ln-qkgs94t-72292-9clnd-master-0	0/1	Pending	0	0s
installer-9-ci-ln-qkgs94t-72292-9clnd-master-0	0/1	Pending	0	0s
installer-9-ci-ln-qkgs94t-72292-9clnd-master-0	0/1	ContainerCr	eating	0 0s
installer-9-ci-ln-qkgs94t-72292-9clnd-master-0	0/1	ContainerCr	eating	0 1s
installer-9-ci-ln-qkgs94t-72292-9clnd-master-0	1/1	Running	0	2s
installer-9-ci-ln-qkgs94t-72292-9clnd-master-0	0/1	Completed	0	34s
installer-9-ci-In-qkgs94t-72292-9cInd-master-0	0/1	Completed	0	36s
installer-9-ci-In-qkgs94t-72292-9cInd-master-0	0/1	Completed	0	36s
etcd-guard-ci-ln-qkgs94t-72292-9clnd-master-0	0/1 Running		0	26m
etcd-ci-ln-qkgs94t-72292-9clnd-master-0	4/4	Terminating	0	11m
etcd-ci-ln-qkgs94t-72292-9clnd-master-0	4/4	Terminating	0	11m
etcd-ci-ln-qkgs94t-72292-9clnd-master-0	0/4	Pending	0	0s
etcd-ci-ln-qkgs94t-72292-9clnd-master-0	0/4	Init:1/3	0	1s
etcd-ci-ln-qkgs94t-72292-9clnd-master-0	0/4	Init:2/3	0	2s
etcd-ci-ln-qkgs94t-72292-9clnd-master-0	0/4	PodInitializing	g 0	3s
etcd-ci-ln-qkgs94t-72292-9clnd-master-0	3/4	Running	0	4s
etcd-guard-ci-ln-qkgs94t-72292-9clnd-master-0	1/	1 Running	0	26m
etcd-ci-ln-qkgs94t-72292-9clnd-master-0	3/4	Running	0	20s
etcd-ci-ln-qkgs94t-72292-9clnd-master-0	4/4	Running	0	20s

6. Enter the following command to review to the values:

\$ oc describe -n openshift-etcd pod/<ETCD\_PODNAME> | grep -e HEARTBEAT\_INTERVAL -e ELECTION\_TIMEOUT



#### **NOTE**

These values might not have changed from the default.

#### Additional resources

Understanding feature gates

## 1.3.5. Increasing the database size for etcd

You can set the disk quota in gibibytes (GiB) for each etcd instance. If you set a disk quota for your etcd instance, you can specify integer values from 8 to 32. The default value is 8. You can specify only increasing values.

You might want to increase the disk quota if you encounter a **low space** alert. This alert indicates that the cluster is too large to fit in etcd despite automatic compaction and defragmentation. If you see this alert, you need to increase the disk quota immediately because after etcd runs out of space, writes fail.

Another scenario where you might want to increase the disk quota is if you encounter an **excessive database growth** alert. This alert is a warning that the database might grow too large in the next four hours. In this scenario, consider increasing the disk quota so that you do not eventually encounter a **low space** alert and possible write fails.

If you increase the disk quota, the disk space that you specify is not immediately reserved. Instead, etcd can grow to that size if needed. Ensure that etcd is running on a dedicated disk that is larger than the value that you specify for the disk quota.

For large etcd databases, the control plane nodes must have additional memory and storage. Because you must account for the API server cache, the minimum memory required is at least three times the configured size of the etcd database.



#### **IMPORTANT**

Increasing the database size for etcd is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see Technology Preview Features Support Scope.

## 1.3.5.1. Changing the etcd database size

To change the database size for etcd, complete the following steps.

#### Procedure

1. Check the current value of the disk quota for each etcd instance by entering the following command:

\$ oc describe etcd/cluster | grep "Backend Quota"

## **Example output**

Backend Quota Gi B: <value>

2. Change the value of the disk quota by entering the following command:

\$ oc patch etcd/cluster --type=merge -p '{"spec": {"backendQuotaGiB": <value>}}'

## **Example output**

etcd.operator.openshift.io/cluster patched

#### Verification

- 1. Verify that the new value for the disk quota is set by entering the following command:
  - \$ oc describe etcd/cluster | grep "Backend Quota"

The etcd Operator automatically rolls out the etcd instances with the new values.

- 2. Verify that the etcd pods are up and running by entering the following command:
  - \$ oc get pods -n openshift-etcd

The following output shows the expected entries.

## Example output

NAME	READY	STATUS		RESTAR	TS	AGE	
etcd-ci-ln-b6kfsw2-72292-mzwbq-	master-0	4/4	Rι	unning	0	3	9m
etcd-ci-ln-b6kfsw2-72292-mzwbq-	master-1	4/4	Rι	unning	0	3	7m
etcd-ci-ln-b6kfsw2-72292-mzwbq-	master-2	4/4	Rι	unning	0	4	1m
etcd-guard-ci-ln-b6kfsw2-72292-m	zwbq-master	-0 1.	/1	Running	, 0		51m
etcd-guard-ci-ln-b6kfsw2-72292-m	zwbq-master	-1 1.	/1	Running	, 0		49m
etcd-guard-ci-ln-b6kfsw2-72292-m	zwbq-master	-2 1.	/1	Running	, 0		54m
installer-5-ci-ln-b6kfsw2-72292-mz	wbq-master-	1 0/1	C	Complete	d 0		51m
installer-7-ci-ln-b6kfsw2-72292-mz	wbq-master-	0 0/1	C	Complete	d 0		46m
installer-7-ci-ln-b6kfsw2-72292-mz	wbq-master-	1 0/1	C	Complete	d 0		44m
installer-7-ci-ln-b6kfsw2-72292-mz	wbq-master-	2 0/1	C	Complete	d 0		49m
installer-8-ci-ln-b6kfsw2-72292-mz	wbq-master-	0 0/1	C	Complete	d 0		40m
installer-8-ci-ln-b6kfsw2-72292-mz	wbq-master-	1 0/1	C	Complete	d 0		38m
installer-8-ci-ln-b6kfsw2-72292-mz	wbq-master-	2 0/1	C	Complete	d 0		42m
revision-pruner-7-ci-ln-b6kfsw2-72	292-mzwbq-r	master-0	0/1	Comp	leted	0	43m
revision-pruner-7-ci-ln-b6kfsw2-72	292-mzwbq-r	master-1	0/1	Comp	leted	0	43m
revision-pruner-7-ci-ln-b6kfsw2-72	292-mzwbq-r	master-2	0/1	Comp	leted	0	43m
revision-pruner-8-ci-ln-b6kfsw2-72	292-mzwbq-r	master-0	0/1	Comp	leted	0	42m
revision-pruner-8-ci-ln-b6kfsw2-72	292-mzwbq-r	master-1	0/1	Comp	leted	0	42m
revision-pruner-8-ci-ln-b6kfsw2-72	292-mzwbq-r	master-2	0/1	Comp	leted	0	42m

3. Verify that the disk quota value is updated for the etcd pod by entering the following command:

\$ oc describe -n openshift-etcd pod/<etcd\_podname> | grep "ETCD\_QUOTA\_BACKEND\_BYTES"

The value might not have changed from the default value of 8.

## **Example output**

ETCD\_QUOTA\_BACKEND\_BYTES:

8589934592



#### NOTE

While the value that you set is an integer in GiB, the value shown in the output is converted to bytes.

#### 1.3.5.2. Troubleshooting

If you encounter issues when you try to increase the database size for etcd, the following troubleshooting steps might help.

#### 1.3.5.2.1. Value is too small

If the value that you specify is less than 8, you see the following error message:

\$ oc patch etcd/cluster --type=merge -p '{"spec": {"backendQuotaGiB": 5}}'

## Example error message

The Etcd "cluster" is invalid:

- \* spec.backendQuotaGiB: Invalid value: 5: spec.backendQuotaGiB in body should be greater than or equal to 8
- \* spec.backendQuotaGiB: Invalid value: "integer": etcd backendQuotaGiB may not be decreased

To resolve this issue, specify an integer between 8 and 32.

#### 1.3.5.2.2. Value is too large

If the value that you specify is greater than 32, you see the following error message:

 $\label{lem:condition} \$ \ \text{oc patch etcd/cluster --type=merge -p '} \\ \text{"spec": } \{ \texttt{"backendQuotaGiB": 64} \} \} \\ \text{"backendQuotaGib": 64} \\ \text{"backendQuotaGib": 64} \} \\ \text{"backendQuotaGib": 64} \\ \text{"backendQu$ 

## Example error message

The Etcd "cluster" is invalid: spec.backendQuotaGiB: Invalid value: 64: spec.backendQuotaGiB in body should be less than or equal to 32

To resolve this issue, specify an integer between 8 and 32.

## 1.3.5.2.3. Value is decreasing

If the value is set to a valid value between **8** and **32**, you cannot decrease the value. Otherwise, you see an error message.

1. Check to see the current value by entering the following command:

\$ oc describe etcd/cluster | grep "Backend Quota"

## **Example output**

Backend Quota Gi B: 10

2. Decrease the disk quota value by entering the following command:

\$ oc patch etcd/cluster --type=merge -p '{"spec": {"backendQuotaGiB": 8}}'

## Example error message

The Etcd "cluster" is invalid: spec.backendQuotaGiB: Invalid value: "integer": etcd backendQuotaGiB may not be decreased

3. To resolve this issue, specify an integer greater than 10.

## **CHAPTER 2. REFERENCE DESIGN SPECIFICATIONS**

## 2.1. TELCO CORE AND RAN DU REFERENCE DESIGN SPECIFICATIONS

The telco core reference design specification (RDS) describes OpenShift Container Platform 4.16 clusters running on commodity hardware that can support large scale telco applications including control plane and some centralized data plane functions.

The telco RAN RDS describes the configuration for clusters running on commodity hardware to host 5G workloads in the Radio Access Network (RAN).

## 2.1.1. Reference design specifications for telco 5G deployments

Red Hat and certified partners offer deep technical expertise and support for networking and operational capabilities required to run telco applications on OpenShift Container Platform 4.16 clusters.

Red Hat's telco partners require a well-integrated, well-tested, and stable environment that can be replicated at scale for enterprise 5G solutions. The telco core and RAN DU reference design specifications (RDS) outline the recommended solution architecture based on a specific version of OpenShift Container Platform. Each RDS describes a tested and validated platform configuration for telco core and RAN DU use models. The RDS ensures an optimal experience when running your applications by defining the set of critical KPIs for telco 5G core and RAN DU. Following the RDS minimizes high severity escalations and improves application stability.

5G use cases are evolving and your workloads are continually changing. Red Hat is committed to iterating over the telco core and RAN DU RDS to support evolving requirements based on customer and partner feedback.

## 2.1.2. Reference design scope

The telco core and telco RAN reference design specifications (RDS) capture the recommended, tested, and supported configurations to get reliable and repeatable performance for clusters running the telco core and telco RAN profiles.

Each RDS includes the released features and supported configurations that are engineered and validated for clusters to run the individual profiles. The configurations provide a baseline OpenShift Container Platform installation that meets feature and KPI targets. Each RDS also describes expected variations for each individual configuration. Validation of each RDS includes many long duration and atscale tests.



#### **NOTE**

The validated reference configurations are updated for each major Y-stream release of OpenShift Container Platform. Z-stream patch releases are periodically re-tested against the reference configurations.

## 2.1.3. Deviations from the reference design

Deviating from the validated telco core and telco RAN DU reference design specifications (RDS) can have significant impact beyond the specific component or feature that you change. Deviations require analysis and engineering in the context of the complete solution.



### **IMPORTANT**

All deviations from the RDS should be analyzed and documented with clear action tracking information. Due diligence is expected from partners to understand how to bring deviations into line with the reference design. This might require partners to provide additional resources to engage with Red Hat to work towards enabling their use case to achieve a best in class outcome with the platform. This is critical for the supportability of the solution and ensuring alignment across Red Hat and with partners.

Deviation from the RDS can have some or all of the following consequences:

- It can take longer to resolve issues.
- There is a risk of missing project service-level agreements (SLAs), project deadlines, end provider performance requirements, and so on.
- Unapproved deviations may require escalation at executive levels.



### **NOTE**

Red Hat prioritizes the servicing of requests for deviations based on partner engagement priorities.

## 2.2. TELCO RAN DU REFERENCE DESIGN SPECIFICATION

## 2.2.1. {rds-caps} 4.16 reference design overview

The Telco RAN distributed unit (DU) 4.16 reference design configures an OpenShift Container Platform 4.16 cluster running on commodity hardware to host telco RAN DU workloads. It captures the recommended, tested, and supported configurations to get reliable and repeatable performance for a cluster running the telco RAN DU profile.

### 2.2.1.1. Deployment architecture overview

You deploy the telco RAN DU 4.16 reference configuration to managed clusters from a centrally managed RHACM hub cluster. The reference design specification (RDS) includes configuration of the managed clusters and the hub cluster components.

GitOps SiteConfig CRs PolicyGenTemplate CRs (Site installation data) (cluster profile) Hub cluster **Red Hat GitOps Operator** Advanced Cluster Management **Topology Aware** Lifecycle Manager Policy-based Assisted service governance PTP or GNSS clock source Install Deploy IPv4 or IPv6 single or dual stack networking Network far edge Spoke cluster 1 Spoke cluster 2 Spoke cluster N Single-node OpenShift DU Single-node OpenShift Supervisor node and 1 worker node DU worker node (xN) DU worker node (x1)

Figure 2.1. Telco RAN DU deployment architecture overview

### 2.2.2. Telco RAN DU use model overview

Use the following information to plan telco RAN DU workloads, cluster resources, and hardware specifications for the hub cluster and managed single-node OpenShift clusters.

## 2.2.2.1. Telco RAN DU application workloads

DU worker nodes must have 3rd Generation Xeon (Ice Lake) 2.20 GHz or better CPUs with firmware tuned for maximum performance.

5G RAN DU user applications and workloads should conform to the following best practices and application limits:

 Develop cloud-native network functions (CNFs) that conform to the latest version of the CNF best practices guide.

- Use SR-IOV for high performance networking.
- Use exec probes sparingly and only when no other suitable options are available
  - Do not use exec probes if a CNF uses CPU pinning. Use other probe implementations, for example, **httpGet** or **tcpSocket**.
  - When you need to use exec probes, limit the exec probe frequency and quantity. The maximum number of exec probes must be kept below 10, and frequency must not be set to less than 10 seconds.
- Avoid using exec probes unless there is absolutely no viable alternative.



#### **NOTE**

Startup probes require minimal resources during steady-state operation. The limitation on exec probes applies primarily to liveness and readiness probes.

### 2.2.2.2. Telco RAN DU representative reference application workload characteristics

The representative reference application workload has the following characteristics:

- Has a maximum of 15 pods and 30 containers for the vRAN application including its management and control functions
- Uses a maximum of 2 **ConfigMap** and 4 **Secret** CRs per pod
- Uses a maximum of 10 exec probes with a frequency of not less than 10 seconds
- Incremental application load on the kube-apiserver is less than 10% of the cluster platform usage



### **NOTE**

You can extract CPU load can from the platform metrics. For example:

query=avg\_over\_time(pod:container\_cpu\_usage:sum{namespace="openshift-kube-apiserver"}[30m])

- Application logs are not collected by the platform log collector
- Aggregate traffic on the primary CNI is less than 1 MBps

#### 2.2.2.3. Telco RAN DU worker node cluster resource utilization

The maximum number of running pods in the system, inclusive of application workloads and OpenShift Container Platform pods, is 120.

### Resource utilization

OpenShift Container Platform resource utilization varies depending on many factors including application workload characteristics such as:

- Pod count
- Type and frequency of probes

- Messaging rates on primary CNI or secondary CNI with kernel networking
- API access rate
- Logging rates
- Storage IOPS

Cluster resource requirements are applicable under the following conditions:

- The cluster is running the described representative application workload.
- The cluster is managed with the constraints described in "Telco RAN DU worker node cluster resource utilization".
- Components noted as optional in the RAN DU use model configuration are not applied.



### **IMPORTANT**

You will need to do additional analysis to determine the impact on resource utilization and ability to meet KPI targets for configurations outside the scope of the Telco RAN DU reference design. You might have to allocate additional resources in the cluster depending on your requirements.

#### Additional resources

• Telco RAN DU 4.16 validated software components

### 2.2.2.4. Hub cluster management characteristics

Red Hat Advanced Cluster Management (RHACM) is the recommended cluster management solution. Configure it to the following limits on the hub cluster:

- Configure a maximum of 5 RHACM policies with a compliant evaluation interval of at least 10 minutes.
- Use a maximum of 10 managed cluster templates in policies. Where possible, use hub-side templating.
- Disable all RHACM add-ons except for the **policy-controller** and **observability-controller** add-ons. Set **Observability** to the default configuration.



## **IMPORTANT**

Configuring optional components or enabling additional features will result in additional resource usage and can reduce overall system performance.

For more information, see Reference design deployment components.


Table 2.1. OpenShift platform resource utilization under reference application load

Metric	Limit	Notes
CPU usage	Less than 4000 mc – 2 cores (4 hyperthreads)	Platform CPU is pinned to reserved cores, including both hyperthreads in each reserved core. The system is engineered to use 3 CPUs (3000mc) at steady-state to allow for periodic system tasks and spikes.
Memory used	Less than 16G	

## 2.2.2.5. Telco RAN DU RDS components

The following sections describe the various OpenShift Container Platform components and configurations that you use to configure and deploy clusters to run telco RAN DU workloads.

Figure 2.2. Telco RAN DU reference design components



319\_OpenShift\_1023



## **NOTE**

Ensure that components that are not included in the telco RAN DU profile do not affect the CPU resources allocated to workload applications.



### **IMPORTANT**

Out of tree drivers are not supported.

### Additional resources

• For details of the telco RAN RDS KPI test results, see Telco RAN DU reference design specification KPI test results. This information is only available to customers and partners.

# 2.2.3. Telco RAN DU 4.16 reference design components

The following sections describe the various OpenShift Container Platform components and configurations that you use to configure and deploy clusters to run RAN DU workloads.

## 2.2.3.1. Host firmware tuning

#### New in this release

• No reference design updates in this release

## Description

Configure system level performance. See Configuring host firmware for low latency and high performance for recommended settings.

If Ironic inspection is enabled, the firmware setting values are available from the per-cluster **BareMetalHost** CR on the hub cluster. You enable Ironic inspection with a label in the **spec.clusters.nodes** field in the **SiteConfig** CR that you use to install the cluster. For example:

### nodes:

- hostName: "example-node1.example.com" ironicInspect: "enabled"



#### NOTE

The telco RAN DU reference **SiteConfig** does not enable the **ironicInspect** field by default.

#### Limits and requirements

• Hyperthreading must be enabled

## **Engineering considerations**

• Tune all settings for maximum performance



### NOTE

You can tune firmware selections for power savings at the expense of performance as required.

## 2.2.3.2. Node Tuning Operator

#### New in this release

- With this release, the Node Tuning Operator supports setting CPU frequencies in the PerformanceProfile for reserved and isolated core CPUs. This is an optional feature that you can use to define specific frequencies. Use this feature to set specific frequencies by enabling the intel\_pstate CPUFreq driver in the Intel hardware. You must follow Intel's recommendations on frequencies for FlexRAN-like applications, which requires the default CPU frequency to be set to a lower value than default running frequency.
- Previously, for the RAN DU-profile, setting the realTime workload hint to true in the PerformanceProfile always disabled the intel\_pstate. With this release, the Node Tuning Operator detects the underlying Intel hardware using TuneD and appropriately sets the intel\_pstate kernel parameter based on the processor's generation.
- In this release, OpenShift Container Platform deployments with a performance profile now default to using cgroups v2 as the underlying resource management layer. If you run workloads that are not ready for this change, you can still revert to using the older cgroups v1 mechanism.

## Description

You tune the cluster performance by creating a performance profile. Settings that you configure with a performance profile include:

- Selecting the realtime or non-realtime kernel.
- Allocating cores to a reserved or isolated **cpuset**. OpenShift Container Platform processes allocated to the management workload partition are pinned to reserved set.
- Enabling kubelet features (CPU manager, topology manager, and memory manager).
- Configuring huge pages.
- Setting additional kernel arguments.
- Setting per-core power tuning and max CPU frequency.
- Reserved and isolated core frequency tuning.

### Limits and requirements

The Node Tuning Operator uses the **PerformanceProfile** CR to configure the cluster. You need to configure the following settings in the RAN DU profile **PerformanceProfile** CR:

- Select reserved and isolated cores and ensure that you allocate at least 4 hyperthreads (equivalent to 2 cores) on Intel 3rd Generation Xeon (Ice Lake) 2.20 GHz CPUs or better with firmware tuned for maximum performance.
- Set the reserved **cpuset** to include both hyperthread siblings for each included core. Unreserved cores are available as allocatable CPU for scheduling workloads. Ensure that hyperthread siblings are not split across reserved and isolated cores.
- Configure reserved and isolated CPUs to include all threads in all cores based on what you have set as reserved and isolated CPUs.
- Set core 0 of each NUMA node to be included in the reserved CPU set.
- Set the huge page size to 1G.



### **NOTE**

You should not add additional workloads to the management partition. Only those pods which are part of the OpenShift management platform should be annotated into the management partition.

### **Engineering considerations**

• You should use the RT kernel to meet performance requirements.



#### NOTE

You can use the non-RT kernel if required.

- The number of huge pages that you configure depends on the application workload requirements. Variation in this parameter is expected and allowed.
- Variation is expected in the configuration of reserved and isolated CPU sets based on selected hardware and additional components in use on the system. Variation must still meet the specified limits.
- Hardware without IRQ affinity support impacts isolated CPUs. To ensure that pods with guaranteed whole CPU QoS have full use of the allocated CPU, all hardware in the server must support IRQ affinity. For more information, see About support of IRQ affinity setting.



#### **IMPORTANT**

cgroup v1 is a deprecated feature. Deprecated functionality is still included in OpenShift Container Platform and continues to be supported; however, it will be removed in a future release of this product and is not recommended for new deployments.

For the most recent list of major functionality that has been deprecated or removed within OpenShift Container Platform, refer to the *Deprecated and removed features* section of the OpenShift Container Platform release notes.

### 2.2.3.3. PTP Operator

### New in this release

- Configuring linuxptp services as grandmaster clock (T-GM) for dual Intel E810 Westport Channel NICs is now a generally available feature.
- You can configure the **linuxptp** services **ptp4l** and **phc2sys** as a highly available (HA) system clock for dual PTP boundary clocks (T-BC).

### Description

See PTP timing for details of support and configuration of PTP in cluster nodes. The DU node can run in the following modes:

- As an ordinary clock (OC) synced to a grandmaster clock or boundary clock (T-BC)
- As a grandmaster clock synced from GPS with support for single or dual card E810 Westport Channel NICs.

- As dual boundary clocks (one per NIC) with support for E810 Westport Channel NICs
- Allow for High Availability of the system clock when there are multiple time sources on different NICs.
- Optional: as a boundary clock for radio units (RUs)

Events and metrics for grandmaster clocks are a Tech Preview feature added in the 4.14 telco RAN DU RDS. For more information see Using the PTP hardware fast event notifications framework .

You can subscribe applications to PTP events that happen on the node where the DU application is running.

### Limits and requirements

- Limited to two boundary clocks for dual NIC and HA
- Limited to two WPC card configuration for T-GM

### **Engineering considerations**

- Configurations are provided for ordinary clock, boundary clock, grandmaster clock, or PTP-HA
- PTP fast event notifications uses **ConfigMap** CRs to store PTP event subscriptions
- Use Intel E810-XXV-4T Westport Channel NICs for PTP grandmaster clocks with GPS timing, minimum firmware version 4.40

### 2.2.3.4. SR-IOV Operator

### New in this release

- With this release, you can use the SR-IOV Network Operator to configure QinQ (802.1ad and 802.1q) tagging. QinQ tagging provides efficient traffic management by enabling the use of both inner and outer VLAN tags. Outer VLAN tagging is hardware accelerated, leading to faster network performance. The update extends beyond the SR-IOV Network Operator itself. You can now configure QinQ on externally managed VFs by setting the outer VLAN tag using nmstate. QinQ support varies across different NICs. For a comprehensive list of known limitations for specific NIC models, see Configuring QinQ support for SR-IOV enabled workloads in the Additional resources section.
- With this release, you can configure the SR-IOV Network Operator to drain nodes in parallel
  during network policy updates, dramatically accelerating the setup process. This translates to
  significant time savings, especially for large cluster deployments that previously took hours
  or even days to complete.

### Description

The SR-IOV Operator provisions and configures the SR-IOV CNI and device plugins. Both **netdevice** (kernel VFs) and **vfio** (DPDK) devices are supported.

### Limits and requirements

Use OpenShift Container Platform supported devices

- SR-IOV and IOMMU enablement in BIOS: The SR-IOV Network Operator will automatically enable IOMMU on the kernel command line.
- SR-IOV VFs do not receive link state updates from the PF. If link down detection is needed you must configure this at the protocol level.
- You can apply multi-network policies on **netdevice** drivers types only. Multi-network policies require the **iptables** tool, which cannot manage **vfio** driver types.

## **Engineering considerations**

- SR-IOV interfaces with the **vfio** driver type are typically used to enable additional secondary networks for applications that require high throughput or low latency.
- Customer variation on the configuration and number of SriovNetwork and SriovNetworkNodePolicy custom resources (CRs) is expected.
- IOMMU kernel command line settings are applied with a MachineConfig CR at install time.
   This ensures that the SriovOperator CR does not cause a reboot of the node when adding them.
- SR-IOV support for draining nodes in parallel is not applicable in a single-node OpenShift cluster.
- If you exclude the **SriovOperatorConfig** CR from your deployment, the CR will not be created automatically.
- In scenarios where you pin or restrict workloads to specific nodes, the SR-IOV parallel node drain feature will not result in the rescheduling of pods. In these scenarios, the SR-IOV Operator disables the parallel node drain functionality.

### Additional resources

- Preparing the GitOps ZTP site configuration repository for version independence
- Configuring QinQ support for SR-IOV enabled workloads

### 2.2.3.5. Logging

#### New in this release

• No reference design updates in this release

### Description

Use logging to collect logs from the far edge node for remote analysis. The recommended log collector is Vector.

### **Engineering considerations**

- Handling logs beyond the infrastructure and audit logs, for example, from the application workload requires additional CPU and network bandwidth based on additional logging rate.
- As of OpenShift Container Platform 4.14, Vector is the reference log collector.



### **NOTE**

Use of fluentd in the RAN use model is deprecated.

### 2.2.3.6. SRIOV-FEC Operator

#### New in this release

• No reference design updates in this release

### Description

SRIOV-FEC Operator is an optional 3rd party Certified Operator supporting FEC accelerator bardware

### Limits and requirements

- Starting with FEC Operator v2.7.0:
  - SecureBoot is supported
  - The vfio driver for the PF requires the usage of vfio-token that is injected into Pods.
     Applications in the pod can pass the VF token to DPDK by using the EAL parameter --vfio-vf-token.

### **Engineering considerations**

- The SRIOV-FEC Operator uses CPU cores from the **isolated** CPU set.
- You can validate FEC readiness as part of the pre-checks for application deployment, for example, by extending the validation policy.

## 2.2.3.7. Local Storage Operator

### New in this release

• No reference design updates in this release

### Description

You can create persistent volumes that can be used as **PVC** resources by applications with the Local Storage Operator. The number and type of **PV** resources that you create depends on your requirements.

### **Engineering considerations**

- Create backing storage for PV CRs before creating the PV. This can be a partition, a local volume, LVM volume, or full disk.
- Refer to the device listing in LocalVolume CRs by the hardware path used to access each device to ensure correct allocation of disks and partitions. Logical names (for example, /dev/sda) are not guaranteed to be consistent across node reboots.
   For more information, see the RHEL 9 documentation on device identifiers.

### 2.2.3.8. LVMS Operator

#### New in this release

• No reference design updates in this release



### NOTE

LVMS Operator is an optional component.

When you use the LVMS Operator as the storage solution, it replaces the Local Storage Operator, and the CPU required will be assigned to the management partition as platform overhead. The reference configuration must include one of these storage solutions but not both.

### Description

The LVMS Operator provides dynamic provisioning of block and file storage. The LVMS Operator creates logical volumes from local devices that can be used as **PVC** resources by applications. Volume expansion and snapshots are also possible.

The following example configuration creates a **vg1** volume group that leverages all available disks on the node except the installation disk:

### StorageLVMCluster.yaml

apiVersion: lvm.topolvm.io/v1alpha1

kind: LVMCluster

metadata:

name: storage-lymcluster namespace: openshift-storage

annotations:

ran.openshift.io/ztp-deploy-wave: "10"

spec: storage:

deviceClasses:

name: vg1 thinPoolConfig: name: thin-pool-1 sizePercent: 90

overprovisionRatio: 10

## Limits and requirements

 In single-node OpenShift clusters, persistent storage must be provided by either LVMS or local storage, not both.

### **Engineering considerations**

• Ensure that sufficient disks or partitions are available for storage requirements.

## 2.2.3.9. Workload partitioning

#### New in this release

• No reference design updates in this release

### Description

Workload partitioning pins OpenShift platform and Day 2 Operator pods that are part of the DU profile to the reserved **cpuset** and removes the reserved CPU from node accounting. This leaves all unreserved CPU cores available for user workloads.

The method of enabling and configuring workload partitioning changed in OpenShift Container Platform 4.14.

#### 4.14 and later

- Configure partitions by setting installation parameters:
  - cpuPartitioningMode: AllNodes
- Configure management partition cores with the reserved CPU set in the PerformanceProfile CR

#### 4.13 and earlier

• Configure partitions with extra **MachineConfiguration** CRs applied at install-time

## Limits and requirements

- **Namespace** and **Pod** CRs must be annotated to allow the pod to be applied to the management partition
- Pods with CPU limits cannot be allocated to the partition. This is because mutation can change the pod QoS.
- For more information about the minimum number of CPUs that can be allocated to the management partition, see Node Tuning Operator.

### **Engineering considerations**

Workload Partitioning pins all management pods to reserved cores. A sufficient number of
cores must be allocated to the reserved set to account for operating system, management
pods, and expected spikes in CPU use that occur when the workload starts, the node
reboots, or other system events happen.

### 2.2.3.10. Cluster tuning

#### New in this release

• No reference design updates in this release

### Description

See the section *Cluster capabilities* section for a full list of optional components that you enable or disable before installation.

### Limits and requirements

- Cluster capabilities are not available for installer-provisioned installation methods.
- You must apply all platform tuning configurations. The following table lists the required platform tuning configurations:

Table 2.2. Cluster capabilities configurations

Feature	Description
Remove optional cluster capabilities	Reduce the OpenShift Container Platform footprint by disabling optional cluster Operators on single-node OpenShift clusters only.  • Remove all optional Operators except the Marketplace and Node Tuning Operators.
Configure cluster monitoring	Configure the monitoring stack for reduced footprint by doing the following:  O Disable the local alertmanager and telemeter components.  O If you use RHACM observability, the CR must be augmented with appropriate additional AlertManagerConfigs CRs to forward alerts to the hub cluster.  O Reduce the Prometheus retention period to 24h.  NOTE  The RHACM hub cluster aggregates managed cluster metrics.
Disable networking diagnostics	Disable networking diagnostics for single-node OpenShift because they are not required.
Configure a single OperatorHub catalog source	Configure the cluster to use a single catalog source that contains only the Operators required for a RAN DU deployment. Each catalog source increases the CPU use on the cluster. Using a single <b>CatalogSource</b> fits within the platform CPU budget.

## **Engineering considerations**

• In this release, OpenShift Container Platform deployments use Control Groups version 2 (cgroup v2) by default. As a consequence, performance profiles in a cluster use cgroups v2 for the underlying resource management layer. If workloads running on the cluster require cgroups v1, you can configure nodes to use cgroups v1. You can make this configuration as part of the initial cluster deployment.

# 2.2.3.11. Machine configuration

### New in this release

• No reference design updates in this release

## Limits and requirements

• The CRI-O wipe disable **MachineConfig** assumes that images on disk are static other than during scheduled maintenance in defined maintenance windows. To ensure the images are static, do not set the pod **imagePullPolicy** field to **Always**.

Table 2.3. Machine configuration options

Feature	Description
Container runtime	Sets the container runtime to <b>crun</b> for all node roles.
kubelet config and container mount hiding	Reduces the frequency of kubelet housekeeping and eviction monitoring to reduce CPU usage. Create a container mount namespace, visible to kubelet and CRI-O, to reduce system mount scanning resource usage.
SCTP	Optional configuration (enabled by default) Enables SCTP. SCTP is required by RAN applications but disabled by default in RHCOS.
kdump	Optional configuration (enabled by default) Enables kdump to capture debug information when a kernel panic occurs.
CRI-O wipe disable	Disables automatic wiping of the CRI-O image cache after unclean shutdown.
SR-IOV-related kernel arguments	Includes additional SR-IOV related arguments in the kernel command line.
RCU Normal systemd service	Sets <b>rcu_normal</b> after the system is fully started.
One-shot time sync	Runs a one-time system time synchronization job for control plane or worker nodes.

# 2.2.3.12. Lifecycle Agent

## New in this release

• Use the Lifecycle Agent to enable image-based upgrades for single-node OpenShift clusters.

### Description

The Lifecycle Agent provides local lifecycle management services for single-node OpenShift clusters.

#### Limits and requirements

- The Lifecycle Agent is not applicable in multi-node clusters or single-node OpenShift clusters with an additional worker.
- Requires a persistent volume.

#### Additional resources

• Understanding the image-based upgrade for single-node OpenShift clusters

### 2.2.3.13. Reference design deployment components

The following sections describe the various OpenShift Container Platform components and configurations that you use to configure the hub cluster with Red Hat Advanced Cluster Management (RHACM).

### 2.2.3.13.1. Red Hat Advanced Cluster Management (RHACM)

#### New in this release

 You can now use **PolicyGenerator** resources and Red Hat Advanced Cluster Management (RHACM) to deploy polices for managed clusters with GitOps ZTP. This is a Technology Preview feature.

## Description

RHACM provides Multi Cluster Engine (MCE) installation and ongoing lifecycle management functionality for deployed clusters. You declaratively specify configurations and upgrades with **Policy** CRs and apply the policies to clusters with the RHACM policy controller as managed by Topology Aware Lifecycle Manager.

- GitOps Zero Touch Provisioning (ZTP) uses the MCE feature of RHACM
- Configuration, upgrades, and cluster status are managed with the RHACM policy controller

During installation RHACM can apply labels to individual nodes as configured in the **SiteConfig** custom resource (CR).

### Limits and requirements

• A single hub cluster supports up to 3500 deployed single-node OpenShift clusters with 5 **Policy** CRs bound to each cluster.

## **Engineering considerations**

- Use RHACM policy hub-side templating to better scale cluster configuration. You can significantly reduce the number of policies by using a single group policy or small number of general group policies where the group and per-cluster values are substituted into templates.
- Cluster specific configuration: managed clusters typically have some number of

configuration values that are specific to the individual cluster. These configurations should be managed using RHACM policy hub-side templating with values pulled from **ConfigMap** CRs based on the cluster name.

• To save CPU resources on managed clusters, policies that apply static configurations should be unbound from managed clusters after GitOps ZTP installation of the cluster.

### 2.2.3.13.2. Topology Aware Lifecycle Manager (TALM)

#### New in this release

• No reference design updates in this release

## Description

## Managed updates

TALM is an Operator that runs only on the hub cluster for managing how changes (including cluster and Operator upgrades, configuration, and so on) are rolled out to the network. TALM does the following:

- Progressively applies updates to fleets of clusters in user-configurable batches by using Policy CRs.
- Adds ztp-done labels or other user configurable labels on a per-cluster basis

### Precaching for single-node OpenShift clusters

operatorsIndexes:

TALM supports optional precaching of OpenShift Container Platform, OLM Operator, and additional user images to single-node OpenShift clusters before initiating an upgrade.

• A **PreCachingConfig** custom resource is available for specifying optional pre-caching configurations. For example:

```
apiVersion: ran.openshift.io/v1alpha1
kind: PreCachingConfig
metadata:
 name: example-config
 namespace: example-ns
spec:
 additionallmages:
quay.io/foobar/application1@sha256:3d5800990dee7cd4727d3fe238a97e2d2976d380
8fc925ada29c559a47e2e
quay.io/foobar/application2@sha256:3d5800123dee7cd4727d3fe238a97e2d2976d380
8fc925ada29c559a47adf
quay.io/foobar/applicationN@sha256:4fe1334adfafadsf987123adfffdaf1243340adfafde
dga0991234afdadfs
 spaceRequired: 45 GiB 1
 overrides:
  preCacheImage: quay.io/test_images/pre-cache:latest
  platformImage: quay.io/openshift-release-dev/ocp-
release@sha256:3d5800990dee7cd4727d3fe238a97e2d2976d3808fc925ada29c559a4
```

- registry.example.com:5000/custom-redhat-operators:1.0.0 operatorsPackagesAndChannels:
  - local-storage-operator: stable
  - ptp-operator: stable
- sriov-network-operator: stable excludePrecachePatterns: 2
  - awsvsphere
- 111 Configurable **space-required** parameter allows you to validate before and after pre-caching storage space
- 2 Configurable filtering allows exclusion of unused images

## Limits and requirements

- TALM supports concurrent cluster deployment in batches of 400
- Precaching and backup features are for single-node OpenShift clusters only.

### **Engineering considerations**

• The **PreCachingConfig** CR is optional and does not need to be created if you just wants to precache platform related (OpenShift and OLM Operator) images. The **PreCachingConfig** CR must be applied before referencing it in the **ClusterGroupUpgrade** CR.

### 2.2.3.13.3. GitOps and GitOps ZTP plugins

### New in this release

• No reference design updates in this release

## Description

GitOps and GitOps ZTP plugins provide a GitOps-based infrastructure for managing cluster deployment and configuration. Cluster definitions and configurations are maintained as a declarative state in Git. ZTP plugins provide support for generating installation CRs from the **SiteConfig** CR and automatic wrapping of configuration CRs in policies based on **PolicyGenTemplate** CRs.

You can deploy and manage multiple versions of OpenShift Container Platform on managed clusters using the baseline reference configuration CRs. You can also use custom CRs alongside the baseline CRs.

### Limits

- 300 **SiteConfig** CRs per ArgoCD application. You can use multiple applications to achieve the maximum number of clusters supported by a single hub cluster.
- Content in the /source-crs folder in Git overrides content provided in the GitOps ZTP plugin container. Git takes precedence in the search path.
- Add the /source-crs folder in the same directory as the **kustomization.yaml** file, which includes the **PolicyGenTemplate** as a generator.



#### NOTE

Alternative locations for the /**source-crs** directory are not supported in this context.

## **Engineering considerations**

- To avoid confusion or unintentional overwriting of files when updating content, use unique and distinguishable names for user-provided CRs in the /source-crs folder and extra manifests in Git.
- The SiteConfig CR allows multiple extra-manifest paths. When files with the same name are
  found in multiple directory paths, the last file found takes precedence. This allows you to put
  the full set of version-specific Day 0 manifests (extra-manifests) in Git and reference them
  from the SiteConfig CR. With this feature, you can deploy multiple OpenShift Container
  Platform versions to managed clusters simultaneously.
- The **extraManifestPath** field of the **SiteConfig** CR is deprecated from OpenShift Container Platform 4.15 and later. Use the new **extraManifests.searchPaths** field instead.

#### Additional resources

- Preparing the GitOps ZTP site configuration repository for version independence
- Adding custom content to the GitOps ZTP pipeline

### 2.2.3.13.4. Agent-based installer

#### New in this release

• No reference design updates in this release

### Description

Agent-based installer (ABI) provides installation capabilities without centralized infrastructure. The installation program creates an ISO image that you mount to the server. When the server boots it installs OpenShift Container Platform and supplied extra manifests.



### **NOTE**

You can also use ABI to install OpenShift Container Platform clusters without a hub cluster. An image registry is still required when you use ABI in this manner.

Agent-based installer (ABI) is an optional component.

### Limits and requirements

- You can supply a limited set of additional manifests at installation time.
- You must include **MachineConfiguration** CRs that are required by the RAN DU use case.

### **Engineering considerations**

• ABI provides a baseline OpenShift Container Platform installation.

 You install Day 2 Operators and the remainder of the RAN DU use case configurations after installation.

# 2.2.4. Telco RAN distributed unit (DU) reference configuration CRs

Use the following custom resources (CRs) to configure and deploy OpenShift Container Platform clusters with the telco RAN DU profile. Some of the CRs are optional depending on your requirements. CR fields you can change are annotated in the CR with YAML comments.



### **NOTE**

You can extract the complete set of RAN DU CRs from the **ztp-site-generate** container image. See Preparing the GitOps ZTP site configuration repository for more information.

## 2.2.4.1. Day 2 Operators reference CRs

Table 2.4. Day 2 Operators CRs

Component	Reference CR	Optional	New in this release
Cluster logging	ClusterLogForwarder.ya ml	No	No
Cluster logging	ClusterLogging.yaml	No	No
Cluster logging	ClusterLogNS.yaml	No	No
Cluster logging	ClusterLogOperGroup.y	No	No
Cluster logging	ClusterLogSubscription.	No	No
Local Storage Operator	StorageClass.yaml	Yes	No
Local Storage Operator	StorageLV.yaml	Yes	No
Local Storage Operator	StorageNS.yaml	Yes	No
Local Storage Operator	StorageOperGroup.yam	Yes	No
Local Storage Operator	StorageSubscription.ya ml	Yes	No
Lifecycle Agent	ImageBasedUpgrade.ya ml	Yes	Yes
Lifecycle Agent	LcaSubscription.yaml	Yes	Yes

Component	Reference CR	Optional	New in this release
Lifecycle Agent	LcaSubscriptionNS.yaml	Yes	Yes
Lifecycle Agent	LcaSubscriptionOperGr oup.yaml	Yes	Yes
LVM Storage	LVMOperatorStatus.ya ml	No	Yes
LVM Storage	StorageLVMCluster.yam	No	Yes
LVM Storage	StorageLVMSubscriptio n.yaml	No	Yes
LVM Storage	StorageLVMSubscriptio nNS.yaml	No	Yes
LVM Storage	StorageLVMSubscriptio nOperGroup.yaml	No	Yes
Node Tuning Operator	PerformanceProfile.yam	No	No
Node Tuning Operator	TunedPerformancePatc h.yaml	No	No
PTP fast event notifications	PtpConfigBoundaryFor Event.yaml	Yes	Yes
PTP fast event notifications	PtpConfigDualCardGm Wpc.yaml	Yes	Yes
PTP fast event notifications	PtpConfigForHAForEve nt.yaml	Yes	Yes
PTP fast event notifications	PtpConfigGmWpc.yaml	Yes	Yes
PTP fast event notifications	PtpConfigMasterForEve nt.yaml	Yes	Yes
PTP fast event notifications	PtpConfigSlaveForEven t.yaml	Yes	Yes
PTP fast event notifications	PtpOperatorConfigForE vent.yaml	Yes	No

Component	Reference CR	Optional	New in this release
PTP Operator	PtpConfigBoundary.yam	No	No
PTP Operator	PtpConfigDualCardGm Wpc.yaml	No	No
PTP Operator	PtpConfigForHA.yaml	No	Yes
PTP Operator	PtpConfigGmWpc.yaml	No	No
PTP Operator	PtpConfigSlave.yaml	No	No
PTP Operator	PtpSubscription.yaml	No	No
PTP Operator	PtpSubscriptionNS.yaml	No	No
PTP Operator	PtpSubscriptionOperGr oup.yaml	No	No
SR-IOV FEC Operator	AcceleratorsNS.yaml	Yes	No
SR-IOV FEC Operator	AcceleratorsOperGroup.	Yes	No
SR-IOV FEC Operator	AcceleratorsSubscriptio n.yaml	Yes	No
SR-IOV FEC Operator	SriovFecClusterConfig.y aml	Yes	No
SR-IOV Operator	SriovNetwork.yaml	No	No
SR-IOV Operator	SriovNetworkNodePolic y.yaml	No	No
SR-IOV Operator	SriovOperatorConfig.ya ml	No	No
SR-IOV Operator	SriovOperatorConfigFor SNO.yaml	No	Yes
SR-IOV Operator	SriovSubscription.yaml	No	No
SR-IOV Operator	SriovSubscriptionNS.ya ml	No	No

Component	Reference CR	Optional	New in this release
SR-IOV Operator	SriovSubscriptionOperG roup.yaml	No	No

# 2.2.4.2. Cluster tuning reference CRs

Table 2.5. Cluster tuning CRs

Component	Reference CR	Optional	New in this release
Cluster capabilities	example-sno.yaml	No	No
Disabling network diagnostics	DisableSnoNetworkDiag .yaml	No	No
Monitoring configuration	ReduceMonitoringFootp rint.yaml	No	No
OperatorHub	DefaultCatsrc.yaml	No	No
OperatorHub	DisableOLMPprof.yaml	No	No
OperatorHub	DisconnectedICSP.yaml	No	No
OperatorHub	Operator Hub. yaml	Yes	No
OperatorHub	09-openshift- marketplace-ns.yaml	No	No

# 2.2.4.3. Machine configuration reference CRs

Table 2.6. Machine configuration CRs

Component	Reference CR	Optional	New in this release
Container runtime (crun)	enable-crun- master.yaml	No	No
Container runtime (crun)	enable-crun- worker.yaml	No	No
Disabling CRI-O wipe	99-crio-disable-wipe- master.yaml	No	No
Disabling CRI-O wipe	99-crio-disable-wipe- worker.yaml	No	No

Component	Reference CR	Optional	New in this release
Enabling kdump	06-kdump-master.yaml	No	No
Enabling kdump	06-kdump-worker.yaml	No	No
Kubelet configuration and container mount hiding	O1-container-mount-ns- and-kubelet-conf- master.yaml	No	No
Kubelet configuration and container mount hiding	O1-container-mount-ns- and-kubelet-conf- worker.yaml	No	No
One-shot time sync	99-sync-time-once- master.yaml	No	No
One-shot time sync	99-sync-time-once- worker.yaml	No	No
SCTP	03-sctp-machine- config-master.yaml	No	No
SCTP	03-sctp-machine- config-worker.yaml	No	No
Set RCU Normal	08-set-rcu-normal- master.yaml	No	No
Set RCU Normal	08-set-rcu-normal- worker.yaml	No	No
SR-IOV related kernel arguments	07-sriov-related- kernel-args-master.yaml	No	Yes
SR-IOV related kernel arguments	07-sriov-related- kernel-args-worker.yaml	No	No

## 2.2.4.4. YAML reference

The following is a complete reference for all the custom resources (CRs) that make up the telco RAN DU 4.16 reference configuration.

# 2.2.4.4.1. Day 2 Operators reference YAML

# ClusterLogForwarder.yaml

apiVersion: "logging.openshift.io/v1" kind: ClusterLogForwarder

```
metadata:
 name: instance
 namespace: openshift-logging
 annotations: {}
spec:
# outputs: $outputs
# pipelines: $pipelines
#apiVersion: "logging.openshift.io/v1"
#kind: ClusterLogForwarder
#metadata:
# name: instance
# namespace: openshift-logging
#spec:
# outputs:
# - type: "kafka"
# name: kafka-open
#
   url: tcp://10.46.55.190:9092/test
# pipelines:
# - inputRefs:
# - audit
# - infrastructure
# labels:
# label1: test1
# label2: test2
# label3: test3
# label4: test4
# name: all-to-default
# outputRefs:
# - kafka-open
```

### ClusterLogging.yaml

```
apiVersion: logging.openshift.io/v1
kind: ClusterLogging
metadata:
name: instance
namespace: openshift-logging
annotations: {}
spec:
managementState: "Managed"
collection:
type: "vector"
```

### ClusterLogNS.yaml

```
apiVersion: v1
kind: Namespace
metadata:
name: openshift-logging
annotations:
workload.openshift.io/allowed: management
```

## ClusterLogOperGroup.yaml

apiVersion: operators.coreos.com/v1 kind: OperatorGroup metadata: name: cluster-logging namespace: openshift-logging annotations: {} spec: targetNamespaces:

## ClusterLogSubscription.yaml

- openshift-logging

apiVersion: operators.coreos.com/v1alpha1 kind: Subscription metadata:
 name: cluster-logging
 namespace: openshift-logging
 annotations: {}
spec:
 channel: "stable"
 name: cluster-logging
 source: redhat-operators-disconnected
 sourceNamespace: openshift-marketplace
 installPlanApproval: Manual
 status:
 state: AtLatestKnown

### StorageClass.yaml

apiVersion: storage.k8s.io/v1 kind: StorageClass metadata: annotations: {} name: example-storage-class provisioner: kubernetes.io/no-provisioner reclaimPolicy: Delete

## StorageLV.yaml

apiVersion: "local.storage.openshift.io/v1"
kind: "LocalVolume"
metadata:
name: "local-disks"
namespace: "openshift-local-storage"
annotations: {}
spec:
logLevel: Normal
managementState: Managed
storageClassDevices:
# The list of storage classes and associated devicePaths need to be specified like this example:
- storageClassName: "example-storage-class"
volumeMode: Filesystem
fsType: xfs

```
# The below must be adjusted to the hardware.
   # For stability and reliability, it's recommended to use persistent
   # naming conventions for devicePaths, such as /dev/disk/by-path.
   devicePaths:
    - /dev/disk/by-path/pci-0000:05:00.0-nvme-1
## How to verify
## 1. Create a PVC
# apiVersion: v1
# kind: PersistentVolumeClaim
# metadata:
# name: local-pvc-name
# spec:
# accessModes:
# - ReadWriteOnce
# volumeMode: Filesystem
# resources:
# requests:
   storage: 100Gi
# storageClassName: example-storage-class
## 2. Create a pod that mounts it
# apiVersion: v1
# kind: Pod
# metadata:
# labels:
# run: busybox
# name: busybox
# spec:
# containers:
# - image: quay.io/quay/busybox:latest
# name: busybox
# resources: {}
# command: ["/bin/sh", "-c", "sleep infinity"]
# volumeMounts:
#
  - name: local-pvc
#
   mountPath: /data
# volumes:
# - name: local-pvc
# persistentVolumeClaim:
   claimName: local-pvc-name
#
# dnsPolicy: ClusterFirst
# restartPolicy: Always
## 3. Run the pod on the cluster and verify the size and access of the `/data` mount
```

## StorageNS.yaml

```
apiVersion: v1
kind: Namespace
metadata:
name: openshift-local-storage
annotations:
workload.openshift.io/allowed: management
```

### StorageOperGroup.yaml

```
apiVersion: operators.coreos.com/v1
kind: OperatorGroup
metadata:
name: openshift-local-storage
namespace: openshift-local-storage
annotations: {}
spec:
targetNamespaces:
- openshift-local-storage
```

### StorageSubscription.yaml

```
apiVersion: operators.coreos.com/v1alpha1kind: Subscription
metadata:
    name: local-storage-operator
    namespace: openshift-local-storage
    annotations: {}
spec:
    channel: "stable"
    name: local-storage-operator
    source: redhat-operators-disconnected
    sourceNamespace: openshift-marketplace
    installPlanApproval: Manual
    status:
    state: AtLatestKnown
```

### ImageBasedUpgrade.yaml

```
apiVersion: lca.openshift.io/v1alpha1
kind: ImageBasedUpgrade
metadata:
name: upgrade
spec:
stage: Idle
# When setting `stage: Prep`, remember to add the seed image reference object below.
# seedImageRef:
# image: $image
# version: $version
```

## LcaSubscription.yaml

```
apiVersion: operators.coreos.com/v1alpha1 kind: Subscription metadata:
name: lifecycle-agent namespace: openshift-lifecycle-agent annotations: {} spec:
channel: "stable"
name: lifecycle-agent source: redhat-operators-disconnected sourceNamespace: openshift-marketplace
```

installPlanApproval: Manual

status:

state: AtLatestKnown

## LcaSubscriptionNS.yaml

apiVersion: v1 kind: Namespace

metadata:

name: openshift-lifecycle-agent

annotations: {}

labels:

kubernetes.io/metadata.name: openshift-lifecycle-agent

## LcaSubscriptionOperGroup.yaml

apiVersion: operators.coreos.com/v1

kind: OperatorGroup

metadata:

name: lifecycle-agent

namespace: openshift-lifecycle-agent

annotations: {}

spec:

targetNamespaces:

- openshift-lifecycle-agent

## LVMOperatorStatus.yaml

# This CR verifies the installation/upgrade of the Sriov Network Operator

apiVersion: operators.coreos.com/v1

kind: Operator metadata:

name: lvms-operator.openshift-storage

annotations: {}

status:

components:

refs:

- kind: Subscription

namespace: openshift-storage

conditions:

- type: CatalogSourcesUnhealthy

status: "False"

- kind: InstallPlan

namespace: openshift-storage

conditions:

type: Installed status: "True"

- kind: ClusterServiceVersion namespace: openshift-storage

conditions:

- type: Succeeded status: "True"

reason: InstallSucceeded

# StorageLVMCluster.yaml

```
apiVersion: lvm.topolvm.io/v1alpha1
kind: LVMCluster
metadata:
 name: lvmcluster
 namespace: openshift-storage
 annotations: {}
spec: {}
#example: creating a vg1 volume group leveraging all available disks on the node
      except the installation disk.
# storage:
# deviceClasses:
# - name: vg1
   thinPoolConfig:
#
#
   name: thin-pool-1
#
    sizePercent: 90
#
     overprovisionRatio: 10
```

## StorageLVMSubscription.yaml

```
apiVersion: operators.coreos.com/v1alpha1 kind: Subscription metadata:
    name: lvms-operator
    namespace: openshift-storage annotations: {}
    spec:
    channel: "stable"
    name: lvms-operator
    source: redhat-operators-disconnected sourceNamespace: openshift-marketplace installPlanApproval: Manual status:
    state: AtLatestKnown
```

### StorageLVMSubscriptionNS.yaml

```
apiVersion: v1
kind: Namespace
metadata:
name: openshift-storage
labels:
openshift.io/cluster-monitoring: "true"
annotations: {}
```

## StorageLVMSubscriptionOperGroup.yaml

```
apiVersion: operators.coreos.com/v1 kind: OperatorGroup metadata: name: lvms-operator-operatorgroup namespace: openshift-storage annotations: {}
```

## spec:

targetNamespaces:

- openshift-storage

## PerformanceProfile.yaml

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
 # if you change this name make sure the 'include' line in TunedPerformancePatch.yaml
 # matches this name: include=openshift-node-performance-${PerformanceProfile.metadata.name}
 # Also in file 'validatorCRs/informDuValidator.yaml':
 # name: 50-performance-${PerformanceProfile.metadata.name}
 name: openshift-node-performance-profile
 annotations:
  ran.openshift.io/reference-configuration: "ran-du.redhat.com"
spec:
 additionalKernelArgs:
  - "rcupdate.rcu_normal_after_boot=0"
  - "efi=runtime"
  - "vfio pci.enable sriov=1"
  - "vfio_pci.disable_idle_d3=1"
  - "module_blacklist=irdma"
 cpu:
  isolated: $isolated
  reserved: $reserved
 hugepages:
  defaultHugepagesSize: $defaultHugepagesSize
  pages:
   - size: $size
    count: $count
     node: $node
 machineConfigPoolSelector:
  pools.operator.machineconfiguration.openshift.io/$mcp: ""
 nodeSelector:
  node-role.kubernetes.io/$mcp: "
 numa:
  topologyPolicy: "restricted"
 # To use the standard (non-realtime) kernel, set enabled to false
 realTimeKernel:
  enabled: true
 workloadHints:
  # WorkloadHints defines the set of upper level flags for different type of workloads.
  # See https://github.com/openshift/cluster-node-tuning-
operator/blob/master/docs/performanceprofile/performance_profile.md#workloadhints
  # for detailed descriptions of each item.
  # The configuration below is set for a low latency, performance mode.
  realTime: true
  highPowerConsumption: false
  perPodPowerManagement: false
```

## TunedPerformancePatch.yaml

apiVersion: tuned.openshift.io/v1

kind: Tuned

```
metadata:
 name: performance-patch
 namespace: openshift-cluster-node-tuning-operator
 annotations: {}
spec:
 profile:
  - name: performance-patch
   # Please note:
   # - The 'include' line must match the associated PerformanceProfile name, following below
pattern
   # include=openshift-node-performance-${PerformanceProfile.metadata.name}
   # - When using the standard (non-realtime) kernel, remove the kernel.timer migration override
from
   # the [sysctl] section and remove the entire section if it is empty.
   data: |
    [main]
     summary=Configuration changes profile inherited from performance created tuned
     include=openshift-node-performance-openshift-node-performance-profile
     [scheduler]
     group.ice-ptp=0:f:10:*:ice-ptp.*
     group.ice-gnss=0:f:10:*:ice-gnss.*
     group.ice-dplls=0:f:10:*:ice-dplls.*
     [service]
     service.stalld=start,enable
     service.chronyd=stop,disable
 recommend:
  - machineConfigLabels:
     machineconfiguration.openshift.io/role: "$mcp"
   priority: 19
   profile: performance-patch
```

## PtpConfigBoundaryForEvent.yaml

```
apiVersion: ptp.openshift.io/v1
kind: PtpConfig
metadata:
 name: boundary
 namespace: openshift-ptp
 annotations: {}
spec:
 profile:
  - name: "boundary"
   ptp4lOpts: "-2 --summary interval -4"
   phc2sysOpts: "-a -r -m -n 24 -N 8 -R 16"
   ptpSchedulingPolicy: SCHED_FIFO
   ptpSchedulingPriority: 10
   ptpSettings:
    logReduce: "true"
   ptp4lConf: |
     # The interface name is hardware-specific
     [$iface_slave]
     masterOnly 0
     [$iface master 1]
     masterOnly 1
     [$iface_master_2]
     masterOnly 1
```

```
[$iface_master_3]
masterOnly 1
[global]
# Default Data Set
twoStepFlag 1
slaveOnly 0
priority1 128
priority2 128
domainNumber 24
#utc offset 37
clockClass 248
clockAccuracy 0xFE
offsetScaledLogVariance 0xFFFF
free running 0
freq_est_interval 1
dscp_event 0
dscp_general 0
dataset comparison G.8275.x
G.8275.defaultDS.localPriority 128
# Port Data Set
logAnnounceInterval -3
logSyncInterval -4
logMinDelayReqInterval -4
logMinPdelayReqInterval -4
announceReceiptTimeout 3
syncReceiptTimeout 0
delayAsymmetry 0
fault_reset_interval -4
neighborPropDelayThresh 20000000
masterOnly 0
G.8275.portDS.localPriority 128
# Run time options
assume_two_step 0
logging_level 6
path_trace_enabled 0
follow_up_info 0
hybrid e2e 0
inhibit_multicast_service 0
net_sync_monitor 0
tc spanning tree 0
tx timestamp timeout 50
unicast listen 0
unicast_master_table 0
unicast reg duration 3600
use_syslog 1
verbose 0
summary_interval 0
kernel_leap 1
check_fup_sync 0
clock_class_threshold 135
```

```
# Servo Options
   pi_proportional_const 0.0
   pi_integral_const 0.0
   pi_proportional_scale 0.0
   pi proportional exponent -0.3
   pi_proportional_norm_max 0.7
   pi_integral_scale 0.0
   pi_integral_exponent 0.4
   pi_integral_norm_max 0.3
   step_threshold 2.0
   first_step_threshold 0.00002
   max_frequency 900000000
   clock_servo pi
   sanity_freq_limit 200000000
   ntpshm_segment 0
   # Transport options
   transportSpecific 0x0
   ptp_dst_mac 01:1B:19:00:00:00
   p2p_dst_mac 01:80:C2:00:00:0E
   udp ttl 1
   udp6_scope 0x0E
   uds_address /var/run/ptp4l
   # Default interface options
   clock_type BC
   network_transport L2
   delay_mechanism E2E
   time stamping hardware
   tsproc mode filter
   delay_filter moving_median
   delay_filter_length 10
   egressLatency 0
   ingressLatency 0
   boundary_clock_jbod 0
   # Clock description
   productDescription;;
   revisionData;;
   manufacturerIdentity 00:00:00
   userDescription;
   timeSource 0xA0
recommend:
 - profile: "boundary"
  priority: 4
  match:
   - nodeLabel: "node-role.kubernetes.io/$mcp"
```

## PtpConfigDualCardGmWpc.yaml

# In this example two cards \$iface nic1 and \$iface nic2 are connected via

```
# SMA1 ports by a cable and $iface_nic2 receives 1PPS signals from $iface_nic1
apiVersion: ptp.openshift.io/v1
kind: PtpConfig
metadata:
 name: grandmaster
 namespace: openshift-ptp
 annotations: {}
spec:
 profile:
  - name: "grandmaster"
   ptp4IOpts: "-2 --summary_interval -4"
   phc2sysOpts: -r -u 0 -m -w -N 8 -R 16 -s $iface_nic1 -n 24
   ptpSchedulingPolicy: SCHED_FIFO
   ptpSchedulingPriority: 10
   ptpSettings:
    logReduce: "true"
   plugins:
    e810:
      enableDefaultConfig: false
      settings:
       LocalMaxHoldoverOffSet: 1500
       LocalHoldoverTimeout: 14400
       MaxInSpecOffset: 100
      pins: $e810 pins
      # "$iface nic1":
         "U.FL2": "0 2"
      # "U.FL1": "0 1"
      # "SMA2": "0 2"
      # "SMA1": "2 1"
      # "$iface nic2":
         "U.FL2": "0 2"
      # "U.FL1": "0 1"
      # "SMA2": "0 2"
      # "SMA1": "1 1"
      ublxCmds:
       - args: #ubxtool -P 29.20 -z CFG-HW-ANT_CFG_VOLTCTRL,1
         - "-P"
         - "29.20"
         - "CFG-HW-ANT_CFG_VOLTCTRL,1"
        reportOutput: false
       - args: #ubxtool -P 29.20 -e GPS
         - "-P"
         - "29.20"
         - "-e"
         - "GPS"
        reportOutput: false
       - args: #ubxtool -P 29.20 -d Galileo
         - "-P"
         - "29.20"
         - "-d"
         - "Galileo"
        reportOutput: false
       - args: #ubxtool -P 29.20 -d GLONASS
         - "-P"
         - "29.20"
```

```
- "-d"
      - "GLONASS"
     reportOutput: false
   - args: #ubxtool -P 29.20 -d BeiDou
      - "-P"
      - "29.20"
      - "-d"
      - "BeiDou"
     reportOutput: false
   - args: #ubxtool -P 29.20 -d SBAS
      - "-P"
      - "29.20"
      - "-d"
      - "SBAS"
     reportOutput: false
   - args: #ubxtool -P 29.20 -t -w 5 -v 1 -e SURVEYIN,600,50000
      - "29.20"
      - "-t"
      - "-W"
      - "5"
      - "-V"
      - "1"
      - "-e"
      - "SURVEYIN,600,50000"
     reportOutput: true
   - args: #ubxtool -P 29.20 -p MON-HW
      - "-P"
      - "29.20"
      - "-p"
      - "MON-HW"
     reportOutput: true
   - args: #ubxtool -P 29.20 -p CFG-MSG,1,38,248
      - "-P"
      - "29.20"
      - "-p"
      - "CFG-MSG,1,38,248"
     reportOutput: true
ts2phcOpts: " "
ts2phcConf: |
 [nmea]
 ts2phc.master 1
 [global]
 use_syslog 0
 verbose 1
 logging level 7
 ts2phc.pulsewidth 100000000
 #cat /dev/GNSS to find available serial port
 #example value of gnss_serialport is /dev/ttyGNSS_1700_0
 ts2phc.nmea serialport $gnss serialport
 [$iface_nic1]
 ts2phc.extts_polarity rising
 ts2phc.extts_correction 0
 [$iface_nic2]
 ts2phc.master 0
 ts2phc.extts_polarity rising
```

```
#this is a measured value in nanoseconds to compensate for SMA cable delay
 ts2phc.extts_correction -10
ptp4lConf: |
 [$iface_nic1]
 masterOnly 1
 [$iface_nic1_1]
 masterOnly 1
 [$iface_nic1_2]
 masterOnly 1
 [$iface nic1 3]
 masterOnly 1
 [$iface_nic2]
 masterOnly 1
 [$iface_nic2_1]
 masterOnly 1
 [$iface_nic2_2]
 masterOnly 1
 [$iface_nic2_3]
 masterOnly 1
 [global]
 # Default Data Set
 twoStepFlag 1
 priority1 128
 priority2 128
 domainNumber 24
 #utc offset 37
 clockClass 6
 clockAccuracy 0x27
 offsetScaledLogVariance 0xFFFF
 free_running 0
 freq est interval 1
 dscp event 0
 dscp_general 0
 dataset_comparison G.8275.x
 G.8275.defaultDS.localPriority 128
 # Port Data Set
 logAnnounceInterval -3
 logSyncInterval -4
 logMinDelayRegInterval -4
 logMinPdelayReqInterval 0
 announceReceiptTimeout 3
 syncReceiptTimeout 0
 delayAsymmetry 0
 fault reset interval -4
 neighborPropDelayThresh 20000000
 masterOnly 0
 G.8275.portDS.localPriority 128
 # Run time options
 assume_two_step 0
 logging_level 6
```

```
path_trace_enabled 0
follow_up_info 0
hybrid_e2e 0
inhibit_multicast_service 0
net_sync_monitor 0
tc_spanning_tree 0
tx_timestamp_timeout 50
unicast_listen 0
unicast_master_table 0
unicast_req_duration 3600
use_syslog 1
verbose 0
summary_interval -4
kernel_leap 1
check_fup_sync 0
clock_class_threshold 7
# Servo Options
pi proportional const 0.0
pi_integral_const 0.0
pi_proportional_scale 0.0
pi_proportional_exponent -0.3
pi proportional norm max 0.7
pi_integral_scale 0.0
pi_integral_exponent 0.4
pi_integral_norm_max 0.3
step_threshold 2.0
first_step_threshold 0.00002
clock_servo pi
sanity_freq_limit 200000000
ntpshm_segment 0
# Transport options
transportSpecific 0x0
ptp dst mac 01:1B:19:00:00:00
p2p_dst_mac 01:80:C2:00:00:0E
udp_ttl 1
udp6_scope 0x0E
uds_address /var/run/ptp4l
# Default interface options
clock_type BC
network transport L2
delay mechanism E2E
time stamping hardware
tsproc_mode filter
delay filter moving median
delay_filter_length 10
egressLatency 0
ingressLatency 0
boundary_clock_jbod 1
# Clock description
```

```
#
productDescription;;
revisionData;;
manufacturerIdentity 00:00:00
userDescription;
timeSource 0x20
recommend:
- profile: "grandmaster"
priority: 4
match:
- nodeLabel: "node-role.kubernetes.io/$mcp"
```

# PtpConfigForHAForEvent.yaml

```
apiVersion: ptp.openshift.io/v1
kind: PtpConfig
metadata:
 name: boundary-ha
 namespace: openshift-ptp
 annotations: {}
spec:
 profile:
  - name: "boundary-ha"
   ptp4lOpts: " "
   phc2sysOpts: "-a -r -m -n 24 -N 8 -R 16"
   ptpSchedulingPolicy: SCHED FIFO
   ptpSchedulingPriority: 10
   ptpSettings:
    logReduce: "true"
    haProfiles: "$profile1,$profile2"
 recommend:
  - profile: "boundary-ha"
   priority: 4
   match:
     - nodeLabel: "node-role.kubernetes.io/$mcp"
```

## PtpConfigGmWpc.yaml

```
apiVersion: ptp.openshift.io/v1
kind: PtpConfig
metadata:
 name: grandmaster
 namespace: openshift-ptp
 annotations: {}
spec:
 profile:
  - name: "grandmaster"
   ptp4lOpts: "-2 --summary interval -4"
   phc2sysOpts: -r -u 0 -m -w -N 8 -R 16 -s $iface master -n 24
   ptpSchedulingPolicy: SCHED FIFO
   ptpSchedulingPriority: 10
   ptpSettings:
    logReduce: "true"
   plugins:
     e810:
```

```
enableDefaultConfig: false
settings:
 LocalMaxHoldoverOffSet: 1500
 LocalHoldoverTimeout: 14400
 MaxInSpecOffset: 100
pins: $e810_pins
# "$iface master":
  "U.FL2": "0 2"
# "U.FL1": "0 1"
# "SMA2": "0 2"
# "SMA1": "0 1"
ublxCmds:
 - args: #ubxtool -P 29.20 -z CFG-HW-ANT_CFG_VOLTCTRL,1
   - "-P"
   - "29.20"
   - "-7"
   - "CFG-HW-ANT_CFG_VOLTCTRL,1"
  reportOutput: false
 - args: #ubxtool -P 29.20 -e GPS
   - "-P"
   - "29.20"
   - "-e"
   - "GPS"
  reportOutput: false
 - args: #ubxtool -P 29.20 -d Galileo
   - "-P"
   - "29.20"
   - "-d"
   - "Galileo"
  reportOutput: false
 - args: #ubxtool -P 29.20 -d GLONASS
   - "-P"
   - "29.20"
   - "-d"
   - "GLONASS"
  reportOutput: false
 - args: #ubxtool -P 29.20 -d BeiDou
   - "-P"
   - "29.20"
   - "-d"
   - "BeiDou"
  reportOutput: false
 - args: #ubxtool -P 29.20 -d SBAS
   - "-P"
   - "29.20"
   - "-d"
   - "SBAS"
  reportOutput: false
 - args: #ubxtool -P 29.20 -t -w 5 -v 1 -e SURVEYIN,600,50000
   - "-P"
   - "29.20"
   - "-t"
   - "-W"
   - "5"
   - "-V"
   - "1"
```

```
- "-e"
      - "SURVEYIN,600,50000"
    reportOutput: true
   - args: #ubxtool -P 29.20 -p MON-HW
      - "-P"
      - "29.20"
     - "-p"
      - "MON-HW"
    reportOutput: true
   - args: #ubxtool -P 29.20 -p CFG-MSG,1,38,248
      - "-P"
     - "29.20"
     - "-p"
      - "CFG-MSG,1,38,248"
    reportOutput: true
ts2phcOpts: " "
ts2phcConf: |
 [nmea]
 ts2phc.master 1
 [global]
 use_syslog 0
 verbose 1
 logging_level 7
 ts2phc.pulsewidth 100000000
 #cat /dev/GNSS to find available serial port
 #example value of gnss_serialport is /dev/ttyGNSS_1700_0
 ts2phc.nmea_serialport $gnss_serialport
 [$iface_master]
 ts2phc.extts_polarity rising
 ts2phc.extts_correction 0
ptp4lConf: |
 [$iface_master]
 masterOnly 1
 [$iface master 1]
 masterOnly 1
 [$iface_master_2]
 masterOnly 1
 [$iface_master_3]
 masterOnly 1
 [global]
 # Default Data Set
 twoStepFlag 1
 priority1 128
 priority2 128
 domainNumber 24
 #utc offset 37
 clockClass 6
 clockAccuracy 0x27
 offsetScaledLogVariance 0xFFFF
 free running 0
 freq_est_interval 1
 dscp_event 0
 dscp_general 0
 dataset_comparison G.8275.x
```

```
G.8275.defaultDS.localPriority 128
# Port Data Set
logAnnounceInterval -3
logSyncInterval -4
logMinDelayRegInterval -4
logMinPdelayReqInterval 0
announceReceiptTimeout 3
syncReceiptTimeout 0
delayAsymmetry 0
fault_reset_interval -4
neighborPropDelayThresh 20000000
masterOnly 0
G.8275.portDS.localPriority 128
# Run time options
assume_two_step 0
logging level 6
path_trace_enabled 0
follow_up_info 0
hybrid_e2e 0
inhibit_multicast_service 0
net_sync_monitor 0
tc_spanning_tree 0
tx_timestamp_timeout 50
unicast_listen 0
unicast master table 0
unicast_req_duration 3600
use_syslog 1
verbose 0
summary interval -4
kernel leap 1
check_fup_sync 0
clock_class_threshold 7
# Servo Options
pi_proportional_const 0.0
pi_integral_const 0.0
pi_proportional_scale 0.0
pi_proportional_exponent -0.3
pi_proportional_norm_max 0.7
pi_integral_scale 0.0
pi_integral_exponent 0.4
pi_integral_norm_max 0.3
step_threshold 2.0
first_step_threshold 0.00002
clock servo pi
sanity_freq_limit 200000000
ntpshm_segment 0
# Transport options
transportSpecific 0x0
```

```
ptp_dst_mac 01:1B:19:00:00:00
   p2p_dst_mac 01:80:C2:00:00:0E
   udp_ttl 1
   udp6_scope 0x0E
   uds address /var/run/ptp4l
   # Default interface options
   clock_type BC
   network transport L2
   delay_mechanism E2E
   time_stamping hardware
   tsproc_mode filter
   delay_filter moving_median
   delay_filter_length 10
   egressLatency 0
   ingressLatency 0
   boundary_clock_jbod 0
   # Clock description
   productDescription;;
   revisionData;;
   manufacturerIdentity 00:00:00
   userDescription;
   timeSource 0x20
recommend:
 - profile: "grandmaster"
  priority: 4
  match:
   - nodeLabel: "node-role.kubernetes.io/$mcp"
```

#### PtpConfigMasterForEvent.yaml

```
# The grandmaster profile is provided for testing only
# It is not installed on production clusters
apiVersion: ptp.openshift.io/v1
kind: PtpConfig
metadata:
 name: grandmaster
 namespace: openshift-ptp
 annotations: {}
spec:
 profile:
  - name: "grandmaster"
   # The interface name is hardware-specific
   interface: $interface
   ptp4lOpts: "-2 --summary_interval -4"
   phc2sysOpts: "-a -r -m -n 24 -N 8 -R 16"
   ptpSchedulingPolicy: SCHED_FIFO
   ptpSchedulingPriority: 10
   ptpSettings:
     logReduce: "true"
   ptp4lConf: |
     [global]
```

```
# Default Data Set
twoStepFlag 1
slaveOnly 0
priority1 128
priority2 128
domainNumber 24
#utc offset 37
clockClass 255
clockAccuracy 0xFE
offsetScaledLogVariance 0xFFFF
free_running 0
freq_est_interval 1
dscp_event 0
dscp_general 0
dataset_comparison G.8275.x
G.8275.defaultDS.localPriority 128
# Port Data Set
logAnnounceInterval -3
logSyncInterval -4
logMinDelayReqInterval -4
logMinPdelayRegInterval -4
announceReceiptTimeout 3
syncReceiptTimeout 0
delayAsymmetry 0
fault_reset_interval -4
neighborPropDelayThresh 20000000
masterOnly 0
G.8275.portDS.localPriority 128
# Run time options
assume_two_step 0
logging_level 6
path_trace_enabled 0
follow_up_info 0
hybrid_e2e 0
inhibit_multicast_service 0
net_sync_monitor 0
tc_spanning_tree 0
tx_timestamp_timeout 50
unicast_listen 0
unicast_master_table 0
unicast req duration 3600
use syslog 1
verbose 0
summary_interval 0
kernel leap 1
check_fup_sync 0
clock_class_threshold 7
# Servo Options
pi_proportional_const 0.0
```

```
pi_integral_const 0.0
   pi_proportional_scale 0.0
   pi_proportional_exponent -0.3
   pi_proportional_norm_max 0.7
   pi_integral_scale 0.0
   pi_integral_exponent 0.4
   pi integral norm max 0.3
   step_threshold 2.0
   first_step_threshold 0.00002
   max_frequency 900000000
   clock_servo pi
   sanity_freq_limit 200000000
   ntpshm_segment 0
   # Transport options
   transportSpecific 0x0
   ptp_dst_mac 01:1B:19:00:00:00
   p2p_dst_mac 01:80:C2:00:00:0E
   udp ttl 1
   udp6 scope 0x0E
   uds_address /var/run/ptp4l
   # Default interface options
   clock_type OC
   network_transport L2
   delay_mechanism E2E
   time stamping hardware
   tsproc_mode filter
   delay_filter moving_median
   delay_filter_length 10
   egressLatency 0
   ingressLatency 0
   boundary_clock_jbod 0
   # Clock description
   productDescription;;
   revisionData;;
   manufacturerIdentity 00:00:00
   userDescription;
   timeSource 0xA0
recommend:
 - profile: "grandmaster"
  priority: 4
   - nodeLabel: "node-role.kubernetes.io/$mcp"
```

## PtpConfigSlaveForEvent.yaml

apiVersion: ptp.openshift.io/v1 kind: PtpConfig metadata: name: du-ptp-slave namespace: openshift-ptp

```
annotations: {}
spec:
 profile:
  - name: "slave"
   # The interface name is hardware-specific
   interface: $interface
   ptp4lOpts: "-2 -s --summary interval -4"
   phc2sysOpts: "-a -r -m -n 24 -N 8 -R 16"
   ptpSchedulingPolicy: SCHED FIFO
   ptpSchedulingPriority: 10
   ptpSettings:
    logReduce: "true"
   ptp4lConf: |
    [global]
     # Default Data Set
     twoStepFlag 1
     slaveOnly 1
     priority1 128
     priority2 128
     domainNumber 24
     #utc offset 37
     clockClass 255
     clockAccuracy 0xFE
     offsetScaledLogVariance 0xFFFF
     free_running 0
     freq_est_interval 1
     dscp event 0
     dscp_general 0
     dataset_comparison G.8275.x
     G.8275.defaultDS.localPriority 128
     # Port Data Set
     logAnnounceInterval -3
     logSyncInterval -4
     logMinDelayRegInterval -4
     logMinPdelayReqInterval -4
     announceReceiptTimeout 3
     syncReceiptTimeout 0
     delayAsymmetry 0
     fault_reset_interval -4
     neighborPropDelayThresh 20000000
     masterOnly 0
     G.8275.portDS.localPriority 128
     # Run time options
     assume two step 0
     logging_level 6
     path_trace_enabled 0
     follow_up_info 0
     hybrid_e2e 0
     inhibit_multicast_service 0
     net_sync_monitor 0
```

```
tc_spanning_tree 0
tx_timestamp_timeout 50
unicast_listen 0
unicast_master_table 0
unicast_req_duration 3600
use_syslog 1
verbose 0
summary_interval 0
kernel leap 1
check_fup_sync 0
clock_class_threshold 7
# Servo Options
pi_proportional_const 0.0
pi_integral_const 0.0
pi_proportional_scale 0.0
pi_proportional_exponent -0.3
pi_proportional_norm_max 0.7
pi integral scale 0.0
pi_integral_exponent 0.4
pi_integral_norm_max 0.3
step_threshold 2.0
first step threshold 0.00002
max_frequency 900000000
clock_servo pi
sanity_freq_limit 200000000
ntpshm_segment 0
# Transport options
transportSpecific 0x0
ptp dst mac 01:1B:19:00:00:00
p2p dst mac 01:80:C2:00:00:0E
udp_ttl 1
udp6_scope 0x0E
uds address /var/run/ptp4l
# Default interface options
clock_type OC
network_transport L2
delay_mechanism E2E
time_stamping hardware
tsproc_mode filter
delay filter moving median
delay filter length 10
egressLatency 0
ingressLatency 0
boundary_clock_jbod 0
# Clock description
productDescription;;
revisionData;;
manufacturerIdentity 00:00:00
```

```
userDescription;
timeSource 0xA0
recommend:
- profile: "slave"
priority: 4
match:
- nodeLabel: "node-role.kubernetes.io/$mcp"
```

## PtpOperatorConfigForEvent.yaml

```
apiVersion: ptp.openshift.io/v1
kind: PtpOperatorConfig
metadata:
name: default
namespace: openshift-ptp
annotations: {}
spec:
daemonNodeSelector:
node-role.kubernetes.io/$mcp: ""
ptpEventConfig:
enableEventPublisher: true
transportHost: "http://ptp-event-publisher-service-NODE_NAME.openshift-ptp.svc.cluster.local:9043"
```

## PtpConfigBoundary.yaml

```
apiVersion: ptp.openshift.io/v1
kind: PtpConfig
metadata:
 name: boundary
 namespace: openshift-ptp
 annotations: {}
spec:
 profile:
  - name: "boundary"
   ptp4lOpts: "-2"
   phc2sysOpts: "-a -r -n 24"
   ptpSchedulingPolicy: SCHED FIFO
   ptpSchedulingPriority: 10
   ptpSettings:
    logReduce: "true"
   ptp4lConf: |
     # The interface name is hardware-specific
     [$iface slave]
     masterOnly 0
     [$iface_master_1]
     masterOnly 1
     [$iface master 2]
     masterOnly 1
     [$iface_master_3]
     masterOnly 1
     [global]
     # Default Data Set
```

```
twoStepFlag 1
slaveOnly 0
priority1 128
priority2 128
domainNumber 24
#utc offset 37
clockClass 248
clockAccuracy 0xFE
offsetScaledLogVariance 0xFFFF
free running 0
freq_est_interval 1
dscp_event 0
dscp_general 0
dataset_comparison G.8275.x
G.8275.defaultDS.localPriority 128
# Port Data Set
logAnnounceInterval -3
logSyncInterval -4
logMinDelayRegInterval -4
logMinPdelayReqInterval -4
announceReceiptTimeout 3
syncReceiptTimeout 0
delayAsymmetry 0
fault_reset_interval -4
neighborPropDelayThresh 20000000
masterOnly 0
G.8275.portDS.localPriority 128
# Run time options
assume two step 0
logging level 6
path_trace_enabled 0
follow_up_info 0
hybrid e2e 0
inhibit_multicast_service 0
net_sync_monitor 0
tc_spanning_tree 0
tx_timestamp_timeout 50
unicast_listen 0
unicast_master_table 0
unicast_req_duration 3600
use_syslog 1
verbose 0
summary_interval 0
kernel leap 1
check_fup_sync 0
clock class threshold 135
# Servo Options
pi_proportional_const 0.0
pi_integral_const 0.0
pi_proportional_scale 0.0
```

```
pi_proportional_exponent -0.3
   pi_proportional_norm_max 0.7
   pi_integral_scale 0.0
   pi_integral_exponent 0.4
   pi_integral_norm_max 0.3
   step_threshold 2.0
   first step threshold 0.00002
   max_frequency 900000000
   clock servo pi
   sanity_freq_limit 200000000
   ntpshm_segment 0
   # Transport options
   transportSpecific 0x0
   ptp_dst_mac 01:1B:19:00:00:00
   p2p_dst_mac 01:80:C2:00:00:0E
   udp_ttl 1
   udp6_scope 0x0E
   uds address /var/run/ptp4l
   # Default interface options
   clock type BC
   network_transport L2
   delay_mechanism E2E
   time_stamping hardware
   tsproc_mode filter
   delay filter moving median
   delay_filter_length 10
   egressLatency 0
   ingressLatency 0
   boundary clock jbod 0
   # Clock description
   productDescription;;
   revisionData ;;
   manufacturerIdentity 00:00:00
   userDescription;
   timeSource 0xA0
recommend:
 - profile: "boundary"
  priority: 4
  match:
   - nodeLabel: "node-role.kubernetes.io/$mcp"
```

## PtpConfigDualCardGmWpc.yaml

```
# In this example two cards $iface_nic1 and $iface_nic2 are connected via

# SMA1 ports by a cable and $iface_nic2 receives 1PPS signals from $iface_nic1

apiVersion: ptp.openshift.io/v1

kind: PtpConfig

metadata:

name: grandmaster

namespace: openshift-ptp
```

```
annotations: {}
spec:
 profile:
  - name: "grandmaster"
   ptp4lOpts: "-2 --summary_interval -4"
   phc2sysOpts: -r -u 0 -m -w -N 8 -R 16 -s $iface_nic1 -n 24
   ptpSchedulingPolicy: SCHED FIFO
   ptpSchedulingPriority: 10
   ptpSettings:
    logReduce: "true"
   plugins:
    e810:
      enableDefaultConfig: false
      settings:
       LocalMaxHoldoverOffSet: 1500
       LocalHoldoverTimeout: 14400
       MaxInSpecOffset: 100
      pins: $e810_pins
      # "$iface nic1":
      # "U.FL2": "0 2"
      # "U.FL1": "0 1"
      # "SMA2": "0 2"
      # "SMA1": "2 1"
      # "$iface_nic2":
      # "U.FL2": "0 2"
      # "U.FL1": "0 1"
      # "SMA2": "0 2"
      # "SMA1": "1 1"
      ublxCmds:
       - args: #ubxtool -P 29.20 -z CFG-HW-ANT_CFG_VOLTCTRL,1
         - "-P"
         - "29.20"
         - "-z"
         - "CFG-HW-ANT CFG VOLTCTRL,1"
        reportOutput: false
       - args: #ubxtool -P 29.20 -e GPS
         - "-P"
         - "29.20"
         - "-e"
         - "GPS"
        reportOutput: false
       - args: #ubxtool -P 29.20 -d Galileo
         - "-P"
         - "29.20"
         - "-d"
         - "Galileo"
        reportOutput: false
       - args: #ubxtool -P 29.20 -d GLONASS
         - "-P"
         - "29.20"
         - "-d"
         - "GLONASS"
        reportOutput: false
       - args: #ubxtool -P 29.20 -d BeiDou
         - "-P"
         - "29.20"
```

```
- "-d"
      - "BeiDou"
     reportOutput: false
   - args: #ubxtool -P 29.20 -d SBAS
      - "-P"
      - "29.20"
     - "-d"
      - "SBAS"
     reportOutput: false
   - args: #ubxtool -P 29.20 -t -w 5 -v 1 -e SURVEYIN,600,50000
      - "-P"
      - "29.20"
      - "-t"
      - "-W"
      - "5"
      - "-V"
      - "1"
      - "-e"
      - "SURVEYIN,600,50000"
     reportOutput: true
   - args: #ubxtool -P 29.20 -p MON-HW
     - "-P"
      - "29.20"
      - "-p"
     - "MON-HW"
     reportOutput: true
   - args: #ubxtool -P 29.20 -p CFG-MSG,1,38,248
     - "-P"
      - "29.20"
     - "-p"
      - "CFG-MSG,1,38,248"
     reportOutput: true
ts2phcOpts: " "
ts2phcConf: |
 [nmea]
 ts2phc.master 1
 [global]
 use_syslog 0
 verbose 1
 logging_level 7
 ts2phc.pulsewidth 100000000
 #cat /dev/GNSS to find available serial port
 #example value of gnss_serialport is /dev/ttyGNSS_1700_0
 ts2phc.nmea_serialport $gnss_serialport
 [$iface_nic1]
 ts2phc.extts_polarity rising
 ts2phc.extts correction 0
 [$iface nic2]
 ts2phc.master 0
 ts2phc.extts polarity rising
 #this is a measured value in nanoseconds to compensate for SMA cable delay
 ts2phc.extts correction -10
ptp4lConf: |
 [$iface_nic1]
 masterOnly 1
 [$iface_nic1_1]
```

```
masterOnly 1
[$iface_nic1_2]
masterOnly 1
[$iface_nic1_3]
masterOnly 1
[$iface_nic2]
masterOnly 1
[$iface_nic2_1]
masterOnly 1
[$iface nic2 2]
masterOnly 1
[$iface_nic2_3]
masterOnly 1
[global]
#
# Default Data Set
twoStepFlag 1
priority1 128
priority2 128
domainNumber 24
#utc_offset 37
clockClass 6
clockAccuracy 0x27
offsetScaledLogVariance 0xFFFF
free_running 0
freq_est_interval 1
dscp_event 0
dscp general 0
dataset_comparison G.8275.x
G.8275.defaultDS.localPriority 128
# Port Data Set
logAnnounceInterval -3
logSyncInterval -4
logMinDelayRegInterval -4
logMinPdelayRegInterval 0
announceReceiptTimeout 3
syncReceiptTimeout 0
delayAsymmetry 0
fault_reset_interval -4
neighborPropDelayThresh 20000000
masterOnly 0
G.8275.portDS.localPriority 128
# Run time options
assume_two_step 0
logging level 6
path_trace_enabled 0
follow_up_info 0
hybrid_e2e 0
inhibit_multicast_service 0
net_sync_monitor 0
tc_spanning_tree 0
```

```
tx_timestamp_timeout 50
unicast_listen 0
unicast_master_table 0
unicast_req_duration 3600
use syslog 1
verbose 0
summary_interval -4
kernel_leap 1
check_fup_sync 0
clock_class_threshold 7
# Servo Options
pi_proportional_const 0.0
pi_integral_const 0.0
pi_proportional_scale 0.0
pi_proportional_exponent -0.3
pi_proportional_norm_max 0.7
pi_integral_scale 0.0
pi integral exponent 0.4
pi_integral_norm_max 0.3
step_threshold 2.0
first_step_threshold 0.00002
clock servo pi
sanity_freq_limit 200000000
ntpshm_segment 0
# Transport options
transportSpecific 0x0
ptp_dst_mac 01:1B:19:00:00:00
p2p_dst_mac 01:80:C2:00:00:0E
udp ttl 1
udp6 scope 0x0E
uds_address /var/run/ptp4l
# Default interface options
clock_type BC
network_transport L2
delay_mechanism E2E
time stamping hardware
tsproc mode filter
delay_filter moving_median
delay_filter_length 10
egressLatency 0
ingressLatency 0
boundary_clock_jbod 1
# Clock description
productDescription;;
revisionData;;
manufacturerIdentity 00:00:00
userDescription;
timeSource 0x20
```

```
recommend:
- profile: "grandmaster"
priority: 4
match:
- nodeLabel: "node-role.kubernetes.io/$mcp"
```

## PtpConfigForHA.yaml

```
apiVersion: ptp.openshift.io/v1
kind: PtpConfig
metadata:
 name: boundary-ha
 namespace: openshift-ptp
 annotations: {}
spec:
 profile:
  - name: "boundary-ha"
   ptp4lOpts: "" 1
   phc2sysOpts: "-a -r -n 24"
   ptpSchedulingPolicy: SCHED FIFO
   ptpSchedulingPriority: 10
   ptpSettings:
    logReduce: "true"
     haProfiles: "$profile1,$profile2"
 recommend:
  - profile: "boundary-ha"
   priority: 4
   match:
     - nodeLabel: "node-role.kubernetes.io/$mcp"
```

## PtpConfigGmWpc.yaml

```
apiVersion: ptp.openshift.io/v1
kind: PtpConfig
metadata:
 name: grandmaster
 namespace: openshift-ptp
 annotations: {}
spec:
 profile:
  - name: "grandmaster"
   ptp4lOpts: "-2 --summary_interval -4"
   phc2sysOpts: -r -u 0 -m -w -N 8 -R 16 -s $iface master -n 24
   ptpSchedulingPolicy: SCHED FIFO
   ptpSchedulingPriority: 10
   ptpSettings:
    logReduce: "true"
   plugins:
     e810:
      enableDefaultConfig: false
      settings:
       LocalMaxHoldoverOffSet: 1500
       LocalHoldoverTimeout: 14400
       MaxInSpecOffset: 100
      pins: $e810_pins
```

```
# "$iface_master":
# "U.FL2": "0 2"
# "U.FL1": "0 1"
# "SMA2": "0 2"
# "SMA1": "0 1"
ublxCmds:
 - args: #ubxtool -P 29.20 -z CFG-HW-ANT CFG VOLTCTRL,1
   - "-P"
   - "29.20"
   - "-Z"
   - "CFG-HW-ANT_CFG_VOLTCTRL,1"
  reportOutput: false
 - args: #ubxtool -P 29.20 -e GPS
   - "-P"
   - "29.20"
   - "-e"
   - "GPS"
  reportOutput: false
 - args: #ubxtool -P 29.20 -d Galileo
   - "-P"
   - "29.20"
   - "-d"
   - "Galileo"
  reportOutput: false
 - args: #ubxtool -P 29.20 -d GLONASS
   - "-P"
   - "29.20"
   - "-d"
   - "GLONASS"
  reportOutput: false
 - args: #ubxtool -P 29.20 -d BeiDou
   - "-P"
   - "29.20"
   - "-d"
   - "BeiDou"
  reportOutput: false
 - args: #ubxtool -P 29.20 -d SBAS
   - "-P"
   - "29.20"
   - "-d"
   - "SBAS"
  reportOutput: false
 - args: #ubxtool -P 29.20 -t -w 5 -v 1 -e SURVEYIN,600,50000
   - "-P"
   - "29.20"
   - "-t"
   - "-W"
   - "5"
   - "-V"
   - "1"
   - "SURVEYIN,600,50000"
  reportOutput: true
 - args: #ubxtool -P 29.20 -p MON-HW
   - "-P"
   - "29.20"
```

```
- "-p"
      - "MON-HW"
    reportOutput: true
   - args: #ubxtool -P 29.20 -p CFG-MSG,1,38,248
      - "29.20"
     - "-p"
      - "CFG-MSG,1,38,248"
    reportOutput: true
ts2phcOpts: " "
ts2phcConf: |
 [nmea]
 ts2phc.master 1
 [global]
 use_syslog 0
 verbose 1
 logging_level 7
 ts2phc.pulsewidth 100000000
 #cat /dev/GNSS to find available serial port
 #example value of gnss serialport is /dev/ttyGNSS 1700 0
 ts2phc.nmea serialport $gnss serialport
 [$iface_master]
 ts2phc.extts_polarity rising
 ts2phc.extts correction 0
ptp4lConf: |
 [$iface_master]
 masterOnly 1
 [$iface_master_1]
 masterOnly 1
 [$iface_master_2]
 masterOnly 1
 [$iface_master_3]
 masterOnly 1
 [global]
 #
 # Default Data Set
 twoStepFlag 1
 priority1 128
 priority2 128
 domainNumber 24
 #utc_offset 37
 clockClass 6
 clockAccuracy 0x27
 offsetScaledLogVariance 0xFFFF
 free running 0
 freq est interval 1
 dscp_event 0
 dscp_general 0
 dataset comparison G.8275.x
 G.8275.defaultDS.localPriority 128
 # Port Data Set
 logAnnounceInterval -3
 logSyncInterval -4
```

```
logMinDelayReqInterval -4
logMinPdelayReqInterval 0
announceReceiptTimeout 3
syncReceiptTimeout 0
delayAsymmetry 0
fault_reset_interval -4
neighborPropDelayThresh 20000000
masterOnly 0
G.8275.portDS.localPriority 128
# Run time options
assume_two_step 0
logging_level 6
path_trace_enabled 0
follow_up_info 0
hybrid_e2e 0
inhibit_multicast_service 0
net_sync_monitor 0
tc spanning tree 0
tx_timestamp_timeout 50
unicast_listen 0
unicast_master_table 0
unicast req duration 3600
use_syslog 1
verbose 0
summary_interval -4
kernel_leap 1
check fup sync 0
clock_class_threshold 7
# Servo Options
pi proportional const 0.0
pi_integral_const 0.0
pi_proportional_scale 0.0
pi proportional exponent -0.3
pi_proportional_norm_max 0.7
pi_integral_scale 0.0
pi_integral_exponent 0.4
pi_integral_norm_max 0.3
step_threshold 2.0
first_step_threshold 0.00002
clock_servo pi
sanity_freq_limit 200000000
ntpshm segment 0
# Transport options
transportSpecific 0x0
ptp_dst_mac 01:1B:19:00:00:00
p2p_dst_mac 01:80:C2:00:00:0E
udp_ttl 1
udp6_scope 0x0E
uds_address /var/run/ptp4l
```

```
# Default interface options
   clock_type BC
   network_transport L2
   delay_mechanism E2E
   time_stamping hardware
   tsproc mode filter
   delay_filter moving_median
   delay_filter_length 10
   egressLatency 0
   ingressLatency 0
   boundary_clock_jbod 0
   # Clock description
   productDescription;;
   revisionData;;
   manufacturerIdentity 00:00:00
   userDescription;
   timeSource 0x20
recommend:
 - profile: "grandmaster"
  priority: 4
  match:
   - nodeLabel: "node-role.kubernetes.io/$mcp"
```

## PtpConfigSlave.yaml

```
apiVersion: ptp.openshift.io/v1
kind: PtpConfig
metadata:
 name: du-ptp-slave
 namespace: openshift-ptp
 annotations: {}
spec:
 profile:
  - name: "slave"
   # The interface name is hardware-specific
   interface: $interface
   ptp4lOpts: "-2 -s"
   phc2sysOpts: "-a -r -n 24"
   ptpSchedulingPolicy: SCHED_FIFO
   ptpSchedulingPriority: 10
   ptpSettings:
    logReduce: "true"
   ptp4lConf: |
    [global]
     # Default Data Set
     twoStepFlag 1
     slaveOnly 1
     priority1 128
     priority2 128
     domainNumber 24
     #utc offset 37
```

```
clockClass 255
clockAccuracy 0xFE
offsetScaledLogVariance 0xFFFF
free running 0
freq est interval 1
dscp_event 0
dscp general 0
dataset_comparison G.8275.x
G.8275.defaultDS.localPriority 128
# Port Data Set
logAnnounceInterval -3
logSyncInterval -4
logMinDelayReqInterval -4
logMinPdelayReqInterval -4
announceReceiptTimeout 3
syncReceiptTimeout 0
delayAsymmetry 0
fault reset interval -4
neighborPropDelayThresh 20000000
masterOnly 0
G.8275.portDS.localPriority 128
# Run time options
assume_two_step 0
logging_level 6
path trace enabled 0
follow_up_info 0
hybrid_e2e 0
inhibit_multicast_service 0
net sync monitor 0
tc spanning tree 0
tx_timestamp_timeout 50
unicast_listen 0
unicast master table 0
unicast_req_duration 3600
use_syslog 1
verbose 0
summary_interval 0
kernel leap 1
check_fup_sync 0
clock_class_threshold 7
# Servo Options
pi proportional const 0.0
pi_integral_const 0.0
pi proportional scale 0.0
pi_proportional_exponent -0.3
pi_proportional_norm_max 0.7
pi_integral_scale 0.0
pi_integral_exponent 0.4
pi_integral_norm_max 0.3
step_threshold 2.0
```

```
first_step_threshold 0.00002
   max_frequency 900000000
   clock_servo pi
   sanity freq limit 200000000
   ntpshm_segment 0
   # Transport options
   transportSpecific 0x0
   ptp dst mac 01:1B:19:00:00:00
   p2p_dst_mac 01:80:C2:00:00:0E
   udp_ttl 1
   udp6_scope 0x0E
   uds_address /var/run/ptp4l
   # Default interface options
   clock_type OC
   network_transport L2
   delay mechanism E2E
   time_stamping hardware
   tsproc_mode filter
   delay_filter moving_median
   delay filter length 10
   egressLatency 0
   ingressLatency 0
   boundary_clock_jbod 0
   # Clock description
   productDescription;;
   revisionData;;
   manufacturerIdentity 00:00:00
   userDescription;
   timeSource 0xA0
recommend:
 - profile: "slave"
  priority: 4
  match:
   - nodeLabel: "node-role.kubernetes.io/$mcp"
```

## PtpSubscription.yaml

```
apiVersion: operators.coreos.com/v1alpha1 kind: Subscription metadata:
name: ptp-operator-subscription namespace: openshift-ptp annotations: {} spec:
channel: "stable"
name: ptp-operator
source: redhat-operators-disconnected sourceNamespace: openshift-marketplace
```

installPlanApproval: Manual

status:

state: AtLatestKnown

## PtpSubscriptionNS.yaml

---

apiVersion: v1 kind: Namespace

metadata:

name: openshift-ptp

annotations:

workload.openshift.io/allowed: management

labels:

openshift.io/cluster-monitoring: "true"

# PtpSubscriptionOperGroup.yaml

apiVersion: operators.coreos.com/v1

kind: OperatorGroup

metadata:

name: ptp-operators namespace: openshift-ptp

annotations: {}

spec:

targetNamespaces:
- openshift-ptp

## AcceleratorsNS.yaml

apiVersion: v1

kind: Namespace metadata:

name: vran-acceleration-operators

annotations: {}

## AcceleratorsOperGroup.yaml

apiVersion: operators.coreos.com/v1

kind: OperatorGroup

metadata:

name: vran-operators

namespace: vran-acceleration-operators

annotations: {}

spec:

targetNamespaces:

- vran-acceleration-operators

#### AcceleratorsSubscription.yaml

apiVersion: operators.coreos.com/v1alpha1

kind: Subscription

metadata:

```
name: sriov-fec-subscription
namespace: vran-acceleration-operators
annotations: {}
spec:
channel: stable
name: sriov-fec
source: certified-operators
sourceNamespace: openshift-marketplace
installPlanApproval: Manual
status:
state: AtLatestKnown
```

# SriovFecClusterConfig.yaml

```
apiVersion: sriovfec.intel.com/v2
kind: SriovFecClusterConfig
metadata:
 name: config
 namespace: vran-acceleration-operators
 annotations: {}
spec:
 drainSkip: $drainSkip # true if SNO, false by default
 priority: 1
 nodeSelector:
  node-role.kubernetes.io/master: ""
 acceleratorSelector:
  pciAddress: $pciAddress
 physicalFunction:
  pfDriver: "vfio-pci"
  vfDriver: "vfio-pci"
  vfAmount: 16
  bbDevConfig: $bbDevConfig
#Recommended configuration for Intel ACC100 (Mount Bryce) FPGA here: https://github.com/smart-
edge-open/openshift-operator/blob/main/spec/openshift-sriov-fec-operator.md#sample-cr-for-
wireless-fec-acc100
#Recommended configuration for Intel N3000 FPGA here: https://github.com/smart-edge-
open/openshift-operator/blob/main/spec/openshift-sriov-fec-operator.md#sample-cr-for-wireless-fec-
n3000
```

## SriovNetwork.yaml

```
apiVersion: sriovnetwork.openshift.io/v1
kind: SriovNetwork
metadata:
    name: ""
    namespace: openshift-sriov-network-operator
    annotations: {}
spec:
    # resourceName: ""
    networkNamespace: openshift-sriov-network-operator
# vlan: ""
# spoofChk: ""
# ipam: ""
# linkState: ""
# maxTxRate: ""
```

```
# minTxRate: ""
# vlanQoS: ""
# trust: ""
# capabilities: ""
```

#### SriovNetworkNodePolicy.yaml

```
apiVersion: sriovnetwork.openshift.io/v1
kind: SriovNetworkNodePolicy
metadata:
 name: $name
 namespace: openshift-sriov-network-operator
 annotations: {}
spec:
 # The attributes for Mellanox/Intel based NICs as below.
     deviceType: netdevice/vfio-pci
     isRdma: true/false
 deviceType: $deviceType
 isRdma: $isRdma
 nicSelector:
  # The exact physical function name must match the hardware used
  pfNames: [$pfNames]
 nodeSelector:
  node-role.kubernetes.io/$mcp: ""
 numVfs: $numVfs
 priority: $priority
 resourceName: $resourceName
```

## SriovOperatorConfig.yaml

```
apiVersion: sriovnetwork.openshift.io/v1
kind: SriovOperatorConfig
metadata:
 name: default
 namespace: openshift-sriov-network-operator
 annotations: {}
spec:
 configDaemonNodeSelector:
  "node-role.kubernetes.io/$mcp": ""
 # Injector and OperatorWebhook pods can be disabled (set to "false") below
 # to reduce the number of management pods. It is recommended to start with the
 # webhook and injector pods enabled, and only disable them after verifying the
 # correctness of user manifests.
 # If the injector is disabled, containers using sr-iov resources must explicitly assign
 # them in the "requests"/"limits" section of the container spec, for example:
 # containers:
 # - name: my-sriov-workload-container
 #
    resources:
 #
      limits:
 #
       openshift.io/<resource name>: "1"
 #
       requests:
        openshift.io/<resource_name>: "1"
 enableInjector: false
 enableOperatorWebhook: false
 logLevel: 0
```

## SriovOperatorConfigForSNO.yaml

```
apiVersion: sriovnetwork.openshift.io/v1
kind: SriovOperatorConfig
metadata:
 name: default
 namespace: openshift-sriov-network-operator
 annotations: {}
spec:
 configDaemonNodeSelector:
  "node-role.kubernetes.io/$mcp": ""
 # Injector and OperatorWebhook pods can be disabled (set to "false") below
 # to reduce the number of management pods. It is recommended to start with the
 # webhook and injector pods enabled, and only disable them after verifying the
 # correctness of user manifests.
 # If the injector is disabled, containers using sr-iov resources must explicitly assign
 # them in the "requests"/"limits" section of the container spec, for example:
 # containers:
 # - name: my-sriov-workload-container
 #
     resources:
 #
      limits:
 #
        openshift.io/<resource name>: "1"
 #
       requests:
        openshift.io/<resource_name>: "1"
 enableInjector: false
 enableOperatorWebhook: false
 # Disable drain is needed for Single Node Openshift
 disableDrain: true
 logLevel: 0
```

#### SriovSubscription.yaml

```
apiVersion: operators.coreos.com/v1alpha1 kind: Subscription metadata: name: sriov-network-operator-subscription namespace: openshift-sriov-network-operator annotations: {} spec: channel: "stable" name: sriov-network-operator source: redhat-operators-disconnected sourceNamespace: openshift-marketplace installPlanApproval: Manual status: state: AtLatestKnown
```

#### SriovSubscriptionNS.yaml

apiVersion: v1 kind: Namespace metadata:

```
name: openshift-sriov-network-operator
annotations:
workload.openshift.io/allowed: management
```

## SriovSubscriptionOperGroup.yaml

```
apiVersion: operators.coreos.com/v1
kind: OperatorGroup
metadata:
name: sriov-network-operators
namespace: openshift-sriov-network-operator
annotations: {}
spec:
targetNamespaces:
- openshift-sriov-network-operator
```

#### 2.2.4.4.2. Cluster tuning reference YAML

#### example-sno.yaml

```
# example-node1-bmh-secret & assisted-deployment-pull-secret need to be created under same
namespace example-sno
apiVersion: ran.openshift.io/v1
kind: SiteConfig
metadata:
 name: "example-sno"
 namespace: "example-sno"
 baseDomain: "example.com"
 pullSecretRef:
  name: "assisted-deployment-pull-secret"
 clusterImageSetNameRef: "openshift-4.16"
 sshPublicKey: "ssh-rsa AAAA..."
 clusters:
  - clusterName: "example-sno"
   networkType: "OVNKubernetes"
   # installConfigOverrides is a generic way of passing install-config
   # parameters through the siteConfig. The 'capabilities' field configures
   # the composable openshift feature. In this 'capabilities' setting, we
   # remove all the optional set of components.
   # - OperatorLifecycleManager is needed for 4.15 and later
   # - NodeTuning is needed for 4.13 and later, not for 4.12 and earlier
   # - Ingress is needed for 4.16 and later
   installConfigOverrides: |
      "capabilities": {
       "baselineCapabilitySet": "None",
       "additionalEnabledCapabilities": [
        "NodeTuning",
        "OperatorLifecycleManager",
        "Ingress"
```

```
# It is strongly recommended to include crun manifests as part of the additional install-time
manifests for 4.13+.
   # The crun manifests can be obtained from source-crs/optional-extra-manifest/ and added to the
git repo ie.sno-extra-manifest.
   # extraManifestPath: sno-extra-manifest
   clusterLabels:
     # These example cluster labels correspond to the bindingRules in the PolicyGenTemplate
examples
     du-profile: "latest"
     # These example cluster labels correspond to the bindingRules in the PolicyGenTemplate
examples in ../policygentemplates:
     # ../policygentemplates/common-ranGen.yaml will apply to all clusters with 'common: true'
     common: true
     # ../policygentemplates/group-du-sno-ranGen.yaml will apply to all clusters with 'group-du-sno:
    group-du-sno: ""
     "../policygentemplates/example-sno-site.yaml will apply to all clusters with 'sites: "example-sno"
     # Normally this should match or contain the cluster name so it only applies to a single cluster
     sites: "example-sno"
   clusterNetwork:
     - cidr: 1001:1::/48
      hostPrefix: 64
   machineNetwork:
     - cidr: 1111:2222:3333:4444::/64
   serviceNetwork:
    - 1001:2::/112
   additionalNTPSources:
    - 1111:2222:3333:4444::2
   # Initiates the cluster for workload partitioning. Setting specific reserved/isolated CPUSets is done
via PolicyTemplate
   # please see Workload Partitioning Feature for a complete guide.
   cpuPartitioningMode: AllNodes
   # Optionally; This can be used to override the KlusterletAddonConfig that is created for this
cluster:
   #crTemplates:
   # KlusterletAddonConfig: "KlusterletAddonConfigOverride.yaml"
     - hostName: "example-node1.example.com"
      role: "master"
      # Optionally; This can be used to configure desired BIOS setting on a host:
      #biosConfigRef:
      # filePath: "example-hw.profile"
      bmcAddress: "idrac-
virtualmedia+https://[1111:2222:3333:4444::bbbb:1]/redfish/v1/Systems/System.Embedded.1"
      bmcCredentialsName:
       name: "example-node1-bmh-secret"
      bootMACAddress: "AA:BB:CC:DD:EE:11"
      # Use UEFISecureBoot to enable secure boot
      bootMode: "UEFI"
      rootDeviceHints:
       deviceName: "/dev/disk/by-path/pci-0000:01:00.0-scsi-0:2:0:0"
      # disk partition at `var/lib/containers` with ignitionConfigOverride. Some values must be
updated. See DiskPartitionContainer.md for more details
      ignitionConfigOverride: |
```

```
"ignition": {
                               "version": "3.2.0"
                            "storage": {
                               "disks": [
                                       "device": "/dev/disk/by-id/wwn-0x6b07b250ebb9d0002a33509f24af1f62",
                                       "partitions": [
                                              "label": "var-lib-containers",
                                              "sizeMiB": 0.
                                              "startMiB": 250000
                                       "wipeTable": false
                               ],
                               "filesystems": [
                                       "device": "/dev/disk/by-partlabel/var-lib-containers",
                                       "format": "xfs",
                                       "mountOptions": [
                                          "defaults",
                                           "prjquota"
                                       "path": "/var/lib/containers",
                                       "wipeFilesystem": true
                              ]
                           "systemd": {
                               "units": [
                                       "contents": "# Generated by Butane\n[Unit]\nRequires=systemd-fsck@dev-disk-
by\\x2dpartlabel-var\\x2dlib\\x2dcontainers.service\nAfter=systemd-fsck@dev-disk-by\\x2dpartlabel-
var\\x2dlib\\x2dcontainers.service\n\n[Mount]\nWhere=/var/lib/containers\nWhat=/dev/disk/by-
partlabel/var-lib-containers \\ \n Type=xfs \\ \n Options=defaults, priquota \\ \n [Install] \\ \n Required By=local-lib-containers \\ \n Type=xfs \\ \n Options=defaults, priquota \\ \n (Install] \\ \n Required By=local-lib-containers \\ \n Type=xfs \\ \n Options=defaults, priquota \\ \n (Install] \\ \n Required By=local-lib-containers \\ \n (Install) \\ \n (In
fs.target",
                                       "enabled": true,
                                       "name": "var-lib-containers.mount"
                       }
                   nodeNetwork:
                       interfaces:
                           - name: eno1
                               macAddress: "AA:BB:CC:DD:EE:11"
                       config:
                           interfaces:
                               - name: eno1
                                   type: ethernet
                                   state: up
                                   ipv4:
                                       enabled: false
```

```
ipv6:
   enabled: true
   address:
     # For SNO sites with static IP addresses, the node-specific,
     # API and Ingress IPs should all be the same and configured on
     # the interface
    - ip: 1111:2222:3333:4444::aaaa:1
      prefix-length: 64
dns-resolver:
 config:
  search:
   - example.com
  server:
   - 1111:2222:3333:4444::2
routes:
 config:
  - destination: ::/0
   next-hop-interface: eno1
   next-hop-address: 1111:2222:3333:4444::1
   table-id: 254
```

## DisableSnoNetworkDiag.yaml

```
apiVersion: operator.openshift.io/v1 kind: Network metadata: name: cluster annotations: {} spec: disableNetworkDiagnostics: true
```

#### ReduceMonitoringFootprint.yaml

```
apiVersion: v1
kind: ConfigMap
metadata:
name: cluster-monitoring-config
namespace: openshift-monitoring
annotations: {}
data:
config.yaml: |
alertmanagerMain:
enabled: false
telemeterClient:
enabled: false
prometheusK8s:
retention: 24h
```

## DefaultCatsrc.yaml

```
apiVersion: operators.coreos.com/v1alpha1 kind: CatalogSource metadata: name: default-cat-source
```

```
namespace: openshift-marketplace
annotations:
   target.workload.openshift.io/management: '{"effect": "PreferredDuringScheduling"}'
spec:
   displayName: default-cat-source
   image: $imageUrl
   publisher: Red Hat
   sourceType: grpc
   updateStrategy:
   registryPoll:
    interval: 1h
status:
   connectionState:
   lastObservedState: READY
```

# DisableOLMPprof.yaml

```
apiVersion: v1
kind: ConfigMap
metadata:
name: collect-profiles-config
namespace: openshift-operator-lifecycle-manager
annotations: {}
data:
pprof-config.yaml: |
disabled: True
```

# DisconnectedICSP.yaml

```
apiVersion: operator.openshift.io/v1alpha1
kind: ImageContentSourcePolicy
metadata:
   name: disconnected-internal-icsp
   annotations: {}
spec:
# repositoryDigestMirrors:
# - $mirrors
```

#### OperatorHub.yaml

```
apiVersion: config.openshift.io/v1 kind: OperatorHub metadata: name: cluster annotations: {} spec: disableAllDefaultSources: true
```

#### 09-openshift-marketplace-ns.yaml

```
# Taken from https://github.com/operator-framework/operator-marketplace/blob/53c124a3f0edfd151652e1f23c87dd39ed7646bb/manifests/01_namespace.yaml # Update it as the source evolves.
apiVersion: v1
```

```
kind: Namespace
metadata:
annotations:
openshift.io/node-selector: ""
workload.openshift.io/allowed: "management"
labels:
openshift.io/cluster-monitoring: "true"
pod-security.kubernetes.io/enforce: baseline
pod-security.kubernetes.io/enforce-version: v1.25
pod-security.kubernetes.io/audit: baseline
pod-security.kubernetes.io/audit-version: v1.25
pod-security.kubernetes.io/warn: baseline
pod-security.kubernetes.io/warn-version: v1.25
name: "openshift-marketplace"
```

#### 2.2.4.4.3. Machine configuration reference YAML

#### enable-crun-master.yaml

```
apiVersion: machineconfiguration.openshift.io/v1
kind: ContainerRuntimeConfig
metadata:
name: enable-crun-master
spec:
machineConfigPoolSelector:
matchLabels:
pools.operator.machineconfiguration.openshift.io/master: ""
containerRuntimeConfig:
defaultRuntime: crun
```

## enable-crun-worker.yaml

```
apiVersion: machineconfiguration.openshift.io/v1
kind: ContainerRuntimeConfig
metadata:
name: enable-crun-worker
spec:
machineConfigPoolSelector:
matchLabels:
pools.operator.machineconfiguration.openshift.io/worker: ""
containerRuntimeConfig:
defaultRuntime: crun
```

#### 99-crio-disable-wipe-master.yaml

```
# Automatically generated by extra-manifests-builder # Do not make changes directly.
apiVersion: machineconfiguration.openshift.io/v1 kind: MachineConfig metadata:
labels:
machineconfiguration.openshift.io/role: master name: 99-crio-disable-wipe-master spec:
```

```
config:
    ignition:
    version: 3.2.0
    storage:
    files:
        - contents:
        source: data:text/plain;charset=utf-
8;base64,W2NyaW9dCmNsZWFuX3NodXRkb3duX2ZpbGUgPSAilgo=
        mode: 420
        path: /etc/crio/crio.conf.d/99-crio-disable-wipe.toml
```

## 99-crio-disable-wipe-worker.yaml

```
# Automatically generated by extra-manifests-builder
# Do not make changes directly.
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
labels:
  machineconfiguration.openshift.io/role: worker
 name: 99-crio-disable-wipe-worker
spec:
 config:
  ignition:
   version: 3.2.0
  storage:
   files:
    - contents:
       source: data:text/plain;charset=utf-
8;base64,W2NyaW9dCmNsZWFuX3NodXRkb3duX2ZpbGUgPSAilgo=
      mode: 420
      path: /etc/crio/crio.conf.d/99-crio-disable-wipe.toml
```

# 06-kdump-master.yaml

```
# Automatically generated by extra-manifests-builder
# Do not make changes directly.
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
 labels:
  machineconfiguration.openshift.io/role: master
 name: 06-kdump-enable-master
spec:
 config:
  ignition:
   version: 3.2.0
  systemd:
   units:
     - enabled: true
      name: kdump.service
 kernelArguments:
  - crashkernel=512M
```

## 06-kdump-worker.yaml

```
# Automatically generated by extra-manifests-builder
# Do not make changes directly.
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
 labels:
  machineconfiguration.openshift.io/role: worker
 name: 06-kdump-enable-worker
spec:
 config:
  ignition:
   version: 3.2.0
  systemd:
   units:
    - enabled: true
      name: kdump.service
 kernelArguments:
  - crashkernel=512M
```

## O1-container-mount-ns-and-kubelet-conf-master.yaml

```
# Automatically generated by extra-manifests-builder
# Do not make changes directly.
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
 labels:
  machineconfiguration.openshift.io/role: master
 name: container-mount-namespace-and-kubelet-conf-master
spec:
 config:
  ignition:
   version: 3.2.0
  storage:
   files:
     - contents:
       source: data:text/plain;charset=utf-
```

8;base64,lyEvYmluL2Jhc2gKCmRlYnVnKCkgewoglGVjaG8gJEAgPiYyCn0KCnVzYWdlKCkgewoglGVj aG8gVXNhZ2U6ICQoYmFzZW5hbWUgJDApIFVOSVQgW2VudmZpbGUgW3Zhcm5hbWVdXQogIGV jaG8KICBIY2hvIEV4dHJhY3QgdGhlIGNvbnRlbnRzIG9mIHRoZSBmaXJzdCBFeGVjU3RhcnQgc3Rhbn phIGZyb20gdGhIIGdpdmVuIHN5c3RlbWQgdW5pdCBhbmQgcmV0dXJuIGI0IHRvIHN0ZG91dAogIGVi aG8KICBIY2hvICJJZiAnZW52ZmlsZScqaXMqcHJvdmlkZWQsIHB1dCBpdCBpbiB0aGVyZSBpbnN0ZW FkLCBhcyBhbiBlbnZpcm9ubWVudCB2YXJpYWJsZSBuYW1IZCAndmFybmFtZSciCiAgZWNobyAiRGV mYXVsdCAndmFybmFtZScgaXMgRVhFQ1NUQVJUIGImIG5vdCBzcGVjaWZpZWQiCiAgZXhpdCAxC n0KClVOSVQ9JDEKRU5WRklMRT0kMgpWQVJOQU1FPSQzCmlmlFtblC16lCRVTklUlHx8lCRVTklUl D09ICltLWhlbHAilHx8ICRVTkIUID09ICltaClgXV07IHRoZW4KICB1c2FnZQpmaQpkZWJ1ZyAiRXh0cm FjdGluZyBFeGVjU3RhcnQgZnJvbSAkVU5JVCIKRklMRT0kKHN5c3RlbWN0bCBjYXQgJFVOSVQgfCB oZWFkIC1uIDEpCkZJTEU9JHtGSUxFI1wjIH0KaWYgW1sgISAtZiAkRklMRSBdXTsgdGhlbgogIGRlYnV nICJGYWIsZWQgdG8gZmluZCByb290IGZpbGUgZm9yIHVuaXQgJFVOSVQgKCRGSUxFKSIKICBle GIOCmZpCmRIYnVnICJTZXJ2aWNIIGRIZmluaXRpb24gaXMgaW4gJEZJTEUiCkVYRUNTVEFSVD0k KHNIZCAtbiAtZSAnL15FeGVjU3RhcnQ9LipcXCQvLC9bXlxcXSQvIHsqcy9eRXhIY1N0YXJ0PS8vOyBw IH0nlC1llCcvXkV4ZWNTdGFydD0uKlteXFxdJC8geyBzL15FeGVjU3RhcnQ9Ly87lHAgfScgJEZJTEUp CgppZiBbWyAkRU5WRkIMRSBdXTsgdGhlbgogIFZBUk5BTUU9JHtWQVJOQU1FOi1FWEVDU1RBUI R9CiAgZWNobyAiJHtWQVJOQU1FfT0ke0VYRUNTVEFSVH0iID4gJEVOVkZJTEUKZWxzZQogIGVja G8gJEVYRUNTVEFSVApmaQo=

```
mode: 493
     path: /usr/local/bin/extractExecStart
    - contents:
      source: data:text/plain;charset=utf-
8;base64,lyEvYmluL2Jhc2gKbnNlbnRlciAtLW1vdW50PS9ydW4vY29udGFpbmVyLW1vdW50LW5hbW\
zcGFjZS9tbnQgliRAlgo=
     mode: 493
     path: /usr/local/bin/nsenterCmns
  systemd:
   units:
    - contents: |
      [Unit]
      Description=Manages a mount namespace that both kubelet and crio can use to share their
container-specific mounts
      [Service]
       Type=oneshot
      RemainAfterExit=yes
      RuntimeDirectory=container-mount-namespace
      Environment=RUNTIME DIRECTORY=%t/container-mount-namespace
      Environment=BIND POINT=%t/container-mount-namespace/mnt
      ExecStartPre=bash -c "findmnt ${RUNTIME DIRECTORY} || mount --make-unbindable --
bind ${RUNTIME DIRECTORY} ${RUNTIME DIRECTORY}"
      ExecStartPre=touch ${BIND POINT}
      ExecStart=unshare --mount=${BIND_POINT} --propagation slave mount --make-rshared /
      ExecStop=umount -R ${RUNTIME_DIRECTORY}
     name: container-mount-namespace.service
    - dropins:
      - contents: |
         [Unit]
         Wants=container-mount-namespace.service
         After=container-mount-namespace.service
         [Service]
         ExecStartPre=/usr/local/bin/extractExecStart %n /%t/%N-execstart.env
ORIG EXECSTART
         EnvironmentFile=-/%t/%N-execstart.env
         ExecStart=
         ExecStart=bash -c "nsenter --mount=%t/container-mount-namespace/mnt \
           ${ORIG_EXECSTART}"
        name: 90-container-mount-namespace.conf
     name: crio.service
    - dropins:
      - contents: |
         [Unit]
         Wants=container-mount-namespace.service
         After=container-mount-namespace.service
         [Service]
         ExecStartPre=/usr/local/bin/extractExecStart %n /%t/%N-execstart.env
ORIG EXECSTART
         EnvironmentFile=-/%t/%N-execstart.env
         ExecStart=
         ExecStart=bash -c "nsenter --mount=%t/container-mount-namespace/mnt \
           ${ORIG EXECSTART} --housekeeping-interval=30s"
        name: 90-container-mount-namespace.conf
```

```
- contents: |
    [Service]
    Environment="OPENSHIFT_MAX_HOUSEKEEPING_INTERVAL_DURATION=60s"
    Environment="OPENSHIFT_EVICTION_MONITORING_PERIOD_DURATION=30s"
    name: 30-kubelet-interval-tuning.conf
name: kubelet.service
```

## O1-container-mount-ns-and-kubelet-conf-worker.yaml

```
# Automatically generated by extra-manifests-builder
# Do not make changes directly.
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
 labels:
  machineconfiguration.openshift.io/role: worker
 name: container-mount-namespace-and-kubelet-conf-worker
spec:
 config:
  ignition:
   version: 3.2.0
  storage:
   files:
     - contents:
       source: data:text/plain;charset=utf-
```

8;base64,lyEvYmluL2Jhc2gKCmRlYnVnKCkgewoglGVjaG8gJEAgPiYyCn0KCnVzYWdlKCkgewoglGVj aG8gVXNhZ2U6ICQoYmFzZW5hbWUgJDApIFVOSVQgW2VudmZpbGUgW3Zhcm5hbWVdXQogIGV jaG8KICBIY2hvIEV4dHJhY3QgdGhlIGNvbnRlbnRzIG9mIHRoZSBmaXJzdCBFeGVjU3RhcnQgc3Rhbn phIGZyb20gdGhIIGdpdmVuIHN5c3RlbWQgdW5pdCBhbmQgcmV0dXJuIGI0IHRvIHN0ZG91dAogIGVj aG8KICBIY2hvICJJZiAnZW52ZmlsZScgaXMgcHJvdmlkZWQsIHB1dCBpdCBpbiB0aGVyZSBpbnN0ZW FkLCBhcyBhbiBlbnZpcm9ubWVudCB2YXJpYWJsZSBuYW1IZCAndmFybmFtZSciCiAgZWNobyAiRGV mYXVsdCAndmFybmFtZScgaXMgRVhFQ1NUQVJUIGImIG5vdCBzcGVjaWZpZWQiCiAgZXhpdCAxC n0KClVOSVQ9JDEKRU5WRklMRT0kMgpWQVJOQU1FPSQzCmlmlFtblC16lCRVTklUlHx8lCRVTklUl D09ICltLWhlbHAilHx8ICRVTklUID09ICltaClgXV07IHRoZW4KICB1c2FnZQpmaQpkZWJ1ZyAiRXh0cm FjdGluZyBFeGVjU3RhcnQqZnJvbSAkVU5JVCIKRklMRT0kKHN5c3RlbWN0bCBjYXQqJFVOSVQqfCB oZWFkIC1uIDEpCkZJTEU9JHtGSUxFI1wjIH0KaWYgW1sgISAtZiAkRkIMRSBdXTsgdGhlbgogIGRIYnV nICJGYWlsZWQqdG8qZmluZCByb290IGZpbGUqZm9yIHVuaXQqJFVOSVQqKCRGSUxFKSIKICBle GI0CmZpCmRIYnVnICJTZXJ2aWNIIGRIZmluaXRpb24gaXMgaW4gJEZJTEUiCkVYRUNTVEFSVD0k KHNIZCAtbiAtZSAnL15FeGVjU3RhcnQ9LipcXCQvLC9bXlxcXSQvIHsqcy9eRXhIY1N0YXJ0PS8vOyBw IH0nlC1llCcvXkV4ZWNTdGFydD0uKlteXFxdJC8geyBzL15FeGVjU3RhcnQ9Ly87lHAgfScgJEZJTEUp CgppZiBbWyAkRU5WRkIMRSBdXTsgdGhlbgogIFZBUk5BTUU9JHtWQVJOQU1FOi1FWEVDU1RBUI R9CiAgZWNobyAiJHtWQVJOQU1FfT0ke0VYRUNTVEFSVH0iID4gJEVOVkZJTEUKZWxzZQogIGVja

```
R9CiAgZWNobyAiJHtWQVJOQU1FfT0ke0VYRUNTVEFSVH0iID4gJEVOVkZJTEUKZWxzZQogIGVja
G8gJEVYRUNTVEFSVApmaQo=
    mode: 493
    path: /usr/local/bin/extractExecStart
    - contents:
        source: data:text/plain;charset=utf-
8;base64,lyEvYmluL2Jhc2gKbnNlbnRlciAtLW1vdW50PS9ydW4vY29udGFpbmVyLW1vdW50LW5hbW\
zcGFjZS9tbnQgliRAlgo=
    mode: 493
    path: /usr/local/bin/nsenterCmns
systemd:
    units:
    - contents: |
        [Unit]
        Description=Manages a mount namespace that both kubelet and crio can use to share their
```

```
container-specific mounts
      [Service]
      Type=oneshot
      RemainAfterExit=yes
      RuntimeDirectory=container-mount-namespace
      Environment=RUNTIME DIRECTORY=%t/container-mount-namespace
      Environment=BIND POINT=%t/container-mount-namespace/mnt
      ExecStartPre=bash -c "findmnt ${RUNTIME DIRECTORY} || mount --make-unbindable --
bind ${RUNTIME DIRECTORY} ${RUNTIME DIRECTORY}"
      ExecStartPre=touch ${BIND POINT}
      ExecStart=unshare --mount=${BIND_POINT} --propagation slave mount --make-rshared /
      ExecStop=umount -R ${RUNTIME DIRECTORY}
     name: container-mount-namespace.service
    - dropins:
      - contents: |
         [Unit]
         Wants=container-mount-namespace.service
         After=container-mount-namespace.service
         [Service]
         ExecStartPre=/usr/local/bin/extractExecStart %n /%t/%N-execstart.env
ORIG EXECSTART
         EnvironmentFile=-/%t/%N-execstart.env
         ExecStart=
         ExecStart=bash -c "nsenter --mount=%t/container-mount-namespace/mnt \
           ${ORIG EXECSTART}"
       name: 90-container-mount-namespace.conf
     name: crio.service
    - dropins:
      - contents: |
         [Unit]
         Wants=container-mount-namespace.service
         After=container-mount-namespace.service
         [Service]
         ExecStartPre=/usr/local/bin/extractExecStart %n /%t/%N-execstart.env
ORIG_EXECSTART
         EnvironmentFile=-/%t/%N-execstart.env
         ExecStart=
         ExecStart=bash -c "nsenter --mount=%t/container-mount-namespace/mnt \
           ${ORIG EXECSTART} --housekeeping-interval=30s"
       name: 90-container-mount-namespace.conf
      - contents: |
        [Service]
         Environment="OPENSHIFT MAX HOUSEKEEPING INTERVAL DURATION=60s"
         Environment="OPENSHIFT EVICTION MONITORING PERIOD DURATION=30s"
       name: 30-kubelet-interval-tuning.conf
     name: kubelet.service
```

### 99-sync-time-once-master.yaml

# Automatically generated by extra-manifests-builder # Do not make changes directly. apiVersion: machineconfiguration.openshift.io/v1 kind: MachineConfig

```
metadata:
 labels:
  machineconfiguration.openshift.io/role: master
 name: 99-sync-time-once-master
spec:
 config:
  ignition:
   version: 3.2.0
  systemd:
   units:
     - contents: |
       [Unit]
       Description=Sync time once
       After=network-online.target
       Wants=network-online.target
       [Service]
       Type=oneshot
       TimeoutStartSec=300
       ExecCondition=/bin/bash -c 'systemctl is-enabled chronyd.service --quiet && exit 1 || exit 0'
       ExecStart=/usr/sbin/chronyd -n -f /etc/chrony.conf -q
       RemainAfterExit=yes
       [Install]
       WantedBy=multi-user.target
      enabled: true
      name: sync-time-once.service
```

## 99-sync-time-once-worker.yaml

```
# Automatically generated by extra-manifests-builder
# Do not make changes directly.
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
 labels:
  machineconfiguration.openshift.io/role: worker
 name: 99-sync-time-once-worker
spec:
 config:
  ignition:
   version: 3.2.0
  systemd:
   units:
     - contents: |
       [Unit]
       Description=Sync time once
       After=network-online.target
       Wants=network-online.target
       [Service]
       Type=oneshot
       TimeoutStartSec=300
       ExecCondition=/bin/bash -c 'systemctl is-enabled chronyd.service --quiet && exit 1 || exit 0'
       ExecStart=/usr/sbin/chronyd -n -f /etc/chrony.conf -q
       RemainAfterExit=yes
       [Install]
```

WantedBy=multi-user.target

enabled: true

name: sync-time-once.service

# 03-sctp-machine-config-master.yaml

```
# Automatically generated by extra-manifests-builder
# Do not make changes directly.
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
labels:
  machineconfiguration.openshift.io/role: master
 name: load-sctp-module-master
spec:
 config:
  ignition:
   version: 2.2.0
  storage:
   files:
     - contents:
       source: data:,
       verification: {}
      filesystem: root
      mode: 420
      path: /etc/modprobe.d/sctp-blacklist.conf
     - contents:
       source: data:text/plain;charset=utf-8,sctp
      filesystem: root
      mode: 420
      path: /etc/modules-load.d/sctp-load.conf
```

# 03-sctp-machine-config-worker.yaml

```
# Automatically generated by extra-manifests-builder
# Do not make changes directly.
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
 labels:
  machineconfiguration.openshift.io/role: worker
 name: load-sctp-module-worker
spec:
 config:
  ignition:
   version: 2.2.0
  storage:
   files:
     - contents:
       source: data:,
       verification: {}
      filesystem: root
      mode: 420
      path: /etc/modprobe.d/sctp-blacklist.conf
     - contents:
```

source: data:text/plain;charset=utf-8,sctp

filesystem: root mode: 420

path: /etc/modules-load.d/sctp-load.conf

## 08-set-rcu-normal-master.yaml

- contents:

```
# Automatically generated by extra-manifests-builder
# Do not make changes directly.
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
labels:
    machineconfiguration.openshift.io/role: master
    name: 08-set-rcu-normal-master
spec:
    config:
    ignition:
        version: 3.2.0
        storage:
        files:
```

source: data:text/plain;charset=utf-64.lvEvYmluL2Jhc2gKlwoiIERpc2Fi

8;base64,lyEvYmluL2Jhc2gKlwojIERpc2FibGUgcmN1X2V4cGVkaXRIZCBhZnRlciBub2RIIGhhcyBmaW 5pc2hlZCBib290aW5nCiMKlyBUaGUgZGVmYXVsdHMgYmVsb3cgY2FulGJIIG92ZXJyaWRkZW4gdml hIGVudmlyb25tZW50IHZhcmlhYmxlcwojCgojIERIZmF1bHQgd2FpdCB0aW1IIGIzIDYwMHMgPSAxMG 06Ck1BWEINVU1fV0FJVF9USU1FPSR7TUFYSU1VTV9XQUIUX1RJTUU6LTYwMH0KCiMgRGVmY XVsdCBzdGVhZHktc3RhdGUgdGhyZXNob2xkID0gMiUKIyBBbGxvd2VkIHZhbHVlczoKIyAgNCAgLSBh YnNvbHV0ZSBwb2QgY291bnQgKCsvLSkKlyAgNCUgLSBwZXJjZW50IGNoYW5nZSAoKy8tKQojlCAt MSAtIGRpc2FibGUgdGhIIHN0ZWFkeS1zdGF0ZSBjaGVjawpTVEVBRFIfU1RBVEVfVEhSRVNIT0xEP SR7U1RFQURZX1NUQVRFX1RIUkVTSE9MRDotMiV9CgojlERIZmF1bHQgc3RIYWR5LXN0YXRIIHd pbmRvdyA9IDYwcwojIEImIHRoZSBydW5uaW5nIHBvZCBjb3VudCBzdGF5cyB3aXRoaW4gdGhlIGdpd mVulHRocmVzaG9sZCBmb3lgdGhpcyB0aW1lCiMgcGVyaW9kLCByZXR1cm4gQ1BVlHV0aWxpemF0 aW9uIHRvIG5vcm1hbCBiZWZvcmUgdGhlIG1heGltdW0gd2FpdCB0aW1lIGhhcwojlGV4cGlyZXMKU1 RFQURZX1NUQVRFX1dJTkRPVz0ke1NURUFEWV9TVEFURV9XSU5ET1c6LTYwfQoKlyBEZWZhd Wx0IHN0ZWFkeS1zdGF0ZSBhbGxvd3MgYW55IHBvZCBjb3VudCB0byBiZSAic3RIYWR5IHN0YXRIIgo jIEluY3JIYXNpbmcgdGhpcyB3aWxsIHNraXAgYW55IHN0ZWFkeS1zdGF0ZSBjaGVja3MgdW50aWwgd GhIIGNvdW50IHJpc2VzIGFib3ZlCiMgdGhpcyBudW1iZXlgdG8gYXZvaWQgZmFsc2UgcG9zaXRpdmV zIGImIHRoZXJIIGFyZSBzb21IIHBlcmlvZHMgd2hlcmUgdGhlCiMgY291bnQgZG9lc24ndCBpbmNyZWF zZSBidXQgd2Uga25vdyB3ZSBjYW4ndCBiZSBhdCBzdGVhZHktc3RhdGUgeWV0LgpTVEVBRFlfU1RB udD0kMiB0aHJlc2hvbGQ9JDMKICBsb2NhbCBkZWx0YT0wIHBjaGFuZ2UKICBkZWx0YT0kKCqqY3Vy cmVudCAtIGxhc3QgKSkKICBpZiBbWyAkY3VycmVudCAtZXEgJGxhc3QgXV07IHRoZW4KICAgIHBjaG FuZ2U9MAogIGVsaWYgW1sgJGxhc3QgLWVxIDAgXV07IHRoZW4KICAgIHBjaGFuZ2U9MTAwMDA wMAogIGVsc2UKICAgIHBjaGFuZ2U9JCgoICggliRkZWx0YSIgKiAxMDApIC8gbGFzdCApKQogIGZpCi AqZWNobyAtbiAibGFzdDokbGFzdCBjdXJyZW50OiRjdXJyZW50IGRlbHRhOiRkZWx0YSBwY2hhbmdl OiR7cGNoYW5nZX0lOiAiCiAgbG9jYWwgYWJzb2x1dGUgbGltaXQKICBjYXNIICR0aHJlc2hvbGQgaW4 KICAgIColKQogICAgICBhYnNvbHV0ZT0ke3BjaGFuZ2Ujly19ICMgYWJzb2x1dGUgdmFsdWUKICAgI CAgbGltaXQ9JHt0aHJlc2hvbGQlJSV9CiAglCAglDs7CiAglCAqKQoglCAglCBhYnNvbHV0ZT0ke2RlbH RhlyMtfSAjIGFic29sdXRIIHZhbHVlCiAgICAgIGxpbWl0PSR0aHJlc2hvbGQKlCAgICAgOzsKlCBlc2FjCiA gaWYgW1sgJGFic29sdXRIIC1sZSAkbGltaXQgXV07IHRoZW4KICAgIGVjaG8gIndpdGhpbiAoKy8tKSR 0aHJlc2hvbGQiCiAglCByZXR1cm4gMAoglGVsc2UKlCAglGVjaG8gIm91dHNpZGUgKCsvLSkkdGhyZ XNob2xklgoglCAgcmV0dXJuIDEKICBmaQp9CgpzdGVhZHlzdGF0ZSgpIHsKICBsb2NhbCBsYXN0PS QxIGN1cnJlbnQ9JDIKICBpZiBbWyAkbGFzdCAtbHQgJFNURUFEWV9TVEFURV9NSU5JTVVNIF1dO yB0aGVuCiAgICBIY2hvICJsYXN00iRsYXN0IGN1cnJlbnQ6JGN1cnJlbnQgV2FpdGluZyB0byByZWFja

CAkU1RFQURZX1NUQVRFX01JTkINVU0gYmVmb3JIIGNoZWNraW5nIGZvciBzdGVhZHktc3RhdGUi CiAgICByZXR1cm4gMQogIGZpCiAgd2l0aGluIClkbGFzdClgliRjdXJyZW50liAiJFNURUFEWV9TVEFU RV9USFJFU0hPTEQiCn0KCndhaXRGb3JSZWFkeSqpIHsKICBsb2dnZXlqIIJIY292ZXJ5OiBXYWI0aW 5nlCR7TUFYSU1VTV9XQUIUX1RJTUV9cyBmb3lgdGhlIGluaXRpYWxpemF0aW9ulHRvIGNvbXBsZX RIIgogIGxvY2FsIHQ9MCBzPTEwCiAgbG9jYWwgbGFzdENjb3VudD0wIGNjb3VudD0wIHN0ZWFkeVN 0YXRIVGltZT0wCiAgd2hpbGUgW1sgJHQgLWx0ICRNQVhJTVVNX1dBSVRfVEINRSBdXTsgZG8KIC AgIHNsZWVwICRzCiAgICAoKHQgKz0gcykpCiAgICAjIERldGVjdCBzdGVhZHktc3RhdGUgcG9kIGNvd W50CiAglCBjY291bnQ9JChjcmljdGwgcHMgMj4vZGV2L251bGwgfCB3YyAtbCkKlCAglGlmlFtblCRjY2 91bnQgLWd0IDAgXV0gJiYgc3RIYWR5c3RhdGUgIiRsYXN0Q2NvdW50IiAiJGNjb3VudCI7IHRoZW4KI CAgICAgKChzdGVhZHITdGF0ZVRpbWUgKz0gcykpCiAgICAgIGVjaG8gIIN0ZWFkeS1zdGF0ZSBmb3 IgJHtzdGVhZHITdGF0ZVRpbWV9cy8ke1NURUFEWV9TVEFURV9XSU5ET1d9cyIKICAqICAqaWYqW 1sgJHN0ZWFkeVN0YXRIVGltZSAtZ2UgJFNURUFEWV9TVEFURV9XSU5ET1cgXV07IHRoZW4KICA qlCAglCBsb2dnZXlgllJlY292ZXJ5OiBTdGVhZHktc3RhdGUgKCsvLSAkU1RFQURZX1NUQVRFX1RI UkVTSE9MRCkgZm9ylCR7U1RFQURZX1NUQVRFX1dJTkRPV31zOiBEb25llgoglCAglCAglHJldHVy biAwCiAgICAgIGZpCiAgICBlbHNlCiAgICAgIGImIFtblCRzdGVhZHlTdGF0ZVRpbWUgLWd0IDAgXV07 IHRoZW4KICAqICAqICBIY2hvICJSZXNIdHRpbmcqc3RIYWR5LXN0YXRIIHRpbWVyIqoqICAqICAqIHN 0ZWFkeVN0YXRIVGltZT0wCiAgICAgIGZpCiAgICBmaQogICAgbGFzdENjb3VudD0kY2NvdW50CiAgZ G9uZQogIGxvZ2dlciAiUmVjb3Zlcnk6IFJIY292ZXJ5IENvbXBsZXRIIFRpbWVvdXQiCn0KCnNldFJjdU5vc m1hbCgpIHsKICBIY2hvICJTZXR0aW5nIHJjdV9ub3JtYWwgdG8gMSIKICBIY2hvIDEgPiAvc3lzL2tlcm5lk C9yY3Vfbm9ybWFsCn0KCm1haW4oKSB7CiAgd2FpdEZvclJIYWR5CiAgZWNobyAiV2FpdGluZyBmb3I gc3RIYWR5IHN0YXRIIHRvb2s6ICQoYXdrICd7cHJpbnQgaW50KCQxLzM2MDApImgiLCBpbnQoKCQ xJTM2MDApLzYwKSJtliwgaW50KCQxJTYwKSJzIn0nIC9wcm9jL3VwdGltZSkiCiAgc2V0UmN1Tm9yb WFsCn0KCmlmlFtblClke0JBU0hfU09VUkNFWzBdfSlgPSAiJHswfSlgXV07lHRoZW4KlCBtYWlulClke0 B9lgoglGV4aXQgJD8KZmkK

```
mode: 493
   path: /usr/local/bin/set-rcu-normal.sh
systemd:
 units:
  - contents: |
    [Unit]
    Description=Disable rcu expedited after node has finished booting by setting rcu normal to 1
    [Service]
    Type=simple
    ExecStart=/usr/local/bin/set-rcu-normal.sh
    # Maximum wait time is 600s = 10m:
    Environment=MAXIMUM WAIT TIME=600
    # Steady-state threshold = 2%
    # Allowed values:
    # 4 - absolute pod count (+/-)
    # 4% - percent change (+/-)
    # -1 - disable the steady-state check
    # Note: '%' must be escaped as '%%' in systemd unit files
    Environment=STEADY STATE THRESHOLD=2%%
    # Steady-state window = 120s
    # If the running pod count stays within the given threshold for this time
    # period, return CPU utilization to normal before the maximum wait time has
    # expires
    Environment=STEADY STATE WINDOW=120
    # Steady-state minimum = 40
    # Increasing this will skip any steady-state checks until the count rises above
    # this number to avoid false positives if there are some periods where the
```

```
# count doesn't increase but we know we can't be at steady-state yet. 
Environment=STEADY_STATE_MINIMUM=40
```

[Install]

- contents:

WantedBy=multi-user.target

enabled: true

name: set-rcu-normal.service

## 08-set-rcu-normal-worker.yaml

```
# Automatically generated by extra-manifests-builder
# Do not make changes directly.
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
labels:
    machineconfiguration.openshift.io/role: worker
    name: 08-set-rcu-normal-worker
spec:
    config:
    ignition:
        version: 3.2.0
        storage:
        files:
```

source: data:text/plain;charset=utf-

8;base64,lyEvYmluL2Jhc2gKlwojIERpc2FibGUgcmN1X2V4cGVkaXRIZCBhZnRlciBub2RIIGhhcyBmaW 5pc2hlZCBib290aW5nCiMKlyBUaGUgZGVmYXVsdHMgYmVsb3cgY2FulGJIIG92ZXJyaWRkZW4gdml hIGVudmlyb25tZW50IHZhcmlhYmxlcwojCgojIERIZmF1bHQgd2FpdCB0aW1IIGIzIDYwMHMgPSAxMG 06Ck1BWEINVU1fV0FJVF9USU1FPSR7TUFYSU1VTV9XQUIUX1RJTUU6LTYwMH0KCiMqRGVmY XVsdCBzdGVhZHktc3RhdGUgdGhyZXNob2xkID0gMiUKlyBBbGxvd2VkIHZhbHVlczoKlyAgNCAgLSBh YnNvbHV0ZSBwb2QgY291bnQgKCsvLSkKlyAgNCUgLSBwZXJjZW50IGNoYW5nZSAoKy8tKQojlCAt MSAtIGRpc2FibGUgdGhIIHN0ZWFkeS1zdGF0ZSBjaGVjawpTVEVBRFlfU1RBVEVfVEhSRVNIT0xEP SR7U1RFQURZX1NUQVRFX1RIUkVTSE9MRDotMiV9CgojlERIZmF1bHQgc3RIYWR5LXN0YXRIIHd pbmRvdyA9IDYwcwojIEImIHRoZSBydW5uaW5nIHBvZCBjb3VudCBzdGF5cyB3aXRoaW4qdGhlIGdpd mVulHRocmVzaG9sZCBmb3lgdGhpcyB0aW1lCiMgcGVyaW9kLCByZXR1cm4gQ1BVlHV0aWxpemF0 aW9uIHRvIG5vcm1hbCBiZWZvcmUgdGhlIG1heGltdW0gd2FpdCB0aW1lIGhhcwojIGV4cGlyZXMKU1 RFQURZX1NUQVRFX1dJTkRPVz0ke1NURUFEWV9TVEFURV9XSU5ET1c6LTYwfQoKlyBEZWZhd Wx0IHN0ZWFkeS1zdGF0ZSBhbGxvd3MgYW55IHBvZCBjb3VudCB0byBiZSAic3RIYWR5IHN0YXRIIgo jIEluY3JJYXNpbmcgdGhpcyB3aWxsIHNraXAgYW55IHN0ZWFkeS1zdGF0ZSBjaGVja3MgdW50aWwgd GhIIGNvdW50IHJpc2VzIGFib3ZlCiMgdGhpcyBudW1iZXlgdG8gYXZvaWQgZmFsc2UgcG9zaXRpdmV zIGImIHRoZXJIIGFyZSBzb21IIHBlcmlvZHMgd2hlcmUgdGhlCiMgY291bnQgZG9lc24ndCBpbmNyZWF zZSBidXQqd2Uqa25vdyB3ZSBjYW4ndCBiZSBhdCBzdGVhZHktc3RhdGUqeWV0LqpTVEVBRFlfU1RB udD0kMiB0aHJlc2hvbGQ9JDMKICBsb2NhbCBkZWx0YT0wIHBjaGFuZ2UKICBkZWx0YT0kKCggY3Vy cmVudCAtIGxhc3QgKSkKICBpZiBbWyAkY3VycmVudCAtZXEgJGxhc3QgXV07IHRoZW4KICAgIHBjaG FuZ2U9MAogIGVsaWYgW1sgJGxhc3QqLWVxIDAqXV07IHRoZW4KICAqIHBjaGFuZ2U9MTAwMDA wMAogIGVsc2UKICAgIHBjaGFuZ2U9JCgoICggIiRkZWx0YSIgKiAxMDApIC8gbGFzdCApKQogIGZpCi AgZWNobyAtbiAibGFzdDokbGFzdCBjdXJyZW50OiRjdXJyZW50IGRlbHRhOiRkZWx0YSBwY2hhbmdl OiR7cGNoYW5nZX0lOiAiCiAgbG9jYWwgYWJzb2x1dGUgbGltaXQKICBjYXNlICR0aHJlc2hvbGQgaW4 KICAgIColKQogICAgICBhYnNvbHV0ZT0ke3BjaGFuZ2Ujly19ICMgYWJzb2x1dGUgdmFsdWUKICAgI CAgbGltaXQ9JHt0aHJlc2hvbGQlJSV9CiAglCAglDs7CiAglCAqKQoglCAglCBhYnNvbHV0ZT0ke2RlbH RhlyMtfSAjlGFic29sdXRlIHZhbHVlCiAglCAglGxpbWl0PSR0aHJlc2hvbGQKlCAglCAgOzsKlCBlc2FjCiA gaWYgW1sgJGFic29sdXRIIC1sZSAkbGltaXQgXV07lHRoZW4KlCAgIGVjaG8gIndpdGhpbiAoKy8tKSR 0aHJlc2hvbGQiCiAglCByZXR1cm4gMAoglGVsc2UKlCAglGVjaG8gIm91dHNpZGUgKCsvLSkkdGhyZ

XNob2xklgoglCAgcmV0dXJuIDEKICBmaQp9CgpzdGVhZHlzdGF0ZSgpIHsKlCBsb2NhbCBsYXN0PS QxIGN1cnJlbnQ9JDIKICBpZiBbWyAkbGFzdCAtbHQgJFNURUFEWV9TVEFURV9NSU5JTVVNIF1dO yB0aGVuCiAqlCBlY2hvlCJsYXN00iRsYXN0IGN1cnJlbnQ6JGN1cnJlbnQqV2FpdGluZyB0byByZWFja CAkU1RFQURZX1NUQVRFX01JTkINVU0gYmVmb3JIIGNoZWNraW5nIGZvciBzdGVhZHktc3RhdGUi CiAgICByZXR1cm4gMQogIGZpCiAgd2l0aGluIClkbGFzdClgliRjdXJyZW50liAiJFNURUFEWV9TVEFU RV9USFJFU0hPTEQiCn0KCndhaXRGb3JSZWFkeSgpIHsKICBsb2dnZXlgIIJIY292ZXJ5OiBXYWI0aW 5nlCR7TUFYSU1VTV9XQUIUX1RJTUV9cyBmb3lgdGhlIGluaXRpYWxpemF0aW9ulHRvIGNvbXBsZX RIIgogIGxvY2FsIHQ9MCBzPTEwCiAgbG9jYWwgbGFzdENjb3VudD0wIGNjb3VudD0wIHN0ZWFkeVN 0YXRIVGItZT0wCiAgd2hpbGUgW1sgJHQgLWx0ICRNQVhJTVVNX1dBSVRfVEINRSBdXTsgZG8KICAgIHNsZWVwICRzCiAgICAoKHQgKz0gcykpCiAgICAjIERldGVjdCBzdGVhZHktc3RhdGUgcG9kIGNvd W50CiAqlCBjY291bnQ9JChjcmljdGwgcHMgMj4vZGV2L251bGwgfCB3YyAtbCkKlCAqlGlmlFtblCRjY2 91bnQqLWd0IDAqXV0qJiYqc3RIYWR5c3RhdGUqliRsYXN0Q2NvdW50liAiJGNjb3VudCl7IHRoZW4KI CAgICAgKChzdGVhZHITdGF0ZVRpbWUgKz0gcykpCiAgICAgIGVjaG8gIIN0ZWFkeS1zdGF0ZSBmb3 IgJHtzdGVhZHITdGF0ZVRpbWV9cy8ke1NURUFEWV9TVEFURV9XSU5ET1d9cyIKICAgICAgaWYqW 1sgJHN0ZWFkeVN0YXRIVGltZSAtZ2UgJFNURUFEWV9TVEFURV9XSU5ET1cgXV07IHRoZW4KICA qICAqICBsb2dnZXIqIIJIY292ZXJ5OiBTdGVhZHktc3RhdGUqKCsvLSAkU1RFQURZX1NUQVRFX1RI UkVTSE9MRCkgZm9ylCR7U1RFQURZX1NUQVRFX1dJTkRPV31zOiBEb25llgoglCAglCAglHJldHVy biAwCiAgICAgIGZpCiAgICBlbHNlCiAgICAgIGImIFtblCRzdGVhZHlTdGF0ZVRpbWUgLWd0IDAgXV07 IHRoZW4KICAgICAgICBIY2hvICJSZXNIdHRpbmcgc3RIYWR5LXN0YXRIIHRpbWVyIgogICAgICAgIHN 0ZWFkeVN0YXRIVGltZT0wCiAgICAgIGZpCiAgICBmaQogICAgbGFzdENjb3VudD0kY2NvdW50CiAgZ G9uZQogIGxvZ2dlciAiUmVjb3Zlcnk6IFJIY292ZXJ5IENvbXBsZXRIIFRpbWVvdXQiCn0KCnNldFJjdU5vc C9yY3Vfbm9ybWFsCn0KCm1haW4oKSB7CiAgd2FpdEZvclJIYWR5CiAgZWNobyAiV2FpdGluZyBmb3I gc3RIYWR5IHN0YXRIIHRvb2s6ICQoYXdrICd7cHJpbnQgaW50KCQxLzM2MDApImgiLCBpbnQoKCQ xJTM2MDApLzYwKSJtliwgaW50KCQxJTYwKSJzIn0nIC9wcm9jL3VwdGltZSkiCiAgc2V0UmN1Tm9yb WFsCn0KCmlmlFtblClke0JBU0hfU09VUkNFWzBdfSlgPSAiJHswfSlgXV07lHRoZW4KlCBtYWlulClke0 B9lgoglGV4aXQgJD8KZmkK

```
mode: 493
   path: /usr/local/bin/set-rcu-normal.sh
systemd:
 units:
  - contents: |
    [Unit]
    Description=Disable rcu expedited after node has finished booting by setting rcu normal to 1
    [Service]
    Type=simple
    ExecStart=/usr/local/bin/set-rcu-normal.sh
    # Maximum wait time is 600s = 10m:
    Environment=MAXIMUM_WAIT_TIME=600
    # Steady-state threshold = 2%
    # Allowed values:
    # 4 - absolute pod count (+/-)
    # 4% - percent change (+/-)
    # -1 - disable the steady-state check
    # Note: '%' must be escaped as '%%' in systemd unit files
    Environment=STEADY_STATE_THRESHOLD=2%%
    # Steady-state window = 120s
    # If the running pod count stays within the given threshold for this time
    # period, return CPU utilization to normal before the maximum wait time has
    # expires
    Environment=STEADY_STATE_WINDOW=120
```

```
# Steady-state minimum = 40
# Increasing this will skip any steady-state checks until the count rises above
# this number to avoid false positives if there are some periods where the
# count doesn't increase but we know we can't be at steady-state yet.
Environment=STEADY_STATE_MINIMUM=40

[Install]
WantedBy=multi-user.target
enabled: true
name: set-rcu-normal.service
```

# 07-sriov-related-kernel-args-master.yaml

```
# Automatically generated by extra-manifests-builder
# Do not make changes directly.
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
labels:
    machineconfiguration.openshift.io/role: master
    name: 07-sriov-related-kernel-args-master
spec:
    config:
    ignition:
        version: 3.2.0
    kernelArguments:
    - intel_iommu=on
    - iommu=pt
```

# 07-sriov-related-kernel-args-worker.yaml

```
# Automatically generated by extra-manifests-builder
# Do not make changes directly.
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
labels:
machineconfiguration.openshift.io/role: worker
name: 07-sriov-related-kernel-args-worker
spec:
config:
ignition:
version: 3.2.0
kernelArguments:
- intel_iommu=on
- iommu=pt
```

# 2.2.5. Telco RAN DU reference configuration software specifications

The following information describes the telco RAN DU reference design specification (RDS) validated software versions.

## 2.2.5.1. Telco RAN DU 4.16 validated software components

The Red Hat telco RAN DU 4.16 solution has been validated using the following Red Hat software products for OpenShift Container Platform managed clusters and hub clusters.

Table 2.7. Telco RAN DU managed cluster validated software components

Component	Software version
Managed cluster version	4.16
Cluster Logging Operator	5.9
Local Storage Operator	4.16
PTP Operator	4.16
SRIOV Operator	4.16
Node Tuning Operator	4.16
Logging Operator	4.16
SRIOV-FEC Operator	2.9

Table 2.8. Hub cluster validated software components

Component	Software version
Hub cluster version	4.16
GitOps ZTP plugin	4.16
Red Hat Advanced Cluster Management (RHACM)	2.10, 2.11
Red Hat OpenShift GitOps	1.12
Topology Aware Lifecycle Manager (TALM)	4.16

# 2.3. TELCO CORE REFERENCE DESIGN SPECIFICATION

# 2.3.1. Telco RAN DU 4.16 reference design overview


The telco core reference design specification (RDS) configures a OpenShift Container Platform cluster running on commodity hardware to host telco core workloads.

# 2.3.2. Telco core 4.16 use model overview

The Telco core reference design specification (RDS) describes a platform that supports large-scale telco applications including control plane functions such as signaling and aggregation. It also includes

some centralized data plane functions, for example, user plane functions (UPF). These functions generally require scalability, complex networking support, resilient software-defined storage, and support performance requirements that are less stringent and constrained than far-edge deployments like RAN.

#### Telco core use model architecture



The networking prerequisites for telco core functions are diverse and encompass an array of networking attributes and performance benchmarks. IPv6 is mandatory, with dual-stack configurations being prevalent. Certain functions demand maximum throughput and transaction rates, necessitating user plane networking support such as DPDK. Other functions adhere to conventional cloud-native patterns and can use solutions such as OVN-K, kernel networking, and load balancing.

Telco core clusters are configured as standard three control plane clusters with worker nodes configured with the stock non real-time (RT) kernel. To support workloads with varying networking and performance requirements, worker nodes are segmented using **MachineConfigPool** CRs. For example, this is done to separate non-user data plane nodes from high-throughput nodes. To support the required telco operational features, the clusters have a standard set of Operator Lifecycle Manager (OLM) Day 2 Operators installed.

#### 2.3.2.1. Common baseline model

The following configurations and use model description are applicable to all telco core use cases.

#### Cluster

The cluster conforms to these requirements:

- High-availability (3+ supervisor nodes) control plane
- Non-schedulable supervisor nodes
- Multiple MachineConfigPool resources

### Storage

Core use cases require persistent storage as provided by external OpenShift Data Foundation. For more information, see the "Storage" subsection in "Reference core design components".

## Networking

Telco core clusters networking conforms to these requirements:

- Dual stack IPv4/IPv6
- Fully disconnected: Clusters do not have access to public networking at any point in their lifecycle.
- Multiple networks: Segmented networking provides isolation between OAM, signaling, and storage traffic.
- Cluster network type: OVN-Kubernetes is required for IPv6 support.

Core clusters have multiple layers of networking supported by underlying RHCOS, SR-IOV Operator, Load Balancer, and other components detailed in the following "Networking" section. At a high level these layers include:

- Cluster networking: The cluster network configuration is defined and applied through the installation configuration. Updates to the configuration can be done at day-2 through the NMState Operator. Initial configuration can be used to establish:
  - Host interface configuration
  - Active/Active Bonding (Link Aggregation Control Protocol (LACP))
- Secondary or additional networks: OpenShift CNI is configured through the Network additionalNetworks or NetworkAttachmentDefinition CRs.
  - MACVLAN
- Application Workload: User plane networking is running in cloud-native network functions (CNFs).

#### Service Mesh

Use of Service Mesh by telco CNFs is very common. It is expected that all core clusters will include a Service Mesh implementation. Service Mesh implementation and configuration is outside the scope of this specification.

### 2.3.2.1.1. Engineering Considerations common use model

The following engineering considerations are relevant for the common use model.

#### Worker nodes

- Worker nodes run on Intel 3rd Generation Xeon (IceLake) processors or newer. Alternatively, if using Skylake or earlier processors, the mitigations for silicon security vulnerabilities such as Spectre must be disabled; failure to do so may result in a significant 40 percent decrease in transaction performance.
- IRQ Balancing is enabled on worker nodes. The PerformanceProfile sets
  globallyDisableIrqLoadBalancing: false. Guaranteed QoS Pods are annotated to ensure
  isolation as described in "CPU partitioning and performance tuning" subsection in
  "Reference core design components" section.

#### All nodes

- Hyper-Threading is enabled on all nodes
- CPU architecture is **x86\_64** only
- Nodes are running the stock (non-RT) kernel
- Nodes are not configured for workload partitioning

The balance of node configuration between power management and maximum performance varies between **MachineConfigPools** in the cluster. This configuration is consistent for all nodes within a **MachineConfigPool**.

## **CPU** partitioning

CPU partitioning is configured using the PerformanceProfile and applied on a per **MachineConfigPool** basis. See the "CPU partitioning and performance tuning" subsection in "Reference core design components".

## 2.3.2.1.2. Application workloads

Application workloads running on core clusters might include a mix of high-performance networking CNFs and traditional best-effort or burstable pod workloads.

Guaranteed QoS scheduling is available to pods that require exclusive or dedicated use of CPUs due to performance or security requirements. Typically pods hosting high-performance and low-latency-sensitive Cloud Native Functions (CNFs) utilizing user plane networking with DPDK necessitate the exclusive utilization of entire CPUs. This is accomplished through node tuning and guaranteed Quality of Service (QoS) scheduling. For pods that require exclusive use of CPUs, be aware of the potential implications of hyperthreaded systems and configure them to request multiples of 2 CPUs when the entire core (2 hyperthreads) must be allocated to the pod.

Pods running network functions that do not require the high throughput and low latency networking are typically scheduled with best-effort or burstable QoS and do not require dedicated or isolated CPU cores.

# **Description of limits**

- CNF applications should conform to the latest version of the Red Hat Best Practices for Kubernetes guide.
- For a mix of best-effort and burstable QoS pods.
  - Guaranteed QoS pods might be used but require correct configuration of reserved and isolated CPUs in the **PerformanceProfile**.
  - Guaranteed QoS Pods must include annotations for fully isolating CPUs.
  - Best effort and burstable pods are not guaranteed exclusive use of a CPU. Workloads might be preempted by other workloads, operating system daemons, or kernel tasks.
- Exec probes should be avoided unless there is no viable alternative.
  - Do not use exec probes if a CNF is using CPU pinning.
  - Other probe implementations, for example httpGet/tcpSocket, should be used.



#### NOTE

Startup probes require minimal resources during steady-state operation. The limitation on exec probes applies primarily to liveness and readiness probes.

## Signaling workload

- Signaling workloads typically use SCTP, REST, gRPC, or similar TCP or UDP protocols.
- The transactions per second (TPS) is in the order of hundreds of thousands using secondary CNI (multus) configured as MACVLAN or SR-IOV.
- Signaling workloads run in pods with either guaranteed or burstable QoS.

# 2.3.3. Telco core reference design components

The following sections describe the various OpenShift Container Platform components and configurations that you use to configure and deploy clusters to run telco core workloads.

## 2.3.3.1. CPU partitioning and performance tuning

#### New in this release

• In this release, OpenShift Container Platform deployments use Control Groups version 2 (cgroup v2) by default. As a consequence, performance profiles in a cluster use cgroups v2 for the underlying resource management layer.

## Description

CPU partitioning allows for the separation of sensitive workloads from generic purposes, auxiliary processes, interrupts, and driver work queues to achieve improved performance and latency. The CPUs allocated to those auxiliary processes are referred to as **reserved** in the following sections. In hyperthreaded systems, a CPU is one hyperthread.

### Limits and requirements

- The operating system needs a certain amount of CPU to perform all the support tasks including kernel networking.
  - A system with just user plane networking applications (DPDK) needs at least one Core (2) hyperthreads when enabled) reserved for the operating system and the infrastructure components.
- A system with Hyper-Threading enabled must always put all core sibling threads to the same pool of CPUs.
- The set of reserved and isolated cores must include all CPU cores.
- Core O of each NUMA node must be included in the reserved CPU set.
- Isolated cores might be impacted by interrupts. The following annotations must be attached to the pod if guaranteed QoS pods require full use of the CPU:

cpu-load-balancing.crio.io: "disable"

cpu-quota.crio.io: "disable"

irq-load-balancing.crio.io: "disable"

When per-pod power management is enabled with
 PerformanceProfile.workloadHints.perPodPowerManagement the following annotations must also be attached to the pod if guaranteed QoS pods require full use of the CPU:

cpu-c-states.crio.io: "disable" cpu-freq-governor.crio.io: "performance"

# **Engineering considerations**

- The minimum reserved capacity (systemReserved) required can be found by following the guidance in "Which amount of CPU and memory are recommended to reserve for the system in OpenShift 4 nodes?"
- The actual required reserved CPU capacity depends on the cluster configuration and workload attributes.
- This reserved CPU value must be rounded up to a full core (2 hyper-thread) alignment.
- Changes to the CPU partitioning will drain and reboot the nodes in the MCP.
- The reserved CPUs reduce the pod density, as the reserved CPUs are removed from the allocatable capacity of the OpenShift node.
- The real-time workload hint should be enabled if the workload is real-time capable.
- Hardware without Interrupt Request (IRQ) affinity support will impact isolated CPUs. To
  ensure that pods with guaranteed CPU QoS have full use of allocated CPU, all hardware in
  the server must support IRQ affinity.
- OVS dynamically manages its cpuset configuration to adapt to network traffic needs. You
  do not need to reserve additional CPUs for handling high network throughput on the primary
  CNI.
- If workloads running on the cluster require cgroups v1, you can configure nodes to use cgroups v1. You can make this configuration as part of initial cluster deployment. For more information, see *Enabling Linux cgroup v1 during installation* in the *Additional resources* section.

#### Additional resources

- Tuning nodes for low latency with the performance profile
- Configuring host firmware for low latency and high performance
- Enabling Linux cgroup v1 during installation

#### 2.3.3.2. Service Mesh

#### Description

Telco core CNFs typically require a service mesh implementation. The specific features and performance required are dependent on the application. The selection of service mesh implementation and configuration is outside the scope of this documentation. The impact of service mesh on cluster resource utilization and performance, including additional latency introduced into pod networking, must be accounted for in the overall solution engineering.

#### Additional resources

About OpenShift Service Mesh

## 2.3.3.3. Networking

OpenShift Container Platform networking is an ecosystem of features, plugins, and advanced networking capabilities that extend Kubernetes networking with the advanced networking-related features that your cluster needs to manage its network traffic for one or multiple hybrid clusters.

#### Additional resources

Understanding networking

# 2.3.3.3.1. Cluster Network Operator (CNO)

#### New in this release

• No reference design updates in this release

## Description

The CNO deploys and manages the cluster network components including the default OVN–Kubernetes network plugin during OpenShift Container Platform cluster installation. It allows configuring primary interface MTU settings, OVN gateway modes to use node routing tables for pod egress, and additional secondary networks such as MACVLAN.

In support of network traffic separation, multiple network interfaces are configured through the CNO. Traffic steering to these interfaces is configured through static routes applied by using the NMState Operator. To ensure that pod traffic is properly routed, OVN-K is configured with the **routingViaHost** option enabled. This setting uses the kernel routing table and the applied static routes rather than OVN for pod egress traffic.

The Whereabouts CNI plugin is used to provide dynamic IPv4 and IPv6 addressing for additional pod network interfaces without the use of a DHCP server.

### Limits and requirements

- OVN-Kubernetes is required for IPv6 support.
- Large MTU cluster support requires connected network equipment to be set to the same or larger value.

### **Engineering considerations**

Pod egress traffic is handled by kernel routing table with the routingViaHost option.
 Appropriate static routes must be configured in the host.

## Additional resources

Cluster Network Operator

#### 2.3.3.3.2. Load Balancer

## New in this release

No reference design updates in this release

## Description

MetalLB is a load-balancer implementation for bare metal Kubernetes clusters using standard routing protocols. It enables a Kubernetes service to get an external IP address which is also added to the host network for the cluster.

Some use cases might require features not available in MetalLB, for example stateful load balancing. Where necessary, you can use an external third party load balancer. Selection and configuration of an external load balancer is outside the scope of this specification. When an external third party load balancer is used, the integration effort must include enough analysis to ensure all performance and resource utilization requirements are met.

## Limits and requirements

- Stateful load balancing is not supported by MetalLB. An alternate load balancer implementation must be used if this is a requirement for workload CNFs.
- The networking infrastructure must ensure that the external IP address is routable from clients to the host network for the cluster.

## **Engineering considerations**

- MetalLB is used in BGP mode only for core use case models.
- For core use models, MetalLB is supported with only the OVN-Kubernetes network provider used in local gateway mode. See **routingViaHost** in the "Cluster Network Operator" section.
- BGP configuration in MetalLB varies depending on the requirements of the network and peers.
- Address pools can be configured as needed, allowing variation in addresses, aggregation length, auto assignment, and other relevant parameters.
- The values of parameters in the Bi-Directional Forwarding Detection (BFD) profile should remain close to the defaults. Shorter values might lead to false negatives and impact performance.

#### Additional resources

About MetalLB and the MetalLB Operator

#### 2.3.3.3.3 SR-IOV

## New in this release

- With this release, you can use the SR-IOV Network Operator to configure QinQ (802.1ad and 802.1q) tagging. QinQ tagging provides efficient traffic management by enabling the use of both inner and outer VLAN tags. Outer VLAN tagging is hardware accelerated, leading to faster network performance. The update extends beyond the SR-IOV Network Operator itself. You can now configure QinQ on externally managed VFs by setting the outer VLAN tag using nmstate. QinQ support varies across different NICs. For a comprehensive list of known limitations for specific NIC models, see the official documentation.
- With this release, you can configure the SR-IOV Network Operator to drain nodes in parallel during network policy updates, dramatically accelerating the setup process. This translates to

significant time savings, especially for large cluster deployments that previously took hours or even days to complete.

## Description

SR-IOV enables physical network interfaces (PFs) to be divided into multiple virtual functions (VFs). VFs can then be assigned to multiple pods to achieve higher throughput performance while keeping the pods isolated. The SR-IOV Network Operator provisions and manages SR-IOV CNI, network device plugin, and other components of the SR-IOV stack.

## Limits and requirements

- The network interface controllers supported are listed in Supported devices
- SR-IOV and IOMMU enablement in BIOS: The SR-IOV Network Operator automatically enables IOMMU on the kernel command line.
- SR-IOV VFs do not receive link state updates from PF. If link down detection is needed, it must be done at the protocol level.
- **MultiNetworkPolicy** CRs can be applied to **netdevice** networks only. This is because the implementation uses the **iptables** tool, which cannot manage **vfio** interfaces.

## **Engineering considerations**

- SR-IOV interfaces in **vfio** mode are typically used to enable additional secondary networks for applications that require high throughput or low latency.
- If you exclude the **SriovOperatorConfig** CR from your deployment, the CR will not be created automatically.

## Additional resources

• About Single Root I/O Virtualization (SR-IOV) hardware networks

## 2.3.3.4. NMState Operator

#### New in this release

• No reference design updates in this release

## Description

The NMState Operator provides a Kubernetes API for performing network configurations across the cluster's nodes. It enables network interface configurations, static IPs and DNS, VLANs, trunks, bonding, static routes, MTU, and enabling promiscuous mode on the secondary interfaces. The cluster nodes periodically report on the state of each node's network interfaces to the API server.

### Limits and requirements

Not applicable

## **Engineering considerations**

• The initial networking configuration is applied using **NMStateConfig** content in the installation CRs. The NMState Operator is used only when needed for network updates.

 When SR-IOV virtual functions are used for host networking, the NMState Operator using NodeNetworkConfigurationPolicy is used to configure those VF interfaces, for example, VLANs and the MTU.

#### Additional resources

• About the Kubernetes NMState Operator

## 2.3.3.4. Logging

#### New in this release

• No reference design updates in this release

### Description

The Cluster Logging Operator enables collection and shipping of logs off the node for remote archival and analysis. The reference configuration ships audit and infrastructure logs to a remote archive by using Kafka.

## Limits and requirements

Not applicable

## **Engineering considerations**

- The impact of cluster CPU use is based on the number or size of logs generated and the amount of log filtering configured.
- The reference configuration does not include shipping of application logs. Inclusion of application logs in the configuration requires evaluation of the application logging rate and sufficient additional CPU resources allocated to the reserved set.

## Additional resources

About logging

### 2.3.3.5. Power Management

#### New in this release

No reference design updates in this release

#### Description

The Performance Profile can be used to configure a cluster in a high power, low power, or mixed mode. The choice of power mode depends on the characteristics of the workloads running on the cluster, particularly how sensitive they are to latency. Configure the maximum latency for a low-latency pod by using the per-pod power management C-states feature.

For more information, see Configuring power saving for nodes.

## Limits and requirements

 Power configuration relies on appropriate BIOS configuration, for example, enabling Cstates and P-states. Configuration varies between hardware vendors.

#### **Engineering considerations**

Latency: To ensure that latency-sensitive workloads meet their requirements, you will need
either a high-power configuration or a per-pod power management configuration. Per-pod
power management is only available for **Guaranteed** QoS Pods with dedicated pinned
CPUs.

#### Additional resources

• Configuring power saving for nodes that run colocated high and low priority workloads

## 2.3.3.6. Storage

#### Overview

Cloud native storage services can be provided by multiple solutions including OpenShift Data Foundation from Red Hat or third parties.

OpenShift Data Foundation is a Ceph based software-defined storage solution for containers. It provides block storage, file system storage, and on-premises object storage, which can be dynamically provisioned for both persistent and non-persistent data requirements. Telco core applications require persistent storage.



### **NOTE**

All storage data may not be encrypted in flight. To reduce risk, isolate the storage network from other cluster networks. The storage network must not be reachable, or routable, from other cluster networks. Only nodes directly attached to the storage network should be allowed to gain access to it.

## 2.3.3.6.1. OpenShift Data Foundation

## New in this release

• No reference design updates in this release

### Description

Red Hat OpenShift Data Foundation is a software-defined storage service for containers. For Telco core clusters, storage support is provided by OpenShift Data Foundation storage services running externally to the application workload cluster. OpenShift Data Foundation supports separation of storage traffic using secondary CNI networks.

## Limits and requirements

In an IPv4/IPv6 dual-stack networking environment, OpenShift Data Foundation uses IPv4
addressing. For more information, see Support OpenShift dual stack with OpenShift Data
Foundation using IPv4.

## **Engineering considerations**

 OpenShift Data Foundation network traffic should be isolated from other traffic on a dedicated network, for example, by using VLAN isolation.

## 2.3.3.6.2. Other Storage

Other storage solutions can be used to provide persistent storage for core clusters. The configuration and integration of these solutions is outside the scope of the telco core RDS. Integration of the storage solution into the core cluster must include correct sizing and performance analysis to ensure the storage meets overall performance and resource utilization requirements.

#### Additional resources

• Red Hat OpenShift Data Foundation

## 2.3.3.7. Monitoring

#### New in this release

• No reference design updates in this release

## Description

The Cluster Monitoring Operator (CMO) is included by default on all OpenShift clusters and provides monitoring (metrics, dashboards, and alerting) for the platform components and optionally user projects as well.

Configuration of the monitoring operator allows for customization, including:

- Default retention period
- Custom alert rules

The default handling of pod CPU and memory metrics is based on upstream Kubernetes **cAdvisor** and makes a tradeoff that prefers handling of stale data over metric accuracy. This leads to spiky data that will create false triggers of alerts over user-specified thresholds. OpenShift supports an opt-in dedicated service monitor feature creating an additional set of pod CPU and memory metrics that do not suffer from the spiky behavior. For additional information, see this solution guide.

In addition to default configuration, the following metrics are expected to be configured for telco core clusters:

Pod CPU and memory metrics and alerts for user workloads

#### Limits and requirements

 Monitoring configuration must enable the dedicated service monitor feature for accurate representation of pod metrics

### **Engineering considerations**

 The Prometheus retention period is specified by the user. The value used is a tradeoff between operational requirements for maintaining historical data on the cluster against CPU and storage resources. Longer retention periods increase the need for storage and require additional CPU to manage the indexing of data.

#### Additional resources

About 4.16 monitoring

### 2.3.3.8. Scheduling

#### New in this release

• No reference design updates in this release

## Description

The scheduler is a cluster-wide component responsible for selecting the right node for a
given workload. It is a core part of the platform and does not require any specific
configuration in the common deployment scenarios. However, there are few specific use
cases described in the following section. NUMA-aware scheduling can be enabled through
the NUMA Resources Operator. For more information, see Scheduling NUMA-aware
workloads.

## Limits and requirements

- The default scheduler does not understand the NUMA locality of workloads. It only knows
  about the sum of all free resources on a worker node. This might cause workloads to be
  rejected when scheduled to a node with Topology manager policy set to single-numa-node
  or restricted.
  - For example, consider a pod requesting 6 CPUs and being scheduled to an empty node that has 4 CPUs per NUMA node. The total allocatable capacity of the node is 8 CPUs and the scheduler will place the pod there. The node local admission will fail, however, as there are only 4 CPUs available in each of the NUMA nodes.
  - All clusters with multi-NUMA nodes are required to use the NUMA Resources Operator.
     The machineConfigPoolSelector of the NUMA Resources Operator must select all nodes where NUMA aligned scheduling is needed.
- All machine config pools must have consistent hardware configuration for example all nodes are expected to have the same NUMA zone count.

## **Engineering considerations**

- Pods might require annotations for correct scheduling and isolation. For more information on annotations, see CPU partitioning and performance tuning.
- You can configure SR-IOV virtual function NUMA affinity to be ignored during scheduling by using the **excludeTopology** field in **SriovNetworkNodePolicy** CR.

## Additional resources

- See Controlling pod placement using the scheduler
- Scheduling NUMA-aware workloads

### 2.3.3.9. Installation

### New in this release

• No reference design updates in this release

### Description

Telco core clusters can be installed using the Agent Based Installer (ABI). This method allows users to install OpenShift Container Platform on bare metal servers without requiring additional servers or

VMs for managing the installation. The ABI installer can be run on any system for example a laptop to generate an ISO installation image. This ISO is used as the installation media for the cluster supervisor nodes. Progress can be monitored using the ABI tool from any system with network connectivity to the supervisor node's API interfaces.

- Installation from declarative CRs
- Does not require additional servers to support installation
- Supports install in disconnected environment

## Limits and requirements

• Disconnected installation requires a reachable registry with all required content mirrored.

## **Engineering considerations**

• Networking configuration should be applied as NMState configuration during installation in preference to day-2 configuration by using the NMState Operator.

#### Additional resources

Installing an OpenShift Container Platform cluster with the Agent-based Installer

## 2.3.3.10. Security

#### New in this release

• No reference design updates in this release

#### Description

Telco operators are security conscious and require clusters to be hardened against multiple attack vectors. Within OpenShift Container Platform, there is no single component or feature responsible for securing a cluster. This section provides details of security-oriented features and configuration for the use models covered in this specification.

- SecurityContextConstraints: All workload pods should be run with restricted-v2 or restricted SCC.
- Seccomp: All pods should be run with the **RuntimeDefault** (or stronger) seccomp profile.
- Rootless DPDK pods: Many user-plane networking (DPDK) CNFs require pods to run with
  root privileges. With this feature, a conformant DPDK pod can be run without requiring root
  privileges. Rootless DPDK pods create a tap device in a rootless pod that injects traffic from
  a DPDK application to the kernel.
- **Storage**: The storage network should be isolated and non-routable to other cluster networks. See the "Storage" section for additional details.

## Limits and requirements

- Rootless DPDK pods requires the following additional configuration steps:
  - Configure the TAP plugin with the **container t** SELinux context.

• Enable the **container\_use\_devices** SELinux boolean on the hosts.

## **Engineering considerations**

• For rootless DPDK pod support, the SELinux boolean **container\_use\_devices** must be enabled on the host for the TAP device to be created. This introduces a security risk that is acceptable for short to mid-term use. Other solutions will be explored.

#### Additional resources

Managing security context constraints

## 2.3.3.11. Scalability

#### New in this release

• No reference design updates in this release

## Description

Clusters will scale to the sizing listed in the limits and requirements section. Scaling of workloads is described in the use model section.

## Limits and requirements

Cluster scales to at least 120 nodes

## **Engineering considerations**

Not applicable

### 2.3.3.12. Additional configuration

## 2.3.3.12.1. Disconnected environment

## Description

Telco core clusters are expected to be installed in networks without direct access to the internet. All container images needed to install, configure, and operator the cluster must be available in a disconnected registry. This includes OpenShift Container Platform images, day-2 Operator Lifecycle Manager (OLM) Operator images, and application workload images. The use of a disconnected environment provides multiple benefits, for example:

- Limiting access to the cluster for security
- Curated content: The registry is populated based on curated and approved updates for the clusters

### Limits and requirements

- A unique name is required for all custom CatalogSources. Do not reuse the default catalog names.
- A valid time source must be configured as part of cluster installation.

## **Engineering considerations**

Not applicable

#### Additional resources

• About cluster updates in a disconnected environment

#### 2.3.3.12.2. Kernel

## New in this release

• No reference design updates in this release

## Description

The user can install the following kernel modules by using **MachineConfig** to provide extended kernel functionality to CNFs:

- sctp
- ip\_gre
- ip6\_tables
- ip6t\_REJECT
- ip6table\_filter
- ip6table\_mangle
- iptable\_filter
- iptable\_mangle
- iptable\_nat
- xt\_multiport
- xt\_owner
- xt\_REDIRECT
- xt\_statistic
- xt\_TCPMSS

## Limits and requirements

• Use of functionality available through these kernel modules must be analyzed by the user to determine the impact on CPU load, system performance, and ability to sustain KPI.



### **NOTE**

Out of tree drivers are not supported.

## **Engineering considerations**

Not applicable

# 2.3.4. Telco core 4.16 reference configuration CRs

Use the following custom resources (CRs) to configure and deploy OpenShift Container Platform clusters with the telco core profile. Use the CRs to form the common baseline used in all the specific use models unless otherwise indicated.

# 2.3.4.1. Extracting the telco core reference design configuration CRs

You can extract the complete set of custom resources (CRs) for the telco core profile from the **telco-core-rds-rhel9** container image. The container image has both the required CRs, and the optional CRs, for the telco core profile.

## **Prerequisites**

• You have installed **podman**.

#### **Procedure**

 Extract the content from the telco-core-rds-rhel9 container image by running the following commands:


```
$ mkdir -p ./out
```


\$ podman run -it registry.redhat.io/openshift4/telco-core-rds-rhel9:v4.16 | base64 -d | tar xv - C out

#### Verification

• The **out** directory has the following folder structure. You can view the telco core CRs in the **out/telco-core-rds**/ directory.

## **Example output**





# 2.3.4.2. Resource Tuning reference CRs

Table 2.9. Resource Tuning CRs

Component	Reference CR	Optional	New in this release
System reserved capacity	control-plane-system- reserved.yaml	Yes	No
System reserved capacity	pid-limits-cr.yaml	Yes	No

# 2.3.4.3. Storage reference CRs

Table 2.10. Storage CRs

Component	Reference CR	Optional	New in this release
External ODF configuration	O1-rook-ceph-external- cluster- details.secret.yaml	No	No
External ODF configuration	02-ocs-external- storagecluster.yaml	No	No
External ODF configuration	odfNS.yaml	No	No
External ODF configuration	odfOperGroup.yaml	No	No
External ODF configuration	odfSubscription.yaml	No	No

# 2.3.4.4. Networking reference CRs

Table 2.11. Networking CRs

Component	Reference CR	Optional	New in this release
Baseline	Network.yaml	No	No
Baseline	networkAttachmentDefi nition.yaml	Yes	Yes

Component	Reference CR	Optional	New in this release
Load balancer	addr-pool.yaml	No	No
Load balancer	bfd-profile.yaml	No	No
Load balancer	bgp-advr.yaml	No	No
Load balancer	bgp-peer.yaml	No	No
Load balancer	community.yaml	No	Yes
Load balancer	metallb.yaml	No	No
Load balancer	metallbNS.yaml	Yes	No
Load balancer	metallbOperGroup.yaml	Yes	No
Load balancer	metallbSubscription.yam	No	No
Multus - Tap CNI for rootless DPDK pod	mc_rootless_pods_selinu x.yaml	No	No
NMState Operator	NMState.yaml	No	Yes
NMState Operator	NMStateNS.yaml	No	Yes
NMState Operator	NMStateOperGroup.ya ml	No	Yes
NMState Operator	NMStateSubscription.ya ml	No	Yes
SR-IOV Network Operator	sriovNetwork.yaml	Yes	No
SR-IOV Network Operator	sriovNetworkNodePolicy .yaml	No	No
SR-IOV Network Operator	SriovOperatorConfig.ya ml	No	No
SR-IOV Network Operator	SriovSubscription.yaml	No	No

Component	Reference CR	Optional	New in this release
SR-IOV Network Operator	SriovSubscriptionNS.ya ml	No	No
SR-IOV Network Operator	SriovSubscriptionOperG roup.yaml	No	No

# 2.3.4.5. Scheduling reference CRs

Table 2.12. Scheduling CRs

Component	Reference CR	Optional	New in this release
NUMA-aware scheduler	nrop.yaml	No	No
NUMA-aware scheduler	NROPSubscription.yaml	No	No
NUMA-aware scheduler	NROPSubscriptionNS.ya ml	No	No
NUMA-aware scheduler	NROPSubscriptionOper Group.yaml	No	No
NUMA-aware scheduler	sched.yaml	No	No
NUMA-aware scheduler	Scheduler.yaml	No	Yes

# 2.3.4.6. Other reference CRs

Table 2.13. Other CRs

Component	Reference CR	Optional	New in this release
Additional kernel modules	control-plane-load- kernel-modules.yaml	Yes	No
Additional kernel modules	sctp_module_mc.yaml	Yes	No
Additional kernel modules	worker-load-kernel- modules.yaml	Yes	No
Cluster logging	ClusterLogForwarder.ya ml	No	No
Cluster logging	ClusterLogging.yaml	No	No

Component	Reference CR	Optional	New in this release
Cluster logging	ClusterLogNS.yaml	No	No
Cluster logging	ClusterLogOperGroup.y	No	No
Cluster logging	ClusterLogSubscription. yaml	No	No
Disconnected configuration	catalog-source.yaml	No	No
Disconnected configuration	icsp.yaml	No	No
Disconnected configuration	operator-hub.yaml	No	No
Monitoring and observability	monitoring-config- cm.yaml	Yes	No
Power management	PerformanceProfile.yam	No	No

# 2.3.4.7. YAML reference

# 2.3.4.7.1. Resource Tuning reference YAML

# control-plane-system-reserved.yaml

```
# optional
# count: 1
```

apiVersion: machineconfiguration.openshift.io/v1

kind: KubeletConfig

metadata:

name: autosizing-master

spec:

autoSizingReserved: true machineConfigPoolSelector:

matchLabels:

pools.operator.machineconfiguration.openshift.io/master: ""

# pid-limits-cr.yaml

# optional # count: 1

apiVersion: machineconfiguration.openshift.io/v1

kind: ContainerRuntimeConfig

```
metadata:
name: 99-change-pidslimit-custom
spec:
machineConfigPoolSelector:
matchLabels:
# Set to appropriate MCP
pools.operator.machineconfiguration.openshift.io/master: ""
containerRuntimeConfig:
pidsLimit: $pidsLimit
# Example:
#pidsLimit: 4096
```

## 2.3.4.7.2. Storage reference YAML

## 01-rook-ceph-external-cluster-details.secret.yaml

```
# required
# count: 1
---
apiVersion: v1
kind: Secret
metadata:
name: rook-ceph-external-cluster-details
namespace: openshift-storage
type: Opaque
data:
# encoded content has been made generic
external_cluster_details:
eyJuYW1IIjoicm9vay1jZXBoLW1vbi1lbmRwb
```

eyJuYW1lljoicm9vay1jZXBoLW1vbi1lbmRwb2ludHMiLCJraW5kljoiQ29uZmlnTWFwliwiZGF0YSl6eyJkY XRhljoiY2VwaHVzYTE9MS4yLjMuNDo2Nzg5liwibWF4TW9uSWQiOilwliwibWFwcGluZyl6Int9In19LHsi bmFtZSI6InJvb2stY2VwaC1tb24iLCJraW5kljoiU2VjcmV0IiwiZGF0YSI6eyJhZG1pbi1zZWNyZXQiOiJhZ G1pbi1zZWNyZXQiLCJmc2lkljoiMTExMTExMTEtMTExMS0xMTExLTExMTEtMTExMTExMTExMTExMTExII wibW9uLXNIY3JldCl6lm1vbi1zZWNyZXQifX0seyJuYW1lljoicm9vay1jZXBoLW9wZXJhdG9yLWNyZWR liwia2luZCl6llNlY3JldClsImRhdGEiOnsidXNlcklEljoiY2xpZW50LmhlYWx0aGNoZWNrZXliLCJ1c2VyS2\ 5IjoiYzJWamNtVjAifX0seyJuYW1IIjoibW9uaXRvcmluZy1lbmRwb2ludClsImtpbmQiOiJDZXBoQ2x1c3Rk IsImRhdGEiOnsiTW9uaXRvcmluZ0VuZHBvaW50IjoiMS4yLjMuNCwxLjluMy4zLDEuMi4zLjIiLCJNb25pd G9yaW5nUG9ydCl6IjkyODMifX0seyJuYW1IIjoiY2VwaC1yYmQiLCJraW5kIjoiU3RvcmFnZUNsYXNzliwi ZGF0YSI6eyJwb29sIjoib2RmX3Bvb2wifX0seyJuYW1IIjoicm9vay1jc2ktcmJkLW5vZGUiLCJraW5kIjoiU2 jcmV0liwiZGF0YSl6eyJ1c2VySUQiOiJjc2ktcmJkLW5vZGUiLCJ1c2VyS2V5ljoiIn19LHsibmFtZSl6InJvb2 stY3NpLXJiZC1wcm92aXNpb25lcilsImtpbmQiOiJTZWNyZXQiLCJkYXRhIjp7InVzZXJJRCI6ImNzaS1yY mQtcHJvdmlzaW9uZXliLCJ1c2VyS2V5ljoiYzJWamNtVjAifX0seyJuYW1lljoicm9vay1jc2ktY2VwaGZzLXl yb3Zpc2lvbmVyliwia2luZCI6llNlY3JldClsImRhdGEiOnsiYWRtaW5JRCI6lmNzaS1jZXBoZnMtcHJvdmlze W9uZXIiLCJhZG1pbktleSI6IiJ9fSx7Im5hbWUiOiJyb29rLWNzaS1jZXBoZnMtbm9kZSIsImtpbmQiOiJTZ WNyZXQiLCJkYXRhIjp7lmFkbWluSUQiOiJjc2ktY2VwaGZzLW5vZGUiLCJhZG1pbktleSI6lmMyVmpjbV YwIn19LHsibmFtZSI6ImNlcGhmcyIsImtpbmQiOiJTdG9yYWdlQ2xhc3MiLCJkYXRhIjp7ImZzTmFtZSI6I mNlcGhmcylsInBvb2wiOiJtYW5pbGFfZGF0YSJ9fQ==

### 02-ocs-external-storagecluster.yaml

```
# required
# count: 1
---
apiVersion: ocs.openshift.io/v1
kind: StorageCluster
```

```
metadata:
    name: ocs-external-storagecluster
    namespace: openshift-storage
    spec:
    externalStorage:
    enable: true
    labelSelector: {}
    status:
    phase: Ready
```

# odfNS.yaml

```
# required: yes
# count: 1
---
apiVersion: v1
kind: Namespace
metadata:
name: openshift-storage
annotations:
workload.openshift.io/allowed: management
labels:
openshift.io/cluster-monitoring: "true"
```

## odfOperGroup.yaml

```
# required: yes
# count: 1
---
apiVersion: operators.coreos.com/v1
kind: OperatorGroup
metadata:
name: openshift-storage-operatorgroup
namespace: openshift-storage
spec:
targetNamespaces:
- openshift-storage
```

# odfSubscription.yaml

```
# required: yes
# count: 1
---
apiVersion: operators.coreos.com/v1alpha1
kind: Subscription
metadata:
name: odf-operator
namespace: openshift-storage
spec:
channel: "stable-4.14"
name: odf-operator
source: redhat-operators-disconnected
sourceNamespace: openshift-marketplace
```

installPlanApproval: Automatic status: state: AtLatestKnown

### 2.3.4.7.3. Networking reference YAML

## Network.yaml

```
# required
# count: 1
apiVersion: operator.openshift.io/v1
kind: Network
metadata:
 name: cluster
spec:
 defaultNetwork:
  ovnKubernetesConfig:
   gatewayConfig:
     routingViaHost: true
 # additional networks are optional and may alternatively be specified using
NetworkAttachmentDefinition CRs
 additionalNetworks: [$additionalNetworks]
 # ea
 #- name: add-net-1
 # namespace: app-ns-1
 # rawCNIConfig: '{ "cniVersion": "0.3.1", "name": "add-net-1", "plugins": [{"type": "macvlan",
"master": "bond1", "ipam": {}}] }'
 # type: Raw
 #- name: add-net-2
 # namespace: app-ns-1
 # rawCNIConfig: '{ "cniVersion": "0.4.0", "name": "add-net-2", "plugins": [ {"type": "macvlan",
"master": "bond1", "mode": "private" },{ "type": "tuning", "name": "tuning-arp" }] }'
 # type: Raw
 # Enable to use MultiNetworkPolicy CRs
 useMultiNetworkPolicy: true
```

## networkAttachmentDefinition.yaml

```
# optional
# copies: 0-N
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
  name: $name
  namespace: $ns
spec:
  nodeSelector:
    kubernetes.io/hostname: $nodeName
  config: $config
  #eg
  #config: '{
    # "cniVersion": "0.3.1",
    # "name": "external-169",
```

```
# "type": "vlan",
# "master": "ens8f0",
# "mode": "bridge",
# "vlanid": 169,
# "ipam": {
# "type": "static",
# }
#}'
```

## addr-pool.yaml

```
# required
# count: 1-N
apiVersion: metallb.io/v1beta1
kind: IPAddressPool
metadata:
 name: $name # eg addresspool3
 namespace: metallb-system
 annotations:
  metallb.universe.tf/address-pool: $name # eg addresspool3
spec:
 ##############
 # Expected variation in this configuration
 addresses: [$pools]
 #- 3.3.3.0/24
 autoAssign: true
 ##############
```

# bfd-profile.yaml

```
# required
# count: 1-N
apiVersion: metallb.io/v1beta1
kind: BFDProfile
metadata:
 name: bfdprofile
 namespace: metallb-system
spec:
 ################
 # These values may vary. Recommended values are included as default
 receiveInterval: 150 # default 300ms
 transmitInterval: 150 # default 300ms
 #echoInterval: 300 # default 50ms
 detectMultiplier: 10 # default 3
 echoMode: true
 passiveMode: true
 minimumTtl: 5 # default 254
 #################
```

## bgp-advr.yaml

```
# required
# count: 1-N
```

```
apiVersion: metallb.io/v1beta1
kind: BGPAdvertisement
metadata:
 name: $name # eg bgpadvertisement-1
 namespace: metallb-system
spec:
 ipAddressPools: [$pool]
 # eg:
 # - addresspool3
 peers: [$peers]
 # eg:
    - peer-one
 communities: [$communities]
 # Note correlation with address pool, or Community
 # eg:
    - bgpcommunity
 # - 65535:65282
 aggregationLength: 32
 aggregationLengthV6: 128
 localPref: 100
```

# bgp-peer.yaml

```
# required
# count: 1-N
apiVersion: metallb.io/v1beta2
kind: BGPPeer
metadata:
name: $name
namespace: metallb-system
spec:
peerAddress: $ip # eg 192.168.1.2
peerASN: $peerasn # eg 64501
myASN: $myasn # eg 64500
routerID: $id # eg 10.10.10.10
bfdProfile: bfdprofile
passwordSecret: {}
```

# community.yaml

```
apiVersion: metallb.io/v1beta1 kind: Community metadata: name: bgpcommunity namespace: metallb-system spec: communities: [$comm]
```

## metallb.yaml

```
# required
# count: 1
apiVersion: metallb.io/v1beta1
kind: MetalLB
metadata:
name: metallb
namespace: metallb-system
spec:
nodeSelector:
node-role.kubernetes.io/worker: ""
```

## metallbNS.yaml

```
# required: yes
# count: 1
---
apiVersion: v1
kind: Namespace
metadata:
name: metallb-system
annotations:
workload.openshift.io/allowed: management
labels:
openshift.io/cluster-monitoring: "true"
```

## metallbOperGroup.yaml

```
# required: yes
# count: 1
---
apiVersion: operators.coreos.com/v1
kind: OperatorGroup
metadata:
name: metallb-operator
namespace: metallb-system
```

## metallbSubscription.yaml

```
# required: yes
# count: 1
---
apiVersion: operators.coreos.com/v1alpha1
kind: Subscription
metadata:
name: metallb-operator-sub
namespace: metallb-system
spec:
channel: stable
name: metallb-operator
source: redhat-operators-disconnected
sourceNamespace: openshift-marketplace
installPlanApproval: Automatic
status:
state: AtLatestKnown
```

## mc\_rootless\_pods\_selinux.yaml

```
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
 labels:
  machineconfiguration.openshift.io/role: worker
 name: 99-worker-setsebool
spec:
 config:
  ignition:
   version: 3.2.0
  systemd:
   units:
     - contents: |
       [Unit]
       Description=Set SELinux boolean for tap cni plugin
       Before=kubelet.service
       [Service]
       Type=oneshot
       ExecStart=/sbin/setsebool container_use_devices=on
       RemainAfterExit=true
       [Install]
       WantedBy=multi-user.target graphical.target
      enabled: true
      name: setsebool.service
```

#### NMState.yaml

apiVersion: nmstate.io/v1 kind: NMState metadata: name: nmstate spec: {}

## NMStateNS.yaml

apiVersion: v1
kind: Namespace
metadata:
name: openshift-nmstate
annotations:

workload.openshift.io/allowed: management

### NMStateOperGroup.yaml

apiVersion: operators.coreos.com/v1 kind: OperatorGroup metadata: name: openshift-nmstate namespace: openshift-nmstate

#### spec:

targetNamespaces:

- openshift-nmstate

### NMStateSubscription.yaml

apiVersion: operators.coreos.com/v1alpha1

kind: Subscription

metadata:

name: kubernetes-nmstate-operator namespace: openshift-nmstate

spec:

channel: "stable"

name: kubernetes-nmstate-operator source: redhat-operators-disconnected sourceNamespace: openshift-marketplace

installPlanApproval: Automatic

status:

state: AtLatestKnown

#### sriovNetwork.yaml

```
# optional (though expected for all)
```

# count: 0-N

apiVersion: sriovnetwork.openshift.io/v1

kind: SriovNetwork

metadata:

name: \$name # eg sriov-network-abcd namespace: openshift-sriov-network-operator

spec:

capabilities: "\$capabilities" # eg '{"mac": true, "ips": true}'

ipam: "\$ipam" # eg '{ "type": "host-local", "subnet": "10.3.38.0/24" }'

networkNamespace: \$nns # eg cni-test resourceName: \$resource # eg resourceTest

#### sriovNetworkNodePolicy.yaml

```
# optional (though expected in all deployments)
```

# count: 0-N

apiVersion: sriovnetwork.openshift.io/v1

kind: SriovNetworkNodePolicy

metadata:

name: \$name

namespace: openshift-sriov-network-operator

spec: {} # \$spec

# eg

#deviceType: netdevice

#nicSelector:

# deviceID: "1593"

# pfNames:

# - ens8f0np0#0-9

# rootDevices:

# - 0000:d8:00.0

# vendor: "8086"

#nodeSelector:

# kubernetes.io/hostname: host.sample.lab

#numVfs: 20 #priority: 99

#excludeTopology: true

#resourceName: resourceNameABCD

### SriovOperatorConfig.yaml

# required # count: 1

---

apiVersion: sriovnetwork.openshift.io/v1

kind: SriovOperatorConfig

metadata: name: default

namespace: openshift-sriov-network-operator

spec:

configDaemonNodeSelector:

node-role.kubernetes.io/worker: ""

enableInjector: true

enableOperatorWebhook: true

disableDrain: false

logLevel: 2

### SriovSubscription.yaml

# required: yes

# count: 1

apiVersion: operators.coreos.com/v1alpha1

kind: Subscription

metadata:

name: sriov-network-operator-subscription namespace: openshift-sriov-network-operator

spec:

channel: "stable"

name: sriov-network-operator

source: redhat-operators-disconnected sourceNamespace: openshift-marketplace

installPlanApproval: Automatic

status:

state: AtLatestKnown

# SriovSubscriptionNS.yaml

# required: yes
# count: 1

apiVersion: v1 kind: Namespace

metadata:

name: openshift-sriov-network-operator

annotations:

workload.openshift.io/allowed: management

## SriovSubscriptionOperGroup.yaml

# required: yes
# count: 1
apiVersion: operators.coreos.com/v1
kind: OperatorGroup
metadata:
name: sriov-network-operators
namespace: openshift-sriov-network-operator
spec:
targetNamespaces:
- openshift-sriov-network-operator

#### 2.3.4.7.4. Scheduling reference YAML

## nrop.yaml

```
# Optional
# count: 1
apiVersion: nodetopology.openshift.io/v1
kind: NUMAResourcesOperator
metadata:
    name: numaresourcesoperator
spec:
    nodeGroups:
    - config:
        # Periodic is the default setting
        infoRefreshMode: Periodic
        machineConfigPoolSelector:
        matchLabels:
        # This label must match the pool(s) you want to run NUMA-aligned workloads
        pools.operator.machineconfiguration.openshift.io/worker: ""
```

### NROPSubscription.yaml

```
# required
# count: 1
apiVersion: operators.coreos.com/v1alpha1
kind: Subscription
metadata:
name: numaresources-operator
namespace: openshift-numaresources
spec:
channel: "4.14"
name: numaresources-operator
source: redhat-operators-disconnected
sourceNamespace: openshift-marketplace
```

#### NROPSubscriptionNS.yaml

# required: yes
# count: 1
apiVersion: v1

kind: Namespace metadata:

name: openshift-numaresources

annotations:

workload.openshift.io/allowed: management

## NROPSubscriptionOperGroup.yaml

# required: yes # count: 1

apiVersion: operators.coreos.com/v1

kind: OperatorGroup

metadata:

name: numaresources-operator namespace: openshift-numaresources

spec:

targetNamespaces:

- openshift-numaresources

#### sched.yaml

# Optional
# count: 1
apiVersion: nodetopology.openshift.io/v1
kind: NUMAResourcesScheduler
metadata:
name: numaresourcesscheduler
spec:
#cacheResyncPeriod: "0"
# Image spec should be the latest for the release
imageSpec: "registry.redhat.io/openshift4/noderesourcetopology-scheduler-rhel9:v4.14.0"
#logLevel: "Trace"
schedulerName: topo-aware-scheduler

# Scheduler.yaml

apiVersion: config.openshift.io/v1
kind: Scheduler
metadata:
name: cluster
spec:
# non-schedulable control plane is the default. This ensures
# compliance.
mastersSchedulable: false
policy:
name: ""

#### 2.3.4.7.5. Other reference YAML

#### control-plane-load-kernel-modules.yaml

# optional # count: 1

```
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
labels:
  machineconfiguration.openshift.io/role: master
 name: 40-load-kernel-modules-control-plane
spec:
config:
  # Release info found in https://github.com/coreos/butane/releases
   version: 3.2.0
  storage:
   files:
    - contents:
      source: data:,
     mode: 420
     overwrite: true
     path: /etc/modprobe.d/kernel-blacklist.conf
    - contents:
      source: data:text/plain;charset=utf-
8;base64,aXBfZ3JlCmlwNl90YWJsZXMKaXA2dF9SRUpFQ1QKaXA2dGFibGVfZmlsdGVyCmlwNnRh
YmxlX21hbmdsZQppcHRhYmxlX2ZpbHRlcgppcHRhYmxlX21hbmdsZQppcHRhYmxlX25hdAp4dF9tdW
mode: 420
     overwrite: true
     path: /etc/modules-load.d/kernel-load.conf
```

#### sctp\_module\_mc.yaml

```
# optional
# count: 1
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
 labels:
  machineconfiguration.openshift.io/role: worker
 name: load-sctp-module
spec:
 config:
  ignition:
   version: 2.2.0
  storage:
   files:
     - contents:
       source: data:,
       verification: {}
      filesystem: root
      mode: 420
      path: /etc/modprobe.d/sctp-blacklist.conf
       source: data:text/plain;charset=utf-8;base64,c2N0cA==
      filesystem: root
      mode: 420
      path: /etc/modules-load.d/sctp-load.conf
```

## worker-load-kernel-modules.yaml

```
# optional
# count: 1
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
 labels:
  machineconfiguration.openshift.io/role: worker
 name: 40-load-kernel-modules-worker
spec:
 config:
  # Release info found in https://github.com/coreos/butane/releases
  ignition:
   version: 3.2.0
  storage:
   files:
    - contents:
      source: data:.
     mode: 420
     overwrite: true
     path: /etc/modprobe.d/kernel-blacklist.conf
    - contents:
      source: data:text/plain;charset=utf-
8;base64,aXBfZ3JlCmlwNl90YWJsZXMKaXA2dF9SRUpFQ1QKaXA2dGFibGVfZmlsdGVyCmlwNnRh
YmxlX21hbmdsZQppcHRhYmxlX2ZpbHRlcgppcHRhYmxlX21hbmdsZQppcHRhYmxlX25hdAp4dF9tdW
x0aXBvcnQKeHRfb3duZXIKeHRfUkVESVJFQ1QKeHRfc3RhdGlzdGljCnh0X1RDUE1TUwo=
     mode: 420
     overwrite: true
     path: /etc/modules-load.d/kernel-load.conf
```

#### ClusterLogForwarder.yaml

```
# required
# count: 1
apiVersion: logging.openshift.io/v1
kind: ClusterLogForwarder
metadata:
 name: instance
 namespace: openshift-logging
spec:
 outputs:
  type: "kafka"
   name: kafka-open
   url: tcp://10.11.12.13:9092/test
 pipelines:
  - inputRefs:
     - infrastructure
     #- application
     - audit
   labels:
     label1: test1
     label2: test2
     label3: test3
     label4: test4
```

label5: test5 name: all-to-default outputRefs: - kafka-open

#### ClusterLogging.yaml

# required # count: 1

apiVersion: logging.openshift.io/v1

kind: ClusterLogging

metadata: name: instance

namespace: openshift-logging

spec: collection: type: vector

managementState: Managed

# ClusterLogNS.yaml

---

apiVersion: v1 kind: Namespace metadata:

name: openshift-logging

annotations:

workload.openshift.io/allowed: management

## ClusterLogOperGroup.yaml

---

apiVersion: operators.coreos.com/v1

kind: OperatorGroup

metadata:

name: cluster-logging

namespace: openshift-logging

spec:

targetNamespaces:
- openshift-logging

#### ClusterLogSubscription.yaml

apiVersion: operators.coreos.com/v1alpha1

kind: Subscription

metadata:

name: cluster-logging

namespace: openshift-logging

spec:

channel: "stable" name: cluster-logging

source: redhat-operators-disconnected sourceNamespace: openshift-marketplace

installPlanApproval: Automatic

status:

state: AtLatestKnown

## catalog-source.yaml

```
# required
# count: 1..N
apiVersion: operators.coreos.com/v1alpha1
kind: CatalogSource
metadata:
 name: redhat-operators-disconnected
 namespace: openshift-marketplace
spec:
 displayName: Red Hat Disconnected Operators Catalog
 image: $imageUrl
 publisher: Red Hat
 sourceType: grpc
# updateStrategy:
# registryPoll:
#
    interval: 1h
status:
```

# icsp.yaml

connectionState:

lastObservedState: READY

```
# required
# count: 1
apiVersion: operator.openshift.io/v1alpha1
kind: ImageContentSourcePolicy
metadata:
   name: disconnected-internal-icsp
spec:
   repositoryDigestMirrors: []
# - $mirrors
```

# operator-hub.yaml

```
# required
# count: 1
apiVersion: config.openshift.io/v1
kind: OperatorHub
metadata:
name: cluster
spec:
disableAllDefaultSources: true
```

## monitoring-config-cm.yaml

```
# optional
# count: 1
---
apiVersion: v1
```

```
kind: ConfigMap
metadata:
 name: cluster-monitoring-config
 namespace: openshift-monitoring
data:
 config.yaml: |
  prometheusK8s:
   retention: 15d
   volumeClaimTemplate:
    spec:
      storageClassName: ocs-external-storagecluster-ceph-rbd
      resources:
       requests:
        storage: 100Gi
  alertmanagerMain:
   volumeClaimTemplate:
    spec:
      storageClassName: ocs-external-storagecluster-ceph-rbd
      resources:
       requests:
        storage: 20Gi
```

### PerformanceProfile.yaml

```
# required
# count: 1
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
 name: $name
 annotations:
  # Some pods want the kernel stack to ignore IPv6 router Advertisement.
  kubeletconfig.experimental: |
   {"allowedUnsafeSysctls":["net.ipv6.conf.all.accept ra"]}
spec:
 cpu:
  # node0 CPUs: 0-17,36-53
  # node1 CPUs: 18-34,54-71
  # siblings: (0,36), (1,37)...
  # we want to reserve the first Core of each NUMA socket
  # no CPU left behind! all-cpus == isolated + reserved
  isolated: $isolated # eq 1-17.19-35.37-53.55-71
  reserved: $reserved # eg 0,18,36,54
 # Guaranteed QoS pods will disable IRQ balancing for cores allocated to the pod.
 # default value of globallyDisableIrqLoadBalancing is false
 globallyDisableIrgLoadBalancing: false
 hugepages:
  defaultHugepagesSize: 1G
  pages:
   # 32GB per numa node
   - count: $count # eg 64
     size: 1G
 machineConfigPoolSelector:
  # For SNO: machineconfiguration.openshift.io/role: 'master'
  pools.operator.machineconfiguration.openshift.io/worker: "
```

nodeSelector:
#For SNO: node-role.kubernetes.io/master: ""
node-role.kubernetes.io/worker: ""
workloadHints:
realTime: false
highPowerConsumption: false
perPodPowerManagement: true
realTimeKernel:
enabled: false
numa:
# All guaranteed QoS containers get resources from a single NUMA node
topologyPolicy: "single-numa-node"
net:
userLevelNetworking: false

# 2.3.5. Telco core reference configuration software specifications

The following information describes the telco core reference design specification (RDS) validated software versions.

#### 2.3.5.1. Software stack

The following software versions were used for validating the telco core reference design specification:

Table 2.14. Software versions for validation

Component	Software version
Cluster Logging Operator	5.9.1
OpenShift Data Foundation	4.16
SR-IOV Operator	4.16
MetalLB	4.16
NMState Operator	4.16
NUMA-aware scheduler	4.16

# CHAPTER 3. PLANNING YOUR ENVIRONMENT ACCORDING TO OBJECT MAXIMUMS

Consider the following tested object maximums when you plan your OpenShift Container Platform cluster.

These guidelines are based on the largest possible cluster. For smaller clusters, the maximums are lower. There are many factors that influence the stated thresholds, including the etcd version or storage data format.

In most cases, exceeding these numbers results in lower overall performance. It does not necessarily mean that the cluster will fail.



#### **WARNING**

Clusters that experience rapid change, such as those with many starting and stopping pods, can have a lower practical maximum size than documented.

# 3.1. OPENSHIFT CONTAINER PLATFORM TESTED CLUSTER MAXIMUMS FOR MAJOR RELEASES



#### **NOTE**

Red Hat does not provide direct guidance on sizing your OpenShift Container Platform cluster. This is because determining whether your cluster is within the supported bounds of OpenShift Container Platform requires careful consideration of all the multidimensional factors that limit the cluster scale.

OpenShift Container Platform supports tested cluster maximums rather than absolute cluster maximums. Not every combination of OpenShift Container Platform version, control plane workload, and network plugin are tested, so the following table does not represent an absolute expectation of scale for all deployments. It might not be possible to scale to a maximum on all dimensions simultaneously. The table contains tested maximums for specific workload and deployment configurations, and serves as a scale guide as to what can be expected with similar deployments.

Maximum type	4.x tested maximum
Number of nodes	2,000 [1]
Number of pods <sup>[2]</sup>	150,000
Number of pods per node	2,500 <sup>[3][4]</sup>
Number of pods per core	There is no default value.

Maximum type	4.x tested maximum
Number of namespaces <sup>[5]</sup>	10,000
Number of builds	10,000 (Default pod RAM 512 Mi) - Source-to- Image (S2I) build strategy
Number of pods per namespace <sup>[6]</sup>	25,000
Number of routes and back ends per Ingress Controller	2,000 per router
Number of secrets	80,000
Number of config maps	90,000
Number of services <sup>[7]</sup>	10,000
Number of services per namespace	5,000
Number of back-ends per service	5,000
Number of deployments per namespace <sup>[6]</sup>	2,000
Number of build configs	12,000
Number of custom resource definitions (CRD)	1,024 [8]

- 1. Pause pods were deployed to stress the control plane components of OpenShift Container Platform at 2000 node scale. The ability to scale to similar numbers will vary depending upon specific deployment and workload parameters.
- 2. The pod count displayed here is the number of test pods. The actual number of pods depends on the application's memory, CPU, and storage requirements.
- 3. This was tested on a cluster with 31 servers: 3 control planes, 2 infrastructure nodes, and 26 worker nodes. If you need 2,500 user pods, you need both a **hostPrefix** of **20**, which allocates a network large enough for each node to contain more than 2000 pods, and a custom kubelet config with **maxPods** set to **2500**. For more information, see Running 2500 pods per node on OCP 4.13.
- 4. The maximum tested pods per node is 2,500 for clusters using the **OVNKubernetes** network plugin. The maximum tested pods per node for the **OpenShiftSDN** network plugin is 500 pods.
- 5. When there are a large number of active projects, etcd might suffer from poor performance if the keyspace grows excessively large and exceeds the space quota. Periodic maintenance of etcd, including defragmentation, is highly recommended to free etcd storage.

- 6. There are several control loops in the system that must iterate over all objects in a given namespace as a reaction to some changes in state. Having a large number of objects of a given type in a single namespace can make those loops expensive and slow down processing given state changes. The limit assumes that the system has enough CPU, memory, and disk to satisfy the application requirements.
- 7. Each service port and each service back-end has a corresponding entry in **iptables**. The number of back-ends of a given service impact the size of the **Endpoints** objects, which impacts the size of data that is being sent all over the system.
- 8. Tested on a cluster with 29 servers: 3 control planes, 2 infrastructure nodes, and 24 worker nodes. The cluster had 500 namespaces. OpenShift Container Platform has a limit of 1,024 total custom resource definitions (CRD), including those installed by OpenShift Container Platform, products integrating with OpenShift Container Platform and user-created CRDs. If there are more than 1,024 CRDs created, then there is a possibility that **oc** command requests might be throttled.

# 3.1.1. Example scenario

As an example, 500 worker nodes (m5.2xl) were tested, and are supported, using OpenShift Container Platform 4.16, the OVN-Kubernetes network plugin, and the following workload objects:

- 200 namespaces, in addition to the defaults
- 60 pods per node; 30 server and 30 client pods (30k total)
- 57 image streams/ns (11.4k total)
- 15 services/ns backed by the server pods (3k total)
- 15 routes/ns backed by the previous services (3k total)
- 20 secrets/ns (4k total)
- 10 config maps/ns (2k total)
- 6 network policies/ns, including deny-all, allow-from ingress and intra-namespace rules
- 57 builds/ns

The following factors are known to affect cluster workload scaling, positively or negatively, and should be factored into the scale numbers when planning a deployment. For additional information and guidance, contact your sales representative or Red Hat support.

- Number of pods per node
- Number of containers per pod
- Type of probes used (for example, liveness/readiness, exec/http)
- Number of network policies
- Number of projects, or namespaces
- Number of image streams per project
- Number of builds per project

- Number of services/endpoints and type
- Number of routes
- Number of shards
- Number of secrets
- Number of config maps
- Rate of API calls, or the cluster "churn", which is an estimation of how quickly things change in the cluster configuration.
  - Prometheus query for pod creation requests per second over 5 minute windows: sum(irate(apiserver\_request\_count{resource="pods",verb="POST"}[5m]))
  - Prometheus query for all API requests per second over 5 minute windows: sum(irate(apiserver\_request\_count{}[5m]))
- Cluster node resource consumption of CPU
- Cluster node resource consumption of memory

# 3.2. OPENSHIFT CONTAINER PLATFORM ENVIRONMENT AND CONFIGURATION ON WHICH THE CLUSTER MAXIMUMS ARE TESTED

## 3.2.1. AWS cloud platform

Node	Flavor	vCPU	RAM(GiB)	Disk type	Disk size(GiB) /IOS	Count	Region
Control plane/etc d <sup>[1]</sup>	r5.4xlarge	16	128	gp3	220	3	us-west-2
Infra <sup>[2]</sup>	m5.12xlarg e	48	192	gp3	100	3	us-west-2
Workload [3]	m5.4xlarg e	16	64	gp3	500 [4]	1	us-west-2
Compute	m5.2xlarg e	8	32	gp3	100	3/25/250 /500 <sup>[5]</sup>	us-west-2

- 1. gp3 disks with a baseline performance of 3000 IOPS and 125 MiB per second are used for control plane/etcd nodes because etcd is latency sensitive. gp3 volumes do not use burst performance.
- 2. Infra nodes are used to host Monitoring, Ingress, and Registry components to ensure they have enough resources to run at large scale.

- 3. Workload node is dedicated to run performance and scalability workload generators.
- 4. Larger disk size is used so that there is enough space to store the large amounts of data that is collected during the performance and scalability test run.
- 5. Cluster is scaled in iterations and performance and scalability tests are executed at the specified node counts.

## 3.2.2. IBM Power platform

Node	vCPU	RAM(GiB)	Disk type	Disk size(GiB)/IOS	Count
Control plane/etcd <sup>[1]</sup>	16	32	io1	120 / 10 IOPS per GiB	3
Infra <sup>[2]</sup>	16	64	gp2	120	2
Workload <sup>[3]</sup>	16	256	gp2	120 <sup>[4]</sup>	1
Compute	16	64	gp2	120	2 to 100 <sup>[5]</sup>

- 1. io1 disks with 120 / 10 IOPS per GiB are used for control plane/etcd nodes as etcd is I/O intensive and latency sensitive.
- 2. Infra nodes are used to host Monitoring, Ingress, and Registry components to ensure they have enough resources to run at large scale.
- 3. Workload node is dedicated to run performance and scalability workload generators.
- 4. Larger disk size is used so that there is enough space to store the large amounts of data that is collected during the performance and scalability test run.
- 5. Cluster is scaled in iterations.

# 3.2.3. IBM Z platform

Node	vCPU [4]	RAM(GiB)[5]	Disk type	Disk size(GiB)/IOS	Count
Control plane/etcd <sup>[1,2]</sup>	8	32	ds8k	300/LCU1	3
Compute <sup>[1,3]</sup>	8	32	ds8k	150 / LCU 2	4 nodes (scaled to 100/250/500 pods per node)

- 1. Nodes are distributed between two logical control units (LCUs) to optimize disk I/O load of the control plane/etcd nodes as etcd is I/O intensive and latency sensitive. Etcd I/O demand should not interfere with other workloads.
- Four compute nodes are used for the tests running several iterations with 100/250/500 pods at the same time. First, idling pods were used to evaluate if pods can be instanced. Next, a network and CPU demanding client/server workload were used to evaluate the stability of the system under stress. Client and server pods were pairwise deployed and each pair was spread over two compute nodes.
- 3. No separate workload node was used. The workload simulates a microservice workload between two compute nodes.
- 4. Physical number of processors used is six Integrated Facilities for Linux (IFLs).
- 5. Total physical memory used is 512 GiB.

# 3.3. HOW TO PLAN YOUR ENVIRONMENT ACCORDING TO TESTED CLUSTER MAXIMUMS



#### **IMPORTANT**

Oversubscribing the physical resources on a node affects resource guarantees the Kubernetes scheduler makes during pod placement. Learn what measures you can take to avoid memory swapping.

Some of the tested maximums are stretched only in a single dimension. They will vary when many objects are running on the cluster.

The numbers noted in this documentation are based on Red Hat's test methodology, setup, configuration, and tunings. These numbers can vary based on your own individual setup and environments.

While planning your environment, determine how many pods are expected to fit per node:

required pods per cluster / pods per node = total number of nodes needed

The default maximum number of pods per node is 250. However, the number of pods that fit on a node is dependent on the application itself. Consider the application's memory, CPU, and storage requirements, as described in "How to plan your environment according to application requirements".

#### Example scenario

If you want to scope your cluster for 2200 pods per cluster, you would need at least five nodes, assuming that there are 500 maximum pods per node:

2200 / 500 = 4.4

If you increase the number of nodes to 20, then the pod distribution changes to 110 pods per node:

2200 / 20 = 110

Where:

required pods per cluster / total number of nodes = expected pods per node

OpenShift Container Platform comes with several system pods, such as SDN, DNS, Operators, and others, which run across every worker node by default. Therefore, the result of the above formula can vary.

# 3.4. HOW TO PLAN YOUR ENVIRONMENT ACCORDING TO APPLICATION REQUIREMENTS

Consider an example application environment:

Pod type	Pod quantity	Max memory	CPU cores	Persistent storage
apache	100	500 MB	0.5	1GB
node.js	200	1GB	1	1GB
postgresql	100	1GB	2	10 GB
JBoss EAP	100	1GB	1	1GB

Extrapolated requirements: 550 CPU cores, 450GB RAM, and 1.4TB storage.

Instance size for nodes can be modulated up or down, depending on your preference. Nodes are often resource overcommitted. In this deployment scenario, you can choose to run additional smaller nodes or fewer larger nodes to provide the same amount of resources. Factors such as operational agility and cost-per-instance should be considered.

Node type	Quantity	CPUs	RAM (GB)
Nodes (option 1)	100	4	16
Nodes (option 2)	50	8	32
Nodes (option 3)	25	16	64

Some applications lend themselves well to overcommitted environments, and some do not. Most Java applications and applications that use huge pages are examples of applications that would not allow for overcommitment. That memory can not be used for other applications. In the example above, the environment would be roughly 30 percent overcommitted, a common ratio.

The application pods can access a service either by using environment variables or DNS. If using environment variables, for each active service the variables are injected by the kubelet when a pod is run on a node. A cluster-aware DNS server watches the Kubernetes API for new services and creates a set of DNS records for each one. If DNS is enabled throughout your cluster, then all pods should automatically be able to resolve services by their DNS name. Service discovery using DNS can be used in case you must go beyond 5000 services. When using environment variables for service discovery, the

argument list exceeds the allowed length after 5000 services in a namespace, then the pods and deployments will start failing. Disable the service links in the deployment's service specification file to overcome this:

```
apiVersion: template.openshift.io/v1
kind: Template
metadata:
 name: deployment-config-template
 creationTimestamp:
 annotations:
  description: This template will create a deploymentConfig with 1 replica, 4 env vars and a service.
objects:
- apiVersion: apps.openshift.io/v1
 kind: DeploymentConfig
 metadata:
  name: deploymentconfig${IDENTIFIER}
 spec:
  template:
   metadata:
    labels:
      name: replicationcontroller${IDENTIFIER}
   spec:
    enableServiceLinks: false
    containers:
    - name: pause${IDENTIFIER}
      image: "${IMAGE}"
      ports:
      - containerPort: 8080
       protocol: TCP
      - name: ENVVAR1_${IDENTIFIER}
       value: "${ENV_VALUE}"
      - name: ENVVAR2_${IDENTIFIER}
       value: "${ENV VALUE}"
      - name: ENVVAR3 ${IDENTIFIER}
       value: "${ENV_VALUE}"
      - name: ENVVAR4_${IDENTIFIER}
       value: "${ENV VALUE}"
      resources: {}
      imagePullPolicy: IfNotPresent
      capabilities: {}
      securityContext:
       capabilities: {}
       privileged: false
    restartPolicy: Always
    serviceAccount: "
  replicas: 1
  selector:
   name: replicationcontroller${IDENTIFIER}
  triggers:
  - type: ConfigChange
  strategy:
   type: Rolling
 apiVersion: v1
```

```
kind: Service
 metadata:
  name: service${IDENTIFIER}
 spec:
  selector:
   name: replicationcontroller${IDENTIFIER}
  ports:
  - name: serviceport${IDENTIFIER}
   protocol: TCP
   port: 80
   targetPort: 8080
  clusterIP: "
  type: ClusterIP
  sessionAffinity: None
 status:
  loadBalancer: {}
parameters:
- name: IDENTIFIER
 description: Number to append to the name of resources
 value: '1'
 required: true
- name: IMAGE
 description: Image to use for deploymentConfig
 value: gcr.io/google-containers/pause-amd64:3.0
 required: false
- name: ENV_VALUE
 description: Value to use for environment variables
 generate: expression
 from: "[A-Za-z0-9]{255}"
 required: false
labels:
 template: deployment-config-template
```

The number of application pods that can run in a namespace is dependent on the number of services and the length of the service name when the environment variables are used for service discovery. **ARG\_MAX** on the system defines the maximum argument length for a new process and it is set to 2097152 bytes (2 MiB) by default. The Kubelet injects environment variables in to each pod scheduled to run in the namespace including:

- <SERVICE NAME> SERVICE HOST=<IP>
- <SERVICE\_NAME>\_SERVICE\_PORT=<PORT>
- <SERVICE\_NAME>\_PORT=tcp://<IP>:<PORT>
- <SERVICE\_NAME>\_PORT\_<PORT>\_TCP=tcp://<IP>:<PORT>
- <SERVICE NAME> PORT <PORT> TCP PROTO=tcp
- <SERVICE\_NAME>\_PORT\_<PORT>\_TCP\_PORT=<PORT>
- <SERVICE\_NAME>\_PORT\_<PORT>\_TCP\_ADDR=<ADDR>

The pods in the namespace will start to fail if the argument length exceeds the allowed value and the number of characters in a service name impacts it. For example, in a namespace with 5000 services, the limit on the service name is 33 characters, which enables you to run 5000 pods in the namespace.

# CHAPTER 4. RECOMMENDED HOST PRACTICES FOR IBM Z & IBM LINUXONE ENVIRONMENTS

This topic provides recommended host practices for OpenShift Container Platform on IBM Z<sup>®</sup> and IBM<sup>®</sup> LinuxONE.



#### **NOTE**

The s390x architecture is unique in many aspects. Therefore, some recommendations made here might not apply to other platforms.



#### **NOTE**

Unless stated otherwise, these practices apply to both z/VM and Red Hat Enterprise Linux (RHEL) KVM installations on IBM Z<sup>®</sup> and IBM<sup>®</sup> LinuxONE.

### 4.1. MANAGING CPU OVERCOMMITMENT

In a highly virtualized IBM Z<sup>®</sup> environment, you must carefully plan the infrastructure setup and sizing. One of the most important features of virtualization is the capability to do resource overcommitment, allocating more resources to the virtual machines than actually available at the hypervisor level. This is very workload dependent and there is no golden rule that can be applied to all setups.

Depending on your setup, consider these best practices regarding CPU overcommitment:

- At LPAR level (PR/SM hypervisor), avoid assigning all available physical cores (IFLs) to each LPAR. For example, with four physical IFLs available, you should not define three LPARs with four logical IFLs each.
- Check and understand LPAR shares and weights.
- An excessive number of virtual CPUs can adversely affect performance. Do not define more virtual processors to a guest than logical processors are defined to the LPAR.
- Configure the number of virtual processors per guest for peak workload, not more.
- Start small and monitor the workload. Increase the vCPU number incrementally if necessary.
- Not all workloads are suitable for high overcommitment ratios. If the workload is CPU intensive, you will probably not be able to achieve high ratios without performance problems. Workloads that are more I/O intensive can keep consistent performance even with high overcommitment ratios.

#### Additional resources

- z/VM Common Performance Problems and Solutions
- z/VM overcommitment considerations
- LPAR CPU management

#### 4.2. DISABLE TRANSPARENT HUGE PAGES

Transparent Huge Pages (THP) attempt to automate most aspects of creating, managing, and using

huge pages. Since THP automatically manages the huge pages, this is not always handled optimally for all types of workloads. THP can lead to performance regressions, since many applications handle huge pages on their own. Therefore, consider disabling THP.

# 4.3. BOOST NETWORKING PERFORMANCE WITH RECEIVE FLOW STEERING

Receive Flow Steering (RFS) extends Receive Packet Steering (RPS) by further reducing network latency. RFS is technically based on RPS, and improves the efficiency of packet processing by increasing the CPU cache hit rate. RFS achieves this, and in addition considers queue length, by determining the most convenient CPU for computation so that cache hits are more likely to occur within the CPU. Thus, the CPU cache is invalidated less and requires fewer cycles to rebuild the cache. This can help reduce packet processing run time.

# 4.3.1. Use the Machine Config Operator (MCO) to activate RFS

#### **Procedure**

1. Copy the following MCO sample profile into a YAML file. For example, **enable-rfs.yaml**:

```
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
 labels:
  machineconfiguration.openshift.io/role: worker
 name: 50-enable-rfs
spec:
config:
  ignition:
   version: 2.2.0
  storage:
   files:
   - contents:
     source: data:text/plain;charset=US-
ASCII,%23%20turn%20on%20Receive%20Flow%20Steering%20%28RFS%29%20for%20all
%20network%20interfaces%0ASUBSYSTEM%3D%3D%22net%22%2C%20ACTION%3D%
3D%22add%22%2C%20RUN%7Bprogram%7D%2B%3D%22/bin/bash%20-
c%20%27for%20x%20in%20/sys/%24DEVPATH/gueues/rx-
%2A%3B%20do%20echo%208192%20%3E%20%24x/rps flow cnt%3B%20%20done%27
%22%0A
    filesystem: root
    mode: 0644
    path: /etc/udev/rules.d/70-persistent-net.rules
   - contents:
     source: data:text/plain;charset=US-
ASCII,%23%20define%20sock%20flow%20enbtried%20for%20%20Receive%20Flow%20Ste
ering%20%28RFS%29%0Anet.core.rps_sock_flow_entries%3D8192%0A
    filesystem: root
    mode: 0644
    path: /etc/sysctl.d/95-enable-rps.conf
```

2. Create the MCO profile:

\$ oc create -f enable-rfs.yaml

- 3. Verify that an entry named **50-enable-rfs** is listed:
  - \$ oc get mc
- 4. To deactivate, enter:
  - \$ oc delete mc 50-enable-rfs

#### Additional resources

- OpenShift Container Platform on IBM Z®: Tune your network performance with RFS
- Configuring Receive Flow Steering (RFS)
- Scaling in the Linux Networking Stack

#### 4.4. CHOOSE YOUR NETWORKING SETUP

The networking stack is one of the most important components for a Kubernetes-based product like OpenShift Container Platform. For IBM  $Z^{\odot}$  setups, the networking setup depends on the hypervisor of your choice. Depending on the workload and the application, the best fit usually changes with the use case and the traffic pattern.

Depending on your setup, consider these best practices:

- Consider all options regarding networking devices to optimize your traffic pattern. Explore the advantages of OSA-Express, RoCE Express, HiperSockets, z/VM VSwitch, Linux Bridge (KVM), and others to decide which option leads to the greatest benefit for your setup.
- Always use the latest available NIC version. For example, OSA Express 7S 10 GbE shows great improvement compared to OSA Express 6S 10 GbE with transactional workload types, although both are 10 GbE adapters.
- Each virtual switch adds an additional layer of latency.
- The load balancer plays an important role for network communication outside the cluster. Consider using a production-grade hardware load balancer if this is critical for your application.
- OpenShift Container Platform SDN introduces flows and rules, which impact the networking performance. Make sure to consider pod affinities and placements, to benefit from the locality of services where communication is critical.
- Balance the trade-off between performance and functionality.

#### Additional resources

- OpenShift Container Platform on IBM Z<sup>®</sup> Performance Experiences, Hints and Tips
- OpenShift Container Platform on IBM Z<sup>®</sup> Networking Performance
- Controlling pod placement on nodes using node affinity rules

# 4.5. ENSURE HIGH DISK PERFORMANCE WITH HYPERPAV ON Z/VM

DASD and ECKD devices are commonly used disk types in IBM Z<sup>®</sup> environments. In a typical OpenShift Container Platform setup in z/VM environments, DASD disks are commonly used to support the local storage for the nodes. You can set up HyperPAV alias devices to provide more throughput and overall better I/O performance for the DASD disks that support the z/VM guests.

Using HyperPAV for the local storage devices leads to a significant performance benefit. However, you must be aware that there is a trade-off between throughput and CPU costs.

# 4.5.1. Use the Machine Config Operator (MCO) to activate HyperPAV aliases in nodes using z/VM full-pack minidisks

For z/VM-based OpenShift Container Platform setups that use full-pack minidisks, you can leverage the advantage of MCO profiles by activating HyperPAV aliases in all of the nodes. You must add YAML configurations for both control plane and compute nodes.

#### **Procedure**

1. Copy the following MCO sample profile into a YAML file for the control plane node. For example, **05-master-kernelarg-hpav.yaml**:

```
$ cat 05-master-kernelarg-hpav.yaml
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
labels:
machineconfiguration.openshift.io/role: master
name: 05-master-kernelarg-hpav
spec:
config:
ignition:
version: 3.1.0
kernelArguments:
- rd.dasd=800-805
```

2. Copy the following MCO sample profile into a YAML file for the compute node. For example, **05-worker-kernelarg-hpav.yaml**:

```
$ cat 05-worker-kernelarg-hpav.yaml apiVersion: machineconfiguration.openshift.io/v1 kind: MachineConfig metadata: labels: machineconfiguration.openshift.io/role: worker name: 05-worker-kernelarg-hpav spec: config: ignition: version: 3.1.0 kernelArguments: - rd.dasd=800-805
```



#### **NOTE**

You must modify the **rd.dasd** arguments to fit the device IDs.

3. Create the MCO profiles:

```
$ oc create -f 05-master-kernelarg-hpav.yaml
```

\$ oc create -f 05-worker-kernelarg-hpav.yaml

4. To deactivate, enter:

```
$ oc delete -f 05-master-kernelarg-hpav.yaml
```

\$ oc delete -f 05-worker-kernelarg-hpav.yaml

#### Additional resources

- Using HyperPAV for ECKD DASD
- Scaling HyperPAV alias devices on Linux guests on z/VM

## 4.6. RHEL KVM ON IBM Z HOST RECOMMENDATIONS

Optimizing a KVM virtual server environment strongly depends on the workloads of the virtual servers and on the available resources. The same action that enhances performance in one environment can have adverse effects in another. Finding the best balance for a particular setting can be a challenge and often involves experimentation.

The following section introduces some best practices when using OpenShift Container Platform with RHEL KVM on IBM Z<sup>®</sup> and IBM<sup>®</sup> LinuxONE environments.

# 4.6.1. Use I/O threads for your virtual block devices

To make virtual block devices use I/O threads, you must configure one or more I/O threads for the virtual server and each virtual block device to use one of these I/O threads.

The following example specifies **<iothreads>3</iothreads>** to configure three I/O threads, with consecutive decimal thread IDs 1, 2, and 3. The **iothread="2"** parameter specifies the driver element of the disk device to use the I/O thread with ID 2.

#### Sample I/O thread specification

```
...
<domain>
<iothreads>3</iothreads>
1
...
<devices>
...
<disk type="block" device="disk">2
<driver ... iothread="2"/>
</disk>
...
</devices>
...
</domain>
```

- 1 The number of I/O threads.
- 2 The driver element of the disk device.

Threads can increase the performance of I/O operations for disk devices, but they also use memory and CPU resources. You can configure multiple devices to use the same thread. The best mapping of threads to devices depends on the available resources and the workload.

Start with a small number of I/O threads. Often, a single I/O thread for all disk devices is sufficient. Do not configure more threads than the number of virtual CPUs, and do not configure idle threads.

You can use the **virsh iothreadadd** command to add I/O threads with specific thread IDs to a running virtual server.

#### 4.6.2. Avoid virtual SCSI devices

Configure virtual SCSI devices only if you need to address the device through SCSI-specific interfaces. Configure disk space as virtual block devices rather than virtual SCSI devices, regardless of the backing on the host.

However, you might need SCSI-specific interfaces for:

- A LUN for a SCSI-attached tape drive on the host.
- A DVD ISO file on the host file system that is mounted on a virtual DVD drive.

# 4.6.3. Configure guest caching for disk

Configure your disk devices to do caching by the guest and not by the host.

Ensure that the driver element of the disk device includes the **cache="none"** and **io="native"** parameters.

```
<disk type="block" device="disk">
        <driver name="qemu" type="raw" cache="none" io="native" iothread="1"/>
...
</disk>
```

## 4.6.4. Exclude the memory balloon device

Unless you need a dynamic memory size, do not define a memory balloon device and ensure that libvirt does not create one for you. Include the **memballoon** parameter as a child of the devices element in your domain configuration XML file.

Check the list of active profiles:

```
<memballoon model="none"/>
```

## 4.6.5. Tune the CPU migration algorithm of the host scheduler



#### **IMPORTANT**

Do not change the scheduler settings unless you are an expert who understands the implications. Do not apply changes to production systems without testing them and confirming that they have the intended effect.

The **kernel.sched\_migration\_cost\_ns** parameter specifies a time interval in nanoseconds. After the last execution of a task, the CPU cache is considered to have useful content until this interval expires. Increasing this interval results in fewer task migrations. The default value is 500000 ns.

If the CPU idle time is higher than expected when there are runnable processes, try reducing this interval. If tasks bounce between CPUs or nodes too often, try increasing it.

To dynamically set the interval to 60000 ns, enter the following command:

# sysctl kernel.sched\_migration\_cost\_ns=60000

To persistently change the value to 60000 ns, add the following entry to /etc/sysctl.conf:

kernel.sched\_migration\_cost\_ns=60000

## 4.6.6. Disable the cpuset cgroup controller



#### **NOTE**

This setting applies only to KVM hosts with cgroups version 1. To enable CPU hotplug on the host, disable the cgroup controller.

#### **Procedure**

- 1. Open /etc/libvirt/qemu.conf with an editor of your choice.
- 2. Go to the **cgroup\_controllers** line.
- 3. Duplicate the entire line and remove the leading number sign (#) from the copy.
- 4. Remove the **cpuset** entry, as follows:
  - cgroup\_controllers = [ "cpu", "devices", "memory", "blkio", "cpuacct" ]
- 5. For the new setting to take effect, you must restart the libvirtd daemon:
  - a. Stop all virtual machines.
  - b. Run the following command:
    - # systemctl restart libvirtd
  - c. Restart the virtual machines.

This setting persists across host reboots.

## 4.6.7. Tune the polling period for idle virtual CPUs

When a virtual CPU becomes idle, KVM polls for wakeup conditions for the virtual CPU before allocating the host resource. You can specify the time interval, during which polling takes place in sysfs at /sys/module/kvm/parameters/halt\_poll\_ns. During the specified time, polling reduces the wakeup latency for the virtual CPU at the expense of resource usage. Depending on the workload, a longer or shorter time for polling can be beneficial. The time interval is specified in nanoseconds. The default is 50000 ns.

- To optimize for low CPU consumption, enter a small value or write 0 to disable polling:
  - # echo 0 > /sys/module/kvm/parameters/halt\_poll\_ns
- To optimize for low latency, for example for transactional workloads, enter a large value:
  - # echo 80000 > /sys/module/kvm/parameters/halt\_poll\_ns

#### Additional resources

- Linux on IBM Z<sup>®</sup> Performance Tuning for KVM
- Getting started with virtualization on IBM Z®

# CHAPTER 5. USING THE NODE TUNING OPERATOR

Learn about the Node Tuning Operator and how you can use it to manage node-level tuning by orchestrating the tuned daemon.

#### 5.1. ABOUT THE NODE TUNING OPERATOR

The Node Tuning Operator helps you manage node-level tuning by orchestrating the TuneD daemon and achieves low latency performance by using the Performance Profile controller. The majority of high-performance applications require some level of kernel tuning. The Node Tuning Operator provides a unified management interface to users of node-level sysctls and more flexibility to add custom tuning specified by user needs.

The Operator manages the containerized TuneD daemon for OpenShift Container Platform as a Kubernetes daemon set. It ensures the custom tuning specification is passed to all containerized TuneD daemons running in the cluster in the format that the daemons understand. The daemons run on all nodes in the cluster, one per node.

Node-level settings applied by the containerized TuneD daemon are rolled back on an event that triggers a profile change or when the containerized TuneD daemon is terminated gracefully by receiving and handling a termination signal.

The Node Tuning Operator uses the Performance Profile controller to implement automatic tuning to achieve low latency performance for OpenShift Container Platform applications.

The cluster administrator configures a performance profile to define node-level settings such as the following:

- Updating the kernel to kernel-rt.
- Choosing CPUs for housekeeping.
- Choosing CPUs for running workloads.

The Node Tuning Operator is part of a standard OpenShift Container Platform installation in version 4.1 and later.



#### **NOTE**

In earlier versions of OpenShift Container Platform, the Performance Addon Operator was used to implement automatic tuning to achieve low latency performance for OpenShift applications. In OpenShift Container Platform 4.11 and later, this functionality is part of the Node Tuning Operator.

# 5.2. ACCESSING AN EXAMPLE NODE TUNING OPERATOR SPECIFICATION

Use this process to access an example Node Tuning Operator specification.

#### **Procedure**

• Run the following command to access an example Node Tuning Operator specification:

oc get tuned.tuned.openshift.io/default -o yaml -n openshift-cluster-node-tuning-operator

The default CR is meant for delivering standard node-level tuning for the OpenShift Container Platform platform and it can only be modified to set the Operator Management state. Any other custom changes to the default CR will be overwritten by the Operator. For custom tuning, create your own Tuned CRs. Newly created CRs will be combined with the default CR and custom tuning applied to OpenShift Container Platform nodes based on node or pod labels and profile priorities.



#### **WARNING**

While in certain situations the support for pod labels can be a convenient way of automatically delivering required tuning, this practice is discouraged and strongly advised against, especially in large-scale clusters. The default Tuned CR ships without pod label matching. If a custom profile is created with pod label matching, then the functionality will be enabled at that time. The pod label functionality will be deprecated in future versions of the Node Tuning Operator.

### 5.3. DEFAULT PROFILES SET ON A CLUSTER

The following are the default profiles set on a cluster.

apiVersion: tuned.openshift.io/v1

kind: Tuned metadata: name: default

namespace: openshift-cluster-node-tuning-operator

spec: profile: - data: | [main]

summary=Optimize systems running OpenShift (provider specific parent profile)

include=-provider-\${f:exec:cat:/var/lib/ocp-tuned/provider},openshift

name: openshift recommend:

- profile: openshift-control-plane

priority: 30 match:

label: node-role.kubernetes.io/masterlabel: node-role.kubernetes.io/infra

- profile: openshift-node

priority: 40

Starting with OpenShift Container Platform 4.9, all OpenShift TuneD profiles are shipped with the TuneD package. You can use the **oc exec** command to view the contents of these profiles:

\$ oc exec \$tuned\_pod -n openshift-cluster-node-tuning-operator -- find /usr/lib/tuned/openshift{,-control-plane,-node} -name tuned.conf -exec grep -H ^ {} \;

#### 5.4. VERIFYING THAT THE TUNED PROFILES ARE APPLIED

Verify the TuneD profiles that are applied to your cluster node.

\$ oc get profile.tuned.openshift.io -n openshift-cluster-node-tuning-operator

#### **Example output**

TUNED	APF	PLIED	DEGR	ADED	AGE
openshift-control-pla	ane	True	False	6h3	3m
openshift-control-pla	ane	True	False	6h3	3m
openshift-control-pla	ane	True	False	6h3	3m
openshift-node	Tr	ue	False	6h28m	1
openshift-node	Tri	ue	False	6h28m	1
	openshift-control-pla openshift-control-pla openshift-control-pla openshift-node	openshift-control-plane openshift-control-plane openshift-control-plane openshift-node Tr	openshift-control-plane True openshift-control-plane True openshift-control-plane True openshift-node True	openshift-control-plane True False openshift-control-plane True False openshift-control-plane True False openshift-node True False	openshift-control-plane True False 6h3 openshift-control-plane True False 6h3 openshift-control-plane True False 6h3 openshift-node True False 6h28m

- **NAME**: Name of the Profile object. There is one Profile object per node and their names match.
- TUNED: Name of the desired TuneD profile to apply.
- APPLIED: True if the TuneD daemon applied the desired profile. ( True/False/Unknown).
- **DEGRADED**: **True** if any errors were reported during application of the TuneD profile (**True/False/Unknown**).
- AGE: Time elapsed since the creation of Profile object.

The **ClusterOperator/node-tuning** object also contains useful information about the Operator and its node agents' health. For example, Operator misconfiguration is reported by **ClusterOperator/node-tuning** status messages.

To get status information about the **ClusterOperator/node-tuning** object, run the following command:

\$ oc get co/node-tuning -n openshift-cluster-node-tuning-operator

#### **Example output**

```
NAME VERSION AVAILABLE PROGRESSING DEGRADED SINCE MESSAGE node-tuning 4.16.1 True False True 60m 1/5 Profiles with bootcmdline conflict
```

If either the **ClusterOperator**/**node-tuning** or a profile object's status is **DEGRADED**, additional information is provided in the Operator or operand logs.

#### 5.5. CUSTOM TUNING SPECIFICATION

The custom resource (CR) for the Operator has two major sections. The first section, **profile:**, is a list of TuneD profiles and their names. The second, **recommend:**, defines the profile selection logic.

Multiple custom tuning specifications can co-exist as multiple CRs in the Operator's namespace. The existence of new CRs or the deletion of old CRs is detected by the Operator. All existing custom tuning specifications are merged and appropriate objects for the containerized TuneD daemons are updated.

### Management state

The Operator Management state is set by adjusting the default Tuned CR. By default, the Operator is in the Managed state and the **spec.managementState** field is not present in the default Tuned CR. Valid values for the Operator Management state are as follows:

• Managed: the Operator will update its operands as configuration resources are updated

- Unmanaged: the Operator will ignore changes to the configuration resources
- Removed: the Operator will remove its operands and resources the Operator provisioned

#### Profile data

The **profile:** section lists TuneD profiles and their names.

```
profile:
- name: tuned_profile_1
 data: |
  # TuneD profile specification
  [main]
  summary=Description of tuned_profile_1 profile
  [sysctl]
  net.ipv4.ip forward=1
  # ... other sysctl's or other TuneD daemon plugins supported by the containerized TuneD
# ...
- name: tuned_profile_n
 data: |
  # TuneD profile specification
  [main]
  summary=Description of tuned_profile_n profile
  # tuned profile n profile settings
```

#### Recommended profiles

The **profile:** selection logic is defined by the **recommend:** section of the CR. The **recommend:** section is a list of items to recommend the profiles based on a selection criteria.

```
recommend:
<recommend-item-1>
# ...
<recommend-item-n>
```

The individual items of the list:

```
- machineConfigLabels: 1

<mcLabels> 2

match: 3

<match> 4

priority: <priority> 5

profile: <tuned_profile_name> 6

operand: 7

debug: <bool> 8

tunedConfig:
reapply_sysctl: <bool> 9
```

1 Optional.

- A dictionary of key/value **MachineConfig** labels. The keys must be unique.
- If omitted, profile match is assumed unless a profile with a higher priority matches first or **machineConfigLabels** is set.
- An optional list.
- A TuneD profile to apply on a match. For example **tuned\_profile\_1**.
- Optional operand configuration.
- Turn debugging on or off for the TuneD daemon. Options are **true** for on or **false** for off. The default is **false**.
- Turn **reapply\_sysctl** functionality on or off for the TuneD daemon. Options are **true** for on and **false** for off.

<match> is an optional list recursively defined as follows:

- label: <label\_name> 1
value: <label\_value> 2
type: <label\_type> 3
<match> 4

- Node or pod label name.
- Optional node or pod label value. If omitted, the presence of **<label\_name>** is enough to match.
- 3 Optional object type (**node** or **pod**). If omitted, **node** is assumed.
- 4 An optional <match> list.

If <match> is not omitted, all nested <match> sections must also evaluate to true. Otherwise, false is assumed and the profile with the respective <match> section will not be applied or recommended. Therefore, the nesting (child <match> sections) works as logical AND operator. Conversely, if any item of the <match> list matches, the entire <match> list evaluates to true. Therefore, the list acts as logical OR operator.

If machineConfigLabels is defined, machine config pool based matching is turned on for the given recommend: list item. <mcLabels> specifies the labels for a machine config. The machine config is created automatically to apply host settings, such as kernel boot parameters, for the profile <tuned\_profile\_name>. This involves finding all machine config pools with machine config selector matching <mcLabels> and setting the profile <tuned\_profile\_name> on all nodes that are assigned the found machine config pools. To target nodes that have both master and worker roles, you must use the master role.

The list items **match** and **machineConfigLabels** are connected by the logical OR operator. The **match** item is evaluated first in a short-circuit manner. Therefore, if it evaluates to **true**, the **machineConfigLabels** item is not considered.



#### **IMPORTANT**

When using machine config pool based matching, it is advised to group nodes with the same hardware configuration into the same machine config pool. Not following this practice might result in TuneD operands calculating conflicting kernel parameters for two or more nodes sharing the same machine config pool.

# Example: Node or pod label based matching

- match:

 label: tuned.openshift.io/elasticsearch match:

 label: node-role.kubernetes.io/master
 label: node-role.kubernetes.io/infra type: pod

priority: 10

profile: openshift-control-plane-es

- match:

label: node-role.kubernetes.io/masterlabel: node-role.kubernetes.io/infra

priority: 20

profile: openshift-control-plane


- priority: 30

profile: openshift-node

The CR above is translated for the containerized TuneD daemon into its **recommend.conf** file based on the profile priorities. The profile with the highest priority (10) is **openshift-control-plane-es** and, therefore, it is considered first. The containerized TuneD daemon running on a given node looks to see if there is a pod running on the same node with the **tuned.openshift.io/elasticsearch** label set. If not, the entire **<match>** section evaluates as **false**. If there is such a pod with the label, in order for the **<match>** section to evaluate to **true**, the node label also needs to be **node-role.kubernetes.io/master** or **node-role.kubernetes.io/infra**.

If the labels for the profile with priority **10** matched, **openshift-control-plane-es** profile is applied and no other profile is considered. If the node/pod label combination did not match, the second highest priority profile (**openshift-control-plane**) is considered. This profile is applied if the containerized TuneD pod runs on a node with labels **node-role.kubernetes.io/master** or **node-role.kubernetes.io/infra**.

Finally, the profile **openshift-node** has the lowest priority of **30**. It lacks the **<match>** section and, therefore, will always match. It acts as a profile catch-all to set **openshift-node** profile, if no other profile with higher priority matches on a given node.



OPENSHIFT\_10\_0319

# Example: Machine config pool based matching

```
apiVersion: tuned.openshift.io/v1
kind: Tuned
metadata:
 name: openshift-node-custom
 namespace: openshift-cluster-node-tuning-operator
spec:
 profile:
 - data: |
   [main]
   summary=Custom OpenShift node profile with an additional kernel parameter
   include=openshift-node
   [bootloader]
   cmdline_openshift_node_custom=+skew_tick=1
  name: openshift-node-custom
 recommend:
 - machineConfigLabels:
   machineconfiguration.openshift.io/role: "worker-custom"
  priority: 20
  profile: openshift-node-custom
```

To minimize node reboots, label the target nodes with a label the machine config pool's node selector will match, then create the Tuned CR above and finally create the custom machine config pool itself.

# Cloud provider-specific TuneD profiles

With this functionality, all Cloud provider-specific nodes can conveniently be assigned a TuneD profile specifically tailored to a given Cloud provider on a OpenShift Container Platform cluster. This can be accomplished without adding additional node labels or grouping nodes into machine config pools.

This functionality takes advantage of **spec.providerID** node object values in the form of **<cloud-provider>:**//**<cloud-provider-specific-id>** and writes the file /**var/lib/ocp-tuned/provider** with the value **<cloud-provider>** in NTO operand containers. The content of this file is then used by TuneD to load **provider-<cloud-provider>** profile if such profile exists.

The **openshift** profile that both **openshift-control-plane** and **openshift-node** profiles inherit settings from is now updated to use this functionality through the use of conditional profile loading. Neither NTO nor TuneD currently include any Cloud provider-specific profiles. However, it is possible to create a custom profile **provider-cloud-provider>** that will be applied to all Cloud provider-specific cluster nodes.

# **Example GCE Cloud provider profile**

apiVersion: tuned.openshift.io/v1
kind: Tuned
metadata:
name: provider-gce
namespace: openshift-cluster-node-tuning-operator
spec:
profile:
- data: |
 [main]
 summary=GCE Cloud provider-specific profile
# Your tuning for GCE Cloud provider goes here.
name: provider-gce



#### NOTE

Due to profile inheritance, any setting specified in the **provider-<cloud-provider>** profile will be overwritten by the **openshift** profile and its child profiles.

## 5.6. CUSTOM TUNING EXAMPLES

Using TuneD profiles from the default CR

The following CR applies custom node-level tuning for OpenShift Container Platform nodes with label **tuned.openshift.io/ingress-node-label** set to any value.

Example: custom tuning using the openshift-control-plane TuneD profile

apiVersion: tuned.openshift.io/v1
kind: Tuned
metadata:
name: ingress
namespace: openshift-cluster-node-tuning-operator
spec:
profile:
- data: |
 [main]
 summary=A custom OpenShift ingress profile
include=openshift-control-plane

```
[sysctl]
net.ipv4.ip_local_port_range="1024 65535"
net.ipv4.tcp_tw_reuse=1
name: openshift-ingress
recommend:
- match:
- label: tuned.openshift.io/ingress-node-label
priority: 10
profile: openshift-ingress
```



#### **IMPORTANT**

Custom profile writers are strongly encouraged to include the default TuneD daemon profiles shipped within the default Tuned CR. The example above uses the default **openshift-control-plane** profile to accomplish this.

# Using built-in TuneD profiles

Given the successful rollout of the NTO-managed daemon set, the TuneD operands all manage the same version of the TuneD daemon. To list the built-in TuneD profiles supported by the daemon, query any TuneD pod in the following way:

 $\$  oc exec  $\$ tuned\_pod -n openshift-cluster-node-tuning-operator -- find /usr/lib/tuned/ -name tuned.conf -printf '%h\n' | sed 's|^.\*/||'

You can use the profile names retrieved by this in your custom tuning specification.

# Example: using built-in hpc-compute TuneD profile

```
apiVersion: tuned.openshift.io/v1
kind: Tuned
metadata:
 name: openshift-node-hpc-compute
 namespace: openshift-cluster-node-tuning-operator
spec:
 profile:
 - data: |
   [main]
   summary=Custom OpenShift node profile for HPC compute workloads
   include=openshift-node,hpc-compute
  name: openshift-node-hpc-compute
 recommend:
 - match:
  - label: tuned.openshift.io/openshift-node-hpc-compute
  priority: 20
  profile: openshift-node-hpc-compute
```

In addition to the built-in **hpc-compute** profile, the example above includes the **openshift-node** TuneD daemon profile shipped within the default Tuned CR to use OpenShift-specific tuning for compute nodes.

#### Overriding host-level sysctls

Various kernel parameters can be changed at runtime by using /run/sysctl.d/, /etc/sysctl.d/, and /etc/sysctl.conf host configuration files. OpenShift Container Platform adds several host configuration files which set kernel parameters at runtime; for example, net.ipv[4-6]., fs.inotify., and vm.max\_map\_count. These runtime parameters provide basic functional tuning for the system prior to the kubelet and the Operator start.

The Operator does not override these settings unless the **reapply\_sysctl** option is set to **false**. Setting this option to **false** results in **TuneD** not applying the settings from the host configuration files after it applies its custom profile.

# Example: overriding host-level sysctls

```
apiVersion: tuned.openshift.io/v1
kind: Tuned
metadata:
 name: openshift-no-reapply-sysctl
 namespace: openshift-cluster-node-tuning-operator
spec:
 profile:
 - data: |
   [main]
   summary=Custom OpenShift profile
   include=openshift-node
   [sysctl]
   vm.max_map_count=>524288
  name: openshift-no-reapply-sysctl
 recommend:
 - match:
  - label: tuned.openshift.io/openshift-no-reapply-sysctl
  profile: openshift-no-reapply-sysctl
  operand:
   tunedConfig:
     reapply sysctl: false
```

# 5.7. SUPPORTED TUNED DAEMON PLUGINS

Excluding the **[main]** section, the following TuneD plugins are supported when using custom profiles defined in the **profile**: section of the Tuned CR:

- audio
- cpu
- disk
- eeepc\_she
- modules
- mounts
- net
- scheduler

- scsi\_host
- selinux
- sysctl
- sysfs
- usb
- video
- vm
- bootloader

There is some dynamic tuning functionality provided by some of these plugins that is not supported. The following TuneD plugins are currently not supported:

- script
- systemd



#### **NOTE**

The TuneD bootloader plugin only supports Red Hat Enterprise Linux CoreOS (RHCOS) worker nodes.

#### Additional resources

- Available TuneD Plugins
- Getting Started with TuneD

# 5.8. CONFIGURING NODE TUNING IN A HOSTED CLUSTER

To set node-level tuning on the nodes in your hosted cluster, you can use the Node Tuning Operator. In hosted control planes, you can configure node tuning by creating config maps that contain **Tuned** objects and referencing those config maps in your node pools.

#### Procedure

 Create a config map that contains a valid tuned manifest, and reference the manifest in a node pool. In the following example, a **Tuned** manifest defines a profile that sets **vm.dirty\_ratio** to 55 on nodes that contain the **tuned-1-node-label** node label with any value. Save the following **ConfigMap** manifest in a file named **tuned-1.yaml**:

apiVersion: v1
kind: ConfigMap
metadata:
name: tuned-1
namespace: clusters
data:
tuning: |
apiVersion: tuned.openshift.io/v1

```
kind: Tuned
metadata:
name: tuned-1
namespace: openshift-cluster-node-tuning-operator
spec:
profile:
- data: |
    [main]
    summary=Custom OpenShift profile
    include=openshift-node
    [sysctl]
    vm.dirty_ratio="55"
    name: tuned-1-profile
recommend:
- priority: 20
    profile: tuned-1-profile
```



#### **NOTE**

If you do not add any labels to an entry in the **spec.recommend** section of the Tuned spec, node-pool-based matching is assumed, so the highest priority profile in the **spec.recommend** section is applied to nodes in the pool. Although you can achieve more fine-grained node-label-based matching by setting a label value in the Tuned **.spec.recommend.match** section, node labels will not persist during an upgrade unless you set the **.spec.management.upgradeType** value of the node pool to **InPlace**.

2. Create the **ConfigMap** object in the management cluster:

```
$ oc --kubeconfig="$MGMT_KUBECONFIG" create -f tuned-1.yaml
```

3. Reference the **ConfigMap** object in the **spec.tuningConfig** field of the node pool, either by editing a node pool or creating one. In this example, assume that you have only one **NodePool**, named **nodepool-1**, which contains 2 nodes.

```
apiVersion: hypershift.openshift.io/v1alpha1 kind: NodePool metadata:
...
name: nodepool-1 namespace: clusters
...
spec:
...
tuningConfig:
- name: tuned-1 status:
...
```



#### **NOTE**

You can reference the same config map in multiple node pools. In hosted control planes, the Node Tuning Operator appends a hash of the node pool name and namespace to the name of the Tuned CRs to distinguish them. Outside of this case, do not create multiple TuneD profiles of the same name in different Tuned CRs for the same hosted cluster.

# Verification

Now that you have created the **ConfigMap** object that contains a **Tuned** manifest and referenced it in a **NodePool**, the Node Tuning Operator syncs the **Tuned** objects into the hosted cluster. You can verify which **Tuned** objects are defined and which TuneD profiles are applied to each node.

1. List the **Tuned** objects in the hosted cluster:

\$ oc --kubeconfig="\$HC\_KUBECONFIG" get tuned.tuned.openshift.io -n openshift-cluster-node-tuning-operator

# **Example output**

NAME AGE default 7m36s rendered 7m36s tuned-1 65s

2. List the **Profile** objects in the hosted cluster:

\$ oc --kubeconfig="\$HC\_KUBECONFIG" get profile.tuned.openshift.io -n openshift-cluster-node-tuning-operator

## **Example output**

NAME	TUNED AP	PLIED	DEGRAD	ED AGE
nodepool-1-worker-1	tuned-1-profil	e True	False	7m43s
nodepool-1-worker-2	tuned-1-profil	e True	False	7m14s



#### **NOTE**

If no custom profiles are created, the **openshift-node** profile is applied by default

3. To confirm that the tuning was applied correctly, start a debug shell on a node and check the sysctl values:

\$ oc --kubeconfig="\$HC\_KUBECONFIG" debug node/nodepool-1-worker-1 -- chroot /host sysctl vm.dirty ratio

## **Example output**

vm.dirty\_ratio = 55

# 5.9. ADVANCED NODE TUNING FOR HOSTED CLUSTERS BY SETTING KERNEL BOOT PARAMETERS

For more advanced tuning in hosted control planes, which requires setting kernel boot parameters, you can also use the Node Tuning Operator. The following example shows how you can create a node pool with huge pages reserved.

#### **Procedure**

1. Create a **ConfigMap** object that contains a **Tuned** object manifest for creating 10 huge pages that are 2 MB in size. Save this **ConfigMap** manifest in a file named **tuned-hugepages.yaml**:

```
apiVersion: v1
kind: ConfigMap
metadata:
 name: tuned-hugepages
 namespace: clusters
data:
 tuning: |
  apiVersion: tuned.openshift.io/v1
  kind: Tuned
  metadata:
   name: hugepages
   namespace: openshift-cluster-node-tuning-operator
  spec:
   profile:
   - data: |
     [main]
     summary=Boot time configuration for hugepages
     include=openshift-node
     [bootloader]
     cmdline openshift node hugepages=hugepagesz=2M hugepages=50
    name: openshift-node-hugepages
   recommend:
   - priority: 20
    profile: openshift-node-hugepages
```



#### **NOTE**

The .spec.recommend.match field is intentionally left blank. In this case, this Tuned object is applied to all nodes in the node pool where this ConfigMap object is referenced. Group nodes with the same hardware configuration into the same node pool. Otherwise, TuneD operands can calculate conflicting kernel parameters for two or more nodes that share the same node pool.

2. Create the **ConfigMap** object in the management cluster:

\$ oc --kubeconfig="\$MGMT\_KUBECONFIG" create -f tuned-hugepages.yaml

3. Create a NodePool manifest YAML file, customize the upgrade type of the NodePool, and reference the ConfigMap object that you created in the spec.tuningConfig section. Create the NodePool manifest and save it in a file named hugepages-nodepool.yaml by using the hcp CLI:

NODEPOOL\_NAME=hugepages-example INSTANCE\_TYPE=m5.2xlarge NODEPOOL\_REPLICAS=2

hcp create nodepool aws \

- --cluster-name \$CLUSTER NAME \
- --name \$NODEPOOL NAME \
- --node-count \$NODEPOOL REPLICAS \
- --instance-type \$INSTANCE TYPE \
- --render > hugepages-nodepool.yaml
- In the hugepages-nodepool.yaml file, set .spec.management.upgradeType to InPlace, and set .spec.tuningConfig to reference the tuned-hugepages ConfigMap object that you created.

```
apiVersion: hypershift.openshift.io/v1alpha1kind: NodePool
metadata:
    name: hugepages-nodepool
    namespace: clusters
    ...
spec:
    management:
    ...
    upgradeType: InPlace
    ...
tuningConfig:
    - name: tuned-hugepages
```



#### NOTE

To avoid the unnecessary re-creation of nodes when you apply the new **MachineConfig** objects, set **.spec.management.upgradeType** to **InPlace**. If you use the **Replace** upgrade type, nodes are fully deleted and new nodes can replace them when you apply the new kernel boot parameters that the TuneD operand calculated.

5. Create the **NodePool** in the management cluster:

\$ oc --kubeconfig="\$MGMT\_KUBECONFIG" create -f hugepages-nodepool.yaml

#### Verification

After the nodes are available, the containerized TuneD daemon calculates the required kernel boot parameters based on the applied TuneD profile. After the nodes are ready and reboot once to apply the generated **MachineConfig** object, you can verify that the TuneD profile is applied and that the kernel boot parameters are set.

1. List the **Tuned** objects in the hosted cluster:

\$ oc --kubeconfig="\$HC\_KUBECONFIG" get tuned.tuned.openshift.io -n openshift-cluster-node-tuning-operator

#### Example output

NAME AGE
default 123m
hugepages-8dfb1fed 1m23s
rendered 123m

2. List the **Profile** objects in the hosted cluster:

\$ oc --kubeconfig="\$HC\_KUBECONFIG" get profile.tuned.openshift.io -n openshift-cluster-node-tuning-operator

# **Example output**

```
NAME
                    TUNED
                                      APPLIED DEGRADED AGE
nodepool-1-worker-1
                                                  False
                                                          132m
                       openshift-node
                                           True
nodepool-1-worker-2
                       openshift-node
                                           True
                                                  False
                                                          131m
hugepages-nodepool-worker-1
                           openshift-node-hugepages True
                                                           False
                                                                   4m8s
hugepages-nodepool-worker-2 openshift-node-hugepages True
                                                           False
                                                                   3m57s
```

Both of the worker nodes in the new **NodePool** have the **openshift-node-hugepages** profile applied.

3. To confirm that the tuning was applied correctly, start a debug shell on a node and check /proc/cmdline.

\$ oc --kubeconfig="\$HC\_KUBECONFIG" debug node/nodepool-1-worker-1 -- chroot /host cat /proc/cmdline

## **Example output**

BOOT\_IMAGE=(hd0,gpt3)/ostree/rhcos-... hugepagesz=2M hugepages=50

#### Additional resources

For more information about hosted control planes, see Hosted control planes.

# CHAPTER 6. USING CPU MANAGER AND TOPOLOGY MANAGER

CPU Manager manages groups of CPUs and constrains workloads to specific CPUs.

CPU Manager is useful for workloads that have some of these attributes:

- Require as much CPU time as possible.
- Are sensitive to processor cache misses.
- Are low-latency network applications.
- Coordinate with other processes and benefit from sharing a single processor cache.

Topology Manager collects hints from the CPU Manager, Device Manager, and other Hint Providers to align pod resources, such as CPU, SR-IOV VFs, and other device resources, for all Quality of Service (QoS) classes on the same non-uniform memory access (NUMA) node.

Topology Manager uses topology information from the collected hints to decide if a pod can be accepted or rejected on a node, based on the configured Topology Manager policy and pod resources requested.

Topology Manager is useful for workloads that use hardware accelerators to support latency-critical execution and high throughput parallel computation.

To use Topology Manager you must configure CPU Manager with the **static** policy.

## 6.1. SETTING UP CPU MANAGER

To configure CPU manager, create a KubeletConfig custom resource (CR) and apply it to the desired set of nodes.

#### Procedure

- 1. Label a node by running the following command:
  - # oc label node perf-node.example.com cpumanager=true
- 2. To enable CPU Manager for all compute nodes, edit the CR by running the following command:
  - # oc edit machineconfigpool worker
- 3. Add the custom-kubelet: cpumanager-enabled label to metadata.labels section.

metadata:

creationTimestamp: 2020-xx-xxx

generation: 3

labels:

custom-kubelet: cpumanager-enabled

4. Create a **KubeletConfig**, **cpumanager-kubeletconfig.yaml**, custom resource (CR). Refer to the label created in the previous step to have the correct nodes updated with the new kubelet config. See the **machineConfigPoolSelector** section:

```
apiVersion: machineconfiguration.openshift.io/v1
kind: KubeletConfig
metadata:
name: cpumanager-enabled
spec:
machineConfigPoolSelector:
matchLabels:
custom-kubelet: cpumanager-enabled
kubeletConfig:
cpuManagerPolicy: static 1
cpuManagerReconcilePeriod: 5s 2
```

- Specify a policy:
  - **none**. This policy explicitly enables the existing default CPU affinity scheme, providing no affinity beyond what the scheduler does automatically. This is the default policy.
  - **static**. This policy allows containers in guaranteed pods with integer CPU requests. It also limits access to exclusive CPUs on the node. If **static**, you must use a lowercase **s**.
- Optional. Specify the CPU Manager reconcile frequency. The default is **5s**.
- 5. Create the dynamic kubelet config by running the following command:
  - # oc create -f cpumanager-kubeletconfig.yaml

This adds the CPU Manager feature to the kubelet config and, if needed, the Machine Config Operator (MCO) reboots the node. To enable CPU Manager, a reboot is not needed.

6. Check for the merged kubelet config by running the following command:

# oc get machineconfig 99-worker-XXXXXX-XXXXX-XXXXX-kubelet -o json | grep ownerReference -A7

# **Example output**

7. Check the compute node for the updated **kubelet.conf** file by running the following command:

# oc debug node/perf-node.example.com sh-4.2# cat /host/etc/kubernetes/kubelet.conf | grep cpuManager

# **Example output**

cpuManagerPolicy: static 1 cpuManagerReconcilePeriod: 5s 2

- cpuManagerPolicy is defined when you create the KubeletConfig CR.
- cpuManagerReconcilePeriod is defined when you create the KubeletConfig CR.
- 8. Create a project by running the following command:
  - \$ oc new-project project\_name>
- 9. Create a pod that requests a core or multiple cores. Both limits and requests must have their CPU value set to a whole integer. That is the number of cores that will be dedicated to this pod:
  - # cat cpumanager-pod.yaml

# **Example output**

```
apiVersion: v1
kind: Pod
metadata:
 generateName: cpumanager-
spec:
 securityContext:
  runAsNonRoot: true
  seccompProfile:
   type: RuntimeDefault
 containers:
 - name: cpumanager
  image: gcr.io/google containers/pause:3.2
  resources:
   requests:
    cpu: 1
    memory: "1G"
   limits:
    cpu: 1
    memory: "1G"
  securityContext:
   allowPrivilegeEscalation: false
   capabilities:
    drop: [ALL]
 nodeSelector:
  cpumanager: "true"
```

10. Create the pod:

# oc create -f cpumanager-pod.yaml

#### Verification

1. Verify that the pod is scheduled to the node that you labeled by running the following command:

# oc describe pod cpumanager

# **Example output**

```
Name:
              cpumanager-6cqz7
Namespace:
                 default
Priority:
             0
PriorityClassName: <none>
Node: perf-node.example.com/xxx.xx.xx.xxx
Limits:
   cpu:
          1
   memory: 1G
  Requests:
   cpu:
   memory:
              1G
QoS Class:
              Guaranteed
Node-Selectors: cpumanager=true
```

2. Verify that a CPU has been exclusively assigned to the pod by running the following command:

# oc describe node --selector='cpumanager=true' | grep -i cpumanager - B2

# **Example output**

```
NAMESPACE NAME CPU Requests CPU Limits Memory Requests Memory Limits Age cpuman cpumanager-mlrrz 1 (28%) 1 (28%) 1 (13%) 1 (13%) 27m
```

3. Verify that the **cgroups** are set up correctly. Get the process ID (PID) of the **pause** process by running the following commands:

# oc debug node/perf-node.example.com

sh-4.2# systemctl status | grep -B5 pause



# NOTE

If the output returns multiple pause process entries, you must identify the correct pause process.

## **Example output**

```
# |--init.scope | 1/usr/lib/systemd/systemd --switched-root --system --deserialize 17 | kubepods.slice | --kubepods-pod69c01f8e_6b74_11e9_ac0f_0a2b62178a22.slice | --crio-b5437308f1a574c542bdf08563b865c0345c8f8c0b0a655612c.scope | --32706/pause
```

4. Verify that pods of quality of service (QoS) tier **Guaranteed** are placed within the **kubepods.slice** subdirectory by running the following commands:

# cd /sys/fs/cgroup/kubepods.slice/kubepods-pod69c01f8e\_6b74\_11e9\_ac0f\_0a2b62178a22.slice/crio-b5437308f1ad1a7db0574c542bdf08563b865c0345c86e9585f8c0b0a655612c.scope

# for i in `ls cpuset.cpus cgroup.procs`; do echo -n "\$i "; cat \$i; done



#### **NOTE**

Pods of other QoS tiers end up in child **cgroups** of the parent **kubepods**.

# **Example output**

cpuset.cpus 1 tasks 32706

5. Check the allowed CPU list for the task by running the following command:

# grep ^Cpus\_allowed\_list /proc/32706/status

# **Example output**

Cpus\_allowed\_list: 1

6. Verify that another pod on the system cannot run on the core allocated for the **Guaranteed** pod. For example, to verify the pod in the **besteffort** QoS tier, run the following commands:

# cat /sys/fs/cgroup/kubepods.slice/kubepods-besteffort.slice/kubepods-besteffort-podc494a073\_6b77\_11e9\_98c0\_06bba5c387ea.slice/crio-c56982f57b75a2420947f0afc6cafe7534c5734efc34157525fa9abbf99e3849.scope/cpuset.cpus

# oc describe node perf-node.example.com

## **Example output**

...

Capacity:

attachable-volumes-aws-ebs: 39

cpu: 2

ephemeral-storage: 124768236Ki

hugepages-1Gi: 0 hugepages-2Mi: 0 memory: 8162900Ki

pods: 250

Allocatable:

attachable-volumes-aws-ebs: 39

cpu: 1500m

ephemeral-storage: 124768236Ki

hugepages-1Gi: 0

hugepages-2Mi: 0 memory: 7548500Ki pods: 250 default cpumanager-6cqz7 1 (66%) 1 (66%) 1G (12%) 1G (12%) 29m Allocated resources: (Total limits may be over 100 percent, i.e., overcommitted.) Resource Limits Requests 1440m (96%) cpu 1 (66%)

This VM has two CPU cores. The **system-reserved** setting reserves 500 millicores, meaning that half of one core is subtracted from the total capacity of the node to arrive at the **Node Allocatable** amount. You can see that **Allocatable CPU** is 1500 millicores. This means you can run one of the CPU Manager pods since each will take one whole core. A whole core is equivalent to 1000 millicores. If you try to schedule a second pod, the system will accept the pod, but it will never be scheduled:

NAME READY STATUS RESTARTS AGE cpumanager-6cqz7 1/1 Running 0 33m cpumanager-7qc2t 0/1 Pending 0 11s

# 6.2. TOPOLOGY MANAGER POLICIES

Topology Manager aligns **Pod** resources of all Quality of Service (QoS) classes by collecting topology hints from Hint Providers, such as CPU Manager and Device Manager, and using the collected hints to align the **Pod** resources.

Topology Manager supports four allocation policies, which you assign in the **KubeletConfig** custom resource (CR) named **cpumanager-enabled**:

### none policy

This is the default policy and does not perform any topology alignment.

#### best-effort policy

For each container in a pod with the **best-effort** topology management policy, kubelet calls each Hint Provider to discover their resource availability. Using this information, the Topology Manager stores the preferred NUMA Node affinity for that container. If the affinity is not preferred, Topology Manager stores this and admits the pod to the node.

#### restricted policy

For each container in a pod with the **restricted** topology management policy, kubelet calls each Hint Provider to discover their resource availability. Using this information, the Topology Manager stores the preferred NUMA Node affinity for that container. If the affinity is not preferred, Topology Manager rejects this pod from the node, resulting in a pod in a **Terminated** state with a pod admission failure.

# single-numa-node policy

For each container in a pod with the **single-numa-node** topology management policy, kubelet calls each Hint Provider to discover their resource availability. Using this information, the Topology Manager determines if a single NUMA Node affinity is possible. If it is, the pod is admitted to the

node. If a single NUMA Node affinity is not possible, the Topology Manager rejects the pod from the node. This results in a pod in a Terminated state with a pod admission failure.

## 6.3. SETTING UP TOPOLOGY MANAGER

To use Topology Manager, you must configure an allocation policy in the **KubeletConfig** custom resource (CR) named **cpumanager-enabled**. This file might exist if you have set up CPU Manager. If the file does not exist, you can create the file.

### **Prerequisites**

• Configure the CPU Manager policy to be **static**.

#### **Procedure**

To activate Topology Manager:

1. Configure the Topology Manager allocation policy in the custom resource.

\$ oc edit KubeletConfig cpumanager-enabled

apiVersion: machineconfiguration.openshift.io/v1

kind: KubeletConfig

metadata:

name: cpumanager-enabled

spec:

machineConfigPoolSelector:

matchLabels:

custom-kubelet: cpumanager-enabled

kubeletConfig:

topologyManagerPolicy: single-numa-node 2

- This parameter must be **static** with a lowercase **s**.
- 2 Specify your selected Topology Manager allocation policy. Here, the policy is **single-numa-node**. Acceptable values are: **default**, **best-effort**, **restricted**, **single-numa-node**.

## 6.4. POD INTERACTIONS WITH TOPOLOGY MANAGER POLICIES

The example **Pod** specs below help illustrate pod interactions with Topology Manager.

The following pod runs in the **BestEffort** QoS class because no resource requests or limits are specified.

spec:

containers:

name: nginx image: nginx

The next pod runs in the **Burstable** QoS class because requests are less than limits.

spec:

```
containers:
- name: nginx
image: nginx
resources:
limits:
memory: "200Mi"
requests:
memory: "100Mi"
```

If the selected policy is anything other than **none**, Topology Manager would not consider either of these **Pod** specifications.

The last example pod below runs in the Guaranteed QoS class because requests are equal to limits.

```
spec:
containers:
- name: nginx
image: nginx
resources:
limits:
memory: "200Mi"
cpu: "2"
example.com/device: "1"
requests:
memory: "200Mi"
cpu: "2"
example.com/device: "1"
```

Topology Manager would consider this pod. The Topology Manager would consult the hint providers, which are CPU Manager and Device Manager, to get topology hints for the pod.

Topology Manager will use this information to store the best topology for this container. In the case of this pod, CPU Manager and Device Manager will use this stored information at the resource allocation stage.

# CHAPTER 7. SCHEDULING NUMA-AWARE WORKLOADS

Learn about NUMA-aware scheduling and how you can use it to deploy high performance workloads in an OpenShift Container Platform cluster.

The NUMA Resources Operator allows you to schedule high-performance workloads in the same NUMA zone. It deploys a node resources exporting agent that reports on available cluster node NUMA resources, and a secondary scheduler that manages the workloads.

## 7.1. ABOUT NUMA-AWARE SCHEDULING

#### Introduction to NUMA

Non-Uniform Memory Access (NUMA) is a compute platform architecture that allows different CPUs to access different regions of memory at different speeds. NUMA resource topology refers to the locations of CPUs, memory, and PCI devices relative to each other in the compute node. Colocated resources are said to be in the same *NUMA zone*. For high-performance applications, the cluster needs to process pod workloads in a single NUMA zone.

#### Performance considerations

NUMA architecture allows a CPU with multiple memory controllers to use any available memory across CPU complexes, regardless of where the memory is located. This allows for increased flexibility at the expense of performance. A CPU processing a workload using memory that is outside its NUMA zone is slower than a workload processed in a single NUMA zone. Also, for I/O-constrained workloads, the network interface on a distant NUMA zone slows down how quickly information can reach the application. High-performance workloads, such as telecommunications workloads, cannot operate to specification under these conditions.

# **NUMA-aware scheduling**

NUMA-aware scheduling aligns the requested cluster compute resources (CPUs, memory, devices) in the same NUMA zone to process latency-sensitive or high-performance workloads efficiently. NUMA-aware scheduling also improves pod density per compute node for greater resource efficiency.

#### Integration with Node Tuning Operator

By integrating the Node Tuning Operator's performance profile with NUMA-aware scheduling, you can further configure CPU affinity to optimize performance for latency-sensitive workloads.


#### Default scheduling logic

The default OpenShift Container Platform pod scheduler scheduling logic considers the available resources of the entire compute node, not individual NUMA zones. If the most restrictive resource alignment is requested in the kubelet topology manager, error conditions can occur when admitting the pod to a node. Conversely, if the most restrictive resource alignment is not requested, the pod can be admitted to the node without proper resource alignment, leading to worse or unpredictable performance. For example, runaway pod creation with **Topology Affinity Error** statuses can occur when the pod scheduler makes suboptimal scheduling decisions for guaranteed pod workloads without knowing if the pod's requested resources are available. Scheduling mismatch decisions can cause indefinite pod startup delays. Also, depending on the cluster state and resource allocation, poor pod scheduling decisions can cause extra load on the cluster because of failed startup attempts.

## NUMA-aware pod scheduling diagram

The NUMA Resources Operator deploys a custom NUMA resources secondary scheduler and other resources to mitigate against the shortcomings of the default OpenShift Container Platform pod scheduler. The following diagram provides a high-level overview of NUMA-aware pod scheduling.

Figure 7.1. NUMA-aware scheduling overview



216 OpenShift 0222

### NodeResourceTopology API

The **NodeResourceTopology** API describes the available NUMA zone resources in each compute node.

#### **NUMA-aware scheduler**

The NUMA-aware secondary scheduler receives information about the available NUMA zones from the **NodeResourceTopology** API and schedules high-performance workloads on a node where it can be optimally processed.

#### Node topology exporter

The node topology exporter exposes the available NUMA zone resources for each compute node to the **NodeResourceTopology** API. The node topology exporter daemon tracks the resource allocation from the kubelet by using the **PodResources** API.

#### PodResources API

The **PodResources** API is local to each node and exposes the resource topology and available resources to the kubelet.



#### NOTE

The **List** endpoint of the **PodResources** API exposes exclusive CPUs allocated to a particular container. The API does not expose CPUs that belong to a shared pool.

The **GetAllocatableResources** endpoint exposes allocatable resources available on a node.

### Additional resources

• For more information about running secondary pod schedulers in your cluster and how to deploy pods with a secondary pod scheduler, see Scheduling pods using a secondary scheduler.

# 7.2. INSTALLING THE NUMA RESOURCES OPERATOR

NUMA Resources Operator deploys resources that allow you to schedule NUMA-aware workloads and deployments. You can install the NUMA Resources Operator using the OpenShift Container Platform CLI or the web console.

# 7.2.1. Installing the NUMA Resources Operator using the CLI

As a cluster administrator, you can install the Operator using the CLI.

# **Prerequisites**

- Install the OpenShift CLI (oc).
- Log in as a user with cluster-admin privileges.

#### **Procedure**

- 1. Create a namespace for the NUMA Resources Operator:
  - a. Save the following YAML in the nro-namespace.yaml file:

apiVersion: v1 kind: Namespace

metadata:

name: openshift-numaresources

- b. Create the **Namespace** CR by running the following command:
  - \$ oc create -f nro-namespace.yaml
- 2. Create the Operator group for the NUMA Resources Operator:
  - a. Save the following YAML in the nro-operatorgroup.yaml file:

apiVersion: operators.coreos.com/v1

kind: OperatorGroup

metadata:

name: numaresources-operator

namespace: openshift-numaresources

spec:

targetNamespaces:

- openshift-numaresources
- b. Create the **OperatorGroup** CR by running the following command:
  - \$ oc create -f nro-operatorgroup.yaml
- 3. Create the subscription for the NUMA Resources Operator:
  - a. Save the following YAML in the **nro-sub.yaml** file:

apiVersion: operators.coreos.com/v1alpha1

kind: Subscription

metadata:

name: numaresources-operator namespace: openshift-numaresources

snec:

channel: "4.16"

name: numaresources-operator

source: redhat-operators

sourceNamespace: openshift-marketplace

b. Create the **Subscription** CR by running the following command:

\$ oc create -f nro-sub.yaml

#### Verification

1. Verify that the installation succeeded by inspecting the CSV resource in the **openshift-numaresources** namespace. Run the following command:

\$ oc get csv -n openshift-numaresources

# **Example output**

NAME DISPLAY VERSION REPLACES PHASE numaresources-operator.v4.16.2 numaresources-operator 4.16.2 Succeeded

# 7.2.2. Installing the NUMA Resources Operator using the web console

As a cluster administrator, you can install the NUMA Resources Operator using the web console.

### Procedure

- 1. Create a namespace for the NUMA Resources Operator:
  - a. In the OpenShift Container Platform web console, click **Administration** → **Namespaces**.
  - b. Click **Create Namespace**, enter **openshift-numaresources** in the **Name** field, and then click **Create**.
- 2. Install the NUMA Resources Operator:
  - a. In the OpenShift Container Platform web console, click **Operators** → **OperatorHub**.
  - b. Choose **numaresources-operator** from the list of available Operators, and then click **Install**.
  - c. In the **Installed Namespaces** field, select the **openshift-numaresources** namespace, and then click **Install**.
- 3. Optional: Verify that the NUMA Resources Operator installed successfully:
  - a. Switch to the **Operators** → **Installed Operators** page.
  - b. Ensure that **NUMA Resources Operator** is listed in the **openshift-numaresources** namespace with a **Status** of **InstallSucceeded**.



#### NOTE

During installation an Operator might display a Failed status. If the installation later succeeds with an InstallSucceeded message, you can ignore the Failed message.

If the Operator does not appear as installed, to troubleshoot further:

- Go to the **Operators** → **Installed Operators** page and inspect the **Operator** Subscriptions and Install Plans tabs for any failure or errors under Status.
- Go to the Workloads → Pods page and check the logs for pods in the default project.

# 7.3. SCHEDULING NUMA-AWARE WORKLOADS

Clusters running latency-sensitive workloads typically feature performance profiles that help to minimize workload latency and optimize performance. The NUMA-aware scheduler deploys workloads based on available node NUMA resources and with respect to any performance profile settings applied to the node. The combination of NUMA-aware deployments, and the performance profile of the workload, ensures that workloads are scheduled in a way that maximizes performance.

For the NUMA Resources Operator to be fully operational, you must deploy the **NUMAResourcesOperator** custom resource and the NUMA-aware secondary pod scheduler.

# 7.3.1. Creating the NUMAResourcesOperator custom resource

When you have installed the NUMA Resources Operator, then create the NUMAResourcesOperator custom resource (CR) that instructs the NUMA Resources Operator to install all the cluster infrastructure needed to support the NUMA-aware scheduler, including daemon sets and APIs.

### **Prerequisites**

- Install the OpenShift CLI (oc).
- Log in as a user with **cluster-admin** privileges.
- Install the NUMA Resources Operator.

#### **Procedure**

- 1. Create the **NUMAResourcesOperator** custom resource:
  - a. Save the following minimal required YAML file example as **nrop.yaml**:

apiVersion: nodetopology.openshift.io/v1

kind: NUMAResourcesOperator

metadata:

name: numaresourcesoperator

nodeGroups:

- machineConfigPoolSelector:

matchLabels:

pools.operator.machineconfiguration.openshift.io/worker: "" 1



This should match the **MachineConfigPool** that you want to configure the NUMA Resources Operator on. For example, you might have created a **MachineConfigPool** 

b. Create the **NUMAResourcesOperator** CR by running the following command:

\$ oc create -f nrop.yaml



#### NOTE

Creating the **NUMAResourcesOperator** triggers a reboot on the corresponding machine config pool and therefore the affected node.

#### Verification

- 1. Verify that the NUMA Resources Operator deployed successfully by running the following command:
  - \$ oc get numaresourcesoperators.nodetopology.openshift.io

# **Example output**

NAME AGE numaresourcesoperator 27s

2. After a few minutes, run the following command to verify that the required resources deployed successfully:

\$ oc get all -n openshift-numaresources

## **Example output**

NAME	READY ST	TATUS	RESTART	S AG	iΕ	
pod/numaresources-controller-manage	er-7d9d84c58	3d-qk2m	nr 1/1 Ru	nning	0	12m
pod/numaresourcesoperator-worker-7	'd96r	2/2	Running (	)	97s	
pod/numaresourcesoperator-worker-c	rsht	2/2	Running 0	,	97s	
pod/numaresourcesoperator-worker-jp	o9mw	2/2	Running	0	97s	

# 7.3.2. Deploying the NUMA-aware secondary pod scheduler

After you install the NUMA Resources Operator, do the following to deploy the NUMA-aware secondary pod scheduler:

#### Procedure

- Create the **NUMAResourcesScheduler** custom resource that deploys the NUMA-aware custom pod scheduler:
  - a. Save the following minimal required YAML in the **nro-scheduler.yaml** file:

apiVersion: nodetopology.openshift.io/v1 kind: NUMAResourcesScheduler

metadata:

name: numaresourcesscheduler

snec:

imageSpec: "registry.redhat.io/openshift4/noderesourcetopology-scheduler-rhel9:v4.16"

b. Create the **NUMAResourcesScheduler** CR by running the following command:

\$ oc create -f nro-scheduler.yaml

2. After a few seconds, run the following command to confirm the successful deployment of the required resources:

\$ oc get all -n openshift-numaresources

# Example output

NAME	READY	STATUS	REST	ARTS A	GE	
pod/numaresources-controller-mail	nager-7d9d84	c58d-qk2r	mr 1/1	Running	g 0	12m
pod/numaresourcesoperator-worke		2/2	Runnii	ng 0	97s	
pod/numaresourcesoperator-worke		2/2	Runnin	g 0	97s	
pod/numaresourcesoperator-worke	,,	2/2	Runn	ing 0	97s	
pod/secondary-scheduler-847cb74	lf84-9whlm	1/1	Runr	ning 0	10m	
NAME D	ESIRED CL	JRRENT	READY	UP-TO-E	DATE	
AVAILABLE NODE SELECTOR	P	\GE				
daemonset.apps/numaresourceso	perator-worke	er 3 (	3 3	3	3	node-
role.kubernetes.io/worker= 98s						
NAME	READY U			LABLE A	AGE	
deployment.apps/numaresources-		nager 1/1	1	1	12m	
deployment.apps/secondary-sched	duler	1/1 1	1	10m	1	
NAME			RRENT	READY	AGE	
replicaset.apps/numaresources-co	ntroller-mana	ger-7d9d8	4c58d	1 1	1	12m
replicaset.apps/secondary-schedu	ler-847cb74f8	34	1	1 1	10m	

# 7.3.3. Configuring a single NUMA node policy

The NUMA Resources Operator requires a single NUMA node policy to be configured on the cluster. This can be achieved in two ways: by creating and applying a performance profile, or by configuring a KubeletConfig.



# **NOTE**

The preferred way to configure a single NUMA node policy is to apply a performance profile. You can use the Performance Profile Creator (PPC) tool to create the performance profile. If a performance profile is created on the cluster, it automatically creates other tuning components like **KubeletConfig** and the **tuned** profile.

For more information about creating a performance profile, see "About the Performance Profile Creator" in the "Additional Resources" section.

#### Additional resources

• About the Performance Profile Creator

# 7.3.4. Sample performance profile

This example YAML shows a performance profile created by using the performance profile creator (PPC) tool:

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
 name: performance
spec:
 cpu:
  isolated: "3"
  reserved: 0-2
 machineConfigPoolSelector:
  pools.operator.machineconfiguration.openshift.io/worker: "" 1
 nodeSelector:
  node-role.kubernetes.io/worker: ""
 numa:
  topologyPolicy: single-numa-node 2
 realTimeKernel:
  enabled: true
 workloadHints:
  highPowerConsumption: true
  perPodPowerManagement: false
  realTime: true
```

- This should match the **MachineConfigPool** that you want to configure the NUMA Resources Operator on. For example, you might have created a **MachineConfigPool** named **worker-cnf** that designates a set of nodes that run telecommunications workloads.
- The **topologyPolicy** must be set to **single-numa-node**. Ensure that this is the case by setting the **topology-manager-policy** argument to **single-numa-node** when running the PPC tool.

# 7.3.5. Creating a KubeletConfig CRD

The recommended way to configure a single NUMA node policy is to apply a performance profile. Another way is by creating and applying a **KubeletConfig** custom resource (CR), as shown in the following procedure.

#### Procedure

- 1. Create the **KubeletConfig** custom resource (CR) that configures the pod admittance policy for the machine profile:
  - a. Save the following YAML in the **nro-kubeletconfig.yaml** file:

apiVersion: machineconfiguration.openshift.io/v1 kind: KubeletConfig metadata: name: worker-tuning spec: machineConfigPoolSelector:

matchLabels: pools.operator.machineconfiguration.openshift.io/worker: "" 1 kubeletConfig: cpuManagerPolicy: "static" 2 cpuManagerReconcilePeriod: "5s" reservedSystemCPUs: "0,1" (3) memoryManagerPolicy: "Static" 4 evictionHard: memory.available: "100Mi" kubeReserved: memory: "512Mi" reservedMemory: - numaNode: 0 limits: memory: "1124Mi" systemReserved: memory: "512Mi" topologyManagerPolicy: "single-numa-node" 5

- Adjust this label to match the **machineConfigPoolSelector** in the **NUMAResourcesOperator** CR.
- For cpuManagerPolicy, static must use a lowercase s.
- Adjust this based on the CPU on your nodes.
- For **memoryManagerPolicy**, **Static** must use an uppercase **S**.
- topologyManagerPolicy must be set to single-numa-node.
- b. Create the **KubeletConfig** CR by running the following command:

\$ oc create -f nro-kubeletconfig.yaml



# NOTE

Applying performance profile or **KubeletConfig** automatically triggers rebooting of the nodes. If no reboot is triggered, you can troubleshoot the issue by looking at the labels in **KubeletConfig** that address the node group.

## 7.3.6. Scheduling workloads with the NUMA-aware scheduler

Now that **topo-aware-scheduler** is installed, the **NUMAResourcesOperator** and **NUMAResourcesScheduler** CRs are applied and your cluster has a matching performance profile or **kubeletconfig**, you can schedule workloads with the NUMA-aware scheduler using deployment CRs that specify the minimum required resources to process the workload.

The following example deployment uses NUMA-aware scheduling for a sample workload.

## **Prerequisites**

• Install the OpenShift CLI (oc).

• Log in as a user with **cluster-admin** privileges.

#### **Procedure**

1. Get the name of the NUMA-aware scheduler that is deployed in the cluster by running the following command:

\$ oc get numaresourcesschedulers.nodetopology.openshift.io numaresourcesscheduler -o json | jq '.status.schedulerName'

# **Example output**

"topo-aware-scheduler"

- 2. Create a **Deployment** CR that uses scheduler named **topo-aware-scheduler**, for example:
  - a. Save the following YAML in the **nro-deployment.yaml** file:

```
apiVersion: apps/v1
kind: Deployment
metadata:
 name: numa-deployment-1
 namespace: openshift-numaresources
spec:
 replicas: 1
 selector:
  matchLabels:
   app: test
 template:
  metadata:
   labels:
    app: test
   schedulerName: topo-aware-scheduler 1
   containers:
   - name: ctnr
    image: quay.io/openshifttest/hello-openshift:openshift
    imagePullPolicy: IfNotPresent
    resources:
      limits:
       memory: "100Mi"
       cpu: "10"
      requests:
       memory: "100Mi"
       cpu: "10"
   - name: ctnr2
    image: registry.access.redhat.com/rhel:latest
    imagePullPolicy: IfNotPresent
    command: ["/bin/sh", "-c"]
    args: [ "while true; do sleep 1h; done;" ]
    resources:
      limits:
       memory: "100Mi"
       cpu: "8"
```

requests:

memory: "100Mi"

cpu: "8"



**schedulerName** must match the name of the NUMA-aware scheduler that is deployed in your cluster, for example **topo-aware-scheduler**.

b. Create the **Deployment** CR by running the following command:

\$ oc create -f nro-deployment.yaml

#### Verification

1. Verify that the deployment was successful:

\$ oc get pods -n openshift-numaresources

# **Example output**

NAME	READY	STATUS	S REST	ARTS	AGE	
numa-deployment-1-6c4f5bdb84-	wgn6g	2/2	Runni	ng 0	5m2	<u>2</u> S
numaresources-controller-manage	er-7d9d84c	58d-4v65j	1/1 F	Running	0	18m
numaresourcesoperator-worker-7	d96r	2/2	Running	4	43m	
numaresourcesoperator-worker-c	rsht	2/2	Running	2	43m	
numaresourcesoperator-worker-jp	9mw	2/2	Runnin	g 2	43m	
secondary-scheduler-847cb74f84	-fpncj	1/1	Running	0	18m	

2. Verify that the **topo-aware-scheduler** is scheduling the deployed pod by running the following command:

\$ oc describe pod numa-deployment-1-6c4f5bdb84-wgn6g -n openshift-numaresources

## **Example output**

Events:

Type Reason Age From Message

---- ----- Normal Scheduled 4m45s topo-aware-scheduler Successfully assigned openshift-numaresources/numa-deployment-1-6c4f5bdb84-wgn6g to worker-1



#### NOTE

Deployments that request more resources than is available for scheduling will fail with a **MinimumReplicasUnavailable** error. The deployment succeeds when the required resources become available. Pods remain in the **Pending** state until the required resources are available.

- 3. Verify that the expected allocated resources are listed for the node.
  - a. Identify the node that is running the deployment pod by running the following command:

\$ oc get pods -n openshift-numaresources -o wide

# **Example output**

NAME READY STATUS RESTARTS AGE IP NODE NOMINATED NODE READINESS GATES numa-deployment-1-6c4f5bdb84-wgn6g 0/2 Running 0 82m 10.128.2.50 worker-1 <none> <none>

b. Run the following command with the name of that node that is running the deployment pod.

\$ oc describe noderesourcetopologies.topology.node.k8s.io worker-1

## **Example output**

...

Zones:

Costs:

Name: node-0 Value: 10 Name: node-1 Value: 21 Name: node-0 Resources:

Allocatable: 39
Available: 21 1
Capacity: 40
Name: cpu

Allocatable: 6442450944
Available: 6442450944
Capacity: 6442450944
Name: hugepages-1Gi
Allocatable: 134217728
Available: 134217728
Capacity: 134217728
Name: hugepages-2Mi
Allocatable: 262415904768
Available: 262206189568
Capacity: 270146007040

Name: memory Type: Node

The **Available** capacity is reduced because of the resources that have been allocated to the guaranteed pod.

Resources consumed by guaranteed pods are subtracted from the available node resources listed under **noderesourcetopologies.topology.node.k8s.io**.

4. Resource allocations for pods with a **Best-effort** or **Burstable** quality of service (**qosClass**) are not reflected in the NUMA node resources under

noderesourcetopologies.topology.node.k8s.io. If a pod's consumed resources are not

reflected in the node resource calculation, verify that the pod has **qosClass** of **Guaranteed** and the CPU request is an integer value, not a decimal value. You can verify the that the pod has a **qosClass** of **Guaranteed** by running the following command:

\$ oc get pod numa-deployment-1-6c4f5bdb84-wgn6g -n openshift-numaresources -o jsonpath="{ .status.qosClass }"

# **Example output**

Guaranteed

# 7.4. OPTIONAL: CONFIGURING POLLING OPERATIONS FOR NUMA RESOURCES UPDATES

The daemons controlled by the NUMA Resources Operator in their **nodeGroup** poll resources to retrieve updates about available NUMA resources. You can fine-tune polling operations for these daemons by configuring the **spec.nodeGroups** specification in the **NUMAResourcesOperator** custom resource (CR). This provides advanced control of polling operations. Configure these specifications to improve scheduling behavior and troubleshoot suboptimal scheduling decisions.

The configuration options are the following:

- **infoRefreshMode**: Determines the trigger condition for polling the kubelet. The NUMA Resources Operator reports the resulting information to the API server.
- **infoRefreshPeriod**: Determines the duration between polling updates.
- **podsFingerprinting**: Determines if point-in-time information for the current set of pods running on a node is exposed in polling updates.



#### NOTE

The default value for podsFingerprinting is EnabledExclusiveResources. To optimize scheduler performance, set podsFingerprinting to either EnabledExclusiveResources or Enabled. Additionally, configure the cacheResyncPeriod in the NUMAResourcesScheduler custom resource (CR) to a value greater than 0. The cacheResyncPeriod specification helps to report more exact resource availability by monitoring pending resources on nodes.

## **Prerequisites**

- Install the OpenShift CLI (oc).
- Log in as a user with **cluster-admin** privileges.
- Install the NUMA Resources Operator.

#### **Procedure**

• Configure the **spec.nodeGroups** specification in your **NUMAResourcesOperator** CR:

apiVersion: nodetopology.openshift.io/v1 kind: NUMAResourcesOperator

metadata:

```
name: numaresourcesoperator spec:
nodeGroups:
- config:
infoRefreshMode: Periodic 1
infoRefreshPeriod: 10s 2
podsFingerprinting: Enabled 3
name: worker
```

- Valid values are **Periodic**, **Events**, **PeriodicAndEvents**. Use **Periodic** to poll the kubelet at intervals that you define in **infoRefreshPeriod**. Use **Events** to poll the kubelet at every pod lifecycle event. Use **PeriodicAndEvents** to enable both methods.
- Define the polling interval for **Periodic** or **PeriodicAndEvents** refresh modes. The field is ignored if the refresh mode is **Events**.
- Valid values are **Enabled**, **Disabled**, and **EnabledExclusiveResources**. Setting to **Enabled** or **EnabledExclusiveResources** is a requirement for the **cacheResyncPeriod** specification in the **NUMAResourcesScheduler**.

#### Verification

1. After you deploy the NUMA Resources Operator, verify that the node group configurations were applied by running the following command:

\$ oc get numaresop numaresourcesoperator -o json | jq '.status'

## **Example output**

```
"config": {
    "infoRefreshMode": "Periodic",
    "infoRefreshPeriod": "10s",
    "podsFingerprinting": "Enabled"
},
    "name": "worker"
...
```

## 7.5. TROUBLESHOOTING NUMA-AWARE SCHEDULING

To troubleshoot common problems with NUMA-aware pod scheduling, perform the following steps.

#### **Prerequisites**

- Install the OpenShift Container Platform CLI (oc).
- Log in as a user with cluster-admin privileges.
- Install the NUMA Resources Operator and deploy the NUMA-aware secondary scheduler.

#### **Procedure**

 Verify that the **noderesourcetopologies** CRD is deployed in the cluster by running the following command:

\$ oc get crd | grep noderesourcetopologies

# **Example output**

NAME CREATED AT noderesourcetopologies.topology.node.k8s.io 2022-01-18T08:28:06Z

2. Check that the NUMA-aware scheduler name matches the name specified in your NUMA-aware workloads by running the following command:

\$ oc get numaresourcesschedulers.nodetopology.openshift.io numaresourcesscheduler -o json | jq '.status.schedulerName'

# **Example output**

topo-aware-scheduler

3. Verify that NUMA-aware schedulable nodes have the **noderesourcetopologies** CR applied to them. Run the following command:

\$ oc get noderesourcetopologies.topology.node.k8s.io

# **Example output**

NAME AGE compute-0.example.com 17h compute-1.example.com 17h



## NOTE

The number of nodes should equal the number of worker nodes that are configured by the machine config pool (**mcp**) worker definition.

4. Verify the NUMA zone granularity for all schedulable nodes by running the following command:

\$ oc get noderesourcetopologies.topology.node.k8s.io -o yaml

#### **Example output**

apiVersion: v1

items:

 apiVersion: topology.node.k8s.io/v1 kind: NodeResourceTopology

metadata: annotations:

k8stopoawareschedwg/rte-update: periodic

creationTimestamp: "2022-06-16T08:55:38Z"

generation: 63760 name: worker-0

resourceVersion: "8450223"

uid: 8b77be46-08c0-4074-927b-d49361471590

topologyPolicies:

- SingleNUMANodeContainerLevel

zones:
- costs:

name: node-0 value: 10name: node-1 value: 21name: node-0 resources:

 allocatable: "38" available: "38" capacity: "40" name: cpu

- allocatable: "134217728" available: "134217728" capacity: "134217728" name: hugepages-2Mi

 allocatable: "262352048128" available: "262352048128" capacity: "270107316224"

name: memory

allocatable: "6442450944"
 available: "6442450944"
 capacity: "6442450944"
 name: hugepages-1Gi

type: Node - costs:

name: node-0 value: 21name: node-1 value: 10name: node-1 resources:

- allocatable: "268435456" available: "268435456" capacity: "268435456" name: hugepages-2Mi

 allocatable: "269231067136" available: "269231067136" capacity: "270573244416"

name: memory
- allocatable: "40"
available: "40"
capacity: "40"
name: cpu

 allocatable: "1073741824" available: "1073741824" capacity: "1073741824" name: hugepages-1Gi

type: Node

- apiVersion: topology.node.k8s.io/v1 kind: NodeResourceTopology metadata: annotations: k8stopoawareschedwg/rte-update: periodic creationTimestamp: "2022-06-16T08:55:37Z" generation: 62061 name: worker-1 resourceVersion: "8450129" uid: e8659390-6f8d-4e67-9a51-1ea34bba1cc3 topologyPolicies: - SingleNUMANodeContainerLevel zones: 1 - costs: - name: node-0 value: 10 - name: node-1 value: 21 name: node-0 resources: 2 - allocatable: "38" available: "38" capacity: "40" name: cpu - allocatable: "6442450944" available: "6442450944" capacity: "6442450944" name: hugepages-1Gi - allocatable: "134217728" available: "134217728" capacity: "134217728" name: hugepages-2Mi - allocatable: "262391033856" available: "262391033856" capacity: "270146301952" name: memory type: Node - costs: - name: node-0 value: 21 - name: node-1 value: 10 name: node-1 resources: - allocatable: "40" available: "40" capacity: "40" name: cpu - allocatable: "1073741824" available: "1073741824" capacity: "1073741824" name: hugepages-1Gi - allocatable: "268435456" available: "268435456" capacity: "268435456" name: hugepages-2Mi

 allocatable: "269192085504" available: "269192085504" capacity: "270534262784"

name: memory type: Node kind: List metadata:

resourceVersion: ""

selfLink: ""

- 1 Each stanza under **zones** describes the resources for a single NUMA zone.
- **resources** describes the current state of the NUMA zone resources. Check that resources listed under **items.zones.resources.available** correspond to the exclusive NUMA zone resources allocated to each guaranteed pod.

## 7.5.1. Reporting more exact resource availability

Enable the **cacheResyncPeriod** specification to help the NUMA Resources Operator report more exact resource availability by monitoring pending resources on nodes and synchronizing this information in the scheduler cache at a defined interval. This also helps to minimize Topology Affinity Error errors because of sub-optimal scheduling decisions. The lower the interval, the greater the network load. The **cacheResyncPeriod** specification is disabled by default.

### **Prerequisites**

- Install the OpenShift CLI (oc).
- Log in as a user with **cluster-admin** privileges.

### **Procedure**

- 1. Delete the currently running **NUMAResourcesScheduler** resource:
  - a. Get the active **NUMAResourcesScheduler** by running the following command:

\$ oc get NUMAResourcesScheduler

### Example output

NAME AGE numaresourcesscheduler 92m

b. Delete the secondary scheduler resource by running the following command:

\$ oc delete NUMAResourcesScheduler numaresourcesscheduler

### Example output

numaresourcesscheduler.nodetopology.openshift.io "numaresourcesscheduler" deleted

2. Save the following YAML in the file **nro-scheduler-cacheresync.yaml**. This example changes the log level to **Debug**:

apiVersion: nodetopology.openshift.io/v1

kind: NUMAResourcesScheduler

metadata:

name: numaresourcesscheduler

spec:

imageSpec: "registry.redhat.io/openshift4/noderesourcetopology-scheduler-container-

rhel8:v4.16"

cacheResyncPeriod: "5s" 1

- Enter an interval value in seconds for synchronization of the scheduler cache. A value of **5s** is typical for most implementations.
- 3. Create the updated **NUMAResourcesScheduler** resource by running the following command:

\$ oc create -f nro-scheduler-cacheresync.yaml

## **Example output**

numare sources scheduler. node topology. open shift. io/numare sources scheduler created

### Verification steps

- 1. Check that the NUMA-aware scheduler was successfully deployed:
  - a. Run the following command to check that the CRD is created successfully:

\$ oc get crd | grep numaresourcesschedulers

## **Example output**

NAME CREATED AT numaresourcesschedulers.nodetopology.openshift.io 2022-02-25T11:57:03Z

- b. Check that the new custom scheduler is available by running the following command:
  - \$ oc get numaresourcesschedulers.nodetopology.openshift.io

## **Example output**

NAME AGE numaresourcesscheduler 3h26m

- 2. Check that the logs for the scheduler show the increased log level:
  - a. Get the list of pods running in the **openshift-numaresources** namespace by running the following command:

\$ oc get pods -n openshift-numaresources

## Example output

NAME	READY S	TATUS	REST	ARTS A	.GE	
numaresources-controller-manage	r-d87d79587	'-76mrm	1/1	Running	0	46h
numaresourcesoperator-worker-5w	/m2k	2/2	Runnin	g 0	45h	
numaresourcesoperator-worker-pb	75c	2/2	Running	0	45h	
secondary-scheduler-7976c4d466-	qm4sc	1/1	Runnii	ng 0	21m	

b. Get the logs for the secondary scheduler pod by running the following command:

\$ oc logs secondary-scheduler-7976c4d466-qm4sc -n openshift-numaresources

## **Example output**

```
10223 11:04:55.614788
                           1 reflector.go:535] k8s.io/client-go/informers/factory.go:134:
Watch close - *v1.Namespace total 11 items received
10223 11:04:56.609114
                           1 reflector.go:535] k8s.io/client-go/informers/factory.go:134:
Watch close - *v1.ReplicationController total 10 items received
10223 11:05:22.626818
                           1 reflector.go:535] k8s.io/client-go/informers/factory.go:134:
Watch close - *v1.StorageClass total 7 items received
10223 11:05:31.610356
                           1 reflector.go:535] k8s.io/client-go/informers/factory.go:134:
Watch close - *v1.PodDisruptionBudget total 7 items received
10223 11:05:31.713032
                           1 eventhandlers.go:186] "Add event for scheduled pod"
pod="openshift-marketplace/certified-operators-thtvg"
10223 11:05:53.461016
                           1 eventhandlers.go:244] "Delete event for scheduled pod"
pod="openshift-marketplace/certified-operators-thtvq"
```

# 7.5.2. Checking the NUMA-aware scheduler logs

Troubleshoot problems with the NUMA-aware scheduler by reviewing the logs. If required, you can increase the scheduler log level by modifying the **spec.logLevel** field of the **NUMAResourcesScheduler** resource. Acceptable values are **Normal**, **Debug**, and **Trace**, with **Trace** being the most verbose option.



### NOTE

To change the log level of the secondary scheduler, delete the running scheduler resource and re-deploy it with the changed log level. The scheduler is unavailable for scheduling new workloads during this downtime.

### **Prerequisites**

- Install the OpenShift CLI (oc).
- Log in as a user with **cluster-admin** privileges.

### Procedure

- 1. Delete the currently running **NUMAResourcesScheduler** resource:
  - a. Get the active **NUMAResourcesScheduler** by running the following command:

\$ oc get NUMAResourcesScheduler

## Example output

NAME AGE numaresourcesscheduler 90m

b. Delete the secondary scheduler resource by running the following command:

\$ oc delete NUMAResourcesScheduler numaresourcesscheduler

## Example output

numaresourcesscheduler.nodetopology.openshift.io "numaresourcesscheduler" deleted

2. Save the following YAML in the file **nro-scheduler-debug.yaml**. This example changes the log level to **Debug**:

apiVersion: nodetopology.openshift.io/v1

kind: NUMAResourcesScheduler

metadata:

name: numaresourcesscheduler

spec:

imageSpec: "registry.redhat.io/openshift4/noderesourcetopology-scheduler-container-

rhel8:v4.16" logLevel: Debug

3. Create the updated **Debug** logging **NUMAResourcesScheduler** resource by running the following command:

\$ oc create -f nro-scheduler-debug.yaml

## **Example output**

numaresourcesscheduler.nodetopology.openshift.io/numaresourcesscheduler created

### Verification steps

- 1. Check that the NUMA-aware scheduler was successfully deployed:
  - a. Run the following command to check that the CRD is created successfully:

\$ oc get crd | grep numaresourcesschedulers

### Example output

NAME CREATED AT numaresourcesschedulers.nodetopology.openshift.io 2022-02-25T11:57:03Z

b. Check that the new custom scheduler is available by running the following command:

\$ oc get numaresourcesschedulers.nodetopology.openshift.io

## Example output

NAME AGE numaresourcesscheduler 3h26m

- 2. Check that the logs for the scheduler shows the increased log level:
  - a. Get the list of pods running in the **openshift-numaresources** namespace by running the following command:

\$ oc get pods -n openshift-numaresources

## **Example output**

NAME	READY S	TATUS	RESTA	RTS A	GE	
numaresources-controller-manage	r-d87d79587	7-76mrm	1/1 F	unning	0	46h
numaresourcesoperator-worker-5w	/m2k	2/2	Running	0	45h	
numaresourcesoperator-worker-pb	75c	2/2	Running	0	45h	
secondary-scheduler-7976c4d466-	qm4sc	1/1	Runnin	g 0	21m	

b. Get the logs for the secondary scheduler pod by running the following command:

\$ oc logs secondary-scheduler-7976c4d466-qm4sc -n openshift-numaresources

## **Example output**

10223 11:04:55.614788 1 reflector.go:535] k8s.io/client-go/informers/factory.go:134: Watch close - \*v1.Namespace total 11 items received 10223 11:04:56.609114 1 reflector.go:535] k8s.io/client-go/informers/factory.go:134: Watch close - \*v1.ReplicationController total 10 items received 10223 11:05:22.626818 1 reflector.go:535] k8s.io/client-go/informers/factory.go:134: Watch close - \*v1.StorageClass total 7 items received 10223 11:05:31.610356 1 reflector.go:535] k8s.io/client-go/informers/factory.go:134: Watch close - \*v1.PodDisruptionBudget total 7 items received 10223 11:05:31.713032 1 eventhandlers.go:186] "Add event for scheduled pod" pod="openshift-marketplace/certified-operators-thtvq" 1 eventhandlers.go:244] "Delete event for scheduled pod" 10223 11:05:53.461016 pod="openshift-marketplace/certified-operators-thtvq"

# 7.5.3. Troubleshooting the resource topology exporter

Troubleshoot **noderesourcetopologies** objects where unexpected results are occurring by inspecting the corresponding **resource-topology-exporter** logs.



### NOTE

It is recommended that NUMA resource topology exporter instances in the cluster are named for nodes they refer to. For example, a worker node with the name **worker** should have a corresponding **noderesourcetopologies** object called **worker**.

### **Prerequisites**

- Install the OpenShift CLI (oc).
- Log in as a user with **cluster-admin** privileges.

### Procedure

1. Get the daemonsets managed by the NUMA Resources Operator. Each daemonset has a corresponding **nodeGroup** in the **NUMAResourcesOperator** CR. Run the following command:

\$ oc get numaresourcesoperators.nodetopology.openshift.io numaresourcesoperator -o jsonpath="{.status.daemonsets[0]}"

## **Example output**

- {"name":"numaresourcesoperator-worker","namespace":"openshift-numaresources"}
- 2. Get the label for the daemonset of interest using the value for **name** from the previous step:

\$ oc get ds -n openshift-numaresources numaresourcesoperator-worker -o jsonpath=" {.spec.selector.matchLabels}"

## **Example output**

- {"name":"resource-topology"}
- 3. Get the pods using the **resource-topology** label by running the following command:

\$ oc get pods -n openshift-numaresources -l name=resource-topology -o wide

### **Example output**

```
NAME READY STATUS RESTARTS AGE IP NODE numaresourcesoperator-worker-5wm2k 2/2 Running 0 2d1h 10.135.0.64 compute-0.example.com numaresourcesoperator-worker-pb75c 2/2 Running 0 2d1h 10.132.2.33 compute-1.example.com
```

4. Examine the logs of the **resource-topology-exporter** container running on the worker pod that corresponds to the node you are troubleshooting. Run the following command:

\$ oc logs -n openshift-numaresources -c resource-topology-exporter numaresourcesoperator-worker-pb75c

### Example output

```
1 sysinfo.go:231] cpus: reserved "0-1"
10221 13:38:18.334381
10221 13:38:18.334493
                          1 sysinfo.go:237] cpus: online "0-103"
10221 13:38:18.546750
                          1 main.go:72]
cpus: allocatable "2-103"
hugepages-1Gi:
 numa cell 0 -> 6
 numa cell 1 -> 1
hugepages-2Mi:
 numa cell 0 -> 64
 numa cell 1 -> 128
memory:
 numa cell 0 -> 45758Mi
 numa cell 1 -> 48372Mi
```

## 7.5.4. Correcting a missing resource topology exporter config map

If you install the NUMA Resources Operator in a cluster with misconfigured cluster settings, in some circumstances, the Operator is shown as active but the logs of the resource topology exporter (RTE) daemon set pods show that the configuration for the RTE is missing, for example:

Info: couldn't find configuration in "/etc/resource-topology-exporter/config.yaml"

This log message indicates that the **kubeletconfig** with the required configuration was not properly applied in the cluster, resulting in a missing RTE **configmap**. For example, the following cluster is missing a **numaresourcesoperator-worker configmap** custom resource (CR):

\$ oc get configmap

## **Example output**

```
NAME DATA AGE
0e2a6bd3.openshift-kni.io 0 6d21h
kube-root-ca.crt 1 6d21h
openshift-service-ca.crt 1 6d21h
topo-aware-scheduler-config 1 6d18h
```

In a correctly configured cluster, **oc get configmap** also returns a **numaresourcesoperator-worker configmap** CR.

### **Prerequisites**

- Install the OpenShift Container Platform CLI (oc).
- Log in as a user with cluster-admin privileges.
- Install the NUMA Resources Operator and deploy the NUMA-aware secondary scheduler.

## Procedure

- 1. Compare the values for **spec.machineConfigPoolSelector.matchLabels** in **kubeletconfig** and **metadata.labels** in the **MachineConfigPool** (**mcp**) worker CR using the following commands:
  - a. Check the **kubeletconfig** labels by running the following command:

\$ oc get kubeletconfig -o yaml

## **Example output**

```
machineConfigPoolSelector:
matchLabels:
cnf-worker-tuning: enabled
```

b. Check the mcp labels by running the following command:

\$ oc get mcp worker -o yaml

## **Example output**

```
labels:
```

```
machineconfiguration.openshift.io/mco-built-in: "" pools.operator.machineconfiguration.openshift.io/worker: ""
```

The cnf-worker-tuning: enabled label is not present in the MachineConfigPool object.

2. Edit the **MachineConfigPool** CR to include the missing label, for example:

```
$ oc edit mcp worker -o yaml
```

## **Example output**

```
labels:
```

```
machineconfiguration.openshift.io/mco-built-in: "" pools.operator.machineconfiguration.openshift.io/worker: "" cnf-worker-tuning: enabled
```

3. Apply the label changes and wait for the cluster to apply the updated configuration. Run the following command:

### Verification

Check that the missing numaresourcesoperator-worker configmap CR is applied:

```
$ oc get configmap
```

## Example output

```
NAME DATA AGE

0e2a6bd3.openshift-kni.io 0 6d21h
kube-root-ca.crt 1 6d21h
numaresourcesoperator-worker 1 5m
openshift-service-ca.crt 1 6d21h
topo-aware-scheduler-config 1 6d18h
```

## 7.5.5. Collecting NUMA Resources Operator data

You can use the **oc adm must-gather** CLI command to collect information about your cluster, including features and objects associated with the NUMA Resources Operator.

## **Prerequisites**

- You have access to the cluster as a user with the **cluster-admin** role.
- You have installed the OpenShift CLI (oc).

### Procedure

• To collect NUMA Resources Operator data with **must-gather**, you must specify the NUMA Resources Operator **must-gather** image.

\$ oc adm must-gather --image=registry.redhat.io/numaresources-must-gather/numaresources-must-gather-rhel9:v4.16

# CHAPTER 8. SCALABILITY AND PERFORMANCE OPTIMIZATION

## 8.1. OPTIMIZING STORAGE

Optimizing storage helps to minimize storage use across all resources. By optimizing storage, administrators help ensure that existing storage resources are working in an efficient manner.

# 8.1.1. Available persistent storage options

Understand your persistent storage options so that you can optimize your OpenShift Container Platform environment.

Table 8.1. Available storage options

Storage type	Description	Examples
Block	<ul> <li>Presented to the operating system (OS) as a block device</li> <li>Suitable for applications that need full control of storage and operate at a low level on files bypassing the file system</li> <li>Also referred to as a Storage Area Network (SAN)</li> <li>Non-shareable, which means that only one client at a time can mount an endpoint of this type</li> </ul>	AWS EBS and VMware vSphere support dynamic persistent volume (PV) provisioning natively in the OpenShift Container Platform.
File	<ul> <li>Presented to the OS as a file system export to be mounted</li> <li>Also referred to as Network Attached Storage (NAS)</li> <li>Concurrency, latency, file locking mechanisms, and other capabilities vary widely between protocols, implementations, vendors, and scales.</li> </ul>	RHEL NFS, NetApp NFS <sup>[1]</sup> , and Vendor NFS
Object	<ul> <li>Accessible through a REST API endpoint</li> <li>Configurable for use in the OpenShift image registry</li> <li>Applications must build their drivers into the application and/or container.</li> </ul>	AWS S3

1. NetApp NFS supports dynamic PV provisioning when using the Trident plugin.

## 8.1.2. Recommended configurable storage technology

The following table summarizes the recommended and configurable storage technologies for the given OpenShift Container Platform cluster application.

Table 8.2. Recommended and configurable storage technology

Storage type	Block	File	Object
ROX <sup>1</sup>	Yes <sup>4</sup>	Yes <sup>4</sup>	Yes
RWX <sup>2</sup>	No	Yes	Yes
Registry	Configurable	Configurable	Recommended
Scaled registry	Not configurable	Configurable	Recommended
Metrics <sup>3</sup>	Recommended	Configurable <sup>5</sup>	Not configurable
Elasticsearch Logging	Recommended	Configurable <sup>6</sup>	Not supported <sup>6</sup>
Loki Logging	Not configurable	Not configurable	Recommended
Apps	Recommended	Recommended	Not configurable <sup>7</sup>

## <sup>1</sup>ReadOnlyMany

## <sup>2</sup> ReadWriteMany

<sup>&</sup>lt;sup>3</sup> Prometheus is the underlying technology used for metrics.

<sup>&</sup>lt;sup>4</sup> This does not apply to physical disk, VM physical disk, VMDK, loopback over NFS, AWS EBS, and Azure Disk.

<sup>&</sup>lt;sup>5</sup> For metrics, using file storage with the **ReadWriteMany** (RWX) access mode is unreliable. If you use file storage, do not configure the RWX access mode on any persistent volume claims (PVCs) that are configured for use with metrics.

<sup>&</sup>lt;sup>6</sup> For logging, review the recommended storage solution in Configuring persistent storage for the log store section. Using NFS storage as a persistent volume or through NAS, such as Gluster, can corrupt the data. Hence, NFS is not supported for Elasticsearch storage and LokiStack log store in OpenShift Container Platform Logging. You must use one persistent volume type per log store.

<sup>&</sup>lt;sup>7</sup> Object storage is not consumed through OpenShift Container Platform's PVs or PVCs. Apps must integrate with the object storage REST API.



### **NOTE**

A scaled registry is an OpenShift image registry where two or more pod replicas are running.

## 8.1.2.1. Specific application storage recommendations



### **IMPORTANT**

Testing shows issues with using the NFS server on Red Hat Enterprise Linux (RHEL) as a storage backend for core services. This includes the OpenShift Container Registry and Quay, Prometheus for monitoring storage, and Elasticsearch for logging storage. Therefore, using RHEL NFS to back PVs used by core services is not recommended.

Other NFS implementations in the marketplace might not have these issues. Contact the individual NFS implementation vendor for more information on any testing that was possibly completed against these OpenShift Container Platform core components.

# 8.1.2.1.1. Registry

In a non-scaled/high-availability (HA) OpenShift image registry cluster deployment:

- The storage technology does not have to support RWX access mode.
- The storage technology must ensure read-after-write consistency.
- The preferred storage technology is object storage followed by block storage.
- File storage is not recommended for OpenShift image registry cluster deployment with production workloads.

# 8.1.2.1.2. Scaled registry

In a scaled/HA OpenShift image registry cluster deployment:

- The storage technology must support RWX access mode.
- The storage technology must ensure read-after-write consistency.
- The preferred storage technology is object storage.
- Red Hat OpenShift Data Foundation (ODF), Amazon Simple Storage Service (Amazon S3), Google Cloud Storage (GCS), Microsoft Azure Blob Storage, and OpenStack Swift are supported.
- Object storage should be S3 or Swift compliant.
- For non-cloud platforms, such as vSphere and bare metal installations, the only configurable technology is file storage.
- Block storage is not configurable.
- The use of Network File System (NFS) storage with OpenShift Container Platform is supported. However, the use of NFS storage with a scaled registry can cause known issues. For more information, see the Red Hat Knowledgebase solution, Is NFS supported for OpenShift cluster internal components in Production?.

### 8.1.2.1.3. Metrics

In an OpenShift Container Platform hosted metrics cluster deployment:

- The preferred storage technology is block storage.
- Object storage is not configurable.



### **IMPORTANT**

It is not recommended to use file storage for a hosted metrics cluster deployment with production workloads.

## 8.1.2.1.4. Logging

In an OpenShift Container Platform hosted logging cluster deployment:

- Loki Operator:
  - The preferred storage technology is S3 compatible Object storage.
  - Block storage is not configurable.
- OpenShift Elasticsearch Operator:
  - The preferred storage technology is block storage.
  - Object storage is not supported.



## NOTE

As of logging version 5.4.3 the OpenShift Elasticsearch Operator is deprecated and is planned to be removed in a future release. Red Hat will provide bug fixes and support for this feature during the current release lifecycle, but this feature will no longer receive enhancements and will be removed. As an alternative to using the OpenShift Elasticsearch Operator to manage the default log storage, you can use the Loki Operator.

## 8.1.2.1.5. Applications

Application use cases vary from application to application, as described in the following examples:

- Storage technologies that support dynamic PV provisioning have low mount time latencies, and are not tied to nodes to support a healthy cluster.
- Application developers are responsible for knowing and understanding the storage requirements for their application, and how it works with the provided storage to ensure that issues do not occur when an application scales or interacts with the storage layer.

## 8.1.2.2. Other specific application storage recommendations



### **IMPORTANT**

It is not recommended to use RAID configurations on **Write** intensive workloads, such as **etcd**. If you are running **etcd** with a RAID configuration, you might be at risk of encountering performance issues with your workloads.

- Red Hat OpenStack Platform (RHOSP) Cinder: RHOSP Cinder tends to be adept in ROX access mode use cases.
- Databases: Databases (RDBMSs, NoSQL DBs, etc.) tend to perform best with dedicated block storage.
- The etcd database must have enough storage and adequate performance capacity to enable a large cluster. Information about monitoring and benchmarking tools to establish ample storage and a high-performance environment is described in *Recommended etcd practices*.

# 8.1.3. Data storage management

The following table summarizes the main directories that OpenShift Container Platform components write data to.

Table 8.3. Main directories for storing OpenShift Container Platform data

Directory	Notes	Sizing	Expected growth
/var/lib/etcd	Used for etcd storage when storing the database.	Less than 20 GB.  Database can grow up to 8 GB.	Will grow slowly with the environment. Only storing metadata.  Additional 20-25 GB for every additional 8 GB of memory.
/var/lib/containers	This is the mount point for the CRI-O runtime. Storage used for active container runtimes, including pods, and storage of local images. Not used for registry storage.	50 GB for a node with 16 GB memory. Note that this sizing should not be used to determine minimum cluster requirements.  Additional 20-25 GB for every additional 8 GB of memory.	Growth is limited by capacity for running containers.
/var/log	Log files for all components.	10 to 30 GB.	Log files can grow quickly; size can be managed by growing disks or by using log rotate.

Directory	Notes	Sizing	Expected growth
/var/lib/kubelet	Ephemeral volume storage for pods. This includes anything external that is mounted into a container at runtime. Includes environment variables, kube secrets, and data volumes not backed by persistent volumes.	Varies	Minimal if pods requiring storage are using persistent volumes. If using ephemeral storage, this can grow quickly.
/var/log	Log files for all components.	10 to 30 GB.	Log files can grow quickly; size can be managed by growing disks or by using log rotate.

## 8.1.4. Optimizing storage performance for Microsoft Azure

OpenShift Container Platform and Kubernetes are sensitive to disk performance, and faster storage is recommended, particularly for etcd on the control plane nodes.

For production Azure clusters and clusters with intensive workloads, the virtual machine operating system disk for control plane machines should be able to sustain a tested and recommended minimum throughput of 5000 IOPS / 200MBps. This throughput can be provided by having a minimum of 1 TiB Premium SSD (P30). In Azure and Azure Stack Hub, disk performance is directly dependent on SSD disk sizes. To achieve the throughput supported by a **Standard\_D8s\_v3** virtual machine, or other similar machine types, and the target of 5000 IOPS, at least a P30 disk is required.

Host caching must be set to **ReadOnly** for low latency and high IOPS and throughput when reading data. Reading data from the cache, which is present either in the VM memory or in the local SSD disk, is much faster than reading from the disk, which is in the blob storage.

## 8.1.5. Additional resources

Configuring the Elasticsearch log store

### 8.2. OPTIMIZING ROUTING

The OpenShift Container Platform HAProxy router can be scaled or configured to optimize performance.

## 8.2.1. Baseline Ingress Controller (router) performance

The OpenShift Container Platform Ingress Controller, or router, is the ingress point for ingress traffic for applications and services that are configured using routes and ingresses.

When evaluating a single HAProxy router performance in terms of HTTP requests handled per second, the performance varies depending on many factors. In particular:

- HTTP keep-alive/close mode
- Route type
- TLS session resumption client support
- Number of concurrent connections per target route
- Number of target routes
- Back end server page size
- Underlying infrastructure (network/SDN solution, CPU, and so on)

While performance in your specific environment will vary, Red Hat lab tests on a public cloud instance of size 4 vCPU/16GB RAM. A single HAProxy router handling 100 routes terminated by backends serving 1kB static pages is able to handle the following number of transactions per second.

In HTTP keep-alive mode scenarios:

Encryption	LoadBalancerService	HostNetwork
none	21515	29622
edge	16743	22913
passthrough	36786	53295
re-encrypt	21583	25198

In HTTP close (no keep-alive) scenarios:

Encryption	LoadBalancerService	HostNetwork
none	5719	8273
edge	2729	4069
passthrough	4121	5344
re-encrypt	2320	2941

The default Ingress Controller configuration was used with the **spec.tuningOptions.threadCount** field set to **4**. Two different endpoint publishing strategies were tested: Load Balancer Service and Host Network. TLS session resumption was used for encrypted routes. With HTTP keep-alive, a single HAProxy router is capable of saturating a 1 Gbit NIC at page sizes as small as 8 kB.

When running on bare metal with modern processors, you can expect roughly twice the performance of the public cloud instance above. This overhead is introduced by the virtualization layer in place on public clouds and holds mostly true for private cloud-based virtualization as well. The following table is a guide to how many applications to use behind the router:

Number of applications	Application type
5-10	static file/web server or caching proxy
100-1000	applications generating dynamic content

In general, HAProxy can support routes for up to 1000 applications, depending on the technology in use. Ingress Controller performance might be limited by the capabilities and performance of the applications behind it, such as language or static versus dynamic content.

Ingress, or router, sharding should be used to serve more routes towards applications and help horizontally scale the routing tier.

For more information on Ingress sharding, see Configuring Ingress Controller sharding by using route labels and Configuring Ingress Controller sharding by using namespace labels.

You can modify the Ingress Controller deployment using the information provided in Setting Ingress Controller thread count for threads and Ingress Controller configuration parameters for timeouts, and other tuning configurations in the Ingress Controller specification.

# 8.2.2. Configuring Ingress Controller liveness, readiness, and startup probes

Cluster administrators can configure the timeout values for the kubelet's liveness, readiness, and startup probes for router deployments that are managed by the OpenShift Container Platform Ingress Controller (router). The liveness and readiness probes of the router use the default timeout value of 1 second, which is too brief when networking or runtime performance is severely degraded. Probe timeouts can cause unwanted router restarts that interrupt application connections. The ability to set larger timeout values can reduce the risk of unnecessary and unwanted restarts.

You can update the **timeoutSeconds** value on the **livenessProbe**, **readinessProbe**, and **startupProbe** parameters of the router container.

Parameter	Description
livenessProbe	The <b>livenessProbe</b> reports to the kubelet whether a pod is dead and needs to be restarted.
readinessProbe	The <b>readinessProbe</b> reports whether a pod is healthy or unhealthy. When the readiness probe reports an unhealthy pod, then the kubelet marks the pod as not ready to accept traffic. Subsequently, the endpoints for that pod are marked as not ready, and this status propagates to the kube-proxy. On cloud platforms with a configured load balancer, the kube-proxy communicates to the cloud load-balancer not to send traffic to the node with that pod.
startupProbe	The <b>startupProbe</b> gives the router pod up to 2 minutes to initialize before the kubelet begins sending the router liveness and readiness probes. This initialization time can prevent routers with many routes or endpoints from prematurely restarting.



### **IMPORTANT**

The timeout configuration option is an advanced tuning technique that can be used to work around issues. However, these issues should eventually be diagnosed and possibly a support case or Jira issue opened for any issues that causes probes to time out.

The following example demonstrates how you can directly patch the default router deployment to set a 5-second timeout for the liveness and readiness probes:

\$ oc -n openshift-ingress patch deploy/router-default --type=strategic --patch='{"spec":{"template": {"spec":{"router","livenessProbe":{"timeoutSeconds":5},"readinessProbe": {"timeoutSeconds":5}}]}}}

### Verification

\$ oc -n openshift-ingress describe deploy/router-default | grep -e Liveness: -e Readiness: Liveness: http-get http://:1936/healthz delay=0s timeout=5s period=10s #success=1 #failure=3 Readiness: http-get http://:1936/healthz/ready delay=0s timeout=5s period=10s #success=1 #failure=3

# 8.2.3. Configuring HAProxy reload interval

When you update a route or an endpoint associated with a route, the OpenShift Container Platform router updates the configuration for HAProxy. Then, HAProxy reloads the updated configuration for those changes to take effect. When HAProxy reloads, it generates a new process that handles new connections using the updated configuration.

HAProxy keeps the old process running to handle existing connections until those connections are all closed. When old processes have long-lived connections, these processes can accumulate and consume resources.

The default minimum HAProxy reload interval is five seconds. You can configure an Ingress Controller using its **spec.tuningOptions.reloadInterval** field to set a longer minimum reload interval.



### WARNING

Setting a large value for the minimum HAProxy reload interval can cause latency in observing updates to routes and their endpoints. To lessen the risk, avoid setting a value larger than the tolerable latency for updates.

### Procedure

• Change the minimum HAProxy reload interval of the default Ingress Controller to 15 seconds by running the following command:

\$ oc -n openshift-ingress-operator patch ingresscontrollers/default --type=merge --patch='{"spec":{"tuningOptions":{"reloadInterval":"15s"}}}'

## 8.3. OPTIMIZING NETWORKING

The OpenShift SDN uses OpenvSwitch, virtual extensible LAN (VXLAN) tunnels, OpenFlow rules, and iptables. This network can be tuned by using jumbo frames, multi-queue, and ethtool settings.

OVN-Kubernetes uses Generic Network Virtualization Encapsulation (Geneve) instead of VXLAN as the tunnel protocol. This network can be tuned by using network interface controller (NIC) offloads.

VXLAN provides benefits over VLANs, such as an increase in networks from 4096 to over 16 million, and layer 2 connectivity across physical networks. This allows for all pods behind a service to communicate with each other, even if they are running on different systems.

VXLAN encapsulates all tunneled traffic in user datagram protocol (UDP) packets. However, this leads to increased CPU utilization. Both these outer- and inner-packets are subject to normal checksumming rules to guarantee data is not corrupted during transit. Depending on CPU performance, this additional processing overhead can cause a reduction in throughput and increased latency when compared to traditional, non-overlay networks.

Cloud, VM, and bare metal CPU performance can be capable of handling much more than one Gbps network throughput. When using higher bandwidth links such as 10 or 40 Gbps, reduced performance can occur. This is a known issue in VXLAN-based environments and is not specific to containers or OpenShift Container Platform. Any network that relies on VXLAN tunnels will perform similarly because of the VXLAN implementation.

If you are looking to push beyond one Gbps, you can:

- Evaluate network plugins that implement different routing techniques, such as border gateway protocol (BGP).
- Use VXLAN-offload capable network adapters. VXLAN-offload moves the packet checksum
  calculation and associated CPU overhead off of the system CPU and onto dedicated hardware
  on the network adapter. This frees up CPU cycles for use by pods and applications, and allows
  users to utilize the full bandwidth of their network infrastructure.

VXLAN-offload does not reduce latency. However, CPU utilization is reduced even in latency tests.

## 8.3.1. Optimizing the MTU for your network

There are two important maximum transmission units (MTUs): the network interface controller (NIC) MTU and the cluster network MTU.

The NIC MTU is only configured at the time of OpenShift Container Platform installation. The MTU must be less than or equal to the maximum supported value of the NIC of your network. If you are optimizing for throughput, choose the largest possible value. If you are optimizing for lowest latency, choose a lower value.

The OpenShift SDN network plugin overlay MTU must be less than the NIC MTU by 50 bytes at a minimum. This accounts for the SDN overlay header. So, on a normal ethernet network, this should be set to **1450**. On a jumbo frame ethernet network, this should be set to **8950**. These values should be set automatically by the Cluster Network Operator based on the NIC's configured MTU. Therefore, cluster administrators do not typically update these values. Amazon Web Services (AWS) and bare-metal environments support jumbo frame ethernet networks. This setting will help throughput, especially with transmission control protocol (TCP).



### **NOTE**

OpenShift SDN CNI is deprecated as of OpenShift Container Platform 4.14. As of OpenShift Container Platform 4.15, the network plugin is not an option for new installations. In a subsequent future release, the OpenShift SDN network plugin is planned to be removed and no longer supported. Red Hat will provide bug fixes and support for this feature until it is removed, but this feature will no longer receive enhancements. As an alternative to OpenShift SDN CNI, you can use OVN Kubernetes CNI instead.

For OVN and Geneve, the MTU must be less than the NIC MTU by 100 bytes at a minimum.



### NOTE

This 50 byte overlay header is relevant to the OpenShift SDN network plugin. Other SDN solutions might require the value to be more or less.

## 8.3.2. Recommended practices for installing large scale clusters

When installing large clusters or scaling the cluster to larger node counts, set the cluster network **cidr** accordingly in your **install-config.yaml** file before you install the cluster:

networking:

clusterNetwork:

cidr: 10.128.0.0/14 hostPrefix: 23 machineNetwork:cidr: 10.0.0.0/16

networkType: OVNKubernetes

serviceNetwork: - 172.30.0.0/16

The default cluster network **cidr 10.128.0.0/14** cannot be used if the cluster size is more than 500 nodes. It must be set to **10.128.0.0/12** or **10.128.0.0/10** to get to larger node counts beyond 500 nodes.

## 8.3.3. Impact of IPsec

Because encrypting and decrypting node hosts uses CPU power, performance is affected both in throughput and CPU usage on the nodes when encryption is enabled, regardless of the IP security system being used.

IPSec encrypts traffic at the IP payload level, before it hits the NIC, protecting fields that would otherwise be used for NIC offloading. This means that some NIC acceleration features might not be usable when IPSec is enabled and will lead to decreased throughput and increased CPU usage.

### 8.3.4. Additional resources

- Specifying advanced network configuration
- Configuration parameters for the OVN-Kubernetes network plugin
- Configuration parameters for the OpenShift SDN network plugin
- Improving cluster stability in high latency environments using worker latency profiles

# 8.4. OPTIMIZING CPU USAGE WITH MOUNT NAMESPACE ENCAPSULATION

You can optimize CPU usage in OpenShift Container Platform clusters by using mount namespace encapsulation to provide a private namespace for kubelet and CRI-O processes. This reduces the cluster CPU resources used by systemd with no difference in functionality.



### **IMPORTANT**

Mount namespace encapsulation is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see Technology Preview Features Support Scope.


## 8.4.1. Encapsulating mount namespaces

Mount namespaces are used to isolate mount points so that processes in different namespaces cannot view each others' files. Encapsulation is the process of moving Kubernetes mount namespaces to an alternative location where they will not be constantly scanned by the host operating system.

The host operating system uses systemd to constantly scan all mount namespaces: both the standard Linux mounts and the numerous mounts that Kubernetes uses to operate. The current implementation of kubelet and CRI-O both use the top-level namespace for all container runtime and kubelet mount points. However, encapsulating these container-specific mount points in a private namespace reduces systemd overhead with no difference in functionality. Using a separate mount namespace for both CRI-O and kubelet can encapsulate container-specific mounts from any systemd or other host operating system interaction.

This ability to potentially achieve major CPU optimization is now available to all OpenShift Container Platform administrators. Encapsulation can also improve security by storing Kubernetes-specific mount points in a location safe from inspection by unprivileged users.

The following diagrams illustrate a Kubernetes installation before and after encapsulation. Both scenarios show example containers which have mount propagation settings of bidirectional, host-to-container, and none.




290\_OpenShift\_1122

Here we see systemd, host operating system processes, kubelet, and the container runtime sharing a single mount namespace.

- systemd, host operating system processes, kubelet, and the container runtime each have access to and visibility of all mount points.
- Container 1, configured with bidirectional mount propagation, can access systemd and host mounts, kubelet and CRI-O mounts. A mount originating in Container 1, such as /run/a is visible to systemd, host operating system processes, kubelet, container runtime, and other containers with host-to-container or bidirectional mount propagation configured (as in Container 2).
- Container 2, configured with host-to-container mount propagation, can access systemd and host mounts, kubelet and CRI-O mounts. A mount originating in Container 2, such as /run/b, is not visible to any other context.
- Container 3, configured with no mount propagation, has no visibility of external mount points. A mount originating in Container 3, such as /run/c, is not visible to any other context.

The following diagram illustrates the system state after encapsulation.



290\_OpenShift\_1122

- The main systemd process is no longer devoted to unnecessary scanning of Kubernetesspecific mount points. It only monitors systemd-specific and host mount points.
- The host operating system processes can access only the systemd and host mount points.
- Using a separate mount namespace for both CRI-O and kubelet completely separates all container-specific mounts away from any systemd or other host operating system interaction whatsoever.
- The behavior of Container 1 is unchanged, except a mount it creates such as /run/a is no longer visible to systemd or host operating system processes. It is still visible to kubelet, CRI-O, and other containers with host-to-container or bidirectional mount propagation configured (like Container 2).
- The behavior of Container 2 and Container 3 is unchanged.

# 8.4.2. Configuring mount namespace encapsulation

You can configure mount namespace encapsulation so that a cluster runs with less resource overhead.



### NOTE

Mount namespace encapsulation is a Technology Preview feature and it is disabled by default. To use it, you must enable the feature manually.

## **Prerequisites**

- You have installed the OpenShift CLI (oc).
- You have logged in as a user with **cluster-admin** privileges.

### **Procedure**

1. Create a file called **mount\_namespace\_config.yaml** with the following YAML:

```
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
 labels:
  machineconfiguration.openshift.io/role: master
 name: 99-kubens-master
spec:
 config:
  ignition:
   version: 3.2.0
  systemd:
   units:
   - enabled: true
    name: kubens.service
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
 labels:
  machineconfiguration.openshift.io/role: worker
 name: 99-kubens-worker
spec:
 config:
  ignition:
   version: 3.2.0
  systemd:
   units:
   - enabled: true
     name: kubens.service
```

2. Apply the mount namespace **MachineConfig** CR by running the following command:

## **Example output**

machineconfig.machineconfiguration.openshift.io/99-kubens-master created machineconfig.machineconfiguration.openshift.io/99-kubens-worker created

3. The **MachineConfig** CR can take up to 30 minutes to finish being applied in the cluster. You can check the status of the **MachineConfig** CR by running the following command:

\$ oc get mcp

## **Example output**

```
NAME CONFIG UPDATED UPDATING DEGRADED MACHINECOUNT READYMACHINECOUNT UPDATEDMACHINECOUNT DEGRADEDMACHINECOUNT AGE master rendered-master-03d4bc4befb0f4ed3566a2c8f7636751 False True False 3 0 0 0 45m worker rendered-worker-10577f6ab0117ed1825f8af2ac687ddf False True False 3 1 1
```

4. Wait for the **MachineConfig** CR to be applied successfully across all control plane and worker nodes after running the following command:

\$ oc wait --for=condition=Updated mcp --all --timeout=30m

## **Example output**

machineconfigpool.machineconfiguration.openshift.io/master condition met machineconfigpool.machineconfiguration.openshift.io/worker condition met

### Verification

To verify encapsulation for a cluster host, run the following commands:

1. Open a debug shell to the cluster host:

\$ oc debug node/<node\_name>

2. Open a chroot session:

sh-4.4# chroot /host

3. Check the systemd mount namespace:

sh-4.4# readlink /proc/1/ns/mnt

## **Example output**

mnt:[4026531953]

4. Check kubelet mount namespace:

sh-4.4# readlink /proc/\$(pgrep kubelet)/ns/mnt

### Example output

mnt:[4026531840]

5. Check the CRI-O mount namespace:

sh-4.4# readlink /proc/\$(pgrep crio)/ns/mnt

## **Example output**

mnt:[4026531840]

These commands return the mount namespaces associated with systemd, kubelet, and the container runtime. In OpenShift Container Platform, the container runtime is CRI-O.

Encapsulation is in effect if systemd is in a different mount namespace to kubelet and CRI-O as in the above example. Encapsulation is not in effect if all three processes are in the same mount namespace.

# 8.4.3. Inspecting encapsulated namespaces

You can inspect Kubernetes-specific mount points in the cluster host operating system for debugging or auditing purposes by using the **kubensenter** script that is available in Red Hat Enterprise Linux CoreOS (RHCOS).

SSH shell sessions to the cluster host are in the default namespace. To inspect Kubernetes-specific mount points in an SSH shell prompt, you need to run the **kubensenter** script as root. The **kubensenter** script is aware of the state of the mount encapsulation, and is safe to run even if encapsulation is not enabled.



### **NOTE**

**oc debug** remote shell sessions start inside the Kubernetes namespace by default. You do not need to run **kubensenter** to inspect mount points when you use **oc debug**.

If the encapsulation feature is not enabled, the **kubensenter findmnt** and **findmnt** commands return the same output, regardless of whether they are run in an **oc debug** session or in an SSH shell prompt.

### **Prerequisites**

- You have installed the OpenShift CLI (oc).
- You have logged in as a user with **cluster-admin** privileges.
- You have configured SSH access to the cluster host.

## Procedure

1. Open a remote SSH shell to the cluster host. For example:

\$ ssh core@<node\_name>

2. Run commands using the provided **kubensenter** script as the root user. To run a single command inside the Kubernetes namespace, provide the command and any arguments to the **kubensenter** script. For example, to run the **findmnt** command inside the Kubernetes namespace, run the following command:

[core@control-plane-1 ~]\$ sudo kubensenter findmnt

## **Example output**

3. To start a new interactive shell inside the Kubernetes namespace, run the **kubensenter** script without any arguments:

[core@control-plane-1 ~]\$ sudo kubensenter

## **Example output**

kubensenter: Autodetect: kubens.service namespace found at /run/kubens/mnt

# 8.4.4. Running additional services in the encapsulated namespace

Any monitoring tool that relies on the ability to run in the host operating system and have visibility of mount points created by kubelet, CRI-O, or containers themselves, must enter the container mount namespace to see these mount points. The **kubensenter** script that is provided with OpenShift Container Platform executes another command inside the Kubernetes mount point and can be used to adapt any existing tools.

The **kubensenter** script is aware of the state of the mount encapsulation feature status, and is safe to run even if encapsulation is not enabled. In that case the script executes the provided command in the default mount namespace.

For example, if a systemd service needs to run inside the new Kubernetes mount namespace, edit the service file and use the **ExecStart=** command line with **kubensenter**.

[Unit]
Description=Example service
[Service]
ExecStart=/usr/bin/kubensenter /path/to/original/command arg1 arg2

### 8.4.5. Additional resources

- What are namespaces
- Manage containers in namespaces by using nsenter
- MachineConfig

## **CHAPTER 9. MANAGING BARE METAL HOSTS**

When you install OpenShift Container Platform on a bare metal cluster, you can provision and manage bare metal nodes using **machine** and **machineset** custom resources (CRs) for bare metal hosts that exist in the cluster.

## 9.1. ABOUT BARE METAL HOSTS AND NODES

To provision a Red Hat Enterprise Linux CoreOS (RHCOS) bare metal host as a node in your cluster, first create a **MachineSet** custom resource (CR) object that corresponds to the bare metal host hardware. Bare metal host compute machine sets describe infrastructure components specific to your configuration. You apply specific Kubernetes labels to these compute machine sets and then update the infrastructure components to run on only those machines.

**Machine** CR's are created automatically when you scale up the relevant **MachineSet** containing a **metal3.io/autoscale-to-hosts** annotation. OpenShift Container Platform uses **Machine** CR's to provision the bare metal node that corresponds to the host as specified in the **MachineSet** CR.

## 9.2. MAINTAINING BARE METAL HOSTS

You can maintain the details of the bare metal hosts in your cluster from the OpenShift Container Platform web console. Navigate to **Compute** → **Bare Metal Hosts**, and select a task from the **Actions** drop down menu. Here you can manage items such as BMC details, boot MAC address for the host, enable power management, and so on. You can also review the details of the network interfaces and drives for the host.

You can move a bare metal host into maintenance mode. When you move a host into maintenance mode, the scheduler moves all managed workloads off the corresponding bare metal node. No new workloads are scheduled while in maintenance mode.

You can deprovision a bare metal host in the web console. Deprovisioning a host does the following actions:

- 1. Annotates the bare metal host CR with cluster.k8s.io/delete-machine: true
- 2. Scales down the related compute machine set



### **NOTE**

Powering off the host without first moving the daemon set and unmanaged static pods to another node can cause service disruption and loss of data.

### Additional resources

Adding compute machines to bare metal

# 9.2.1. Adding a bare metal host to the cluster using the web console

You can add bare metal hosts to the cluster in the web console.

### **Prerequisites**

• Install an RHCOS cluster on bare metal.

• Log in as a user with **cluster-admin** privileges.

### **Procedure**

- 1. In the web console, navigate to Compute → Bare Metal Hosts.
- 2. Select Add Host → New with Dialog.
- 3. Specify a unique name for the new bare metal host.
- 4. Set the **Boot MAC address**.
- 5. Set the Baseboard Management Console (BMC) Address
- 6. Enter the user credentials for the host's baseboard management controller (BMC).
- 7. Select to power on the host after creation, and select **Create**.
- 8. Scale up the number of replicas to match the number of available bare metal hosts. Navigate to **Compute** → **MachineSets**, and increase the number of machine replicas in the cluster by selecting **Edit Machine count** from the **Actions** drop-down menu.



### **NOTE**

You can also manage the number of bare metal nodes using the **oc scale** command and the appropriate bare metal compute machine set.

# 9.2.2. Adding a bare metal host to the cluster using YAML in the web console

You can add bare metal hosts to the cluster in the web console using a YAML file that describes the bare metal host.

## **Prerequisites**

- Install a RHCOS compute machine on bare metal infrastructure for use in the cluster.
- Log in as a user with **cluster-admin** privileges.
- Create a **Secret** CR for the bare metal host.

### Procedure

- 1. In the web console, navigate to **Compute** → **Bare Metal Hosts**.
- 2. Select Add Host → New from YAML.
- 3. Copy and paste the below YAML, modifying the relevant fields with the details of your host:

apiVersion: metal3.io/v1alpha1 kind: BareMetalHost metadata: name: <bare\_metal\_host\_name> spec: online: true bmc: address: <br/> <br/> address>

credentialsName: <secret\_credentials\_name> 1



bootMACAddress: <host\_boot\_mac\_address>

- credentialsName must reference a valid Secret CR. The baremetal-operator cannot manage the bare metal host without a valid Secret referenced in the credentialsName. For more information about secrets and how to create them, see Understanding secrets.
- 2 Setting **disableCertificateVerification** to **true** disables TLS host validation between the cluster and the baseboard management controller (BMC).
- 4. Select Create to save the YAML and create the new bare metal host.
- Scale up the number of replicas to match the number of available bare metal hosts. Navigate to
   Compute → MachineSets, and increase the number of machines in the cluster by selecting Edit
   Machine count from the Actions drop-down menu.



### NOTE

You can also manage the number of bare metal nodes using the **oc scale** command and the appropriate bare metal compute machine set.

# 9.2.3. Automatically scaling machines to the number of available bare metal hosts

To automatically create the number of **Machine** objects that matches the number of available **BareMetalHost** objects, add a **metal3.io/autoscale-to-hosts** annotation to the **MachineSet** object.

### **Prerequisites**

- Install RHCOS bare metal compute machines for use in the cluster, and create corresponding **BareMetalHost** objects.
- Install the OpenShift Container Platform CLI (oc).
- Log in as a user with **cluster-admin** privileges.

### **Procedure**

 Annotate the compute machine set that you want to configure for automatic scaling by adding the metal3.io/autoscale-to-hosts annotation. Replace <machineset> with the name of the compute machine set.

\$ oc annotate machineset <machineset> -n openshift-machine-api 'metal3.io/autoscale-to-hosts=<any\_value>'

Wait for the new scaled machines to start.



### **NOTE**

When you use a **BareMetalHost** object to create a machine in the cluster and labels or selectors are subsequently changed on the **BareMetalHost**, the **BareMetalHost** object continues be counted against the **MachineSet** that the **Machine** object was created from.

## 9.2.4. Removing bare metal hosts from the provisioner node

In certain circumstances, you might want to temporarily remove bare metal hosts from the provisioner node. For example, during provisioning when a bare metal host reboot is triggered by using the OpenShift Container Platform administration console or as a result of a Machine Config Pool update, OpenShift Container Platform logs into the integrated Dell Remote Access Controller (iDrac) and issues a delete of the job queue.

To prevent the management of the number of **Machine** objects that matches the number of available **BareMetalHost** objects, add a **baremetalhost.metal3.io/detached** annotation to the **MachineSet** object.



### **NOTE**

This annotation has an effect for only **BareMetalHost** objects that are in either **Provisioned**, **ExternallyProvisioned** or **Ready/Available** state.

## **Prerequisites**

- Install RHCOS bare metal compute machines for use in the cluster and create corresponding **BareMetalHost** objects.
- Install the OpenShift Container Platform CLI (oc).
- Log in as a user with cluster-admin privileges.

### **Procedure**

1. Annotate the compute machine set that you want to remove from the provisioner node by adding the **baremetalhost.metal3.io/detached** annotation.

\$ oc annotate machineset <machineset> -n openshift-machine-api 'baremetalhost.metal3.io/detached'

Wait for the new machines to start.



### **NOTE**

When you use a **BareMetalHost** object to create a machine in the cluster and labels or selectors are subsequently changed on the **BareMetalHost**, the **BareMetalHost** object continues be counted against the **MachineSet** that the **Machine** object was created from.

2. In the provisioning use case, remove the annotation after the reboot is complete by using the following command:

\$ oc annotate machineset <machineset> -n openshift-machine-api 'baremetalhost.metal3.io/detached-'

# Additional resources

- Expanding the cluster
- MachineHealthChecks on bare metal

# CHAPTER 10. MONITORING BARE-METAL EVENTS WITH THE BARE METAL EVENT RELAY



### **IMPORTANT**

Bare Metal Event Relay is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see Technology Preview Features Support Scope.

## 10.1. ABOUT BARE-METAL EVENTS



### **IMPORTANT**

The Bare Metal Event Relay Operator is deprecated. The ability to monitor bare-metal hosts by using the Bare Metal Event Relay Operator will be removed in a future OpenShift Container Platform release.

Use the Bare Metal Event Relay to subscribe applications that run in your OpenShift Container Platform cluster to events that are generated on the underlying bare-metal host. The Redfish service publishes events on a node and transmits them on an advanced message queue to subscribed applications.

Bare-metal events are based on the open Redfish standard that is developed under the guidance of the Distributed Management Task Force (DMTF). Redfish provides a secure industry-standard protocol with a REST API. The protocol is used for the management of distributed, converged or software-defined resources and infrastructure.

Hardware-related events published through Redfish includes:

- Breaches of temperature limits
- Server status
- Fan status

Begin using bare-metal events by deploying the Bare Metal Event Relay Operator and subscribing your application to the service. The Bare Metal Event Relay Operator installs and manages the lifecycle of the Redfish bare-metal event service.



## **NOTE**

The Bare Metal Event Relay works only with Redfish-capable devices on single-node clusters provisioned on bare-metal infrastructure.

## 10.2. HOW BARE-METAL EVENTS WORK

The Bare Metal Event Relay enables applications running on bare-metal clusters to respond quickly to Redfish hardware changes and failures such as breaches of temperature thresholds, fan failure, disk loss, power outages, and memory failure. These hardware events are delivered using an HTTP transport or


AMQP mechanism. The latency of the messaging service is between 10 to 20 milliseconds.

The Bare Metal Event Relay provides a publish-subscribe service for the hardware events. Applications can use a REST API to subscribe to the events. The Bare Metal Event Relay supports hardware that complies with Redfish OpenAPI v1.8 or later.

## 10.2.1. Bare Metal Event Relay data flow

The following figure illustrates an example bare-metal events data flow:

Figure 10.1. Bare Metal Event Relay data flow



319 OpenShift 0323

# 10.2.1.1. Operator-managed pod

The Operator uses custom resources to manage the pod containing the Bare Metal Event Relay and its components using the **HardwareEvent** CR.

### 10.2.1.2. Bare Metal Event Relay

At startup, the Bare Metal Event Relay queries the Redfish API and downloads all the message registries, including custom registries. The Bare Metal Event Relay then begins to receive subscribed events from the Redfish hardware.

The Bare Metal Event Relay enables applications running on bare-metal clusters to respond quickly to Redfish hardware changes and failures such as breaches of temperature thresholds, fan failure, disk loss, power outages, and memory failure. The events are reported using the **HardwareEvent** CR.

### 10.2.1.3. Cloud native event

Cloud native events (CNE) is a REST API specification for defining the format of event data.

### 10.2.1.4. CNCF CloudEvents

CloudEvents is a vendor-neutral specification developed by the Cloud Native Computing Foundation (CNCF) for defining the format of event data.

## 10.2.1.5. HTTP transport or AMQP dispatch router

The HTTP transport or AMQP dispatch router is responsible for the message delivery service between publisher and subscriber.



### **NOTE**

HTTP transport is the default transport for PTP and bare-metal events. Use HTTP transport instead of AMQP for PTP and bare-metal events where possible. AMQ Interconnect is EOL from 30 June 2024. Extended life cycle support (ELS) for AMQ Interconnect ends 29 November 2029. For more information see, Red Hat AMQ Interconnect support status.

## 10.2.1.6. Cloud event proxy sidecar

The cloud event proxy sidecar container image is based on the O-RAN API specification and provides a publish-subscribe event framework for hardware events.

# 10.2.2. Redfish message parsing service

In addition to handling Redfish events, the Bare Metal Event Relay provides message parsing for events without a **Message** property. The proxy downloads all the Redfish message registries including vendor specific registries from the hardware when it starts. If an event does not contain a **Message** property, the proxy uses the Redfish message registries to construct the **Message** and **Resolution** properties and add them to the event before passing the event to the cloud events framework. This service allows Redfish events to have smaller message size and lower transmission latency.

## 10.2.3. Installing the Bare Metal Event Relay using the CLI

As a cluster administrator, you can install the Bare Metal Event Relay Operator by using the CLI.

### **Prerequisites**

- A cluster that is installed on bare-metal hardware with nodes that have a RedFish-enabled Baseboard Management Controller (BMC).
- Install the OpenShift CLI (oc).
- Log in as a user with **cluster-admin** privileges.

### **Procedure**

- 1. Create a namespace for the Bare Metal Event Relay.
  - a. Save the following YAML in the bare-metal-events-namespace.yaml file:

apiVersion: v1 kind: Namespace metadata:

name: openshift-bare-metal-events

labels:

name: openshift-bare-metal-events openshift.io/cluster-monitoring: "true"

b. Create the Namespace CR:

\$ oc create -f bare-metal-events-namespace.yaml

- 2. Create an Operator group for the Bare Metal Event Relay Operator.
  - a. Save the following YAML in the bare-metal-events-operatorgroup.yaml file:

apiVersion: operators.coreos.com/v1

kind: OperatorGroup

metadata:

name: bare-metal-event-relay-group namespace: openshift-bare-metal-events

spec:

targetNamespaces:

- openshift-bare-metal-events
- b. Create the **OperatorGroup** CR:

\$ oc create -f bare-metal-events-operatorgroup.yaml

- 3. Subscribe to the Bare Metal Event Relay.
  - a. Save the following YAML in the bare-metal-events-sub.yaml file:

apiVersion: operators.coreos.com/v1alpha1

kind: Subscription

metadata:

name: bare-metal-event-relay-subscription namespace: openshift-bare-metal-events

spec:

channel: "stable"

name: bare-metal-event-relay source: redhat-operators

sourceNamespace: openshift-marketplace

b. Create the **Subscription** CR:

\$ oc create -f bare-metal-events-sub.yaml

### Verification

To verify that the Bare Metal Event Relay Operator is installed, run the following command:

\$ oc get csv -n openshift-bare-metal-events -o custom-columns=Name:.metadata.name,Phase:.status.phase

## 10.2.4. Installing the Bare Metal Event Relay using the web console

As a cluster administrator, you can install the Bare Metal Event Relay Operator using the web console.

## **Prerequisites**

• A cluster that is installed on bare-metal hardware with nodes that have a RedFish-enabled Baseboard Management Controller (BMC).

• Log in as a user with **cluster-admin** privileges.

#### **Procedure**

- 1. Install the Bare Metal Event Relay using the OpenShift Container Platform web console:
  - a. In the OpenShift Container Platform web console, click **Operators** → **OperatorHub**.
  - b. Choose Bare Metal Event Relayfrom the list of available Operators, and then click Install.
  - c. On the **Install Operator** page, select or create a **Namespace**, select **openshift-bare-metal-events**, and then click **Install**.

#### Verification

Optional: You can verify that the Operator installed successfully by performing the following check:

- 1. Switch to the **Operators** → **Installed Operators** page.
- 2. Ensure that Bare Metal Event Relayis listed in the project with a Status of InstallSucceeded.



#### NOTE

During installation an Operator might display a **Failed** status. If the installation later succeeds with an **InstallSucceeded** message, you can ignore the **Failed** message.

If the Operator does not appear as installed, to troubleshoot further:

- Go to the Operators → Installed Operators page and inspect the Operator Subscriptions and Install Plans tabs for any failure or errors under Status.
- Go to the **Workloads** → **Pods** page and check the logs for pods in the project namespace.

#### 10.3. INSTALLING THE AMQ MESSAGING BUS

To pass Redfish bare-metal event notifications between publisher and subscriber on a node, you can install and configure an AMQ messaging bus to run locally on the node. You do this by installing the AMQ Interconnect Operator for use in the cluster.



### **NOTE**

HTTP transport is the default transport for PTP and bare-metal events. Use HTTP transport instead of AMQP for PTP and bare-metal events where possible. AMQ Interconnect is EOL from 30 June 2024. Extended life cycle support (ELS) for AMQ Interconnect ends 29 November 2029. For more information see, Red Hat AMQ Interconnect support status.

## **Prerequisites**

- Install the OpenShift Container Platform CLI (oc).
- Log in as a user with **cluster-admin** privileges.

#### **Procedure**

• Install the AMQ Interconnect Operator to its own **amq-interconnect** namespace. See Installing the AMQ Interconnect Operator.

#### Verification

1. Verify that the AMQ Interconnect Operator is available and the required pods are running:

\$ oc get pods -n amq-interconnect

# **Example output**

NAME READY STATUS RESTARTS AGE amq-interconnect-645db76c76-k8ghs 1/1 Running 0 23h interconnect-operator-5cb5fc7cc-4v7qm 1/1 Running 0 23h

2. Verify that the required **bare-metal-event-relay** bare-metal event producer pod is running in the **openshift-bare-metal-events** namespace:

\$ oc get pods -n openshift-bare-metal-events

## **Example output**

NAME READY STATUS RESTARTS AGE hw-event-proxy-operator-controller-manager-74d5649b7c-dzgtl 2/2 Running 0 25s

# 10.4. SUBSCRIBING TO REDFISH BMC BARE-METAL EVENTS FOR A CLUSTER NODE

You can subscribe to Redfish BMC events generated on a node in your cluster by creating a **BMCEventSubscription** custom resource (CR) for the node, creating a **HardwareEvent** CR for the event, and creating a **Secret** CR for the BMC.

# 10.4.1. Subscribing to bare-metal events

You can configure the baseboard management controller (BMC) to send bare-metal events to subscribed applications running in an OpenShift Container Platform cluster. Example Redfish bare-metal events include an increase in device temperature, or removal of a device. You subscribe applications to bare-metal events using a REST API.



### **IMPORTANT**

You can only create a **BMCEventSubscription** custom resource (CR) for physical hardware that supports Redfish and has a vendor interface set to **redfish** or **idracredfish**.



### **NOTE**

Use the **BMCEventSubscription** CR to subscribe to predefined Redfish events. The Redfish standard does not provide an option to create specific alerts and thresholds. For example, to receive an alert event when an enclosure's temperature exceeds 40° Celsius, you must manually configure the event according to the vendor's recommendations.

Perform the following procedure to subscribe to bare-metal events for the node using a **BMCEventSubscription** CR.

## **Prerequisites**

- Install the OpenShift CLI (oc).
- Log in as a user with **cluster-admin** privileges.
- Get the user name and password for the BMC.
- Deploy a bare-metal node with a Redfish-enabled Baseboard Management Controller (BMC) in your cluster, and enable Redfish events on the BMC.



#### **NOTE**

Enabling Redfish events on specific hardware is outside the scope of this information. For more information about enabling Redfish events for your specific hardware, consult the BMC manufacturer documentation.

#### **Procedure**

 Confirm that the node hardware has the Redfish EventService enabled by running the following curl command:

```
$ curl https://<bmc_ip_address>/redfish/v1/EventService --insecure -H 'Content-Type: application/json' -u "<bmc_username>:<password>"
```

where:

#### bmc\_ip\_address

is the IP address of the BMC where the Redfish events are generated.

## **Example output**

```
"@odata.context": "/redfish/v1/$metadata#EventService.EventService",
 "@odata.id": "/redfish/v1/EventService",
 "@odata.type": "#EventService.v1_0_2.EventService",
 "Actions": {
   "#EventService.SubmitTestEvent": {
     "EventType@Redfish.AllowableValues": ["StatusChange", "ResourceUpdated",
"ResourceAdded", "ResourceRemoved", "Alert"],
     "target": "/redfish/v1/EventService/Actions/EventService.SubmitTestEvent"
   }
 "DeliveryRetryAttempts": 3,
 "DeliveryRetryIntervalSeconds": 30,
 "Description": "Event Service represents the properties for the service",
 "EventTypesForSubscription": ["StatusChange", "ResourceUpdated", "ResourceAdded",
"ResourceRemoved", "Alert"],
 "EventTypesForSubscription@odata.count": 5,
 "Id": "EventService",
 "Name": "Event Service",
 "ServiceEnabled": true,
```

```
"Status": {
    "Health": "OK",
    "HealthRollup": "OK",
    "State": "Enabled"
    },
    "Subscriptions": {
        "@odata.id": "/redfish/v1/EventService/Subscriptions"
    }
}
```

2. Get the Bare Metal Event Relay service route for the cluster by running the following command:

\$ oc get route -n openshift-bare-metal-events

# Example output

```
NAME HOST/PORT PATH SERVICES
PORT TERMINATION WILDCARD
hw-event-proxy hw-event-proxy-openshift-bare-metal-events.apps.compute-
1.example.com hw-event-proxy-service 9087 edge None
```

- 3. Create a **BMCEventSubscription** resource to subscribe to the Redfish events:
  - a. Save the following YAML in the bmc\_sub.yaml file:

```
apiVersion: metal3.io/v1alpha1
kind: BMCEventSubscription
metadata:
name: sub-01
namespace: openshift-machine-api
spec:
hostName: <hostname>
destination: <proxy_service_url>
context: "
```

- Specifies the name or UUID of the worker node where the Redfish events are generated.
- Specifies the bare-metal event proxy service, for example, https://hw-event-proxy-openshift-bare-metal-events.apps.compute-1.example.com/webhook.
- b. Create the **BMCEventSubscription** CR:

```
$ oc create -f bmc_sub.yaml
```

4. Optional: To delete the BMC event subscription, run the following command:

```
$ oc delete -f bmc_sub.yaml
```

Optional: To manually create a Redfish event subscription without creating a
 BMCEventSubscription CR, run the following curl command, specifying the BMC username and password.

```
$ curl -i -k -X POST -H "Content-Type: application/json" -d '{"Destination": "https://proxy_service_url>", "Protocol": "Redfish", "EventTypes": ["Alert"], "Context": "root"}' -u <bmc_username>:<password>
'https://<bmc_ip_address>/redfish/v1/EventService/Subscriptions' -v
```

where:

## proxy\_service\_url

is the bare-metal event proxy service, for example, <a href="https://hw-event-proxy-openshift-bare-metal-events.apps.compute-1.example.com/webhook">https://hw-event-proxy-openshift-bare-metal-events.apps.compute-1.example.com/webhook</a>.

#### bmc\_ip\_address

is the IP address of the BMC where the Redfish events are generated.

## **Example output**

HTTP/1.1 201 Created

Server: AMI MegaRAC Redfish Service

Location: /redfish/v1/EventService/Subscriptions/1

Allow: GET, POST

Access-Control-Allow-Origin: \*

Access-Control-Expose-Headers: X-Auth-Token Access-Control-Allow-Headers: X-Auth-Token

Access-Control-Allow-Credentials: true Cache-Control: no-cache, must-revalidate

Link: <a href="http://redfish.dmtf.org/schemas/v1/EventDestination.v1\_6\_0.json">http://redfish.dmtf.org/schemas/v1/EventDestination.v1\_6\_0.json</a>; rel=describedby

Link: <a href="http://redfish.dmtf.org/schemas/v1/EventDestination.v1\_6\_0.json">http://redfish.dmtf.org/schemas/v1/EventDestination.v1\_6\_0.json</a>

Link: </redfish/v1/EventService/Subscriptions>; path=

ETag: "1651135676"

Content-Type: application/json; charset=UTF-8

OData-Version: 4.0 Content-Length: 614

Date: Thu, 28 Apr 2022 08:47:57 GMT

# 10.4.2. Querying Redfish bare-metal event subscriptions with curl

Some hardware vendors limit the amount of Redfish hardware event subscriptions. You can query the number of Redfish event subscriptions by using **curl**.

#### **Prerequisites**

- Get the user name and password for the BMC.
- Deploy a bare-metal node with a Redfish-enabled Baseboard Management Controller (BMC) in your cluster, and enable Redfish hardware events on the BMC.

### **Procedure**

1. Check the current subscriptions for the BMC by running the following **curl** command:

```
$ curl --globoff -H "Content-Type: application/json" -k -X GET --user <bmc_username>: <password> https://<bmc_ip_address>/redfish/v1/EventService/Subscriptions
```

where:

### bmc\_ip\_address

is the IP address of the BMC where the Redfish events are generated.

# **Example output**

```
% Total % Received % Xferd Average Speed Time Time Current
Dload Upload Total Spent Left Speed
100 435 100 435 0 0 399 0 0:00:01 0:00:01 --:---- 399

{
    "@odata.context":
    "/redfish/v1/$metadata#EventDestinationCollection.EventDestinationCollection",
    "@odata.etag": ""
    1651137375 "",
    "@odata.id": "/redfish/v1/EventService/Subscriptions",
    "@odata.type": "#EventDestinationCollection.EventDestinationCollection",
    "Description": "Collection for Event Subscriptions",
    "Members": [
    {
        "@odata.id": "/redfish/v1/EventService/Subscriptions/1"
    }],
    "Members@odata.count": 1,
    "Name": "Event Subscriptions Collection"
}
```

In this example, a single subscription is configured: /redfish/v1/EventService/Subscriptions/1.

2. Optional: To remove the /redfish/v1/EventService/Subscriptions/1 subscription with curl, run the following command, specifying the BMC username and password:

```
$ curl --globoff -L -w "%{http_code} %{url_effective}\n" -k -u <bmc_username>:<password >- H "Content-Type: application/json" -d '{}' -X DELETE https://<bmc_ip_address>/redfish/v1/EventService/Subscriptions/1
```

where:

#### bmc\_ip\_address

is the IP address of the BMC where the Redfish events are generated.

# 10.4.3. Creating the bare-metal event and Secret CRs

To start using bare-metal events, create the **HardwareEvent** custom resource (CR) for the host where the Redfish hardware is present. Hardware events and faults are reported in the **hw-event-proxy** logs.

#### **Prerequisites**

- You have installed the OpenShift Container Platform CLI (oc).
- You have logged in as a user with **cluster-admin** privileges.
- You have installed the Bare Metal Event Relay.
- You have created a **BMCEventSubscription** CR for the BMC Redfish hardware.

#### Procedure

1. Create the **HardwareEvent** custom resource (CR):



#### **NOTE**

Multiple **HardwareEvent** resources are not permitted.

a. Save the following YAML in the **hw-event.yaml** file:

apiVersion: "event.redhat-cne.org/v1alpha1"

kind: "HardwareEvent"

metadata:

name: "hardware-event"

spec:

nodeSelector:

node-role.kubernetes.io/hw-event: "" 1

logLevel: "debug" 2

msgParserTimeout: "10" 3

Required. Use the **nodeSelector** field to target nodes with the specified label, for example, **node-role.kubernetes.io/hw-event: ""**.



#### **NOTE**

In OpenShift Container Platform 4.13 or later, you do not need to set the **spec.transportHost** field in the **HardwareEvent** resource when you use HTTP transport for bare-metal events. Set **transportHost** only when you use AMQP transport for bare-metal events.

- Optional. The default value is **debug**. Sets the log level in **hw-event-proxy** logs. The following log levels are available: **fatal**, **error**, **warning**, **info**, **debug**, **trace**.
- Optional. Sets the timeout value in milliseconds for the Message Parser. If a message parsing request is not responded to within the timeout duration, the original hardware event message is passed to the cloud native event framework. The default value is 10.
- b. Apply the **HardwareEvent** CR in the cluster:

\$ oc create -f hardware-event.yaml

- 2. Create a BMC username and password **Secret** CR that enables the hardware events proxy to access the Redfish message registry for the bare-metal host.
  - a. Save the following YAML in the **hw-event-bmc-secret.yaml** file:

apiVersion: v1 kind: Secret metadata:

name: redfish-basic-auth

type: Opaque stringData: 1

username: <br/> <br/> cusername>

password: <bmc\_password>
# BMC host DNS or IP address
hostaddr: <bmc\_host\_ip\_address>

1

Enter plain text values for the various items under **stringData**.

b. Create the **Secret** CR:

\$ oc create -f hw-event-bmc-secret.yaml

#### Additional resources

• Persistent storage using local volumes

# 10.5. SUBSCRIBING APPLICATIONS TO BARE-METAL EVENTS REST API REFERENCE

Use the bare-metal events REST API to subscribe an application to the bare-metal events that are generated on the parent node.

Subscribe applications to Redfish events by using the resource address /cluster/node/<node\_name>/redfish/event, where <node\_name> is the cluster node running the application.

Deploy your **cloud-event-consumer** application container and **cloud-event-proxy** sidecar container in a separate application pod. The **cloud-event-consumer** application subscribes to the **cloud-event-proxy** container in the application pod.

Use the following API endpoints to subscribe the **cloud-event-consumer** application to Redfish events posted by the **cloud-event-proxy** container at **http://localhost:8089/api/ocloudNotifications/v1/** in the application pod:

- /api/ocloudNotifications/v1/subscriptions
  - **POST**: Creates a new subscription
  - GET: Retrieves a list of subscriptions
- /api/ocloudNotifications/v1/subscriptions/<subscription\_id>
  - PUT: Creates a new status ping request for the specified subscription ID
- /api/ocloudNotifications/v1/health
  - GET: Returns the health status of ocloudNotifications API



#### **NOTE**

**9089** is the default port for the **cloud-event-consumer** container deployed in the application pod. You can configure a different port for your application as required.

api/ocloudNotifications/v1/subscriptions HTTP method GET api/ocloudNotifications/v1/subscriptions

#### Description

Returns a list of subscriptions. If subscriptions exist, a **200 OK** status code is returned along with the list of subscriptions.

# **Example API response**

```
[
{
  "id": "ca11ab76-86f9-428c-8d3a-666c24e34d32",
  "endpointUri": "http://localhost:9089/api/ocloudNotifications/v1/dummy",
  "uriLocation": "http://localhost:8089/api/ocloudNotifications/v1/subscriptions/ca11ab76-86f9-428c-8d3a-666c24e34d32",
  "resource": "/cluster/node/openshift-worker-0.openshift.example.com/redfish/event"
}
]
```

#### **HTTP** method

## POST api/ocloudNotifications/v1/subscriptions

# Description

Creates a new subscription. If a subscription is successfully created, or if it already exists, a **201 Created** status code is returned.

### Table 10.1. Query parameters

Parameter	Туре
subscription	data

# Example payload

```
{
    "uriLocation": "http://localhost:8089/api/ocloudNotifications/v1/subscriptions",
    "resource": "/cluster/node/openshift-worker-0.openshift.example.com/redfish/event"
}
```

# api/ocloudNotifications/v1/subscriptions/<subscription\_id> HTTP method

GET api/ocloudNotifications/v1/subscriptions/<subscription\_id>

## Description

Returns details for the subscription with ID <subscription\_id>

## Table 10.2. Query parameters

Parameter	Туре
<subscription_id></subscription_id>	string

## **Example API response**

{

```
"id":"ca11ab76-86f9-428c-8d3a-666c24e34d32",

"endpointUri":"http://localhost:9089/api/ocloudNotifications/v1/dummy",

"uriLocation":"http://localhost:8089/api/ocloudNotifications/v1/subscriptions/ca11ab76-86f9-428c-8d3a-666c24e34d32",

"resource":"/cluster/node/openshift-worker-0.openshift.example.com/redfish/event"
}
```

api/ocloudNotifications/v1/health/ HTTP method GET api/ocloudNotifications/v1/health/

#### Description

Returns the health status for the ocloudNotifications REST API.

## **Example API response**

OK

# 10.6. MIGRATING CONSUMER APPLICATIONS TO USE HTTP TRANSPORT FOR PTP OR BARE-METAL EVENTS

If you have previously deployed PTP or bare-metal events consumer applications, you need to update the applications to use HTTP message transport.

## **Prerequisites**

- You have installed the OpenShift CLI (oc).
- You have logged in as a user with **cluster-admin** privileges.
- You have updated the PTP Operator or Bare Metal Event Relay to version 4.13+ which uses HTTP transport by default.

# Procedure

 Update your events consumer application to use HTTP transport. Set the http-eventpublishers variable for the cloud event sidecar deployment.

For example, in a cluster with PTP events configured, the following YAML snippet illustrates a cloud event sidecar deployment:

## containers:

- name: cloud-event-sidecar image: cloud-event-sidecar args:
  - "--metrics-addr=127.0.0.1:9091"
  - "--store-path=/store"
  - "--transport-host=consumer-events-subscription-service.cloud-

events.svc.cluster.local:9043"

- "--http-event-publishers=ptp-event-publisher-service-NODE\_NAME.openshift-ptp.svc.cluster.local:9043"

- "--api-port=8089"

1

The PTP Operator automatically resolves **NODE\_NAME** to the host that is generating the PTP events. For example, **compute-1.example.com**.

In a cluster with bare-metal events configured, set the **http-event-publishers** field to **hw-event-publisher-service.openshift-bare-metal-events.svc.cluster.local:9043** in the cloud event sidecar deployment CR.

2. Deploy the **consumer-events-subscription-service** service alongside the events consumer application. For example:

apiVersion: v1 kind: Service metadata: annotations: prometheus.io/scrape: "true" service.alpha.openshift.io/serving-cert-secret-name: sidecar-consumer-secret name: consumer-events-subscription-service namespace: cloud-events labels: app: consumer-service spec: ports: - name: sub-port port: 9043 selector: app: consumer

clusterIP: None sessionAffinity: None type: ClusterIP

# CHAPTER 11. WHAT HUGE PAGES DO AND HOW THEY ARE CONSUMED BY APPLICATIONS

## 11.1. WHAT HUGE PAGES DO

Memory is managed in blocks known as pages. On most systems, a page is 4Ki. 1Mi of memory is equal to 256 pages; 1Gi of memory is 256,000 pages, and so on. CPUs have a built-in memory management unit that manages a list of these pages in hardware. The Translation Lookaside Buffer (TLB) is a small hardware cache of virtual-to-physical page mappings. If the virtual address passed in a hardware instruction can be found in the TLB, the mapping can be determined quickly. If not, a TLB miss occurs, and the system falls back to slower, software-based address translation, resulting in performance issues. Since the size of the TLB is fixed, the only way to reduce the chance of a TLB miss is to increase the page size.

A huge page is a memory page that is larger than 4Ki. On x86\_64 architectures, there are two common huge page sizes: 2Mi and 1Gi. Sizes vary on other architectures. To use huge pages, code must be written so that applications are aware of them. Transparent Huge Pages (THP) attempt to automate the management of huge pages without application knowledge, but they have limitations. In particular, they are limited to 2Mi page sizes. THP can lead to performance degradation on nodes with high memory utilization or fragmentation due to defragmenting efforts of THP, which can lock memory pages. For this reason, some applications may be designed to (or recommend) usage of pre-allocated huge pages instead of THP.

In OpenShift Container Platform, applications in a pod can allocate and consume pre-allocated huge pages.

## 11.2. HOW HUGE PAGES ARE CONSUMED BY APPS

Nodes must pre-allocate huge pages in order for the node to report its huge page capacity. A node can only pre-allocate huge pages for a single size.

Huge pages can be consumed through container-level resource requirements using the resource name **hugepages-<size>**, where size is the most compact binary notation using integer values supported on a particular node. For example, if a node supports 2048KiB page sizes, it exposes a schedulable resource **hugepages-2Mi**. Unlike CPU or memory, huge pages do not support over-commitment.

apiVersion: v1 kind: Pod metadata:

generateName: hugepages-volume-

spec:

containers:

 securityContext: privileged: true image: rhel7:latest command:

- sleep - inf

name: example volumeMounts:

- mountPath: /dev/hugepages

name: hugepage

resources: limits:

hugepages-2Mi: 100Mi 1 memory: "1Gi"

cpu: "1" volumes:

- name: hugepage

emptyDir:

medium: HugePages

Specify the amount of memory for **hugepages** as the exact amount to be allocated. Do not specify this value as the amount of memory for **hugepages** multiplied by the size of the page. For example, given a huge page size of 2MB, if you want to use 100MB of huge-page-backed RAM for your application, then you would allocate 50 huge pages. OpenShift Container Platform handles the math for you. As in the above example, you can specify **100MB** directly.

#### Allocating huge pages of a specific size

Some platforms support multiple huge page sizes. To allocate huge pages of a specific size, precede the huge pages boot command parameters with a huge page size selection parameter **hugepagesz=<size>**. The **<size>** value must be specified in bytes with an optional scale suffix [ **kKmMgG**]. The default huge page size can be defined with the **default\_hugepagesz=<size>** boot parameter.

# Huge page requirements

- Huge page requests must equal the limits. This is the default if limits are specified, but requests are not.
- Huge pages are isolated at a pod scope. Container isolation is planned in a future iteration.
- **EmptyDir** volumes backed by huge pages must not consume more huge page memory than the pod request.
- Applications that consume huge pages via **shmget()** with **SHM\_HUGETLB** must run with a supplemental group that matches *proc/sys/vm/hugetlb\_shm\_group*.

# 11.3. CONSUMING HUGE PAGES RESOURCES USING THE DOWNWARD API

You can use the Downward API to inject information about the huge pages resources that are consumed by a container.

You can inject the resource allocation as environment variables, a volume plugin, or both. Applications that you develop and run in the container can determine the resources that are available by reading the environment variables or files in the specified volumes.

#### Procedure

1. Create a hugepages-volume-pod.yaml file that is similar to the following example:

apiVersion: v1 kind: Pod metadata:

generateName: hugepages-volume-

labels:

app: hugepages-example

```
spec:
 containers:
 - securityContext:
   capabilities:
    add: [ "IPC_LOCK" ]
  image: rhel7:latest
  command:
  - sleep
  - inf
  name: example
  volumeMounts:
  - mountPath: /dev/hugepages
   name: hugepage
  - mountPath: /etc/podinfo
   name: podinfo
  resources:
   limits:
    hugepages-1Gi: 2Gi
    memory: "1Gi"
    cpu: "1"
   requests:
    hugepages-1Gi: 2Gi
  - name: REQUESTS HUGEPAGES 1GI <.>
   valueFrom:
    resourceFieldRef:
     containerName: example
     resource: requests.hugepages-1Gi
 volumes:
 - name: hugepage
  emptyDir:
   medium: HugePages
 - name: podinfo
  downwardAPI:
   items:
    - path: "hugepages_1G_request" <.>
     resourceFieldRef:
      containerName: example
      resource: requests.hugepages-1Gi
      divisor: 1Gi
```

<.> Specifies to read the resource use from requests.hugepages-1Gi and expose the value as the REQUESTS\_HUGEPAGES\_1GI environment variable. <.> Specifies to read the resource use from requests.hugepages-1Gi and expose the value as the file /etc/podinfo/hugepages\_1G\_request.

2. Create the pod from the **hugepages-volume-pod.yaml** file:

\$ oc create -f hugepages-volume-pod.yaml

#### Verification

1. Check the value of the **REQUESTS\_HUGEPAGES\_1GI** environment variable:

```
$ oc exec -it $(oc get pods -l app=hugepages-example -o
jsonpath='{.items[0].metadata.name}') \
    -- env | grep REQUESTS_HUGEPAGES_1GI
```

# **Example output**

REQUESTS\_HUGEPAGES\_1GI=2147483648

2. Check the value of the /etc/podinfo/hugepages\_1G\_request file:

```
$ oc exec -it $(oc get pods -l app=hugepages-example -o
jsonpath='{.items[0].metadata.name}') \
    -- cat /etc/podinfo/hugepages 1G request
```

## **Example output**

2

#### Additional resources

• Allowing containers to consume Downward API objects

# 11.4. CONFIGURING HUGE PAGES AT BOOT TIME

Nodes must pre-allocate huge pages used in an OpenShift Container Platform cluster. There are two ways of reserving huge pages: at boot time and at run time. Reserving at boot time increases the possibility of success because the memory has not yet been significantly fragmented. The Node Tuning Operator currently supports boot time allocation of huge pages on specific nodes.

#### **Procedure**

To minimize node reboots, the order of the steps below needs to be followed:

- 1. Label all nodes that need the same huge pages setting by a label.
  - \$ oc label node <node\_using\_hugepages> node-role.kubernetes.io/worker-hp=
- 2. Create a file with the following content and name it hugepages-tuned-boottime.yaml:

```
apiVersion: tuned.openshift.io/v1
kind: Tuned
metadata:
name: hugepages 1
namespace: openshift-cluster-node-tuning-operator
spec:
profile: 2
- data: |
    [main]
    summary=Boot time configuration for hugepages
    include=openshift-node
    [bootloader]
    cmdline_openshift_node_hugepages=hugepagesz=2M hugepages=50 3
```

name: openshift-node-hugepages

recommend:

- machineConfigLabels: 4

machineconfiguration.openshift.io/role: "worker-hp"

priority: 30

profile: openshift-node-hugepages

- Set the **name** of the Tuned resource to **hugepages**.
- Set the profile section to allocate huge pages.
- Note the order of parameters is important as some platforms support huge pages of various sizes.
- Enable machine config pool based matching.
- 3. Create the Tuned hugepages object

\$ oc create -f hugepages-tuned-boottime.yaml

4. Create a file with the following content and name it hugepages-mcp.yaml:

apiVersion: machineconfiguration.openshift.io/v1

kind: MachineConfigPool

metadata:

name: worker-hp

labels:

worker-hp: ""

spec:

machineConfigSelector:

matchExpressions:

- {key: machineconfiguration.openshift.io/role, operator: In, values: [worker,worker-hp]}

nodeSelector:

matchLabels:

node-role.kubernetes.io/worker-hp: ""

5. Create the machine config pool:

\$ oc create -f hugepages-mcp.yaml

Given enough non-fragmented memory, all the nodes in the **worker-hp** machine config pool should now have 50 2Mi huge pages allocated.

\$ oc get node <node\_using\_hugepages> -o jsonpath="{.status.allocatable.hugepages-2Mi}" 100Mi



## NOTE

The TuneD bootloader plugin only supports Red Hat Enterprise Linux CoreOS (RHCOS) worker nodes.

## 11.5. DISABLING TRANSPARENT HUGE PAGES

Transparent Huge Pages (THP) attempt to automate most aspects of creating, managing, and using huge pages. Since THP automatically manages the huge pages, this is not always handled optimally for all types of workloads. THP can lead to performance regressions, since many applications handle huge pages on their own. Therefore, consider disabling THP. The following steps describe how to disable THP using the Node Tuning Operator (NTO).

#### **Procedure**

1. Create a file with the following content and name it **thp-disable-tuned.yaml**:

```
apiVersion: tuned.openshift.io/v1
kind: Tuned
metadata:
 name: thp-workers-profile
 namespace: openshift-cluster-node-tuning-operator
 profile:
 - data: |
   [main]
   summary=Custom tuned profile for OpenShift to turn off THP on worker nodes
   include=openshift-node
   [vm]
   transparent_hugepages=never
  name: openshift-thp-never-worker
 recommend:
 - match:
  - label: node-role.kubernetes.io/worker
  priority: 25
  profile: openshift-thp-never-worker
```

2. Create the Tuned object:

\$ oc create -f thp-disable-tuned.yaml

3. Check the list of active profiles:

\$ oc get profile -n openshift-cluster-node-tuning-operator

## Verification

• Log in to one of the nodes and do a regular THP check to verify if the nodes applied the profile successfully:

\$ cat /sys/kernel/mm/transparent\_hugepage/enabled

## **Example output**

always madvise [never]

# **CHAPTER 12. LOW LATENCY TUNING**

## 12.1. UNDERSTANDING LOW LATENCY TUNING FOR CLUSTER NODES

Edge computing has a key role in reducing latency and congestion problems and improving application performance for telco and 5G network applications. Maintaining a network architecture with the lowest possible latency is key for meeting the network performance requirements of 5G. Compared to 4G technology, with an average latency of 50 ms, 5G is targeted to reach latency of 1 ms or less. This reduction in latency boosts wireless throughput by a factor of 10.

# 12.1.1. About low latency

Many of the deployed applications in the Telco space require low latency that can only tolerate zero packet loss. Tuning for zero packet loss helps mitigate the inherent issues that degrade network performance. For more information, see Tuning for Zero Packet Loss in Red Hat OpenStack Platform (RHOSP).

The Edge computing initiative also comes in to play for reducing latency rates. Think of it as being on the edge of the cloud and closer to the user. This greatly reduces the distance between the user and distant data centers, resulting in reduced application response times and performance latency.

Administrators must be able to manage their many Edge sites and local services in a centralized way so that all of the deployments can run at the lowest possible management cost. They also need an easy way to deploy and configure certain nodes of their cluster for real-time low latency and high-performance purposes. Low latency nodes are useful for applications such as Cloud-native Network Functions (CNF) and Data Plane Development Kit (DPDK).

OpenShift Container Platform currently provides mechanisms to tune software on an OpenShift Container Platform cluster for real-time running and low latency (around <20 microseconds reaction time). This includes tuning the kernel and OpenShift Container Platform set values, installing a kernel, and reconfiguring the machine. But this method requires setting up four different Operators and performing many configurations that, when done manually, is complex and could be prone to mistakes.

OpenShift Container Platform uses the Node Tuning Operator to implement automatic tuning to achieve low latency performance for OpenShift Container Platform applications. The cluster administrator uses this performance profile configuration that makes it easier to make these changes in a more reliable way. The administrator can specify whether to update the kernel to kernel-rt, reserve CPUs for cluster and operating system housekeeping duties, including pod infra containers, and isolate CPUs for application containers to run the workloads.

OpenShift Container Platform also supports workload hints for the Node Tuning Operator that can tune the **PerformanceProfile** to meet the demands of different industry environments. Workload hints are available for **highPowerConsumption** (very low latency at the cost of increased power consumption) and **realTime** (priority given to optimum latency). A combination of **true/false** settings for these hints can be used to deal with application-specific workload profiles and requirements.

Workload hints simplify the fine-tuning of performance to industry sector settings. Instead of a "one size fits all" approach, workload hints can cater to usage patterns such as placing priority on:

- Low latency
- Real-time capability
- Efficient use of power

Ideally, all of the previously listed items are prioritized. Some of these items come at the expense of others however. The Node Tuning Operator is now aware of the workload expectations and better able to meet the demands of the workload. The cluster admin can now specify into which use case that workload falls. The Node Tuning Operator uses the **PerformanceProfile** to fine tune the performance settings for the workload.

The environment in which an application is operating influences its behavior. For a typical data center with no strict latency requirements, only minimal default tuning is needed that enables CPU partitioning for some high performance workload pods. For data centers and workloads where latency is a higher priority, measures are still taken to optimize power consumption. The most complicated cases are clusters close to latency-sensitive equipment such as manufacturing machinery and software-defined radios. This last class of deployment is often referred to as Far edge. For Far edge deployments, ultralow latency is the ultimate priority, and is achieved at the expense of power management.

# 12.1.2. About Hyper-Threading for low latency and real-time applications

Hyper-Threading is an Intel processor technology that allows a physical CPU processor core to function as two logical cores, executing two independent threads simultaneously. Hyper-Threading allows for better system throughput for certain workload types where parallel processing is beneficial. The default OpenShift Container Platform configuration expects Hyper-Threading to be enabled.

For telecommunications applications, it is important to design your application infrastructure to minimize latency as much as possible. Hyper-Threading can slow performance times and negatively affect throughput for compute-intensive workloads that require low latency. Disabling Hyper-Threading ensures predictable performance and can decrease processing times for these workloads.



#### NOTE

Hyper-Threading implementation and configuration differs depending on the hardware you are running OpenShift Container Platform on. Consult the relevant host hardware tuning information for more details of the Hyper-Threading implementation specific to that hardware. Disabling Hyper-Threading can increase the cost per core of the cluster.

#### Additional resources

Configuring Hyper-Threading for a cluster

# 12.2. TUNING NODES FOR LOW LATENCY WITH THE PERFORMANCE PROFILE

Tune nodes for low latency by using the cluster performance profile. You can restrict CPUs for infra and application containers, configure huge pages, Hyper-Threading, and configure CPU partitions for latency-sensitive processes.

#### Additional resources

Provisioning real-time and low latency workloads

# 12.2.1. Creating a performance profile

Learn about the Performance Profile Creator (PPC) and how you can use it to create a performance profile.

#### 12.2.1.1. About the Performance Profile Creator

The Performance Profile Creator (PPC) is a command-line tool, delivered with the Node Tuning Operator, used to create the performance profile. The tool consumes **must-gather** data from the cluster and several user-supplied profile arguments. The PPC generates a performance profile that is appropriate for your hardware and topology.

The tool is run by one of the following methods:

- Invoking podman
- Calling a wrapper script

## 12.2.1.2. Gathering data about your cluster using the must-gather command

The Performance Profile Creator (PPC) tool requires **must-gather** data. As a cluster administrator, run the **must-gather** command to capture information about your cluster.

#### **Prerequisites**

- Access to the cluster as a user with the **cluster-admin** role.
- The OpenShift CLI (oc) installed.

#### Procedure

1. Optional: Verify that a matching machine config pool exists with a label:

\$ oc describe mcp/worker-rt

## **Example output**

Name: worker-rt

Namespace:

Labels: machineconfiguration.openshift.io/role=worker-rt

2. If a matching label does not exist add a label for a machine config pool (MCP) that matches with the MCP name:

\$ oc label mcp <mcp\_name> machineconfiguration.openshift.io/role=<mcp\_name>

- 3. Navigate to the directory where you want to store the **must-gather** data.
- 4. Collect cluster information by running the following command:
  - \$ oc adm must-gather
- 5. Optional: Create a compressed file from the **must-gather** directory:

\$ tar cvaf must-gather.tar.gz must-gather/



Compressed output is required if you are running the Performance Profile Creator wrapper script.

# 12.2.1.3. Running the Performance Profile Creator using Podman

As a cluster administrator, you can run **podman** and the Performance Profile Creator to create a performance profile.

## **Prerequisites**

- Access to the cluster as a user with the **cluster-admin** role.
- A cluster installed on bare-metal hardware.
- A node with **podman** and OpenShift CLI (**oc**) installed.
- Access to the Node Tuning Operator image.

#### Procedure

1. Check the machine config pool:

\$ oc get mcp

# **Example output**

NAME CONFIG UPDATED UPDATING DEGRADED MACHINECOUNT READYMACHINECOUNT UPDATEDMACHINECOUNT DEGRADEDMACHINECOUNT AGE master rendered-master-acd1358917e9f98cbdb599aea622d78b True False False 3 3 3 0 22h worker-cnf rendered-worker-cnf-1d871ac76e1951d32b2fe92369879826 False True False 2 1 1 0 22h

2. Use Podman to authenticate to registry.redhat.io:

\$ podman login registry.redhat.io

Username: <username> Password: <password>

3. Optional: Display help for the PPC tool:

\$ podman run --rm --entrypoint performance-profile-creator registry.redhat.io/openshift4/ose-cluster-node-tuning-operator:v4.16 -h

## **Example output**

A tool that automates creation of Performance Profiles

Usage:

performance-profile-creator [flags]

Flags:

--disable-ht Disable Hyperthreading

-h, --help help for performance-profile-creator

--info string Show cluster information; requires --must-gather-dir-path,

ignore the other arguments. [Valid values: log, json] (default "log")

--mcp-name string MCP name corresponding to the target machines

(required)

--must-gather-dir-path string Must gather directory path (default "must-gather")

--offlined-cpu-count int Number of offlined CPUs

--per-pod-power-management Enable Per Pod Power Management

--power-consumption-mode string The power consumption mode. [Valid values: default, low-latency, ultra-low-latency] (default "default")

--profile-name string Name of the performance profile to be created (default

"performance")

--rt-kernel Enable Real Time Kernel (required)

--split-reserved-cpus-across-numa Split the Reserved CPUs across NUMA nodes

--topology-manager-policy string Kubelet Topology Manager Policy of the performance profile to be created. [Valid values: single-numa-node, best-effort, restricted] (default "restricted")

--user-level-networking Run with User level Networking(DPDK) enabled

4. Run the Performance Profile Creator tool in discovery mode:



#### NOTE

Discovery mode inspects your cluster by using the output from **must-gather**. The output produced includes information on the following conditions:

- The NUMA cell partitioning with the allocated CPU ids
- Whether Hyper-Threading is enabled

Using this information you can set appropriate values for some of the arguments supplied to the Performance Profile Creator tool.

\$ podman run --entrypoint performance-profile-creator -v <path\_to\_must-gather>/must-gather:/must-gather:z registry.redhat.io/openshift4/ose-cluster-node-tuning-operator:v4.16 -- info log --must-gather-dir-path /must-gather



This command uses the performance profile creator as a new entry point to **podman**. It maps the **must-gather** data for the host into the container image and invokes the required user-supplied profile arguments to produce the **my-performance-profile.yaml** file.

The **-v** option can be the path to either of the following components:

- The **must-gather** output directory
- An existing directory containing the **must-gather** decompressed .tar file

The **info** option requires a value which specifies the output format. Possible values are log and JSON. The JSON format is reserved for debugging.

# 5. Run podman:

\$ podman run --entrypoint performance-profile-creator -v /must-gather:/must-gather:z registry.redhat.io/openshift4/ose-cluster-node-tuning-operator:v4.16 --mcp-name=worker-cnf --reserved-cpu-count=4 --rt-kernel=true --split-reserved-cpus-across-numa=false --must-gather-dir-path /must-gather --power-consumption-mode=ultra-low-latency --offlined-cpu-count=6 > my-performance-profile.yaml



#### **NOTE**

The Performance Profile Creator arguments are shown in the Performance Profile Creator arguments table. The following arguments are required:

- reserved-cpu-count
- mcp-name
- rt-kernel

The **mcp-name** argument in this example is set to **worker-cnf** based on the output of the command **oc get mcp**. For single-node OpenShift use **--mcp-name=master**.

# 6. Review the created YAML file:

\$ cat my-performance-profile.yaml

# Example output

apiVersion: performance.openshift.io/v2 kind: PerformanceProfile metadata: name: performance spec: cpu: isolated: 2-39,48-79 offlined: 42-47 reserved: 0-1,40-41

```
machineConfigPoolSelector:
   machineconfiguration.openshift.io/role: worker-cnf
nodeSelector:
   node-role.kubernetes.io/worker-cnf: ""
numa:
   topologyPolicy: restricted
realTimeKernel:
   enabled: true
workloadHints:
   highPowerConsumption: true
realTime: true
```

7. Apply the generated profile:

\$ oc apply -f my-performance-profile.yaml

#### Additional resources

• For more information about the **must-gather** tool, see Gathering data about your cluster .

# 12.2.1.3.1. How to run podman to create a performance profile

The following example illustrates how to run **podman** to create a performance profile with 20 reserved CPUs that are to be split across the NUMA nodes.

Node hardware configuration:

- 80 CPUs
- Hyperthreading enabled
- Two NUMA nodes
- Even numbered CPUs run on NUMA node 0 and odd numbered CPUs run on NUMA node 1

Run **podman** to create the performance profile:

\$ podman run --entrypoint performance-profile-creator -v /must-gather:/must-gather:z registry.redhat.io/openshift4/ose-cluster-node-tuning-operator:v4.16 --mcp-name=worker-cnf -- reserved-cpu-count=20 --rt-kernel=true --split-reserved-cpus-across-numa=true --must-gather-dir-path /must-gather > my-performance-profile.yaml

The created profile is described in the following YAML:

```
apiVersion: performance.openshift.io/v2 kind: PerformanceProfile metadata: name: performance spec: cpu: isolated: 10-39,50-79 reserved: 0-9,40-49 nodeSelector: node-role.kubernetes.io/worker-cnf: "" numa:
```

topologyPolicy: restricted realTimeKernel: enabled: true



#### NOTE

In this case, 10 CPUs are reserved on NUMA node 0 and 10 are reserved on NUMA node 1.

# 12.2.1.3.2. Running the Performance Profile Creator wrapper script

The performance profile wrapper script simplifies the running of the Performance Profile Creator (PPC) tool. It hides the complexities associated with running **podman** and specifying the mapping directories and it enables the creation of the performance profile.

## **Prerequisites**

- Access to the Node Tuning Operator image.
- Access to the **must-gather** tarball.

#### **Procedure**

- 1. Create a file on your local machine named, for example, run-perf-profile-creator.sh:
  - \$ vi run-perf-profile-creator.sh
- 2. Paste the following code into the file:

```
#!/bin/bash
readonly CONTAINER_RUNTIME=${CONTAINER_RUNTIME:-podman}
readonly CURRENT SCRIPT=$(basename "$0")
readonly CMD="${CONTAINER RUNTIME} run --entrypoint performance-profile-creator"
readonly IMG_EXISTS_CMD="${CONTAINER_RUNTIME} image exists"
readonly IMG_PULL_CMD="${CONTAINER_RUNTIME} image pull"
readonly MUST GATHER VOL="/must-gather"
NTO IMG="registry.redhat.io/openshift4/ose-cluster-node-tuning-operator:v4.16"
MG TARBALL=""
DATA_DIR=""
usage() {
 print "Wrapper usage:"
 print " ${CURRENT_SCRIPT} [-h] [-p image][-t path] -- [performance-profile-creator flags]"
 print ""
 print "Options:"
 print " -h
                   help for ${CURRENT SCRIPT}"
                   Node Tuning Operator image"
 print " -p
 print " -t
                  path to a must-gather tarball"
 ${IMG_EXISTS_CMD} "${NTO_IMG}" && ${CMD} "${NTO_IMG}" -h
function cleanup {
```

```
[-d "${DATA_DIR}" ] && rm -rf "${DATA_DIR}"
trap cleanup EXIT
exit_error() {
 print "error: $*"
 usage
 exit 1
}
print() {
 echo "$*" >&2
check_requirements() {
 ${IMG_EXISTS_CMD} "${NTO_IMG}" || ${IMG_PULL_CMD} "${NTO_IMG}" || \
   exit_error "Node Tuning Operator image not found"
 [ -n "${MG_TARBALL}" ] || exit_error "Must-gather tarball file path is mandatory"
 [-f "${MG TARBALL}"]|| exit error "Must-gather tarball file not found"
 DATA_DIR=$(mktemp -d -t "${CURRENT_SCRIPT}XXXX") || exit_error "Cannot create the
data directory"
 tar -zxf "${MG TARBALL}" --directory "${DATA DIR}" || exit error "Cannot decompress the
must-gather tarball"
 chmod a+rx "${DATA_DIR}"
 return 0
}
main() {
 while getopts ':hp:t:' OPT; do
  case "${OPT}" in
   h)
    usage
    exit 0
   p)
    NTO_IMG="${OPTARG}"
    MG TARBALL="${OPTARG}"
    exit_error "invalid argument: ${OPTARG}"
  esac
 done
 shift $((OPTIND - 1))
 check_requirements || exit 1
 ${CMD} -v "${DATA_DIR}:${MUST_GATHER_VOL}:z" "${NTO_IMG}" "$@" --must-gather-
dir-path "${MUST_GATHER_VOL}"
 echo "" 1>&2
```

```
| }
| main "$@"
```

3. Add execute permissions for everyone on this script:

\$ chmod a+x run-perf-profile-creator.sh

- 4. Optional: Display the **run-perf-profile-creator.sh** command usage:
  - \$ ./run-perf-profile-creator.sh -h

## **Expected output**

```
Wrapper usage:
 run-perf-profile-creator.sh [-h] [-p image][-t path] -- [performance-profile-creator flags]
Options:
 -h
             help for run-perf-profile-creator.sh
             Node Tuning Operator image 1
 -p
             path to a must-gather tarball 2
 -t
A tool that automates creation of Performance Profiles
Usage:
 performance-profile-creator [flags]
   --disable-ht
                            Disable Hyperthreading
 -h, --help
                           help for performance-profile-creator
   --info string
                           Show cluster information; requires --must-gather-dir-path,
ignore the other arguments. [Valid values: log, json] (default "log")
   --mcp-name string
                                MCP name corresponding to the target machines
(required)
   --must-gather-dir-path string
                                  Must gather directory path (default "must-gather")
   --offlined-cpu-count int
                               Number of offlined CPUs
   --per-pod-power-management
                                     Enable Per Pod Power Management
   --power-consumption-mode string
                                      The power consumption mode. [Valid values:
default, low-latency, ultra-low-latency] (default "default")
   --profile-name string
                               Name of the performance profile to be created (default
"performance")
   --reserved-cpu-count int
                                 Number of reserved CPUs (required)
                           Enable Real Time Kernel (required)
   --rt-kernel
   --topology-manager-policy string Kubelet Topology Manager Policy of the performance
profile to be created. [Valid values: single-numa-node, best-effort, restricted] (default
"restricted")
                                Run with User level Networking(DPDK) enabled
   --user-level-networking
   --enable-hardware-tuning
                                  Enable setting maximum CPU frequencies
```



There two types of arguments:

- Wrapper arguments namely -h, -p and -t
- PPC arguments
- Optional: Specify the Node Tuning Operator image. If not set, the default upstream image is used: registry.redhat.io/openshift4/ose-cluster-node-tuning-operator:v4.16.
- **-t** is a required wrapper script argument and specifies the path to a **must-gather** tarball.
- 5. Run the performance profile creator tool in discovery mode:



#### **NOTE**

Discovery mode inspects your cluster using the output from **must-gather**. The output produced includes information on:

- The NUMA cell partitioning with the allocated CPU IDs
- Whether hyperthreading is enabled

Using this information you can set appropriate values for some of the arguments supplied to the Performance Profile Creator tool.

\$ ./run-perf-profile-creator.sh -t /must-gather/must-gather.tar.gz -- --info=log



#### **NOTE**

The **info** option requires a value which specifies the output format. Possible values are log and JSON. The JSON format is reserved for debugging.

6. Check the machine config pool:

\$ oc get mcp

## **Example output**

NAME CONFIG UPDATED UPDATING DEGRADED MACHINECOUNT READYMACHINECOUNT UPDATEDMACHINECOUNT DEGRADEDMACHINECOUNT AGE master rendered-master-acd1358917e9f98cbdb599aea622d78b True False False 3 3 0 22h worker-cnf rendered-worker-cnf-1d871ac76e1951d32b2fe92369879826 False True False 2 1 1 0 22h

7. Create a performance profile:

\$ ./run-perf-profile-creator.sh -t /must-gather/must-gather.tar.gz -- --mcp-name=worker-cnf -- reserved-cpu-count=2 --rt-kernel=true > my-performance-profile.yaml



The Performance Profile Creator arguments are shown in the Performance Profile Creator arguments table. The following arguments are required:

- reserved-cpu-count
- mcp-name
- rt-kernel

The **mcp-name** argument in this example is set to **worker-cnf** based on the output of the command **oc get mcp**. For single-node OpenShift use **--mcp-name=master**.

8. Review the created YAML file:

\$ cat my-performance-profile.yaml

# Example output

apiVersion: performance.openshift.io/v2

kind: PerformanceProfile

metadata:

name: performance

spec: cpu:

isolated: 1-39,41-79 reserved: 0,40

nodeSelector:

node-role.kubernetes.io/worker-cnf: ""

numa:

topologyPolicy: restricted

realTimeKernel: enabled: false



When you pass the argument **--enable-hardware-tuning** as a flag to the Performance Profile Creator, the generated **PerformanceProfile** includes guidance on how to set frequency settings as follows:

apiVersion: performance.openshift.io/v2

kind: PerformanceProfile

metadata:

name: performance

spec:

.....

#HardwareTuning is an advanced feature, and only intended to be used if #user is aware of the vendor recommendation on maximum cpu frequency. #The structure must follow

#

# hardwareTuning:

# isolatedCpuFreq: <Maximum frequency for applications running on isolated CPUs>

# reservedCpuFreq: <Maximum frequency for platform software running on reserved CPUs>

9. Apply the generated profile:



#### NOTE

Install the Node Tuning Operator before applying the profile.

\$ oc apply -f my-performance-profile.yaml

## 12.2.1.3.3. Performance Profile Creator arguments

Table 12.1. Performance Profile Creator arguments

Argument

Description

Argument	Description
disable-ht	Disable hyperthreading.  Possible values: <b>true</b> or <b>false</b> .  Default: <b>false</b> .
	WARNING  If this argument is set to <b>true</b> you should not disable hyperthreading in the BIOS. Disabling hyperthreading is accomplished with a kernel command line argument.
enable-hardware-tuning	Enable the setting of maximum CPU frequencies. This parameter is optional.  To enable this feature, set the maximum frequency for applications running on isolated and reserved CPUs for both of the following:  • spec.hardwareTuning.isolatedCpuFreq  • spec.hardwareTuning.reservedCpuFreq
info	This captures cluster information and is used in discovery mode only.  Discovery mode also requires the <b>must-gather-dir-path</b> argument. If any other arguments are set they are ignored.  Possible values:  • log  • JSON  NOTE  These options define the output format with the JSON format being reserved for debugging.  Default: log.
mcp-name	MCP name for example <b>worker-cnf</b> corresponding to the target machines. This parameter is required.
must-gather-dir-path	Must gather directory path. This parameter is required.  When the user runs the tool with the wrapper script <b>must-gather</b> is supplied by the script itself and the user must not specify it.

Argument	Description
offlined-cpu-count	NOTE  This must be a natural number greater than 0. If not enough logical processors are offlined then error messages are logged. The messages are:  Error: failed to compute the reserved and isolated CPUs: please ensure that reserved-cpu-count plus offlined-cpu-count should be in the range [0,1]  Error: failed to compute the reserved and isolated CPUs: please specify the offlined CPU count in the range [0,1]
power-consumption- mode	The power consumption mode.  Possible values:  • default: CPU partitioning with enabled power management and basic low-latency.  • low-latency: Enhanced measures to improve latency figures.  • ultra-low-latency: Priority given to optimal latency, at the expense of power management.  Default: default.
per-pod-power- management	Enable per pod power management. You cannot use this argument if you configured <b>ultra-low-latency</b> as the power consumption mode.  Possible values: <b>true</b> or <b>false</b> .  Default: <b>false</b> .
profile-name	Name of the performance profile to create. Default: <b>performance</b> .
reserved-cpu-count	Number of reserved CPUs. This parameter is required.  NOTE  This must be a natural number. A value of 0 is not allowed.
rt-kernel	Enable real-time kernel. This parameter is required.  Possible values: <b>true</b> or <b>false</b> .

Argument	Description
split-reserved-cpus- across-numa	Split the reserved CPUs across NUMA nodes.  Possible values: <b>true</b> or <b>false</b> .  Default: <b>false</b> .
topology-manager-policy	Kubelet Topology Manager policy of the performance profile to be created.  Possible values:  • single-numa-node  • best-effort  • restricted  Default: restricted.
user-level-networking	Run with user level networking (DPDK) enabled.  Possible values: <b>true</b> or <b>false</b> .  Default: <b>false</b> .

# 12.2.1.4. Reference performance profiles

Use the following reference performance profiles as the basis to develop your own custom profiles.

# 12.2.1.4.1. Performance profile template for clusters that use OVS-DPDK on OpenStack

To maximize machine performance in a cluster that uses Open vSwitch with the Data Plane Development Kit (OVS-DPDK) on Red Hat OpenStack Platform (RHOSP), you can use a performance profile.

You can use the following performance profile template to create a profile for your deployment.

# Performance profile template for clusters that use OVS-DPDK

apiVersion: performance.openshift.io/v2

kind: PerformanceProfile

metadata:

name: cnf-performanceprofile

spec:

additionalKernelArgs:

- nmi\_watchdog=0
- audit=0
- mce=off
- processor.max\_cstate=1
- idle=poll
- intel\_idle.max\_cstate=0
- default\_hugepagesz=1GB
- hugepagesz=1G

```
- intel_iommu=on
cpu:
isolated: <CPU_ISOLATED>
reserved: <CPU_RESERVED>
hugepages:
defaultHugepagesSize: 1G
pages:
- count: <HUGEPAGES_COUNT>
node: 0
size: 1G
nodeSelector:
node-role.kubernetes.io/worker: "
realTimeKernel:
enabled: false
globallyDisableIrqLoadBalancing: true
```

Insert values that are appropriate for your configuration for the **CPU\_ISOLATED**, **CPU\_RESERVED**, and **HUGEPAGES\_COUNT** keys.

# 12.2.1.4.2. Telco RAN DU reference design performance profile template

The following performance profile configures node-level performance settings for OpenShift Container Platform clusters on commodity hardware to host telco RAN DU workloads.

# Telco RAN DU reference design performance profile

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
 # if you change this name make sure the 'include' line in TunedPerformancePatch.yaml
 # matches this name: include=openshift-node-performance-${PerformanceProfile.metadata.name}
 # Also in file 'validatorCRs/informDuValidator.yaml':
 # name: 50-performance-${PerformanceProfile.metadata.name}
 name: openshift-node-performance-profile
 annotations:
  ran.openshift.io/reference-configuration: "ran-du.redhat.com"
spec:
 additionalKernelArgs:
  - "rcupdate.rcu_normal_after_boot=0"
  - "efi=runtime"
  - "vfio pci.enable sriov=1"
  - "vfio pci.disable idle d3=1"
  - "module blacklist=irdma"
 cpu:
  isolated: $isolated
  reserved: $reserved
 hugepages:
  defaultHugepagesSize: $defaultHugepagesSize
  pages:
   - size: $size
     count: $count
     node: $node
 machineConfigPoolSelector:
  pools.operator.machineconfiguration.openshift.io/$mcp: ""
 nodeSelector:
```

```
node-role.kubernetes.io/$mcp: "
numa:
topologyPolicy: "restricted"
# To use the standard (non-realtime) kernel, set enabled to false
realTimeKernel:
enabled: true
workloadHints:
# WorkloadHints defines the set of upper level flags for different type of workloads.
# See https://github.com/openshift/cluster-node-tuning-
operator/blob/master/docs/performanceprofile/performance_profile.md#workloadhints
# for detailed descriptions of each item.
# The configuration below is set for a low latency, performance mode.
realTime: true
highPowerConsumption: false
perPodPowerManagement: false
```

## 12.2.1.4.3. Telco core reference design performance profile template

The following performance profile configures node-level performance settings for OpenShift Container Platform clusters on commodity hardware to host telco core workloads.

# Telco core reference design performance profile

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
 # if you change this name make sure the 'include' line in TunedPerformancePatch.yaml
 # matches this name: include=openshift-node-performance-${PerformanceProfile.metadata.name}
 # Also in file 'validatorCRs/informDuValidator.yaml':
 # name: 50-performance-${PerformanceProfile.metadata.name}
 name: openshift-node-performance-profile
 annotations:
  ran.openshift.io/reference-configuration: "ran-du.redhat.com"
 additionalKernelArgs:
  - "rcupdate.rcu_normal_after_boot=0"
  - "efi=runtime"
  - "vfio pci.enable sriov=1"
  - "vfio pci.disable idle d3=1"
  - "module blacklist=irdma"
 cpu:
  isolated: $isolated
  reserved: $reserved
 hugepages:
  defaultHugepagesSize: $defaultHugepagesSize
  pages:
   - size: $size
     count: $count
     node: $node
 machineConfigPoolSelector:
  pools.operator.machineconfiguration.openshift.io/$mcp: ""
 nodeSelector:
  node-role.kubernetes.io/$mcp: "
 numa:
  topologyPolicy: "restricted"
```

# To use the standard (non-realtime) kernel, set enabled to false

realTimeKernel: enabled: true workloadHints:

# WorkloadHints defines the set of upper level flags for different type of workloads.

# See https://github.com/openshift/cluster-node-tuning-

operator/blob/master/docs/performanceprofile/performance\_profile.md#workloadhints

# for detailed descriptions of each item.

# The configuration below is set for a low latency, performance mode.

realTime: true

highPowerConsumption: false perPodPowerManagement: false

# 12.2.2. Supported performance profile API versions

The Node Tuning Operator supports **v2**, **v1**, and **v1alpha1** for the performance profile **apiVersion** field. The v1 and v1alpha1 APIs are identical. The v2 API includes an optional boolean field **globallyDisableIrqLoadBalancing** with a default value of **false**.

## Upgrading the performance profile to use device interrupt processing

When you upgrade the Node Tuning Operator performance profile custom resource definition (CRD) from v1 or v1alpha1 to v2, **globallyDisableIrqLoadBalancing** is set to **true** on existing profiles.



#### NOTE

**globallyDisableIrqLoadBalancing** toggles whether IRQ load balancing will be disabled for the Isolated CPU set. When the option is set to **true** it disables IRQ load balancing for the Isolated CPU set. Setting the option to **false** allows the IRQs to be balanced across all CPUs.

## Upgrading Node Tuning Operator API from v1alpha1 to v1

When upgrading Node Tuning Operator API version from v1alpha1 to v1, the v1alpha1 performance profiles are converted on-the-fly using a "None" Conversion strategy and served to the Node Tuning Operator with API version v1.

#### Upgrading Node Tuning Operator API from v1alpha1 or v1 to v2

When upgrading from an older Node Tuning Operator API version, the existing v1 and v1alpha1 performance profiles are converted using a conversion webhook that injects the **globallyDisableIrqLoadBalancing** field with a value of **true**.

# 12.2.3. Configuring node power consumption and realtime processing with workload hints

#### **Procedure**

- 1. Create a **PerformanceProfile** appropriate for the environment's hardware and topology as described in the table in "Understanding workload hints". Adjust the profile to match the expected workload. In this example, we tune for the lowest possible latency.
- 2. Add the **highPowerConsumption** and **realTime** workload hints. Both are set to **true** here.

apiVersion: performance.openshift.io/v2 kind: PerformanceProfile

metadata:

name: workload-hints

spec:

...

workloadHints:

highPowerConsumption: true 1

realTime: true 2

If **highPowerConsumption** is **true**, the node is tuned for very low latency at the cost of increased power consumption.

Disables some debugging and monitoring features that can affect system latency.



## **NOTE**

When the **realTime** workload hint flag is set to **true** in a performance profile, add the **cpu-quota.crio.io: disable** annotation to every guaranteed pod with pinned CPUs. This annotation is necessary to prevent the degradation of the process performance within the pod. If the **realTime** workload hint is not explicitly set then it defaults to **true**.

The following table describes how combinations of power consumption and real-time settings impact latency.

Table 12.2. Impact of combinations of power consumption and real-time settings on latency

Performance Profile creator setting	Hint	Environment	Description
Default	workloadHints: highPowerConsum ption: false realTime: false	High throughput cluster without latency requirements	Performance achieved through CPU partitioning only.
Low-latency	workloadHints: highPowerConsum ption: false realTime: true	Regional data-centers	Both energy savings and low-latency are desirable: compromise between power management, latency and throughput.
Ultra-low-latency	workloadHints: highPowerConsum ption: true realTime: true	Far edge clusters, latency critical workloads	Optimized for absolute minimal latency and maximum determinism at the cost of increased power consumption.

Performance Profile creator setting	Hint	Environment	Description
Per-pod power management	workloadHints: realTime: true highPowerConsum ption: false perPodPowerMana gement: true	Critical and non-critical workloads	Allows for power management per pod.

## 12.2.4. Configuring power saving for nodes that run colocated high and low priority workloads

You can enable power savings for a node that has low priority workloads that are colocated with high priority workloads without impacting the latency or throughput of the high priority workloads. Power saving is possible without modifications to the workloads themselves.



#### **IMPORTANT**

The feature is supported on Intel Ice Lake and later generations of Intel CPUs. The capabilities of the processor might impact the latency and throughput of the high priority workloads.

#### **Prerequisites**

You enabled C-states and operating system controlled P-states in the BIOS

#### **Procedure**

1. Generate a **PerformanceProfile** with the **per-pod-power-management** argument set to **true**:

\$ podman run --entrypoint performance-profile-creator -v \ /must-gather:/must-gather:z registry.redhat.io/openshift4/ose-cluster-node-tuningoperator:v4.16 \

- --mcp-name=worker-cnf --reserved-cpu-count=20 --rt-kernel=true \
- --split-reserved-cpus-across-numa=false --topology-manager-policy=single-numa-node \
- --must-gather-dir-path /must-gather --power-consumption-mode=low-latency \ 11
- --per-pod-power-management=true > my-performance-profile.yaml
- The power-consumption-mode argument must be default or low-latency when the perpod-power-management argument is set to true.

### Example PerformanceProfile with perPodPowerManagement

apiVersion: performance.openshift.io/v2 kind: PerformanceProfile metadata: name: performance spec: [.....]

workloadHints: realTime: true

highPowerConsumption: false perPodPowerManagement: true

2. Set the default **cpufreq** governor as an additional kernel argument in the **PerformanceProfile** custom resource (CR):

apiVersion: performance.openshift.io/v2 kind: PerformanceProfile metadata:

name: performance

spec:

...

additionalKernelArgs:

- cpufreq.default\_governor=schedutil 1
- Using the **schedutil** governor is recommended, however, you can use other governors such as the **ondemand** or **powersave** governors.
- 3. Set the maximum CPU frequency in the **TunedPerformancePatch** CR:

spec:
 profile:
 - data: |
 [sysfs]
 /sys/devices/system/cpu/intel\_pstate/max\_perf\_pct = <x> 1

The max\_perf\_pct controls the maximum frequency that the cpufreq driver is allowed to set as a percentage of the maximum supported cpu frequency. This value applies to all CPUs. You can check the maximum supported frequency in /sys/devices/system/cpu/cpu0/cpufreq/cpuinfo\_max\_freq. As a starting point, you can use a percentage that caps all CPUs at the All Cores Turbo frequency. The All Cores Turbo frequency is the frequency that all cores will run at when the cores are all fully occupied.

#### Additional resources

- Disabling power saving mode for high priority pods
- Managing device interrupt processing for guaranteed pod isolated CPUs

# 12.2.5. Restricting CPUs for infra and application containers

Generic housekeeping and workload tasks use CPUs in a way that may impact latency-sensitive processes. By default, the container runtime uses all online CPUs to run all containers together, which can result in context switches and spikes in latency. Partitioning the CPUs prevents noisy processes from interfering with latency-sensitive processes by separating them from each other. The following table describes how processes run on a CPU after you have tuned the node using the Node Tuning Operator:

## Table 12.3. Process' CPU assignments

Process type	Details
Burstable and BestEffort pods	Runs on any CPU except where low latency workload is running
Infrastructure pods	Runs on any CPU except where low latency workload is running
Interrupts	Redirects to reserved CPUs (optional in OpenShift Container Platform 4.7 and later)
Kernel processes	Pins to reserved CPUs
Latency-sensitive workload pods	Pins to a specific set of exclusive CPUs from the isolated pool
OS processes/systemd services	Pins to reserved CPUs

The allocatable capacity of cores on a node for pods of all QoS process types, **Burstable**, **BestEffort**, or **Guaranteed**, is equal to the capacity of the isolated pool. The capacity of the reserved pool is removed from the node's total core capacity for use by the cluster and operating system housekeeping duties.

## Example 1

A node features a capacity of 100 cores. Using a performance profile, the cluster administrator allocates 50 cores to the isolated pool and 50 cores to the reserved pool. The cluster administrator assigns 25 cores to QoS **Guaranteed** pods and 25 cores for **BestEffort** or **Burstable** pods. This matches the capacity of the isolated pool.

### Example 2

A node features a capacity of 100 cores. Using a performance profile, the cluster administrator allocates 50 cores to the isolated pool and 50 cores to the reserved pool. The cluster administrator assigns 50 cores to QoS **Guaranteed** pods and one core for **BestEffort** or **Burstable** pods. This exceeds the capacity of the isolated pool by one core. Pod scheduling fails because of insufficient CPU capacity.

The exact partitioning pattern to use depends on many factors like hardware, workload characteristics and the expected system load. Some sample use cases are as follows:

- If the latency-sensitive workload uses specific hardware, such as a network interface controller (NIC), ensure that the CPUs in the isolated pool are as close as possible to this hardware. At a minimum, you should place the workload in the same Non-Uniform Memory Access (NUMA) node.
- The reserved pool is used for handling all interrupts. When depending on system networking, allocate a sufficiently-sized reserve pool to handle all the incoming packet interrupts. In 4.16 and later versions, workloads can optionally be labeled as sensitive.

The decision regarding which specific CPUs should be used for reserved and isolated partitions requires detailed analysis and measurements. Factors like NUMA affinity of devices and memory play a role. The selection also depends on the workload architecture and the specific use case.



#### **IMPORTANT**

The reserved and isolated CPU pools must not overlap and together must span all available cores in the worker node.

To ensure that housekeeping tasks and workloads do not interfere with each other, specify two groups of CPUs in the **spec** section of the performance profile.

- **isolated** Specifies the CPUs for the application container workloads. These CPUs have the lowest latency. Processes in this group have no interruptions and can, for example, reach much higher DPDK zero packet loss bandwidth.
- **reserved** Specifies the CPUs for the cluster and operating system housekeeping duties. Threads in the **reserved** group are often busy. Do not run latency-sensitive applications in the **reserved** group. Latency-sensitive applications run in the **isolated** group.

#### **Procedure**

- 1. Create a performance profile appropriate for the environment's hardware and topology.
- 2. Add the **reserved** and **isolated** parameters with the CPUs you want reserved and isolated for the infra and application containers:

apiVersion: performance.openshift.io/v2

kind: PerformanceProfile

metadata:

name: infra-cpus

spec: cpu:

reserved: "0-4,9" 1

isolated: "5-8" 2

nodeSelector: 3

node-role.kubernetes.io/worker: ""

- Specify which CPUs are for infra containers to perform cluster and operating system housekeeping duties.
- 2 Specify which CPUs are for application containers to run workloads.
- Optional: Specify a node selector to apply the performance profile to specific nodes.

# 12.2.6. Configuring Hyper-Threading for a cluster

To configure Hyper-Threading for an OpenShift Container Platform cluster, set the CPU threads in the performance profile to the same cores that are configured for the reserved or isolated CPU pools.



## NOTE

If you configure a performance profile, and subsequently change the Hyper-Threading configuration for the host, ensure that you update the CPU **isolated** and **reserved** fields in the **PerformanceProfile** YAML to match the new configuration.



### **WARNING**

Disabling a previously enabled host Hyper-Threading configuration can cause the CPU core IDs listed in the **PerformanceProfile** YAML to be incorrect. This incorrect configuration can cause the node to become unavailable because the listed CPUs can no longer be found.

## **Prerequisites**

- Access to the cluster as a user with the **cluster-admin** role.
- Install the OpenShift CLI (oc).

### Procedure

Ascertain which threads are running on what CPUs for the host you want to configure.
 You can view which threads are running on the host CPUs by logging in to the cluster and running the following command:

```
$ Iscpu --all --extended
```

## **Example output**

```
CPU NODE SOCKET CORE L1d:L1i:L2:L3 ONLINE MAXMHZ MINMHZ
                   yes 4800.0000 400.0000
0 0
        0:0:0:0
1
  0
        1 1:1:1:0 yes 4800.0000 400.0000
2 0 0 2 2:2:2:0 yes 4800.0000 400.0000
3 0 0 3 3:3:3:0 yes 4800.0000 400.0000
4 0 0 0 0:0:0:0 yes 4800.0000 400.0000
5
 0 0
       1 1:1:1:0
                    yes 4800.0000 400.0000
6
                    yes 4800.0000 400.0000
        2 2:2:2:0
7
         3 3:3:3:0
                    yes 4800.0000 400.0000
```

In this example, there are eight logical CPU cores running on four physical CPU cores. CPU0 and CPU4 are running on physical Core0, CPU1 and CPU5 are running on physical Core 1, and so on.

Alternatively, to view the threads that are set for a particular physical CPU core (**cpu0** in the example below), open a shell prompt and run the following:

\$ cat /sys/devices/system/cpu/cpu0/topology/thread\_siblings\_list

## **Example output**

0-4

2. Apply the isolated and reserved CPUs in the **PerformanceProfile** YAML. For example, you can set logical cores CPU0 and CPU4 as **isolated**, and logical cores CPU1 to CPU3 and CPU5 to CPU7 as **reserved**. When you configure reserved and isolated CPUs, the infra containers in

pods use the reserved CPUs and the application containers use the isolated CPUs.

```
...
cpu:
isolated: 0,4
reserved: 1-3,5-7
...
```



#### NOTE

The reserved and isolated CPU pools must not overlap and together must span all available cores in the worker node.



### **IMPORTANT**

Hyper-Threading is enabled by default on most Intel processors. If you enable Hyper-Threading, all threads processed by a particular core must be isolated or processed on the same core.

When Hyper-Threading is enabled, all guaranteed pods must use multiples of the simultaneous multi-threading (SMT) level to avoid a "noisy neighbor" situation that can cause the pod to fail. See Static policy options for more information.

## 12.2.6.1. Disabling Hyper-Threading for low latency applications

When configuring clusters for low latency processing, consider whether you want to disable Hyper-Threading before you deploy the cluster. To disable Hyper-Threading, perform the following steps:

- 1. Create a performance profile that is appropriate for your hardware and topology.
- 2. Set **nosmt** as an additional kernel argument. The following example performance profile illustrates this setting:

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
 name: example-performanceprofile
spec:
 additionalKernelArgs:
  - nmi_watchdog=0
  - audit=0
  - mce=off
  - processor.max cstate=1
  - idle=poll
  - intel_idle.max_cstate=0
  - nosmt
 cpu:
  isolated: 2-3
  reserved: 0-1
 hugepages:
  defaultHugepagesSize: 1G
  pages:
   - count: 2
    node: 0
    size: 1G
```

nodeSelector: node-role.kubernetes.io/performance: " realTimeKernel: enabled: true



#### NOTE

When you configure reserved and isolated CPUs, the infra containers in pods use the reserved CPUs and the application containers use the isolated CPUs.

## 12.2.7. Managing device interrupt processing for guaranteed pod isolated CPUs

The Node Tuning Operator can manage host CPUs by dividing them into reserved CPUs for cluster and operating system housekeeping duties, including pod infra containers, and isolated CPUs for application containers to run the workloads. This allows you to set CPUs for low latency workloads as isolated.

Device interrupts are load balanced between all isolated and reserved CPUs to avoid CPUs being overloaded, with the exception of CPUs where there is a guaranteed pod running. Guaranteed pod CPUs are prevented from processing device interrupts when the relevant annotations are set for the pod.

In the performance profile, **globallyDisableIrqLoadBalancing** is used to manage whether device interrupts are processed or not. For certain workloads, the reserved CPUs are not always sufficient for dealing with device interrupts, and for this reason, device interrupts are not globally disabled on the isolated CPUs. By default, Node Tuning Operator does not disable device interrupts on isolated CPUs.

## 12.2.7.1. Finding the effective IRQ affinity setting for a node

Some IRQ controllers lack support for IRQ affinity setting and will always expose all online CPUs as the IRQ mask. These IRQ controllers effectively run on CPU 0.

The following are examples of drivers and hardware that Red Hat are aware lack support for IRQ affinity setting. The list is, by no means, exhaustive:

- Some RAID controller drivers, such as megaraid\_sas
- Many non-volatile memory express (NVMe) drivers
- Some LAN on motherboard (LOM) network controllers
- The driver uses managed\_irqs



#### NOTE

The reason they do not support IRQ affinity setting might be associated with factors such as the type of processor, the IRQ controller, or the circuitry connections in the motherboard.

If the effective affinity of any IRQ is set to an isolated CPU, it might be a sign of some hardware or driver not supporting IRQ affinity setting. To find the effective affinity, log in to the host and run the following command:

 $\$  find /proc/irq -name effective\_affinity -printf "%p: " -exec cat {} \;

## Example output

/proc/irq/0/effective affinity: 1 /proc/irq/1/effective affinity: 8 /proc/irq/2/effective affinity: 0 /proc/irq/3/effective affinity: 1 /proc/irq/4/effective\_affinity: 2 /proc/irq/5/effective\_affinity: 1 /proc/irg/6/effective affinity: 1 /proc/irg/7/effective affinity: 1 /proc/irq/8/effective\_affinity: 1 /proc/irq/9/effective\_affinity: 2 /proc/irg/10/effective affinity: 1 /proc/irq/11/effective affinity: 1 /proc/irq/12/effective affinity: 4 /proc/irq/13/effective\_affinity: 1 /proc/irq/14/effective\_affinity: 1 /proc/irq/15/effective affinity: 1 /proc/irg/24/effective affinity: 2 /proc/irq/25/effective\_affinity: 4 /proc/irq/26/effective\_affinity: 2 /proc/irg/27/effective affinity: 1 /proc/irg/28/effective affinity: 8 /proc/irg/29/effective affinity: 4 /proc/irq/30/effective\_affinity: 4 /proc/irq/31/effective\_affinity: 8 /proc/irq/32/effective affinity: 8 /proc/irq/33/effective affinity: 1 /proc/irq/34/effective affinity: 2

Some drivers use **managed\_irqs**, whose affinity is managed internally by the kernel and userspace cannot change the affinity. In some cases, these IRQs might be assigned to isolated CPUs. For more information about **managed\_irqs**, see Affinity of managed interrupts cannot be changed even if they target isolated CPU.

### 12.2.7.2. Configuring node interrupt affinity

Configure a cluster node for IRQ dynamic load balancing to control which cores can receive device interrupt requests (IRQ).

## **Prerequisites**

 For core isolation, all server hardware components must support IRQ affinity. To check if the hardware components of your server support IRQ affinity, view the server's hardware specifications or contact your hardware provider.

### Procedure

- 1. Log in to the OpenShift Container Platform cluster as a user with cluster-admin privileges.
- 2. Set the performance profile apiVersion to use performance.openshift.io/v2.
- 3. Remove the **globallyDisableIrqLoadBalancing** field or set it to **false**.

4. Set the appropriate isolated and reserved CPUs. The following snippet illustrates a profile that reserves 2 CPUs. IRQ load-balancing is enabled for pods running on the **isolated** CPU set:

```
apiVersion: performance.openshift.io/v2 kind: PerformanceProfile metadata: name: dynamic-irq-profile spec: cpu: isolated: 2-5 reserved: 0-1 ...
```



#### NOTE

When you configure reserved and isolated CPUs, operating system processes, kernel processes, and systemd services run on reserved CPUs. Infrastructure pods run on any CPU except where the low latency workload is running. Low latency workload pods run on exclusive CPUs from the isolated pool. For more information, see "Restricting CPUs for infra and application containers".

## 12.2.8. Configuring huge pages

Nodes must pre-allocate huge pages used in an OpenShift Container Platform cluster. Use the Node Tuning Operator to allocate huge pages on a specific node.

OpenShift Container Platform provides a method for creating and allocating huge pages. Node Tuning Operator provides an easier method for doing this using the performance profile.

For example, in the **hugepages pages** section of the performance profile, you can specify multiple blocks of **size**, **count**, and, optionally, **node**:

```
hugepages:
defaultHugepagesSize: "1G"
pages:
- size: "1G"
count: 4
node: 0 1
```

**node** is the NUMA node in which the huge pages are allocated. If you omit **node**, the pages are evenly spread across all NUMA nodes.



### **NOTE**

Wait for the relevant machine config pool status that indicates the update is finished.

These are the only configuration steps you need to do to allocate huge pages.

#### Verification

• To verify the configuration, see the /proc/meminfo file on the node:

\$ oc debug node/ip-10-0-141-105.ec2.internal

# grep -i huge /proc/meminfo

## **Example output**

AnonHugePages: ##### ##
ShmemHugePages: 0 kB
HugePages\_Total: 2
HugePages\_Free: 2
HugePages\_Rsvd: 0
HugePages\_Surp: 0
Hugepagesize: #####
Hugetlb: ######

• Use **oc describe** to report the new size:

\$ oc describe node worker-0.ocp4poc.example.com | grep -i huge

## **Example output**

```
hugepages-1g=true
hugepages-###: ###
hugepages-###: ###
```

## 12.2.8.1. Allocating multiple huge page sizes

You can request huge pages with different sizes under the same container. This allows you to define more complicated pods consisting of containers with different huge page size needs.

For example, you can define sizes **1G** and **2M** and the Node Tuning Operator will configure both sizes on the node, as shown here:

```
spec:
hugepages:
defaultHugepagesSize: 1G
pages:
- count: 1024
node: 0
size: 2M
- count: 4
node: 1
size: 1G
```

## 12.2.9. Reducing NIC queues using the Node Tuning Operator

The Node Tuning Operator facilitates reducing NIC queues for enhanced performance. Adjustments are made using the performance profile, allowing customization of queues for different network devices.

## 12.2.9.1. Adjusting the NIC queues with the performance profile

The performance profile lets you adjust the queue count for each network device.

### Supported network devices:

- Non-virtual network devices
- Network devices that support multiple queues (channels)

### Unsupported network devices:

- Pure software network interfaces
- Block devices
- Intel DPDK virtual functions

### **Prerequisites**

- Access to the cluster as a user with the cluster-admin role.
- Install the OpenShift CLI (oc).

#### **Procedure**

- 1. Log in to the OpenShift Container Platform cluster running the Node Tuning Operator as a user with **cluster-admin** privileges.
- 2. Create and apply a performance profile appropriate for your hardware and topology. For guidance on creating a profile, see the "Creating a performance profile" section.
- 3. Edit this created performance profile:
  - \$ oc edit -f <your\_profile\_name>.yaml
- 4. Populate the **spec** field with the **net** object. The object list can contain two fields:
  - userLevelNetworking is a required field specified as a boolean flag. If
    userLevelNetworking is true, the queue count is set to the reserved CPU count for all
    supported devices. The default is false.
  - **devices** is an optional field specifying a list of devices that will have the queues set to the reserved CPU count. If the device list is empty, the configuration applies to all network devices. The configuration is as follows:
    - **interfaceName**: This field specifies the interface name, and it supports shell-style wildcards, which can be positive or negative.
      - Example wildcard syntax is as follows: <string> .\*
      - Negative rules are prefixed with an exclamation mark. To apply the net queue changes to all devices other than the excluded list, use !<device>, for example, !eno1.
    - **vendorID**: The network device vendor ID represented as a 16-bit hexadecimal number with a **0x** prefix.
    - **deviceID**: The network device ID (model) represented as a 16-bit hexadecimal number with a **0x** prefix.



#### NOTE

When a **deviceID** is specified, the **vendorID** must also be defined. A device that matches all of the device identifiers specified in a device entry **interfaceName**, **vendorID**, or a pair of **vendorID** plus **deviceID** qualifies as a network device. This network device then has its net queues count set to the reserved CPU count.

When two or more devices are specified, the net queues count is set to any net device that matches one of them.

5. Set the queue count to the reserved CPU count for all devices by using this example performance profile:

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
name: manual
spec:
cpu:
isolated: 3-51,55-103
reserved: 0-2,52-54
net:
userLevelNetworking: true
nodeSelector:
node-role.kubernetes.io/worker-cnf: ""
```

6. Set the queue count to the reserved CPU count for all devices matching any of the defined device identifiers by using this example performance profile:

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
name: manual
spec:
cpu:
isolated: 3-51,55-103
reserved: 0-2,52-54
net:
userLevelNetworking: true
devices:
- interfaceName: "eth0"
- interfaceName: "eth1"
- vendorID: "0x1af4"
deviceID: "0x1000"
nodeSelector:
node-role.kubernetes.io/worker-cnf: ""
```

7. Set the queue count to the reserved CPU count for all devices starting with the interface name **eth** by using this example performance profile:

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
name: manual
```

```
spec:
cpu:
isolated: 3-51,55-103
reserved: 0-2,52-54
net:
userLevelNetworking: true
devices:
- interfaceName: "eth*"
nodeSelector:
node-role.kubernetes.io/worker-cnf: ""
```

8. Set the queue count to the reserved CPU count for all devices with an interface named anything other than **eno1** by using this example performance profile:

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
name: manual
spec:
cpu:
isolated: 3-51,55-103
reserved: 0-2,52-54
net:
userLevelNetworking: true
devices:
- interfaceName: "!eno1"
nodeSelector:
node-role.kubernetes.io/worker-cnf: ""
```

9. Set the queue count to the reserved CPU count for all devices that have an interface name **eth0**, **vendorID** of **0x1af4**, and **deviceID** of **0x1000** by using this example performance profile:

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
name: manual
spec:
cpu:
isolated: 3-51,55-103
reserved: 0-2,52-54
net:
userLevelNetworking: true
devices:
- interfaceName: "eth0"
- vendorID: "0x1af4"
deviceID: "0x1000"
nodeSelector:
node-role.kubernetes.io/worker-cnf: ""
```

10. Apply the updated performance profile:

#### Additional resources

Creating a performance profile.

## 12.2.9.2. Verifying the queue status

In this section, a number of examples illustrate different performance profiles and how to verify the changes are applied.

## Example 1

In this example, the net queue count is set to the reserved CPU count (2) for all supported devices.

The relevant section from the performance profile is:

```
apiVersion: performance.openshift.io/v2
metadata:
    name: performance
spec:
    kind: PerformanceProfile
    spec:
    cpu:
    reserved: 0-1 #total = 2
    isolated: 2-8
    net:
    userLevelNetworking: true
# ...
```

• Display the status of the queues associated with a device using the following command:



### NOTE

Run this command on the node where the performance profile was applied.

\$ ethtool -l <device>

• Verify the queue status before the profile is applied:

```
$ ethtool -l ens4
```

## **Example output**

```
Channel parameters for ens4:
Pre-set maximums:
RX: 0
TX: 0
Other: 0
Combined: 4
Current hardware settings:
RX: 0
TX: 0
Other: 0
Combined: 4
```

• Verify the queue status after the profile is applied:

\$ ethtool -I ens4

## **Example output**

Channel parameters for ens4:
Pre-set maximums:
RX: 0
TX: 0
Other: 0
Combined: 4
Current hardware settings:
RX: 0
TX: 0
Other: 0
Combined: 2

The combined channel shows that the total count of reserved CPUs for *all* supported devices is 2. This matches what is configured in the performance profile.

## Example 2

In this example, the net queue count is set to the reserved CPU count (2) for *all* supported network devices with a specific **vendorID**.

The relevant section from the performance profile is:

```
apiVersion: performance.openshift.io/v2
metadata:
    name: performance
spec:
    kind: PerformanceProfile
    spec:
    cpu:
    reserved: 0-1 #total = 2
    isolated: 2-8
    net:
    userLevelNetworking: true
    devices:
    - vendorID = 0x1af4
# ...
```

• Display the status of the queues associated with a device using the following command:



#### **NOTE**

Run this command on the node where the performance profile was applied.

\$ ethtool -l <device>

• Verify the queue status after the profile is applied:

\$ ethtool -l ens4

## Example output

```
Channel parameters for ens4:
Pre-set maximums:
RX: 0
TX: 0
Other: 0
Combined: 4
Current hardware settings:
RX: 0
TX: 0
Other: 0
Combined: 2
```

The total count of reserved CPUs for all supported devices with **vendorID=0x1af4** is 2. For example, if there is another network device **ens2** with **vendorID=0x1af4** it will also have total net queues of 2. This matches what is configured in the performance profile.

## Example 3

In this example, the net queue count is set to the reserved CPU count (2) for all supported network devices that match any of the defined device identifiers.

The command **udevadm info** provides a detailed report on a device. In this example the devices are:

```
# udevadm info -p /sys/class/net/ens4
...
E: ID_MODEL_ID=0x1000
E: ID_VENDOR_ID=0x1af4
E: INTERFACE=ens4
...

# udevadm info -p /sys/class/net/eth0
...
E: ID_MODEL_ID=0x1002
E: ID_VENDOR_ID=0x1001
E: INTERFACE=eth0
...
```

• Set the net queues to 2 for a device with **interfaceName** equal to **eth0** and any devices that have a **vendorID=0x1af4** with the following performance profile:

```
apiVersion: performance.openshift.io/v2
metadata:
name: performance
spec:
kind: PerformanceProfile
spec:
cpu:
reserved: 0-1 #total = 2
isolated: 2-8
net:
userLevelNetworking: true
devices:
```

```
interfaceName = eth0vendorID = 0x1af4
```

Verify the queue status after the profile is applied:

\$ ethtool -l ens4

## **Example output**

Channel parameters for ens4:

Pre-set maximums:

RX: 0 TX: 0 Other: 0 Combined: 4

Current hardware settings:

RX: 0 TX: 0 Other: 0 Combined: 2 1

The total count of reserved CPUs for all supported devices with **vendorID=0x1af4** is set to 2. For example, if there is another network device **ens2** with **vendorID=0x1af4**, it will also have the total net queues set to 2. Similarly, a device with **interfaceName** equal to **eth0** will have total net queues set to 2.

## 12.2.9.3. Logging associated with adjusting NIC queues

Log messages detailing the assigned devices are recorded in the respective Tuned daemon logs. The following messages might be recorded to the /var/log/tuned/tuned.log file:

- An INFO message is recorded detailing the successfully assigned devices:
  - INFO tuned.plugins.base: instance net\_test (net): assigning devices ens1, ens2, ens3
- A WARNING message is recorded if none of the devices can be assigned:
  - WARNING tuned.plugins.base: instance net\_test: no matching devices available

## 12.3. PROVISIONING REAL-TIME AND LOW LATENCY WORKLOADS

Many organizations need high performance computing and low, predictable latency, especially in the financial and telecommunications industries.

OpenShift Container Platform provides the Node Tuning Operator to implement automatic tuning to achieve low latency performance and consistent response time for OpenShift Container Platform applications. You use the performance profile configuration to make these changes. You can update the kernel to kernel-rt, reserve CPUs for cluster and operating system housekeeping duties, including pod infra containers, isolate CPUs for application containers to run the workloads, and disable unused CPUs to reduce power consumption.



#### **NOTE**

When writing your applications, follow the general recommendations described in RHEL for Real Time processes and threads.

#### Additional resources

• Tuning nodes for low latency with the performance profile

## 12.3.1. Scheduling a low latency workload onto a worker with real-time capabilities

You can schedule low latency workloads onto a worker node where a performance profile that configures real-time capabilities is applied.



#### NOTE

To schedule the workload on specific nodes, use label selectors in the **Pod** custom resource (CR). The label selectors must match the nodes that are attached to the machine config pool that was configured for low latency by the Node Tuning Operator.

## **Prerequisites**

- You have installed the OpenShift CLI (oc).
- You have logged in as a user with **cluster-admin** privileges.
- You have applied a performance profile in the cluster that tunes worker nodes for low latency workloads.

#### **Procedure**

1. Create a **Pod** CR for the low latency workload and apply it in the cluster, for example:

### Example Pod spec configured to use real-time processing

```
apiVersion: v1
kind: Pod
metadata:
 name: dynamic-low-latency-pod
 annotations:
  cpu-quota.crio.io: "disable" 1
  cpu-load-balancing.crio.io: "disable" (2)
  irq-load-balancing.crio.io: "disable" (3)
spec:
 securityContext:
  runAsNonRoot: true
  seccompProfile:
   type: RuntimeDefault
 containers:
 - name: dynamic-low-latency-pod
  image: "registry.redhat.io/openshift4/cnf-tests-rhel8:v4.16"
  command: ["sleep", "10h"]
  resources:
   requests:
```

```
cpu: 2
memory: "200M"

limits:
cpu: 2
memory: "200M"

securityContext:
allowPrivilegeEscalation: false
capabilities:
drop: [ALL]
nodeSelector:
node-role.kubernetes.io/worker-cnf: ""

runtimeClassName: performance-dynamic-low-latency-profile

...
```

- 1 Disables the CPU completely fair scheduler (CFS) quota at the pod run time.
- Disables CPU load balancing.
- Opts the pod out of interrupt handling on the node.
- The **nodeSelector** label must match the label that you specify in the **Node** CR.
- **runtimeClassName** must match the name of the performance profile configured in the cluster.
- Enter the pod runtimeClassName in the form performance-<profile\_name>, where
   <profile\_name> is the name from the PerformanceProfile YAML. In the previous example, the name is performance-dynamic-low-latency-profile.
- 3. Ensure the pod is running correctly. Status should be **running**, and the correct cnf-worker node should be set:

\$ oc get pod -o wide

## **Expected output**

NAME READY STATUS RESTARTS AGE IP NODE dynamic-low-latency-pod 1/1 Running 0 5h33m 10.131.0.10 cnf-worker.example.com

4. Get the CPUs that the pod configured for IRQ dynamic load balancing runs on:

\$ oc exec -it dynamic-low-latency-pod -- /bin/bash -c "grep Cpus\_allowed\_list /proc/self/status | awk '{print \$2}'"

## **Expected output**

Cpus\_allowed\_list: 2-3

### Verification

Ensure the node configuration is applied correctly.

1. Log in to the node to verify the configuration.

\$ oc debug node/<node-name>

2. Verify that you can use the node file system:

sh-4.4# chroot /host

## **Expected output**

sh-4.4#

3. Ensure the default system CPU affinity mask does not include the **dynamic-low-latency-pod** CPUs, for example, CPUs 2 and 3.

sh-4.4# cat /proc/irq/default\_smp\_affinity

## **Example output**

33

4. Ensure the system IRQs are not configured to run on the **dynamic-low-latency-pod** CPUs:

```
sh-4.4# find /proc/irq/ -name smp_affinity_list -exec sh -c 'i="$1"; mask=$(cat $i); file=$(echo $i); echo $file: $mask' _ {} \
```

### Example output

```
/proc/irq/0/smp_affinity_list: 0-5
/proc/irq/1/smp_affinity_list: 5
/proc/irq/2/smp_affinity_list: 0-5
/proc/irq/3/smp_affinity_list: 0-5
/proc/irq/4/smp_affinity_list: 0
/proc/irq/5/smp_affinity_list: 0-5
/proc/irq/6/smp_affinity_list: 0-5
/proc/irq/7/smp_affinity_list: 0-5
/proc/irq/8/smp_affinity_list: 4
/proc/irq/9/smp_affinity_list: 4
/proc/irq/10/smp_affinity_list: 0-5
/proc/irq/11/smp_affinity_list: 0
/proc/irq/12/smp affinity list: 1
/proc/irq/13/smp_affinity_list: 0-5
/proc/irq/14/smp_affinity_list: 1
/proc/irq/15/smp_affinity_list: 0
/proc/irq/24/smp affinity list: 1
/proc/irq/25/smp_affinity_list: 1
/proc/irq/26/smp_affinity_list: 1
/proc/irq/27/smp_affinity_list: 5
/proc/irq/28/smp_affinity_list: 1
/proc/irg/29/smp affinity list: 0
/proc/irq/30/smp_affinity_list: 0-5
```



### **WARNING**

When you tune nodes for low latency, the usage of execution probes in conjunction with applications that require guaranteed CPUs can cause latency spikes. Use other probes, such as a properly configured set of network probes, as an alternative.

### Additional resources

- Placing pods on specific nodes using node selectors
- Assigning pods to nodes

## 12.3.2. Creating a pod with a guaranteed QoS class

Keep the following in mind when you create a pod that is given a QoS class of **Guaranteed**:

- Every container in the pod must have a memory limit and a memory request, and they must be the same.
- Every container in the pod must have a CPU limit and a CPU request, and they must be the same.

The following example shows the configuration file for a pod that has one container. The container has a memory limit and a memory request, both equal to 200 MiB. The container has a CPU limit and a CPU request, both equal to 1 CPU.

```
apiVersion: v1
kind: Pod
metadata:
 name: gos-demo
 namespace: qos-example
spec:
 securityContext:
  runAsNonRoot: true
  seccompProfile:
   type: RuntimeDefault
 containers:
 - name: gos-demo-ctr
  image: <image-pull-spec>
  resources:
   limits:
    memory: "200Mi"
     cpu: "1"
   requests:
     memory: "200Mi"
     cpu: "1"
  securityContext:
   allowPrivilegeEscalation: false
   capabilities:
     drop: [ALL]
```

1. Create the pod:

\$ oc apply -f qos-pod.yaml --namespace=qos-example

2. View detailed information about the pod:

\$ oc get pod qos-demo --namespace=qos-example --output=yaml

## **Example output**

```
spec:
containers:
...
status:
qosClass: Guaranteed
```



### **NOTE**

If you specify a memory limit for a container, but do not specify a memory request, OpenShift Container Platform automatically assigns a memory request that matches the limit. Similarly, if you specify a CPU limit for a container, but do not specify a CPU request, OpenShift Container Platform automatically assigns a CPU request that matches the limit.

## 12.3.3. Disabling CPU load balancing in a Pod

Functionality to disable or enable CPU load balancing is implemented on the CRI-O level. The code under the CRI-O disables or enables CPU load balancing only when the following requirements are met.

The pod must use the performance-rofile-name runtime class. You can get the proper name by looking at the status of the performance profile, as shown here:

```
apiVersion: performance.openshift.io/v2 kind: PerformanceProfile ... status: ... runtimeClass: performance-manual
```

The Node Tuning Operator is responsible for the creation of the high-performance runtime handler config snippet under relevant nodes and for creation of the high-performance runtime class under the cluster. It will have the same content as the default runtime handler except that it enables the CPU load balancing configuration functionality.

To disable the CPU load balancing for the pod, the **Pod** specification must include the following fields:

```
apiVersion: v1
kind: Pod
metadata:
#...
annotations:
#...
cpu-load-balancing.crio.io: "disable"
```

```
#...
#...
spec:
#...
runtimeClassName: performance-<profile_name>
#...
```



#### NOTE

Only disable CPU load balancing when the CPU manager static policy is enabled and for pods with guaranteed QoS that use whole CPUs. Otherwise, disabling CPU load balancing can affect the performance of other containers in the cluster.

## 12.3.4. Disabling power saving mode for high priority pods

You can configure pods to ensure that high priority workloads are unaffected when you configure power saving for the node that the workloads run on.

When you configure a node with a power saving configuration, you must configure high priority workloads with performance configuration at the pod level, which means that the configuration applies to all the cores used by the pod.

By disabling P-states and C-states at the pod level, you can configure high priority workloads for best performance and lowest latency.

Table 12.4. Configuration for high priority workloads

Annotation	Possible Values	Description
cpu-c- states.crio.io :	<ul><li> "enable"</li><li> "disable"</li><li> "max_latency:micro seconds"</li></ul>	This annotation allows you to enable or disable C-states for each CPU. Alternatively, you can also specify a maximum latency in microseconds for the C-states. For example, enable C-states with a maximum latency of 10 microseconds with the setting cpu-c-states.crio.io: "max_latency:10". Set the value to "disable" to provide the best performance for a pod.
cpu-freq- governor.cri o.io:	Any supported <b>cpufreq governor</b> .	Sets the <b>cpufreq</b> governor for each CPU. The <b>"performance"</b> governor is recommended for high priority workloads.

## **Prerequisites**

• You have configured power saving in the performance profile for the node where the high priority workload pods are scheduled.

#### Procedure

1. Add the required annotations to your high priority workload pods. The annotations override the **default** settings.

## Example high priority workload annotation

```
apiVersion: v1
kind: Pod
metadata:
#...
annotations:
#...
cpu-c-states.crio.io: "disable"
cpu-freq-governor.crio.io: "performance"
#...
#...
spec:
#...
runtimeClassName: performance-<profile_name>
#...
```

2. Restart the pods to apply the annotation.

#### Additional resources

Configuring power saving for nodes that run colocated high and low priority workloads

## 12.3.5. Disabling CPU CFS quota

To eliminate CPU throttling for pinned pods, create a pod with the **cpu-quota.crio.io: "disable"** annotation. This annotation disables the CPU completely fair scheduler (CFS) quota when the pod runs.

## Example pod specification with cpu-quota.crio.io disabled

```
apiVersion: v1
kind: Pod
metadata:
annotations:
cpu-quota.crio.io: "disable"
spec:
runtimeClassName: performance-<profile_name>
#...
```



#### **NOTE**

Only disable CPU CFS quota when the CPU manager static policy is enabled and for pods with guaranteed QoS that use whole CPUs. For example, pods that contain CPU-pinned containers. Otherwise, disabling CPU CFS quota can affect the performance of other containers in the cluster.

### Additional resources

Recommended firmware configuration for vDU cluster hosts

## 12.3.6. Disabling interrupt processing for CPUs where pinned containers are running

To achieve low latency for workloads, some containers require that the CPUs they are pinned to do not process device interrupts. A pod annotation, **irq-load-balancing.crio.io**, is used to define whether device interrupts are processed or not on the CPUs where the pinned containers are running. When

configured, CRI-O disables device interrupts where the pod containers are running.

To disable interrupt processing for CPUs where containers belonging to individual pods are pinned, ensure that **globallyDisableIrqLoadBalancing** is set to **false** in the performance profile. Then, in the pod specification, set the **irq-load-balancing.crio.io** pod annotation to **disable**.

The following pod specification contains this annotation:

```
apiVersion: performance.openshift.io/v2
kind: Pod
metadata:
annotations:
irq-load-balancing.crio.io: "disable"
spec:
runtimeClassName: performance-<profile_name>
...
```

#### Additional resources

Managing device interrupt processing for guaranteed pod isolated CPUs

# 12.4. DEBUGGING LOW LATENCY NODE TUNING STATUS

Use the **PerformanceProfile** custom resource (CR) status fields for reporting tuning status and debugging latency issues in the cluster node.

## 12.4.1. Debugging low latency CNF tuning status

The **PerformanceProfile** custom resource (CR) contains status fields for reporting tuning status and debugging latency degradation issues. These fields report on conditions that describe the state of the operator's reconciliation functionality.

A typical issue can arise when the status of machine config pools that are attached to the performance profile are in a degraded state, causing the **PerformanceProfile** status to degrade. In this case, the machine config pool issues a failure message.

The Node Tuning Operator contains the **performanceProfile.spec.status.Conditions** status field:

## Status:

Conditions:

Last Heartbeat Time: 2020-06-02T10:01:24Z Last Transition Time: 2020-06-02T10:01:24Z

Status: True Type: Available

Last Heartbeat Time: 2020-06-02T10:01:24Z Last Transition Time: 2020-06-02T10:01:24Z

Status: True

Type: Upgradeable

Last Heartbeat Time: 2020-06-02T10:01:24Z Last Transition Time: 2020-06-02T10:01:24Z

Status: False
Type: Progressing

Last Heartbeat Time: 2020-06-02T10:01:24Z

Last Transition Time: 2020-06-02T10:01:24Z

Status: False Type: Degraded

The **Status** field contains **Conditions** that specify **Type** values that indicate the status of the performance profile:

#### **Available**

All machine configs and Tuned profiles have been created successfully and are available for cluster components are responsible to process them (NTO, MCO, Kubelet).

## **Upgradeable**

Indicates whether the resources maintained by the Operator are in a state that is safe to upgrade.

## **Progressing**

Indicates that the deployment process from the performance profile has started.

### **Degraded**

Indicates an error if:

- Validation of the performance profile has failed.
- Creation of all relevant components did not complete successfully.

Each of these types contain the following fields:

### Status

The state for the specific type (**true** or **false**).

## **Timestamp**

The transaction timestamp.

#### Reason string

The machine readable reason.

#### Message string

The human readable reason describing the state and error details, if any.

## 12.4.1.1. Machine config pools

A performance profile and its created products are applied to a node according to an associated machine config pool (MCP). The MCP holds valuable information about the progress of applying the machine configurations created by performance profiles that encompass kernel args, kube config, huge pages allocation, and deployment of rt-kernel. The Performance Profile controller monitors changes in the MCP and updates the performance profile status accordingly.

The only conditions returned by the MCP to the performance profile status is when the MCP is **Degraded**, which leads to **performanceProfile.status.condition.Degraded = true**.

## Example

The following example is for a performance profile with an associated machine config pool (**worker-cnf**) that was created for it:

1. The associated machine config pool is in a degraded state:

# oc get mcp

\_

## **Example output**

NAME **CONFIG** UPDATED UPDATING DEGRADED MACHINECOUNT READYMACHINECOUNT UPDATEDMACHINECOUNT DEGRADEDMACHINECOUNT AGE master rendered-master-2ee57a93fa6c9181b546ca46e1571d2d False False 2d21h worker rendered-worker-d6b2bdc07d9f5a59a6b68950acf25e5f True False False 2 2 2d21h worker-cnf rendered-worker-cnf-6c838641b8a08fff08dbd8b02fb63f7c False True True 2d20h

2. The **describe** section of the MCP shows the reason:

# oc describe mcp worker-cnf

## Example output

Message: Node node-worker-cnf is reporting: "prepping update: machineconfig.machineconfiguration.openshift.io \"rendered-worker-cnf-40b996919c08e335f3ff230ce1d170\" not

found"

Reason: 1 nodes are reporting degraded status on sync

3. The degraded state should also appear under the performance profile **status** field marked as **degraded = true**:

# oc describe performanceprofiles performance

### Example output

Message: Machine config pool worker-cnf Degraded Reason: 1 nodes are reporting degraded status on sync.

Machine config pool worker-cnf Degraded Message: Node yquinn-q8s5v-w-b-z5lqn.c.openshift-gce-devel.internal is

 $reporting: "prepping update: machine config.machine configuration. open shift. io \verb|\| left of the configuration of the configuration$ 

MCPDegraded Status: True Type: Degraded

## 12.4.2. Collecting low latency tuning debugging data for Red Hat Support

When opening a support case, it is helpful to provide debugging information about your cluster to Red Hat Support.

The **must-gather** tool enables you to collect diagnostic information about your OpenShift Container Platform cluster, including node tuning, NUMA topology, and other information needed to debug issues with low latency setup.

For prompt support, supply diagnostic information for both OpenShift Container Platform and low latency tuning.

## 12.4.2.1. About the must-gather tool

The **oc adm must-gather** CLI command collects the information from your cluster that is most likely needed for debugging issues, such as:

- Resource definitions
- Audit logs
- Service logs

You can specify one or more images when you run the command by including the **--image** argument. When you specify an image, the tool collects data related to that feature or product. When you run **oc adm must-gather**, a new pod is created on the cluster. The data is collected on that pod and saved in a new directory that starts with **must-gather.local**. This directory is created in your current working directory.

## 12.4.2.2. Gathering low latency tuning data

Use the **oc adm must-gather** CLI command to collect information about your cluster, including features and objects associated with low latency tuning, including:

- The Node Tuning Operator namespaces and child objects.
- MachineConfigPool and associated MachineConfig objects.
- The Node Tuning Operator and associated Tuned objects.
- Linux kernel command line options.
- CPU and NUMA topology
- Basic PCI device information and NUMA locality.

### **Prerequisites**

- Access to the cluster as a user with the **cluster-admin** role.
- The OpenShift Container Platform CLI (oc) installed.

### **Procedure**

- 1. Navigate to the directory where you want to store the **must-gather** data.
- 2. Collect debugging information by running the following command:
  - \$ oc adm must-gather

## Example output

[must-gather ] OUT Using must-gather plug-in image: quay.io/openshift-release When opening a support case, bugzilla, or issue please include the following summary data along with any other requested information:

ClusterID: 829er0fa-1ad8-4e59-a46e-2644921b7eb6

ClusterVersion: Stable at "<cluster\_version>"

ClusterOperators:

### All healthy and stable

[must-gather ] OUT namespace/openshift-must-gather-8fh4x created

[must-gather ] OUT clusterrolebinding.rbac.authorization.k8s.io/must-gather-rhlgc created

[must-gather-5564g] POD 2023-07-17T10:17:37.610340849Z Gathering data for ns/openshift-cluster-version...

[must-gather-5564g] POD 2023-07-17T10:17:38.786591298Z Gathering data for ns/default... [must-gather-5564g] POD 2023-07-17T10:17:39.117418660Z Gathering data for ns/openshift...

[must-gather-5564g] POD 2023-07-17T10:17:39.447592859Z Gathering data for ns/kube-system...

[must-gather-5564g] POD 2023-07-17T10:17:39.803381143Z Gathering data for ns/openshift-etcd...

. . .

Reprinting Cluster State:

When opening a support case, bugzilla, or issue please include the following summary data along with any other requested information:

ClusterID: 829er0fa-1ad8-4e59-a46e-2644921b7eb6

ClusterVersion: Stable at "<cluster version>"

ClusterOperators:
All healthy and stable

- 3. Create a compressed file from the **must-gather** directory that was created in your working directory. For example, on a computer that uses a Linux operating system, run the following command:
  - \$ tar cvaf must-gather.tar.gz must-gather-local.5421342344627712289
  - Replace **must-gather-local.5421342344627712289**// with the directory name created by the **must-gather** tool.



#### NOTE

Create a compressed file to attach the data to a support case or to use with the Performance Profile Creator wrapper script when you create a performance profile.

4. Attach the compressed file to your support case on the Red Hat Customer Portal.

#### Additional resources

- Gathering data about your cluster with the **must-gather** tool
- Managing nodes with MachineConfig and KubeletConfig CRs
- Using the Node Tuning Operator
- Configuring huge pages at boot time
- How huge pages are consumed by apps

## 12.5. PERFORMING LATENCY TESTS FOR PLATFORM VERIFICATION

You can use the Cloud-native Network Functions (CNF) tests image to run latency tests on a CNF-enabled OpenShift Container Platform cluster, where all the components required for running CNF workloads are installed. Run the latency tests to validate node tuning for your workload.

The cnf-tests container image is available at registry.redhat.io/openshift4/cnf-tests-rhel8:v4.16.

## 12.5.1. Prerequisites for running latency tests

Your cluster must meet the following requirements before you can run the latency tests:

- 1. You have configured a performance profile with the Node Tuning Operator.
- 2. You have applied all the required CNF configurations in the cluster.
- 3. You have a pre-existing **MachineConfigPool** CR applied in the cluster. The default worker pool is **worker-cnf**.

#### Additional resources

• Scheduling a workload onto a worker with real-time capabilities

## 12.5.2. Measuring latency

The **cnf-tests** image uses three tools to measure the latency of the system:

- hwlatdetect
- cyclictest
- oslat

Each tool has a specific use. Use the tools in sequence to achieve reliable test results.

#### hwlatdetect

Measures the baseline that the bare-metal hardware can achieve. Before proceeding with the next latency test, ensure that the latency reported by **hwlatdetect** meets the required threshold because you cannot fix hardware latency spikes by operating system tuning.

## cyclictest

Verifies the real-time kernel scheduler latency after **hwlatdetect** passes validation. The **cyclictest** tool schedules a repeated timer and measures the difference between the desired and the actual trigger times. The difference can uncover basic issues with the tuning caused by interrupts or process priorities. The tool must run on a real-time kernel.

#### oslat

Behaves similarly to a CPU-intensive DPDK application and measures all the interruptions and disruptions to the busy loop that simulates CPU heavy data processing.

The tests introduce the following environment variables:

## Table 12.5. Latency test environment variables

Environment variables	Description	
LATENCY_TEST_DE LAY	Specifies the amount of time in seconds after which the test starts running. You can use the variable to allow the CPU manager reconcile loop to update the default CPU pool. The default value is 0.	
LATENCY_TEST_CP US	Specifies the number of CPUs that the pod running the latency tests uses. If you do not set the variable, the default configuration includes all isolated CPUs.	
LATENCY_TEST_RU NTIME	Specifies the amount of time in seconds that the latency test must run. The default value is 300 seconds.  NOTE  To prevent the Ginkgo 2.0 test suite from timing out before the latency tests complete, set the -ginkgo.timeout flag to a value greater than LATENCY_TEST_RUNTIME + 2 minutes. If you also set a LATENCY_TEST_DELAY value then you must set-ginkgo.timeout to a value greater than LATENCY_TEST_RUNTIME + LATENCY_TEST_DELAY + 2 minutes. The default timeout value for the Ginkgo 2.0 test suite is 1 hour.	
HWLATDETECT_MA XIMUM_LATENCY	Specifies the maximum acceptable hardware latency in microseconds for the workload and operating system. If you do not set the value of <b>HWLATDETECT_MAXIMUM_LATENCY</b> or <b>MAXIMUM_LATENCY</b> , the tool compares the default expected threshold (20µs) and the actual maximum latency in the tool itself. Then, the test fails or succeeds accordingly.	
CYCLICTEST_MAXI MUM_LATENCY	Specifies the maximum latency in microseconds that all threads expect before waking up during the <b>cyclictest</b> run. If you do not set the value of <b>CYCLICTEST_MAXIMUM_LATENCY</b> or <b>MAXIMUM_LATENCY</b> , the tool skips the comparison of the expected and the actual maximum latency.	
OSLAT_MAXIMUM_L ATENCY	Specifies the maximum acceptable latency in microseconds for the <b>oslat</b> test results. If you do not set the value of <b>OSLAT_MAXIMUM_LATENCY</b> or <b>MAXIMUM_LATENCY</b> , the tool skips the comparison of the expected and the actual maximum latency.	
MAXIMUM_LATENC Y	Unified variable that specifies the maximum acceptable latency in microseconds.  Applicable for all available latency tools.	



## **NOTE**

Variables that are specific to a latency tool take precedence over unified variables. For example, if **OSLAT\_MAXIMUM\_LATENCY** is set to 30 microseconds and **MAXIMUM\_LATENCY** is set to 10 microseconds, the **oslat** test will run with maximum acceptable latency of 30 microseconds.

# 12.5.3. Running the latency tests

Run the cluster latency tests to validate node tuning for your Cloud-native Network Functions (CNF) workload.



### **NOTE**

When executing **podman** commands as a non-root or non-privileged user, mounting paths can fail with **permission denied** errors. To make the **podman** command work, append :**Z** to the volumes creation; for example, -v \$(pwd)/:/kubeconfig:**Z**. This allows **podman** to do the proper SELinux relabeling.

#### Procedure

- Open a shell prompt in the directory containing the kubeconfig file.
   You provide the test image with a kubeconfig file in current directory and its related
   \$KUBECONFIG environment variable, mounted through a volume. This allows the running container to use the kubeconfig file from inside the container.
- 2. Run the latency tests by entering the following command:

\$ podman run -v \$(pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig \

- -e LATENCY TEST RUNTIME=<time in seconds>\
- -e MAXIMUM\_LATENCY=<time\_in\_microseconds> \
- registry.redhat.io/openshift4/cnf-tests-rhel8:v4.16 /usr/bin/test-run.sh \
- --ginkgo.v --ginkgo.timeout="24h"
- 3. Optional: Append **--ginkgo.dryRun** flag to run the latency tests in dry-run mode. This is useful for checking what commands the tests run.
- 4. Optional: Append **--ginkgo.v** flag to run the tests with increased verbosity.
- 5. Optional: Append **--ginkgo.timeout="24h"** flag to ensure the Ginkgo 2.0 test suite does not timeout before the latency tests complete.



#### **IMPORTANT**

The default runtime for each test is 300 seconds. For valid latency test results, run the tests for at least 12 hours by updating the **LATENCY\_TEST\_RUNTIME** variable.

### 12.5.3.1. Running hwlatdetect

The **hwlatdetect** tool is available in the **rt-kernel** package with a regular subscription of Red Hat Enterprise Linux (RHEL) 9.x.



#### NOTE

When executing **podman** commands as a non-root or non-privileged user, mounting paths can fail with **permission denied** errors. To make the **podman** command work, append :**Z** to the volumes creation; for example, -v \$(pwd)/:/kubeconfig:**Z**. This allows **podman** to do the proper SELinux relabeling.

## **Prerequisites**

• You have installed the real-time kernel in the cluster.

• You have logged in to **registry.redhat.io** with your Customer Portal credentials.

#### **Procedure**

 To run the **hwlatdetect** tests, run the following command, substituting variable values as appropriate:

\$ podman run -v \$(pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig \ -e LATENCY\_TEST\_RUNTIME=600 -e MAXIMUM\_LATENCY=20 \ registry.redhat.io/openshift4/cnf-tests-rhel8:v4.16 \ /usr/bin/test-run.sh --ginkgo.focus="hwlatdetect" --ginkgo.v --ginkgo.timeout="24h"

The **hwlatdetect** test runs for 10 minutes (600 seconds). The test runs successfully when the maximum observed latency is lower than **MAXIMUM LATENCY** (20  $\mu$ s).

If the results exceed the latency threshold, the test fails.



#### **IMPORTANT**

For valid results, the test should run for at least 12 hours.

## Example failure output

running /usr/bin/cnftests -ginkgo.v -ginkgo.focus=hwlatdetect

10908 15:25:20.023712 27 request.go:601] Waited for 1.046586367s due to client-side throttling, not priority and fairness, request:

GET:https://api.hlxcl6.lab.eng.tlv2.redhat.com:6443/apis/imageregistry.operator.openshift.io/v1?timeout=32s

Running Suite: CNF Features e2e integration tests

\_\_\_\_\_

Random Seed: 1662650718

Will run 1 of 3 specs

[...]

• Failure [283.574 seconds]

[performance] Latency Test

/remote-source/app/vendor/github.com/openshift/cluster-node-tuning-operator/test/e2e/performanceprofile/functests/4\_latency/latency.go:62 with the hwlatdetect image

/remote-source/app/vendor/github.com/openshift/cluster-node-tuningoperator/test/e2e/performanceprofile/functests/4\_latency/latency.go:228 should succeed [lt]

 $/remote-source/app/vendor/github.com/openshift/cluster-node-tuning-operator/test/e2e/performanceprofile/functests/4\_latency/latency.go:236$ 

Log file created at: 2022/09/08 15:25:27 Running on machine: hwlatdetect-b6n4n Binary: Built with gc go1.17.12 for linux/amd64

Log line format: [IWEF]mmdd hh:mm:ss.uuuuuu threadid file:line] msg

I0908 15:25:27.160620 1 node.go:39] Environment information: /proc/cmdline:

BOOT IMAGE=(hd1,gpt3)/ostree/rhcos-

c6491e1eedf6c1f12ef7b95e14ee720bf48359750ac900b7863c625769ef5fb9/vmlinuz-4.18.0-372.19.1.el8\_6.x86\_64 random.trust\_cpu=on console=tty0 console=ttyS0,115200n8 ignition.platform.id=metal

```
ostree=/ostree/boot.1/rhcos/c6491e1eedf6c1f12ef7b95e14ee720bf48359750ac900b7863c625
769ef5fb9/0 ip=dhcp root=UUID=5f80c283-f6e6-4a27-9b47-a287157483b2 rw
rootflags=priguota boot=UUID=773bf59a-bafd-48fc-9a87-f62252d739d3 skew tick=1
nohz=on rcu nocbs=0-3 tuned.non isolcpus=0000ffff,fffffffff0
systemd.cpu affinity=4,5,6,7,8,9,10,11,12,13,14,15,16,17,18,19,20,21,22,23,24,25,26,27,28,29
,30,31,32,33,34,35,36,37,38,39,40,41,42,43,44,45,46,47,48,49,50,51,52,53,54,55,56,57,58,59,
60,61,62,63,64,65,66,67,68,69,70,71,72,73,74,75,76,77,78,79 intel iommu=on iommu=pt
isolcpus=managed_irq,0-3 nohz_full=0-3 tsc=nowatchdog nosoftlockup nmi_watchdog=0
mce=off skew tick=1 rcutree.kthread prio=11 + +
  10908 15:25:27.160830
                            1 node.go:46] Environment information: kernel version 4.18.0-
372.19.1.el8 6.x86 64
  10908 15:25:27.160857
                            1 main.go:50] running the hwlatdetect command with
arguments [/usr/bin/hwlatdetect --threshold 1 --hardlimit 1 --duration 100 --window
10000000us --width 950000us]
  F0908 15:27:10.603523
                             1 main.go:53] failed to run hwlatdetect command; out:
hwlatdetect: test duration 100 seconds
    detector: tracer
    parameters:
       Latency threshold: 1us 1
       Sample window: 10000000us
       Sample width:
                        950000us
     Non-sampling period: 9050000us
       Output File:
                      None
  Starting test
  test finished
  Max Latency: 326us 2
  Samples recorded: 5
  Samples exceeding threshold: 5
  ts: 1662650739.017274507, inner:6, outer:6
  ts: 1662650749.257272414, inner:14, outer:326
  ts: 1662650779.977272835, inner:314, outer:12
  ts: 1662650800.457272384, inner:3, outer:9
  ts: 1662650810.697273520, inner:3, outer:2
[...]
JUnit report was created: /junit.xml/cnftests-junit.xml
Summarizing 1 Failure:
[Fail] [performance] Latency Test with the hwlatdetect image [It] should succeed
/remote-source/app/vendor/github.com/openshift/cluster-node-tuning-
operator/test/e2e/performanceprofile/functests/4 latency/latency.go:476
Ran 1 of 194 Specs in 365.797 seconds
FAIL! -- 0 Passed | 1 Failed | 0 Pending | 2 Skipped
--- FAIL: TestTest (366.08s)
FAIL
```

- You can configure the latency threshold by using the MAXIMUM\_LATENCY or the HWLATDETECT MAXIMUM LATENCY environment variables.
- 2 The maximum latency value measured during the test.

### Example hwlatdetect test results

You can capture the following types of results:

- Rough results that are gathered after each run to create a history of impact on any changes made throughout the test.
- The combined set of the rough tests with the best results and configuration settings.

## Example of good results

hwlatdetect: test duration 3600 seconds

detector: tracer parameters:

Latency threshold: 10us Sample window: 1000000us Sample width: 950000us Non-sampling period: 50000us

Output File: None

Starting test test finished

Max Latency: Below threshold

Samples recorded: 0

The hwlatdetect tool only provides output if the sample exceeds the specified threshold.

## Example of bad results

hwlatdetect: test duration 3600 seconds

detector: tracer

parameters:Latency threshold: 10usSample window: 1000000us

Sample width: 950000usNon-sampling period: 50000usOutput File: None

Starting tests:1610542421.275784439, inner:78, outer:81

ts: 1610542444.330561619, inner:27, outer:28

ts: 1610542445.332549975, inner:39, outer:38

ts: 1610542541.568546097, inner:47, outer:32

ts: 1610542590.681548531, inner:13, outer:17

ts: 1610543033.818801482, inner:29, outer:30

ts: 1610543080.938801990, inner:90, outer:76

ts: 1610543129.065549639, inner:28, outer:39

ts: 1610543474.859552115, inner:28, outer:35

ts: 1610543523.973856571, inner:52, outer:49

ts: 1610543572.089799738, inner:27, outer:30

ts: 1610543573.091550771, inner:34, outer:28

ts: 1610543574.093555202, inner:116, outer:63

The output of **hwlatdetect** shows that multiple samples exceed the threshold. However, the same output can indicate different results based on the following factors:

- The duration of the test
- The number of CPU cores
- The host firmware settings



#### **WARNING**

Before proceeding with the next latency test, ensure that the latency reported by **hwlatdetect** meets the required threshold. Fixing latencies introduced by hardware might require you to contact the system vendor support.

Not all latency spikes are hardware related. Ensure that you tune the host firmware to meet your workload requirements. For more information, see Setting firmware parameters for system tuning.

## 12.5.3.2. Running cyclictest

The **cyclictest** tool measures the real-time kernel scheduler latency on the specified CPUs.



#### NOTE

When executing **podman** commands as a non-root or non-privileged user, mounting paths can fail with **permission denied** errors. To make the **podman** command work, append :**Z** to the volumes creation; for example, -v \$(pwd)/:/kubeconfig:**Z**. This allows **podman** to do the proper SELinux relabeling.

#### **Prerequisites**

- You have logged in to **registry.redhat.io** with your Customer Portal credentials.
- You have installed the real-time kernel in the cluster.
- You have applied a cluster performance profile by using Node Tuning Operator.

#### Procedure

• To perform the **cyclictest**, run the following command, substituting variable values as appropriate:

\$ podman run -v \$(pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig \ -e LATENCY\_TEST\_CPUS=10 -e LATENCY\_TEST\_RUNTIME=600 -e MAXIMUM\_LATENCY=20 \ registry.redhat.io/openshift4/cnf-tests-rhel8:v4.16 \ /usr/bin/test-run.sh --ginkgo.focus="cyclictest" --ginkgo.v --ginkgo.timeout="24h"

The command runs the **cyclictest** tool for 10 minutes (600 seconds). The test runs successfully when the maximum observed latency is lower than **MAXIMUM\_LATENCY** (in this example, 20  $\mu$ s). Latency spikes of 20  $\mu$ s and above are generally not acceptable for telco RAN workloads.

If the results exceed the latency threshold, the test fails.



#### **IMPORTANT**

For valid results, the test should run for at least 12 hours.

## Example failure output

running /usr/bin/cnftests -ginkgo.v -ginkgo.focus=cyclictest I0908 13:01:59.193776 27 request.go:601] Waited for 1.046228824s due to client-side throttling, not priority and fairness, request: GET:https://api.compute-

1.example.com:6443/apis/packages.operators.coreos.com/v1?timeout=32s

Running Suite: CNF Features e2e integration tests

\_\_\_\_\_

Random Seed: 1662642118

Will run 1 of 3 specs

[...]

Summarizing 1 Failure:

[Fail] [performance] Latency Test with the cyclictest image [It] should succeed /remote-source/app/vendor/github.com/openshift/cluster-node-tuning-operator/test/e2e/performanceprofile/functests/4\_latency/latency.go:220

Ran 1 of 194 Specs in 161.151 seconds
FAIL! -- 0 Passed | 1 Failed | 0 Pending | 2 Skipped
--- FAIL: TestTest (161.48s)
FAIL

#### **Example cyclictest results**

The same output can indicate different results for different workloads. For example, spikes up to  $18\mu s$  are acceptable for 4G DU workloads, but not for 5G DU workloads.

## Example of good results

running cmd: cyclictest -q -D 10m -p 1 -t 16 -a 2,4,6,8,10,12,14,16,54,56,58,60,62,64,66,68 -h 30 -i 1000 -m

# Histogram

 $000000\ 000000\ 000000\ 000000\ 000000$ 

000002 579506 535967 418614 573648 532870 529897 489306 558076 582350 585188

583793 223781 532480 569130 472250 576043

More histogram entries ...

# Total: 000600000 000600000 000600000 000599999 000599999 000599999 000599998 000599998 000599997 000599997 000599996 000599996 000599995 000599995 000599995

# Min Latencies: 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002

# Avg Latencies: 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002

# Max Latencies: 00005 00005 00004 00005 00004 00005 00005 00005 00006 00005 00004 00005 00004 00005 00004 00005 00004

# Histogram Overflow at cycle number:

# Thread 0:

# Thread 1:

# Thread 2:

```
# Thread 3:
# Thread 4:
# Thread 5:
# Thread 6:
# Thread 7:
# Thread 8:
# Thread 9:
# Thread 10:
# Thread 11:
# Thread 12:
# Thread 13:
# Thread 14:
# Thread 15:
```

## Example of bad results

```
running cmd: cyclictest -q -D 10m -p 1 -t 16 -a 2,4,6,8,10,12,14,16,54,56,58,60,62,64,66,68 -h 30 -i
1000 -m
# Histogram
000000 000000 000000 000000 000000
000000 000000 000000 000000 000000
000002 564632 579686 354911 563036 492543 521983 515884 378266 592621 463547
482764 591976 590409 588145 589556 353518
More histogram entries ...
# Total: 000599999 000599999 000599999 000599997 000599997 000599998 000599998
000599997 000599997 000599996 000599995 000599996 000599995 000599995 000599995
000599993
# Min Latencies: 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002
00002 00002 00002 00002
# Avg Latencies: 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002 00002
00002 00002 00002 00002
# Max Latencies: 00493 00387 00271 00619 00541 00513 00009 00389 00252 00215 00539 00498
00363 00204 00068 00520
# Histogram Overflows: 00001 00001 00001 00002 00002 00001 00000 00001 00001 00001 00002
00001 00001 00001 00001 00002
# Histogram Overflow at cycle number:
# Thread 0: 155922
# Thread 1: 110064
# Thread 2: 110064
# Thread 3: 110063 155921
# Thread 4: 110063 155921
# Thread 5: 155920
# Thread 6:
# Thread 7: 110062
# Thread 8: 110062
# Thread 9: 155919
# Thread 10: 110061 155919
# Thread 11: 155918
# Thread 12: 155918
# Thread 13: 110060
# Thread 14: 110060
# Thread 15: 110059 155917
```

## 12.5.3.3. Running oslat

The **oslat** test simulates a CPU-intensive DPDK application and measures all the interruptions and disruptions to test how the cluster handles CPU heavy data processing.



#### **NOTE**

When executing **podman** commands as a non-root or non-privileged user, mounting paths can fail with **permission denied** errors. To make the **podman** command work, append :**Z** to the volumes creation; for example, -v \$(pwd)/:/kubeconfig:**Z**. This allows **podman** to do the proper SELinux relabeling.

#### **Prerequisites**

- You have logged in to **registry.redhat.io** with your Customer Portal credentials.
- You have applied a cluster performance profile by using the Node Tuning Operator.

#### Procedure

• To perform the **oslat** test, run the following command, substituting variable values as appropriate:

\$ podman run -v \$(pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig \ -e LATENCY\_TEST\_CPUS=10 -e LATENCY\_TEST\_RUNTIME=600 -e MAXIMUM\_LATENCY=20 \ registry.redhat.io/openshift4/cnf-tests-rhel8:v4.16 \ /usr/bin/test-run.sh --ginkgo.focus="oslat" --ginkgo.v --ginkgo.timeout="24h"

**LATENCY\_TEST\_CPUS** specifies the number of CPUs to test with the **oslat** command.

The command runs the **oslat** tool for 10 minutes (600 seconds). The test runs successfully when the maximum observed latency is lower than **MAXIMUM LATENCY** (20  $\mu$ s).

If the results exceed the latency threshold, the test fails.



#### **IMPORTANT**

For valid results, the test should run for at least 12 hours.

## Example failure output

running /usr/bin/cnftests -ginkgo.v -ginkgo.focus=oslat I0908 12:51:55.999393 27 request.go:601] Waited for 1.044848101s due to client-side throttling, not priority and fairness, request: GET:https://compute-1.example.com:6443/apis/machineconfiguration.openshift.io/v1?timeout=32s Running Suite: CNF Features e2e integration tests

\_\_\_\_\_\_

Random Seed: 1662641514 Will run 1 of 3 specs

[...]

• Failure [77.833 seconds]

[performance] Latency Test

/remote-source/app/vendor/github.com/openshift/cluster-node-tuningoperator/test/e2e/performanceprofile/functests/4\_latency/latency.go:62 with the oslat image

/remote-source/app/vendor/github.com/openshift/cluster-node-tuningoperator/test/e2e/performanceprofile/functests/4\_latency/latency.go:128 should succeed [It]

/remote-source/app/vendor/github.com/openshift/cluster-node-tuningoperator/test/e2e/performanceprofile/functests/4 latency/latency.go:153

The current latency 304 is bigger than the expected one 1: 1



[...]

Summarizing 1 Failure:

[Fail] [performance] Latency Test with the oslat image [It] should succeed /remote-source/app/vendor/github.com/openshift/cluster-node-tuningoperator/test/e2e/performanceprofile/functests/4\_latency/latency.go:177

Ran 1 of 194 Specs in 161.091 seconds FAIL! -- 0 Passed | 1 Failed | 0 Pending | 2 Skipped --- FAIL: TestTest (161.42s) **FAIL** 

In this example, the measured latency is outside the maximum allowed value.

## 12.5.4. Generating a latency test failure report

Use the following procedures to generate a JUnit latency test output and test failure report.

## **Prerequisites**

- You have installed the OpenShift CLI (oc).
- You have logged in as a user with **cluster-admin** privileges.

### **Procedure**

 Create a test failure report with information about the cluster state and resources for troubleshooting by passing the --report parameter with the path to where the report is dumped:

\$ podman run -v \$(pwd)/:/kubeconfig:Z -v \$(pwd)/reportdest:<report\_folder\_path> \ -e KUBECONFIG=/kubeconfig/kubeconfig registry.redhat.io/openshift4/cnf-tests-rhel8:v4.16 \ /usr/bin/test-run.sh --report <report\_folder\_path> --ginkgo.v

where:

## <report\_folder\_path>

Is the path to the folder where the report is generated.

## 12.5.5. Generating a JUnit latency test report

Use the following procedures to generate a JUnit latency test output and test failure report.

#### **Prerequisites**

- You have installed the OpenShift CLI (oc).
- You have logged in as a user with cluster-admin privileges.

#### **Procedure**

• Create a JUnit-compliant XML report by passing the **--junit** parameter together with the path to where the report is dumped:



#### NOTE

You must create the **junit** folder before running this command.

\$ podman run -v \$(pwd)/:/kubeconfig:Z -v \$(pwd)/junit:/junit \
-e KUBECONFIG=/kubeconfig/kubeconfig registry.redhat.io/openshift4/cnf-tests-rhel8:v4.16 \
/usr/bin/test-run.sh --ginkgo.junit-report junit/<file-name>.xml --ginkgo.v

where:

#### junit

Is the folder where the junit report is stored.

## 12.5.6. Running latency tests on a single-node OpenShift cluster

You can run latency tests on single-node OpenShift clusters.



#### **NOTE**

When executing **podman** commands as a non-root or non-privileged user, mounting paths can fail with **permission denied** errors. To make the **podman** command work, append :**Z** to the volumes creation; for example, -v \$(pwd)/:/kubeconfig:**Z**. This allows **podman** to do the proper SELinux relabeling.

#### **Prerequisites**

- You have installed the OpenShift CLI (oc).
- You have logged in as a user with **cluster-admin** privileges.
- You have applied a cluster performance profile by using the Node Tuning Operator.

#### Procedure

• To run the latency tests on a single-node OpenShift cluster, run the following command:

 $\$  podman run -v  $\$  (pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig \ -e LATENCY\_TEST\_RUNTIME=<time\_in\_seconds> registry.redhat.io/openshift4/cnf-tests-rhel8:v4.16 \

/usr/bin/test-run.sh --ginkgo.v --ginkgo.timeout="24h"



#### **NOTE**

The default runtime for each test is 300 seconds. For valid latency test results, run the tests for at least 12 hours by updating the **LATENCY\_TEST\_RUNTIME** variable. To run the buckets latency validation step, you must specify a maximum latency. For details on maximum latency variables, see the table in the "Measuring latency" section.

After running the test suite, all the dangling resources are cleaned up.

## 12.5.7. Running latency tests in a disconnected cluster

The CNF tests image can run tests in a disconnected cluster that is not able to reach external registries. This requires two steps:

- 1. Mirroring the **cnf-tests** image to the custom disconnected registry.
- 2. Instructing the tests to consume the images from the custom disconnected registry.

## Mirroring the images to a custom registry accessible from the cluster

A **mirror** executable is shipped in the image to provide the input required by **oc** to mirror the test image to a local registry.

1. Run this command from an intermediate machine that has access to the cluster and registry.redhat.io:

\$ podman run -v \$(pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig \ registry.redhat.io/openshift4/cnf-tests-rhel8:v4.16 \ /usr/bin/mirror -registry <disconnected\_registry> | oc image mirror -f -

where:

## <disconnected\_registry>

Is the disconnected mirror registry you have configured, for example, **my.local.registry:5000**/.

2. When you have mirrored the **cnf-tests** image into the disconnected registry, you must override the original registry used to fetch the images when running the tests, for example:

```
podman run -v $(pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig \
-e IMAGE_REGISTRY="<disconnected_registry>" \
-e CNF_TESTS_IMAGE="cnf-tests-rhel8:v4.16" \
-e LATENCY_TEST_RUNTIME=<time_in_seconds> \
<disconnected_registry>/cnf-tests-rhel8:v4.16 /usr/bin/test-run.sh --ginkgo.v --
ginkgo.timeout="24h"
```

#### Configuring the tests to consume images from a custom registry

You can run the latency tests using a custom test image and image registry using **CNF\_TESTS\_IMAGE** and **IMAGE\_REGISTRY** variables.

 To configure the latency tests to use a custom test image and image registry, run the following command:

```
$ podman run -v $(pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig \
-e IMAGE_REGISTRY="<custom_image_registry>" \
```

```
-e CNF_TESTS_IMAGE="<custom_cnf-tests_image>" \
-e LATENCY_TEST_RUNTIME=<time_in_seconds> \
registry.redhat.io/openshift4/cnf-tests-rhel8:v4.16 /usr/bin/test-run.sh --ginkgo.v --
ginkgo.timeout="24h"
```

where:

#### <custom\_image\_registry>

is the custom image registry, for example, custom.registry:5000/.

## <custom\_cnf-tests\_image>

is the custom cnf-tests image, for example, custom-cnf-tests-image:latest.

## Mirroring images to the cluster OpenShift image registry

OpenShift Container Platform provides a built-in container image registry, which runs as a standard workload on the cluster.

#### **Procedure**

1. Gain external access to the registry by exposing it with a route:

```
$ oc patch configs.imageregistry.operator.openshift.io/cluster --patch '{"spec": {"defaultRoute":true}}' --type=merge
```

2. Fetch the registry endpoint by running the following command:

```
$ REGISTRY=$(oc get route default-route -n openshift-image-registry --template='{{ .spec.host }}')
```

3. Create a namespace for exposing the images:

```
$ oc create ns cnftests
```

4. Make the image stream available to all the namespaces used for tests. This is required to allow the tests namespaces to fetch the images from the **cnf-tests** image stream. Run the following commands:

```
$ oc policy add-role-to-user system:image-puller system:serviceaccount:cnf-features-testing:default --namespace=cnftests
```

\$ oc policy add-role-to-user system:image-puller system:serviceaccount:performance-addon-operators-testing:default --namespace=cnftests

5. Retrieve the docker secret name and auth token by running the following commands:

```
$ SECRET=$(oc -n cnftests get secret | grep builder-docker | awk {'print $1'}
```

\$ TOKEN=\$(oc -n cnftests get secret \$SECRET -o jsonpath="{.data['\.dockercfg']}" | base64 --decode | jq '.["image-registry.openshift-image-registry.svc:5000"].auth')

6. Create a **dockerauth.json** file, for example:

```
\ensuremath{\$} echo "{\"auth\": \hline{$}": { \"auth\": $TOKEN } }}" > dockerauth.json
```

7. Do the image mirroring:

```
\ podman run -v (pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig \ registry.redhat.io/openshift4/cnf-tests-rhel8:4.16 \ /usr/bin/mirror -registry $REGISTRY/cnftests | oc image mirror --insecure=true \ -a=$(pwd)/dockerauth.json -f -
```

8. Run the tests:

## Mirroring a different set of test images

You can optionally change the default upstream images that are mirrored for the latency tests.

#### **Procedure**

1. The **mirror** command tries to mirror the upstream images by default. This can be overridden by passing a file with the following format to the image:

2. Pass the file to the **mirror** command, for example saving it locally as **images.json**. With the following command, the local path is mounted in /**kubeconfig** inside the container and that can be passed to the mirror command.

```
$ podman run -v $(pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig \ registry.redhat.io/openshift4/cnf-tests-rhel8:v4.16 /usr/bin/mirror \ --registry "my.local.registry:5000/" --images "/kubeconfig/images.json" \ | oc image mirror -f -
```

## 12.5.8. Troubleshooting errors with the cnf-tests container

To run latency tests, the cluster must be accessible from within the **cnf-tests** container.

#### **Prerequisites**

- You have installed the OpenShift CLI (oc).
- You have logged in as a user with **cluster-admin** privileges.

#### **Procedure**

• Verify that the cluster is accessible from inside the **cnf-tests** container by running the following command:

-

 $\$  podman run -v (pwd):/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig \ registry.redhat.io/openshift4/cnf-tests-rhel8:v4.16 \ oc get nodes

If this command does not work, an error related to spanning across DNS, MTU size, or firewall access might be occurring.

# CHAPTER 13. IMPROVING CLUSTER STABILITY IN HIGH LATENCY ENVIRONMENTS USING WORKER LATENCY PROFILES

If the cluster administrator has performed latency tests for platform verification, they can discover the need to adjust the operation of the cluster to ensure stability in cases of high latency. The cluster administrator need change only one parameter, recorded in a file, which controls four parameters affecting how supervisory processes read status and interpret the health of the cluster. Changing only the one parameter provides cluster tuning in an easy, supportable manner.

The **Kubelet** process provides the starting point for monitoring cluster health. The **Kubelet** sets status values for all nodes in the OpenShift Container Platform cluster. The Kubernetes Controller Manager (**kube controller**) reads the status values every 10 seconds, by default. If the **kube controller** cannot read a node status value, it loses contact with that node after a configured period. The default behavior is:

- 1. The node controller on the control plane updates the node health to **Unhealthy** and marks the node **Ready** condition`Unknown`.
- 2. In response, the scheduler stops scheduling pods to that node.
- The Node Lifecycle Controller adds a node.kubernetes.io/unreachable taint with a NoExecute effect to the node and schedules any pods on the node for eviction after five minutes, by default.

This behavior can cause problems if your network is prone to latency issues, especially if you have nodes at the network edge. In some cases, the Kubernetes Controller Manager might not receive an update from a healthy node due to network latency. The **Kubelet** evicts pods from the node even though the node is healthy.

To avoid this problem, you can use *worker latency profiles* to adjust the frequency that the **Kubelet** and the Kubernetes Controller Manager wait for status updates before taking action. These adjustments help to ensure that your cluster runs properly if network latency between the control plane and the worker nodes is not optimal.

These worker latency profiles contain three sets of parameters that are pre-defined with carefully tuned values to control the reaction of the cluster to increased latency. No need to experimentally find the best values manually.

You can configure worker latency profiles when installing a cluster or at any time you notice increased latency in your cluster network.

## 13.1. UNDERSTANDING WORKER LATENCY PROFILES

Worker latency profiles are four different categories of carefully-tuned parameters. The four parameters which implement these values are **node-status-update-frequency**, **node-monitor-grace-period**, **default-not-ready-toleration-seconds** and **default-unreachable-toleration-seconds**. These parameters can use values which allow you control the reaction of the cluster to latency issues without needing to determine the best values using manual methods.



### **IMPORTANT**

Setting these parameters manually is not supported. Incorrect parameter settings adversely affect cluster stability.

All worker latency profiles configure the following parameters:

#### node-status-update-frequency

Specifies how often the kubelet posts node status to the API server.

#### node-monitor-grace-period

Specifies the amount of time in seconds that the Kubernetes Controller Manager waits for an update from a kubelet before marking the node unhealthy and adding the **node.kubernetes.io/not-ready** or **node.kubernetes.io/unreachable** taint to the node.

#### default-not-ready-toleration-seconds

Specifies the amount of time in seconds after marking a node unhealthy that the Kube API Server Operator waits before evicting pods from that node.

#### default-unreachable-toleration-seconds

Specifies the amount of time in seconds after marking a node unreachable that the Kube API Server Operator waits before evicting pods from that node.

The following Operators monitor the changes to the worker latency profiles and respond accordingly:

- The Machine Config Operator (MCO) updates the **node-status-update-frequency** parameter on the worker nodes.
- The Kubernetes Controller Manager updates the **node-monitor-grace-period** parameter on the control plane nodes.
- The Kubernetes API Server Operator updates the **default-not-ready-toleration-seconds** and **default-unreachable-toleration-seconds** parameters on the control plane nodes.

Although the default configuration works in most cases, OpenShift Container Platform offers two other worker latency profiles for situations where the network is experiencing higher latency than usual. The three worker latency profiles are described in the following sections:

## Default worker latency profile

With the **Default** profile, each **Kubelet** updates its status every 10 seconds ( **node-status-update-frequency**). The **Kube Controller Manager** checks the statuses of **Kubelet** every 5 seconds ( **node-monitor-grace-period**).

The Kubernetes Controller Manager waits 40 seconds for a status update from **Kubelet** before considering the **Kubelet** unhealthy. If no status is made available to the Kubernetes Controller Manager, it then marks the node with the **node.kubernetes.io/not-ready** or **node.kubernetes.io/unreachable** taint and evicts the pods on that node.

If a pod on that node has the **NoExecute** taint, the pod is run according to **tolerationSeconds**. If the pod has no taint, it will be evicted in 300 seconds (**default-not-ready-toleration-seconds** and **default-unreachable-toleration-seconds** settings of the **Kube API Server**).

Profile	Component	Parameter	Value
Default	kubelet	node-status-update- frequency	10s
	Kubelet Controller Manager	node-monitor-grace-period	40s

Profile	Component	Parameter	Value
	Kubernetes API Server Operator	default-not-ready- toleration-seconds	300s
	Kubernetes API Server Operator	default-unreachable- toleration-seconds	300s

## Medium worker latency profile

Use the **MediumUpdateAverageReaction** profile if the network latency is slightly higher than usual. The **MediumUpdateAverageReaction** profile reduces the frequency of kubelet updates to 20 seconds and changes the period that the Kubernetes Controller Manager waits for those updates to 2 minutes. The pod eviction period for a pod on that node is reduced to 60 seconds. If the pod has the **tolerationSeconds** parameter, the eviction waits for the period specified by that parameter.

The Kubernetes Controller Manager waits for 2 minutes to consider a node unhealthy. In another minute, the eviction process starts.

Profile	Component	Parameter	Value
MediumUpdateAverageReaction	kubelet	node-status-update- frequency	20s
	Kubelet Controller Manager	node-monitor-grace-period	2m
	Kubernetes API Server Operator	default-not-ready- toleration-seconds	60s
	Kubernetes API Server Operator	default-unreachable- toleration-seconds	60s

## Low worker latency profile

Use the **LowUpdateSlowReaction** profile if the network latency is extremely high.

The **LowUpdateSlowReaction** profile reduces the frequency of kubelet updates to 1 minute and changes the period that the Kubernetes Controller Manager waits for those updates to 5 minutes. The pod eviction period for a pod on that node is reduced to 60 seconds. If the pod has the **tolerationSeconds** parameter, the eviction waits for the period specified by that parameter.

The Kubernetes Controller Manager waits for 5 minutes to consider a node unhealthy. In another minute, the eviction process starts.

Profile	Component	Parameter	Value
LowUpdateSlowReaction	kubelet	node-status-update- frequency	1m
	Kubelet Controller Manager	node-monitor-grace-period	5m
	Kubernetes API Server Operator	default-not-ready- toleration-seconds	60s
	Kubernetes API Server Operator	default-unreachable- toleration-seconds	60s

# 13.2. IMPLEMENTING WORKER LATENCY PROFILES AT CLUSTER CREATION



#### **IMPORTANT**

To edit the configuration of the installer, you will first need to use the command **openshift-install create manifests** to create the default node manifest as well as other manifest YAML files. This file structure must exist before we can add workerLatencyProfile. The platform on which you are installing may have varying requirements. Refer to the Installing section of the documentation for your specific platform.

The **workerLatencyProfile** must be added to the manifest in the following sequence:

- 1. Create the manifest needed to build the cluster, using a folder name appropriate for your installation.
- 2. Create a YAML file to define **config.node**. The file must be in the **manifests** directory.
- When defining workerLatencyProfile in the manifest for the first time, specify any of the profiles at cluster creation time: Default, MediumUpdateAverageReaction or LowUpdateSlowReaction.

#### Verification

- Here is an example manifest creation showing the spec.workerLatencyProfile Default value in the manifest file:
  - \$ openshift-install create manifests --dir=<cluster-install-dir>
- Edit the manifest and add the value. In this example we use **vi** to show an example manifest file with the "Default" **workerLatencyProfile** value added:

\$ vi <cluster-install-dir>/manifests/config-node-default-profile.yaml

## **Example output**

apiVersion: config.openshift.io/v1

kind: Node metadata: name: cluster

spec:

workerLatencyProfile: "Default"

## 13.3. USING AND CHANGING WORKER LATENCY PROFILES

To change a worker latency profile to deal with network latency, edit the **node.config** object to add the name of the profile. You can change the profile at any time as latency increases or decreases.

You must move one worker latency profile at a time. For example, you cannot move directly from the **Default** profile to the **LowUpdateSlowReaction** worker latency profile. You must move from the **Default** worker latency profile to the **MediumUpdateAverageReaction** profile first, then to **LowUpdateSlowReaction**. Similarly, when returning to the **Default** profile, you must move from the low profile to the medium profile first, then to **Default**.



#### NOTE

You can also configure worker latency profiles upon installing an OpenShift Container Platform cluster.

#### **Procedure**

To move from the default worker latency profile:

- 1. Move to the medium worker latency profile:
  - a. Edit the **node.config** object:

\$ oc edit nodes.config/cluster

b. Add spec.workerLatencyProfile: MediumUpdateAverageReaction:

## Example node.config object

apiVersion: config.openshift.io/v1
kind: Node
metadata:
annotations:
include.release.openshift.io/ibm-cloud-managed: "true"
include.release.openshift.io/self-managed-high-availability: "true"
include.release.openshift.io/single-node-developer: "true"
release.openshift.io/create-only: "true"
creationTimestamp: "2022-07-08T16:02:51Z"
generation: 1
name: cluster
ownerReferences:

- apiVersion: config.openshift.io/v1 kind: ClusterVersion name: version uid: 36282574-bf9f-409e-a6cd-3032939293eb resourceVersion: "1865" uid: 0c0f7a4c-4307-4187-b591-6155695ac85b spec: workerLatencyProfile: MediumUpdateAverageReaction 1

Specifies the medium worker latency policy.

Scheduling on each worker node is disabled as the change is being applied.

- 2. Optional: Move to the low worker latency profile:
  - a. Edit the **node.config** object:
    - \$ oc edit nodes.config/cluster
  - b. Change the spec.workerLatencyProfile value to LowUpdateSlowReaction:

## Example node.config object

```
apiVersion: config.openshift.io/v1
kind: Node
metadata:
 annotations:
  include.release.openshift.io/ibm-cloud-managed: "true"
  include.release.openshift.io/self-managed-high-availability: "true"
  include.release.openshift.io/single-node-developer: "true"
  release.openshift.io/create-only: "true"
 creationTimestamp: "2022-07-08T16:02:51Z"
 generation: 1
 name: cluster
 ownerReferences:
 - apiVersion: config.openshift.io/v1
  kind: ClusterVersion
  name: version
  uid: 36282574-bf9f-409e-a6cd-3032939293eb
 resourceVersion: "1865"
 uid: 0c0f7a4c-4307-4187-b591-6155695ac85b
spec:
 workerLatencyProfile: LowUpdateSlowReaction 1
```

Specifies use of the low worker latency policy.

Scheduling on each worker node is disabled as the change is being applied.

#### Verification

• When all nodes return to the **Ready** condition, you can use the following command to look in the Kubernetes Controller Manager to ensure it was applied:

\$ oc get KubeControllerManager -o yaml | grep -i workerlatency -A 5 -B 5

## **Example output**

# ... - lastTransitionTime: "2022-07-11T19:47:10Z" reason: ProfileUpdated status: "False" type: WorkerLatencyProfileProgressing - lastTransitionTime: "2022-07-11T19:47:10Z" 1 message: all static pod revision(s) have updated latency profile reason: ProfileUpdated status: "True" type: WorkerLatencyProfileComplete - lastTransitionTime: "2022-07-11T19:20:11Z" reason: AsExpected status: "False" type: WorkerLatencyProfileDegraded - lastTransitionTime: "2022-07-11T19:20:36Z" status: "False"

Specifies that the profile is applied and active.

To change the medium profile to default or change the default to medium, edit the **node.config** object and set the **spec.workerLatencyProfile** parameter to the appropriate value.

# 13.4. EXAMPLE STEPS FOR DISPLAYING RESULTING VALUES OF WORKERLATENCYPROFILE

You can display the values in the **workerLatencyProfile** with the following commands.

#### Verification

Check the default-not-ready-toleration-seconds and default-unreachable-toleration-seconds fields output by the Kube API Server:

\$ oc get KubeAPIServer -o yaml | grep -A 1 default-

## Example output

default-not-ready-toleration-seconds:
- "300"
default-unreachable-toleration-seconds:
- "300"

2. Check the values of the **node-monitor-grace-period** field from the Kube Controller Manager:

\$ oc get KubeControllerManager -o yaml | grep -A 1 node-monitor

\_

## **Example output**

node-monitor-grace-period:

- 40s
- 3. Check the **nodeStatusUpdateFrequency** value from the Kubelet. Set the directory /**host** as the root directory within the debug shell. By changing the root directory to /**host**, you can run binaries contained in the host's executable paths:

\$ oc debug node/<worker-node-name>

\$ chroot /host

# cat /etc/kubernetes/kubelet.conf|grep nodeStatusUpdateFrequency

## Example output

"nodeStatusUpdateFrequency": "10s"

These outputs validate the set of timing variables for the Worker Latency Profile.

## **CHAPTER 14. WORKLOAD PARTITIONING**

Workload partitioning separates compute node CPU resources into distinct CPU sets. The primary objective is to keep platform pods on the specified cores to avoid interrupting the CPUs the customer workloads are running on.

Workload partitioning isolates OpenShift Container Platform services, cluster management workloads, and infrastructure pods to run on a reserved set of CPUs. This ensures that the remaining CPUs in the cluster deployment are untouched and available exclusively for non-platform workloads. The minimum number of reserved CPUs required for the cluster management is four CPU Hyper-Threads (HTs).

In the context of enabling workload partitioning and managing CPU resources effectively, nodes that are not configured correctly will not be permitted to join the cluster through a node admission webhook. When the workload partitioning feature is enabled, the machine config pools for control plane and worker will be supplied with configurations for nodes to use. Adding new nodes to these pools will make sure they are correctly configured before joining the cluster.

Currently, nodes must have uniform configurations per machine config pool to ensure that correct CPU affinity is set across all nodes within that pool. After admission, nodes within the cluster identify themselves as supporting a new resource type called **management.workload.openshift.io/cores** and accurately report their CPU capacity. Workload partitioning can be enabled during cluster installation only by adding the additional field **cpuPartitioningMode** to the **install-config.yaml** file.

When workload partitioning is enabled, the **management.workload.openshift.io/cores** resource allows the scheduler to correctly assign pods based on the **cpushares** capacity of the host, not just the default **cpuset**. This ensures more precise allocation of resources for workload partitioning scenarios.

Workload partitioning ensures that CPU requests and limits specified in the pod's configuration are respected. In OpenShift Container Platform 4.16 or later, accurate CPU usage limits are set for platform pods through CPU partitioning. As workload partitioning uses the custom resource type of **management.workload.openshift.io/cores**, the values for requests and limits are the same due to a requirement by Kubernetes for extended resources. However, the annotations modified by workload partitioning correctly reflect the desired limits.



#### **NOTE**

Extended resources cannot be overcommitted, so request and limit must be equal if both are present in a container spec.

## 14.1. ENABLING WORKLOAD PARTITIONING

With workload partitioning, cluster management pods are annotated to correctly partition them into a specified CPU affinity. These pods operate normally within the minimum size CPU configuration specified by the reserved value in the Performance Profile. Additional Day 2 Operators that make use of workload partitioning should be taken into account when calculating how many reserved CPU cores should be set aside for the platform.

Workload partitioning isolates user workloads from platform workloads using standard Kubernetes scheduling capabilities.



#### NOTE

Workload partitioning can only be enabled during cluster installation. You cannot disable workload partitioning postinstallation.

Use this procedure to enable workload partitioning cluster wide:

#### **Procedure**

 In the install-config.yaml file, add the additional field cpuPartitioningMode and set it to AllNodes.

apiVersion: v1
baseDomain: devcluster.openshift.com
cpuPartitioningMode: AllNodes
compute:
- architecture: amd64
 hyperthreading: Enabled
 name: worker
 platform: {}
 replicas: 3
controlPlane:
 architecture: amd64
 hyperthreading: Enabled
 name: master
 platform: {}
 replicas: 3

Sets up a cluster for CPU partitioning at install time. The default value is **None**.

## 14.2. PERFORMANCE PROFILES AND WORKLOAD PARTITIONING

Applying a performance profile allows you to make use of the workload partitioning feature. An appropriately configured performance profile specifies the **isolated** and **reserved** CPUs. The recommended way to create a performance profile is to use the Performance Profile Creator (PPC) tool to create the performance profile.

#### Additional resources

About the Performance Profile Creator

## 14.3. SAMPLE PERFORMANCE PROFILE CONFIGURATION

apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:

# if you change this name make sure the 'include' line in TunedPerformancePatch.yaml
# matches this name: include=openshift-node-performance-\${PerformanceProfile.metadata.name}}
# Also in file 'validatorCRs/informDuValidator.yaml':
# name: 50-performance-\${PerformanceProfile.metadata.name}}
name: openshift-node-performance-profile
annotations:
 ran.openshift.io/reference-configuration: "ran-du.redhat.com"
spec:
 additionalKernelArgs:
 - "rcupdate.rcu\_normal\_after\_boot=0"
 - "efi=runtime"
 - "vfio pci.enable sriov=1"

- "vfio\_pci.disable\_idle\_d3=1" - "module\_blacklist=irdma" cpu: isolated: \$isolated reserved: \$reserved hugepages: defaultHugepagesSize: \$defaultHugepagesSize pages: - size: \$size count: \$count node: \$node machineConfigPoolSelector: pools.operator.machineconfiguration.openshift.io/\$mcp: "" nodeSelector: node-role.kubernetes.io/\$mcp: " numa: topologyPolicy: "restricted" # To use the standard (non-realtime) kernel, set enabled to false realTimeKernel: enabled: true workloadHints: # WorkloadHints defines the set of upper level flags for different type of workloads. # See https://github.com/openshift/cluster-node-tuningoperator/blob/master/docs/performanceprofile/performance\_profile.md#workloadhints # for detailed descriptions of each item. # The configuration below is set for a low latency, performance mode. realTime: true highPowerConsumption: false perPodPowerManagement: false

Table 14.1. PerformanceProfile CR options for single-node OpenShift clusters

PerformanceProfile CR field	Description
metadata.name	Ensure that name matches the following fields set in related GitOps ZTP custom resources (CRs):  • include=openshift-node-performance- \${PerformanceProfile.metadata.name} in TunedPerformancePatch.yaml  • name: 50-performance- \${PerformanceProfile.metadata.name} in validatorCRs/informDuValidator.yaml
spec.additionalKernelArgs	"efi=runtime" Configures UEFI secure boot for the cluster host.

PerformanceProfile CR field	Description	
spec.cpu.isolated	Set the isolated CPUs. Ensure all of the Hyper- Threading pairs match.	
	IMPORTANT  The reserved and isolated CPU pools must not overlap and together must span all available cores. CPU cores that are not accounted for cause an undefined behaviour in the system.	
spec.cpu.reserved	Set the reserved CPUs. When workload partitioning is enabled, system processes, kernel threads, and system container threads are restricted to these CPUs. All CPUs that are not isolated should be reserved.	
spec.hugepages.pages	<ul> <li>Set the number of huge pages (count)</li> <li>Set the huge pages size (size).</li> <li>Set node to the NUMA node where the hugepages are allocated (node)</li> </ul>	
spec.realTimeKernel	Set <b>enabled</b> to <b>true</b> to use the realtime kernel.	
spec.workloadHints	Use <b>workloadHints</b> to define the set of top level flags for different type of workloads. The example configuration configures the cluster for low latency and high performance.	

## Additional resources

ullet Recommended single-node OpenShift cluster configuration for vDU application workloads ullet Workload partitioning

## CHAPTER 15. USING THE NODE OBSERVABILITY OPERATOR

The Node Observability Operator collects and stores CRI-O and Kubelet profiling or metrics from scripts of compute nodes.

With the Node Observability Operator, you can query the profiling data, enabling analysis of performance trends in CRI-O and Kubelet. It supports debugging performance-related issues and executing embedded scripts for network metrics by using the **run** field in the custom resource definition. To enable CRI-O and Kubelet profiling or scripting, you can configure the **type** field in the custom resource definition.



#### **IMPORTANT**

The Node Observability Operator is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see Technology Preview Features Support Scope.

## 15.1. WORKFLOW OF THE NODE OBSERVABILITY OPERATOR

The following workflow outlines on how to query the profiling data using the Node Observability Operator:

- 1. Install the Node Observability Operator in the OpenShift Container Platform cluster.
- 2. Create a NodeObservability custom resource to enable the CRI-O profiling on the worker nodes of your choice.
- 3. Run the profiling query to generate the profiling data.

## 15.2. INSTALLING THE NODE OBSERVABILITY OPERATOR

The Node Observability Operator is not installed in OpenShift Container Platform by default. You can install the Node Observability Operator by using the OpenShift Container Platform CLI or the web console.

## 15.2.1. Installing the Node Observability Operator using the CLI

You can install the Node Observability Operator by using the OpenShift CLI (oc).

## **Prerequisites**

- You have installed the OpenShift CLI (oc).
- You have access to the cluster with **cluster-admin** privileges.

#### **Procedure**

1. Confirm that the Node Observability Operator is available by running the following command:

\$ oc get packagemanifests -n openshift-marketplace node-observability-operator

## **Example output**

```
NAME CATALOG AGE node-observability-operator Red Hat Operators 9h
```

2. Create the **node-observability-operator** namespace by running the following command:

\$ oc new-project node-observability-operator

3. Create an **OperatorGroup** object YAML file:

```
cat <<EOF | oc apply -f -
apiVersion: operators.coreos.com/v1
kind: OperatorGroup
metadata:
name: node-observability-operator
namespace: node-observability-operator
spec:
targetNamespaces: []
EOF
```

4. Create a **Subscription** object YAML file to subscribe a namespace to an Operator:

```
cat <<EOF | oc apply -f -
apiVersion: operators.coreos.com/v1alpha1
kind: Subscription
metadata:
name: node-observability-operator
namespace: node-observability-operator
spec:
channel: alpha
name: node-observability-operator
source: redhat-operators
sourceNamespace: openshift-marketplace
EOF
```

#### Verification

1. View the install plan name by running the following command:

\$ oc -n node-observability-operator get sub node-observability-operator -o yaml | yq '.status.installplan.name'

## **Example output**

install-dt54w

2. Verify the install plan status by running the following command:

\$ oc -n node-observability-operator get ip <install\_plan\_name> -o yaml | yq '.status.phase'

<install\_plan\_name> is the install plan name that you obtained from the output of the previous command.

## **Example output**

COMPLETE

- 3. Verify that the Node Observability Operator is up and running:
  - \$ oc get deploy -n node-observability-operator

## **Example output**

NAME READY UP-TO-DATE AVAILABLE AGE node-observability-operator-controller-manager 1/1 1 40h

## 15.2.2. Installing the Node Observability Operator using the web console

You can install the Node Observability Operator from the OpenShift Container Platform web console.

## **Prerequisites**

- You have access to the cluster with **cluster-admin** privileges.
- You have access to the OpenShift Container Platform web console.

#### Procedure

- 1. Log in to the OpenShift Container Platform web console.
- 2. In the Administrator's navigation panel, expand **Operators** → **OperatorHub**.
- 3. In the **All items** field, enter **Node Observability Operator** and select the **Node Observability Operator** tile.
- 4. Click Install.
- 5. On the **Install Operator** page, configure the following settings:
  - a. In the **Update channel** area, click **alpha**.
  - b. In the Installation mode area, click A specific namespace on the cluster
  - c. From the Installed Namespace list, select node-observability-operator from the list.
  - d. In the **Update approval** area, select **Automatic**.
  - e. Click Install.

#### Verification

- 1. In the Administrator's navigation panel, expand **Operators** → **Installed Operators**.
- 2. Verify that the Node Observability Operator is listed in the Operators list.

## 15.3. REQUESTING CRI-O AND KUBELET PROFILING DATA USING THE NODE OBSERVABILITY OPERATOR

Creating a Node Observability custom resource to collect CRI-O and Kubelet profiling data.

## 15.3.1. Creating the Node Observability custom resource

You must create and run the **NodeObservability** custom resource (CR) before you run the profiling query. When you run the NodeObservability CR, it creates the necessary machine config and machine config pool CRs to enable the CRI-O profiling on the worker nodes matching the **nodeSelector**.



### **IMPORTANT**

If CRI-O profiling is not enabled on the worker nodes, the

NodeObservabilityMachineConfig resource gets created. Worker nodes matching the nodeSelector specified in NodeObservability CR restarts. This might take 10 or more minutes to complete.



#### **NOTE**

Kubelet profiling is enabled by default.

The CRI-O unix socket of the node is mounted on the agent pod, which allows the agent to communicate with CRI-O to run the pprof request. Similarly, the **kubelet-serving-ca** certificate chain is mounted on the agent pod, which allows secure communication between the agent and node's kubelet endpoint.

## **Prerequisites**

- You have installed the Node Observability Operator.
- You have installed the OpenShift CLI (oc).
- You have access to the cluster with **cluster-admin** privileges.


## **Procedure**

- 1. Log in to the OpenShift Container Platform CLI by running the following command:
  - \$ oc login -u kubeadmin https://<HOSTNAME>:6443
- 2. Switch back to the **node-observability-operator** namespace by running the following command:
  - \$ oc project node-observability-operator
- 3. Create a CR file named **nodeobservability.yaml** that contains the following text:

apiVersion: nodeobservability.olm.openshift.io/v1alpha2

kind: NodeObservability

metadata:



spec:

nodeSelector:

kubernetes.io/hostname: <node\_hostname> 2

type: crio-kubelet

- You must specify the name as **cluster** because there should be only one **NodeObservability** CR per cluster.
- Specify the nodes on which the Node Observability agent must be deployed.
- 4. Run the NodeObservability CR:

oc apply -f nodeobservability.yaml

## Example output

nodeobservability.olm.openshift.io/cluster created

5. Review the status of the **NodeObservability** CR by running the following command:

\$ oc get nob/cluster -o yaml | yq '.status.conditions'

## **Example output**

conditions:

conditions:

- lastTransitionTime: "2022-07-05T07:33:54Z"

message: 'DaemonSet node-observability-ds ready: true NodeObservabilityMachineConfig

ready: true' reason: Ready status: "True" type: Ready

**NodeObservability** CR run is completed when the reason is **Ready** and the status is **True**.

## 15.3.2. Running the profiling query

To run the profiling query, you must create a **NodeObservabilityRun** resource. The profiling query is a blocking operation that fetches CRI-O and Kubelet profiling data for a duration of 30 seconds. After the profiling query is complete, you must retrieve the profiling data inside the container file system /run/node-observability directory. The lifetime of data is bound to the agent pod through the **emptyDir** volume, so you can access the profiling data while the agent pod is in the **running** status.



#### **IMPORTANT**

You can request only one profiling query at any point of time.

#### **Prerequisites**

- You have installed the Node Observability Operator.
- You have created the **NodeObservability** custom resource (CR).

• You have access to the cluster with **cluster-admin** privileges.

#### **Procedure**

1. Create a **NodeObservabilityRun** resource file named **nodeobservabilityrun.yaml** that contains the following text:

```
apiVersion: nodeobservability.olm.openshift.io/v1alpha2
kind: NodeObservabilityRun
metadata:
name: nodeobservabilityrun
spec:
nodeObservabilityRef:
name: cluster
```

2. Trigger the profiling guery by running the **NodeObservabilityRun** resource:

\$ oc apply -f nodeobservabilityrun.yaml

3. Review the status of the **NodeObservabilityRun** by running the following command:

\$ oc get nodeobservabilityrun nodeobservabilityrun -o yaml | yq '.status.conditions'

## Example output

```
conditions:
- lastTransitionTime: "2022-07-07T14:57:34Z"
message: Ready to start profiling
reason: Ready
status: "True"
type: Ready
- lastTransitionTime: "2022-07-07T14:58:10Z"
message: Profiling query done
reason: Finished
status: "True"
type: Finished
```

The profiling query is complete once the status is **True** and type is **Finished**.

4. Retrieve the profiling data from the container's /**run**/**node-observability** path by running the following bash script:

```
for a in $(oc get nodeobservabilityrun nodeobservabilityrun -o yaml | yq .status.agents[].name); do echo "agent ${a}" mkdir -p "/tmp/${a}" for p in $(oc exec "${a}" -c node-observability-agent -- bash -c "ls /run/node-observability/*.pprof"); do f="$(basename ${p})" echo "copying ${f} to /tmp/${a}/${f}" oc exec "${a}" -c node-observability-agent -- cat "${p}" > "/tmp/${a}/${f}" done done
```

#### 15.4. NODE OBSERVABILITY OPERATOR SCRIPTING

Scripting allows you to run pre-configured bash scripts, using the current Node Observability Operator and Node Observability Agent.

These scripts monitor key metrics like CPU load, memory pressure, and worker node issues. They also collect sar reports and custom performance metrics.

## 15.4.1. Creating the Node Observability custom resource for scripting

You must create and run the **NodeObservability** custom resource (CR) before you run the scripting. When you run the **NodeObservability** CR, it enables the agent in scripting mode on the compute nodes matching the **nodeSelector** label.

#### **Prerequisites**

- You have installed the Node Observability Operator.
- You have installed the OpenShift CLI (oc).
- You have access to the cluster with **cluster-admin** privileges.

#### **Procedure**

- 1. Log in to the OpenShift Container Platform cluster by running the following command:
  - \$ oc login -u kubeadmin https://<host\_name>:6443
- 2. Switch to the **node-observability-operator** namespace by running the following command:
  - \$ oc project node-observability-operator
- 3. Create a file named **nodeobservability.yaml** that contains the following content:

apiVersion: nodeobservability.olm.openshift.io/v1alpha2 kind: NodeObservability metadata: name: cluster 1 spec: nodeSelector: kubernetes.io/hostname: <node\_hostname> 2 type: scripting 3

- You must specify the name as **cluster** because there should be only one **NodeObservability** CR per cluster.
- Specify the nodes on which the Node Observability agent must be deployed.
- To deploy the agent in scripting mode, you must set the type to **scripting**.
- 4. Create the **NodeObservability** CR by running the following command:

\$ oc apply -f nodeobservability.yaml

## **Example output**

nodeobservability.olm.openshift.io/cluster created

5. Review the status of the **NodeObservability** CR by running the following command:

\$ oc get nob/cluster -o yaml | yq '.status.conditions'

## **Example output**

conditions:

conditions:

- lastTransitionTime: "2022-07-05T07:33:54Z"

message: 'DaemonSet node-observability-ds ready: true NodeObservabilityScripting

ready: true' reason: Ready status: "True" type: Ready

The NodeObservability CR run is completed when the reason is Ready and status is "True".

## 15.4.2. Configuring Node Observability Operator scripting

## **Prerequisites**

- You have installed the Node Observability Operator.
- You have created the **NodeObservability** custom resource (CR).
- You have access to the cluster with **cluster-admin** privileges.

#### Procedure

1. Create a file named **nodeobservabilityrun-script.yaml** that contains the following content:

apiVersion: nodeobservability.olm.openshift.io/v1alpha2

kind: NodeObservabilityRun

metadata:

name: nodeobservabilityrun-script

namespace: node-observability-operator

spec:

nodeObservabilityRef:

name: cluster type: scripting



#### **IMPORTANT**

You can request only the following scripts:

- metrics.sh
- network-metrics.sh (uses monitor.sh)

2. Trigger the scripting by creating the **NodeObservabilityRun** resource with the following command:

\$ oc apply -f nodeobservabilityrun-script.yaml

3. Review the status of the **NodeObservabilityRun** scripting by running the following command:

\$ oc get nodeobservabilityrun nodeobservabilityrun-script -o yaml | yq '.status.conditions'

## **Example output**

```
Status:
Agents:
  lp: 10.128.2.252
  Name: node-observability-agent-n2fpm
  Port: 8443
  lp: 10.131.0.186
  Name: node-observability-agent-wcc8p
  Port: 8443
 Conditions:
  Conditions:
   Last Transition Time: 2023-12-19T15:10:51Z
   Message:
                    Ready to start profiling
   Reason:
                    Ready
   Status:
                  True
   Type:
                  Ready
   Last Transition Time: 2023-12-19T15:11:01Z
   Message:
                    Profiling query done
                    Finished
   Reason:
   Status:
                  True
   Type:
                  Finished
 Finished Timestamp:
                        2023-12-19T15:11:01Z
 Start Timestamp:
                       2023-12-19T15:10:51Z
```

The scripting is complete once **Status** is **True** and **Type** is **Finished**.

4. Retrieve the scripting data from the root path of the container by running the following bash script:

```
#!/bin/bash

RUN=$(oc get nodeobservabilityrun --no-headers | awk '{print $1}')

for a in $(oc get nodeobservabilityruns.nodeobservability.olm.openshift.io/${RUN} -o json | jq .status.agents[].name); do
    echo "agent ${a}"
    agent=$(echo ${a} | tr -d "\"\\")
    base_dir=$(oc exec "${agent}" -c node-observability-agent -- bash -c "ls -t | grep node-observability-agent" | head -1)
    echo "${base_dir}"
    mkdir -p "/tmp/${agent}"
    for p in $(oc exec "${agent}" -c node-observability-agent -- bash -c "ls ${base_dir}"); do
    f="/${base_dir}/${p}"
    echo "copying ${f} to /tmp/${agent}/${p}"
```

oc exec " ${agent}$ " -c node-observability-agent -- cat  ${f} > "/tmp/{agent}/{p}"$  done done

## 15.5. ADDITIONAL RESOURCES

For more information on how to collect worker metrics, see  $\operatorname{\mathsf{Red}}$  Hat Knowledgebase article.