

Mark Craig Vanessa Richie Mike Jang

ForgeRock AS 33 New Montgomery St., Suite 1500 San Francisco, CA 94105, USA +1 415-599-1100 www.forgerock.com

Copyright © 2011-2014 ForgeRock AS

Abstract

Reference documentation for OpenAM. OpenAM provides open source Authentication, Authorization, Entitlement and Federation software.



This work is licensed under the Creative Commons Attribution-NonCommercial-NoDerivs 3.0 Unported License.

To view a copy of this license, visit http://creativecommons.org/licenses/by-nc-nd/3.0/ or send a letter to Creative Commons, 444 Castro Street, Suite 900, Mountain View, California, 94041, USA.

ForgeRock™ is the trademark of ForgeRock Inc. or its subsidiaries in the U.S. and in other countries. Trademarks are the property of their respective owners.

UNLESS OTHERWISE MUTUALLY AGREED BY THE PARTIES IN WRITING, LICENSOR OFFERS THE WORK AS-IS AND MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND CONCERNING THE WORK, EXPRESS, IMPLIED, STATUTORY OR OTHERWISE, INCLUDING, WITHOUT LIMITATION, WARRANTIES OF TITLE, MERCHANTIBILITY, FITNESS FOR A PARTICULAR PURPOSE, NONINFERINGEMENT, OR THE ABSENCE OF LATENT OR OTHER DEFECTS, ACCURACY, OR THE PRESENCE OF ABSENCE OF BESINGE OF ROOT DISCOVERABLE. SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OF IMPLIED WARRANTIES, SO SUCH EXCLUSION MAY NOT APPLY TO YOU.

EXCEPT TO THE EXTENT REQUIRED BY APPLICABLE LAW, IN NO EVENT WILL LICENSOR BE LIABLE TO YOU ON ANY LEGAL THEORY FOR ANY SPECIAL, INCIDENTAL, CONSEQUENTIAL, PUNITIVE OR EXEMPLARY DAMAGES ARISING OUT OF THIS LICENSE OR THE USE OF THE WORK, EVEN IF LICENSOR HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

DejaVu Fonts

Bitstream Vera Fonts Copyright

Copyright (c) 2003 by Bitstream, Inc. All Rights Reserved. Bitstream Vera is a trademark of Bitstream, Inc.

Permission is hereby granted, free of charge, to any person obtaining a copy of the fonts accompanying this license ("Fonts") and associated documentation files (the "Font Software"), to reproduce and distribute the Font Software, including without limitation the rights to use, copy, merge, publish, distribute, and/or sell copies of the Font Software, and to permit persons to whom the Font Software is furnished to do so, subject to the following conditions:

The above copyright and trademark notices and this permission notice shall be included in all copies of one or more of the Font Software typefaces

The Font Software may be modified, altered, or added to, and in particular the designs of glyphs or characters in the Fonts may be modified and additional glyphs or characters may be added to the Fonts, only if the fonts are renamed to names not containing either the words "Bitstream" or the word "Vera".

This License becomes null and void to the extent applicable to Fonts or Font Software that has been modified and is distributed under the "Bitstream Vera" names.

The Font Software may be sold as part of a larger software package but no copy of one or more of the Font Software typefaces may be sold by itself

THE FONT SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF COPYRIGHT, PATENT, TRADEMARK, OR OTHER RIGHT, IN NO EVENT SHALL BITSTREAM OR THE GNOME FOUNDATION BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABLITY, INCLUDING ANY GENERAL, SPECIAL, INDIRECT, INCIDING EQUENTIAL DAMAGES, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF THE USE OR INABILITY TO USE THE FONT SOFTWARE OR FROM OTHER DEALINGS IN THE FONT SOFTWARE.

Except as contained in this notice, the names of Gnome, the Gnome Foundation, and Bitstream Inc., shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Font Software without prior written authorization from the Gnome Foundation or Bitstream Inc., respectively. For further information, contact: fonts at gnome dot org.

Arev Fonts Copyright

Copyright (c) 2006 by Tavmjong Bah. All Rights Reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of the fonts accompanying this license ("Fonts") and associated documentation files (the "Font Software"), to reproduce and distribute the modifications to the Bitstream Vera Font Software, including without limitation the rights to use, copy, merge, publish, distribute, and/or sell copies of the Font Software, and to permit persons to whom the Font Software is furnished to do so, subject to the following conditions:

The above copyright and trademark notices and this permission notice shall be included in all copies of one or more of the Font Software type faces.

The Font Software may be modified, altered, or added to, and in particular the designs of glyphs or characters in the Fonts may be modified and additional glyphs or characters may be added to the Fonts, only if the fonts are renamed to names not containing either the words "Tavmjong Bah" or the word "Arev".

This License becomes null and void to the extent applicable to Fonts or Font Software that has been modified and is distributed under the "Tavmjong Bah Arev" names.

The Font Software may be sold as part of a larger software package but no copy of one or more of the Font Software typefaces may be sold by itself.

THE FONT SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF COPYRIGHT, PATENT, TRADEMARK, OR OTHER RIGHT. IN NO EVENT SHALL TAYMJONG BAH BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABLITY, INCLUDING ANY GENERAL, SPECIAL, INDIRECT, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF THE USE OR INABILITY TO USE THE FONT SOFTWARE OF FROM OTHER DEALINGS IN THE FONT SOFTWARE.

Except as contained in this notice, the name of Tavmjong Bah shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Font Software without prior written authorization from Tavmjong Bah. For further information, contact: tavmjong @ free . fr.

Table of Contents

Preface	
1. Who Should Use this Reference	v
2. Formatting Conventions	
3. Accessing Documentation Online	vi
4. Joining the ForgeRock Community	
I. OpenAM Command Line Tools	1
agentadmin	
ampassword	
amverifyarchive	
configurator.jar	
ssoadm	
1. Configuration Reference	
1.1. Authentication Configuration	
1.2. Console Configuration	
1.3. System Configuration	
1.4. Global Configuration	
1.5. Servers and Sites Configuration	
2. Log Files and Messages	
2.1. Log Files	
2.2. Log Messages	
3. Error Messages	
4. Ports Used	
5. Localization	
6. Supported Standards	
7. Service Endpoints	
7.1. JSP Endpoints	
7.2. Main Directory JSP Endpoints	
7.3. User Interface JSP Endpoints	
7.4. Default Authentication JSP Endpoints	
7.5. Default Federation JSP Endpoints	
7.6. Console Agent Configuration JSP Endpoints	
7.7. Console Ajax JSP Endpoints	
7.8. Console Authentication JSP Endpoints	580
7.9. Base Console JSP Endpoints	
7.10. Delegation Console JSP Endpoints	
7.11. Federation Console JSP Endpoints	
7.12. Policy Console JSP Endpoints	
7.13. IDM Console JSP Endpoints	
7.14. Console Realm JSP Endpoints	
7.15. Service Console JSP Endpoints	
7.16. Session Console JSP Endpoints	
7.17. Task Console JSP Endpoints	
7.18. User Console JSP Endpoints	600

OpenAM Reference

7.19. Web Services Console JSP Endpoints	601
7.20. OAuth JSP Endpoints	602
7.21. Password JSP Endpoints	602
7.22. SAML2 JSP Endpoints	603
7.23. WS Federation JSP Endpoints	606
7.24. WEB-INF Endpoints	606
7.25. JSON REST Endpoints	617
7.26. Well-Known Endpoints	618
8. XUI Configuration Parameters	619
Index	623

Preface

This reference covers OpenAM tools, log formats, error codes, file layout, ports used, standards supported, locales supported, and configuration file semantics.

1 Who Should Use this Reference

This references is written for access management designers, developers, and administrators using OpenAM tools, logs, and configuration files. For API specifications, see the appropriate Javadoc.

2 Formatting Conventions

Most examples in the documentation are created on GNU/Linux or Mac OS X. Where it is helpful to make a distinction between operating environments, examples for UNIX, GNU/Linux, Mac OS X, and so forth are labeled (UNIX). Mac OS X specific examples can be labeled (Mac OS X). Examples for Microsoft Windows can be labeled (Windows). To avoid repetition, however, file system directory names are often given only in UNIX format as in /path/to/server, even if the text applies to C:\path\to\server as well.

Absolute path names usually begin with the placeholder /path/to/. This path might translate to /opt/, C:\Program Files\, or somewhere else on your system.

Command line, terminal sessions are formatted as follows.

\$ echo \$JAVA_HOME
/path/to/jdk

Accessing Documentation Online

Command output is sometimes formatted for narrower, more readable output even though formatting parameters are not shown in the command. In the following example, the query string parameter prettyPrint=true is omitted.

```
$ curl https://bjensen:hifalutin@opendj.example.com:8443/users/newuser
 "_rev" : "000000005b337348",
 "schemas" : [ "urn:scim:schemas:core:1.0" ],
  "contactInformation" : {
   "telephoneNumber" : "+1 408 555 1212",
    "emailAddress" : "newuser@example.com"
  " id" : "newuser",
  "name" : {
   "familyName" : "New",
    "givenName" : "User"
  "userName" : "newuser@example.com",
  "displayName" : "New User",
  "meta" : {
    "created": "2014-06-03T09:58:27Z"
  "manager" : [ {
    "_id" : "kvaughan",
    "displayName" : "Kirsten Vaughan"
```

Program listings are formatted as follows.

```
class Test {
    public static void main(String [] args) {
        System.out.println("This is a program listing.");
    }
}
```

3 Accessing Documentation Online

ForgeRock core documentation, such as what you are now reading, aims to be technically accurate and complete with respect to the software documented.

Core documentation therefore follows a three-phase review process designed to eliminate errors.

- Product managers and software architects review project documentation design with respect to the users' software lifecycle needs.
- Subject matter experts review proposed documentation changes for technical accuracy and completeness with respect to the corresponding software.

Joining the ForgeRock Community

• Quality experts validate implemented documentation changes for technical validity with respect to the software, technical completeness with respect to the scope of the document, and usability for the expected audience.

The review process helps to ensure that documentation published for a ForgeRock release is technically accurate and complete.

Fully reviewed, published core documentation is available at http://docs.forgerock.org/. Use this documentation when working with a ForgeRock Enterprise release.

In-progress documentation can be found at each project site under the Developer Community projects page. Use this documentation when trying a nightly build.

The ForgeRock Community Wikis and provide additional, user-created information. We encourage you to join the community, so that you can update the Wikis, too.

4 Joining the ForgeRock Community

After you sign up to join the ForgeRock community, you can edit the Community Wikis, and also log bugs and feature requests in the issue tracker.

If you have a question regarding a project but cannot find an answer in the project documentation or Wiki, browse to the Developer Community page for the project, where you can find details on joining the project mailing lists, and find links to mailing list archives. You can also suggest updates to documentation through the ForgeRock docs mailing list.

The Community Wikis describe how to check out and build source code. Should you want to contribute a patch, test, or feature, or want to author part of the core documentation, first have a look on the ForgeRock site at how to get involved.

OpenAM Command Line Tools

Table of Contents

agentadmin	. 3
ampassword	. 7
amverifyarchive	
configurator.jar	
ssoadm	

agentadmin

agentadmin — manage OpenAM policy agent installation

agentadmin

agentadmin {options}

1 Description

This command manages OpenAM policy agent installations. The **agentadmin** command requires a Java runtime environment.

2 Options

The following options are supported.

--install

Installs a new Agent instance.

Usage: agentadmin --install [--useResponse | --saveResponse file-name]

--useResponse

Use this option to install in silent mode by specifying all the responses in a response specified by *file-name*. When this option is used the installer runs in non-interactive mode.

--saveResponse

Use this option to save all the supplied responses to a response file specified by *file-name*.

--custom-install

Installs a new Agent instance

Usage: agentadmin --custom-install [--useResponse | --saveResponse file-name]

--useResponse

Use this option to install in silent mode by specifying all the responses in a response specified by *file-name*. When this option is used the installer runs in non-interactive mode.

--saveResponse

Use this option to save all the supplied responses to a response file specified by *file-name*.

--uninstall

Uninstalls an existing Agent instance.

Usage: agentadmin --uninstall [--useResponse | --saveResponse file-name]

--useResponse

Use this option to install in silent mode by specifying all the responses in a response specified by *file-name*. When this option is used the installer runs in non-interactive mode.

--saveResponse

Use this option to save all the supplied responses to a response file specified by *file-name*.

--version

Displays the version information.

--uninstallAll

Uninstalls all the agent instances.

--migrate

Migrate agent to newer version

--listAgents

Displays details of all the configured agents.

--agentInfo

Displays details of the agent corresponding to the specified agent ID.

Usage: agentadmin --agentInfo agent-id

--agentInfo

Displays details of the agent corresponding to the specified agent-id.

Example: agentadmin --agentInfo agent_001

--encrypt

Encrypts a given string.

Usage: agentadmin --encrypt agent-instance password-file

agent-instance

Agent instance identifier. The encryption functionality requires the use of agent instance specific encryption key present in its configuration file.

password-file

File containing the password to encrypt.

--getEncryptKey

Generates an agent encryption key.

3 Examples

The following example installs an Apache HTTP Server 2.2 interactively, where Apache HTTP Server has been installed under /path/to/apache22.

```
$ ./agentadmin --install
SUMMARY OF YOUR RESPONSES
Apache Server Config Directory : /path/to/apache22/conf
OpenSSO server URL : http://openam.example.com:8080/openam
Agent URL : http://www.example.com:80
Agent Profile name : Apache Web Agent
Agent Profile Password file name : /tmp/pwd.txt
SUMMARY OF AGENT INSTALLATION
Agent instance name: Agent_001
Agent Bootstrap file location:
/path/to/web_agents/apache22_agent/Agent_001/config/
OpenSSOAgentBootstrap.properties
Agent Configuration Tag file location
/path/to/web_agents/apache22_agent/Agent_001/config/
OpenSSOAgentConfiguration.properties
Agent Audit directory location:
/path/to/web_agents/apache22_agent/Agent_001/logs/audit
Agent Debug directory location:
/path/to/web_agents/apache22_agent/Agent_001/logs/debug
Install log file location:
/path/to/web agents/apache22 agent/installer-logs/audit/install.log
```

ampassword

ampassword — change passwords for the OpenAM Administrator

ampassword

ampassword {options}

1 Description

This command allows you to change passwords held in the configuration store, and to encrypt passwords.

2 Options

The following options are supported.

- -a | --admin [-o | --old old-password-file -n | --new new-password-file]
 Change the password for amAdmin from the value stored in old-password-file to the value stored in new-password-file.
- -p | --proxy [-o | --old old-password-file -n | --new new-password-file] Change the password for the proxy administrator from the value stored in old-password-file to the value stored in new-password-file.

The proxy administrator password is shown encrypted in the output from **ssoadm get-svrcfg-xml**.

- -e | --encrypt [password-file]
 Display the password value provided encrypted with the key generated
 during OpenAM installation.
- -h | --help Display the usage message.

3 Examples

The following example encrypts the value password.

```
$ echo password > pwd.file
$ ampassword -e pwd.file
AQICkZs3qy5QUCXir9tebIEEZYGFXI2lCC4B
```

amverifyarchive

amverifyarchive — check OpenAM log archives for tampering

amverifyarchive

amverifyarchive {options}

1 Description

This command checks log archive integrity.

2 Options

The following options are required.

-l logName

Verify log files of the specified type. To specify an individual log rather than a type, provide the entire log file name.

-p path

Path to log files to verify.

-u userName

User who can read log files.

-w password

Password of the user who can read log files.

3 Examples

The following example checks the amConsole logs.

```
$ amverifyarchive -l amConsole -p $HOME/openam/openam/log
-u amadmin -w password
```

configurator.jar

configurator.jar — install or upgrade OpenAM using a configuration file

configurator.jar

configurator.jar {options}

1 Description

This executable .jar file, openam-configurator-tool-11.0.0.jar, lets you perform silent installation, configuring a deployed OpenAM server by applying settings from a configuration file.

2 Options

The following options are supported.

- -f | --file configuration-file
 - Configure a deployed OpenAM web application archive using the specified configuration file. Installation and upgrade configuration files are described in the sections below.
- -? | --help Display the usage message.

3 Installation Configuration File

Base your configuration on the sampleconfiguration file delivered with OpenAM, and using the hints in this section, or the comments included in the file.

Server Properties

These properties pertain to the OpenAM server instance.

SERVER URL

URL to the web container where you want OpenAM to run, such as http://openam.example.com:8080

DEPLOYMENT URI

URI where you want to deploy OpenAM on the web container, such as $\ensuremath{\text{\prime}}$ openam

BASE DIR

Configuration directory where OpenAM stores files and embedded configuration directory servers, such as \$HOME/openam

locale

The user locale, such as en_GB

PLATFORM LOCALE

The locale of the OpenAM server, such as en_US

AM ENC KEY

The password encryption key, which must be the same on all servers in a multi-server installation, such as 06QWwHP04os+zEz3Nqn/2daAYWyiFE32. If left blank, installing OpenAM generates a random password encryption key that you can later view in OpenAM console under Configuration > Servers and Sites > Server Name > Security.

ADMIN PWD

Password of the OpenAM administrator user amadmin, which must be at least 8 characters in length and must match that of other servers in a multiserver deployment

AMLDAPUSERPASSWD

Password of the default policy agent UrlAccessAgent, which must be at least 8 characters in length and must not be the same as the value of $ADMIN_PWD$

COOKIE DOMAIN

Name of the trusted DNS domain OpenAM returns to a browser when it grants a session ID to a user, such as .example.com

Configuration Store Properties

These properties pertain to the directory server where OpenAM stores its configuration.

DATA STORE

Type of the configuration data store. The value embedded means set up OpenAM with an embedded, OpenDJ based configuration store. The value dirServer means an external directory server, such as OpenDJ, or Sun Java System Directory Server. If you set this to dirServer, and the configuration store contains the configuration of other OpenAM servers, then the server is added to the existing multiserver installation.

DIRECTORY SSL

To use LDAP without SSL, set this to SIMPLE. To use LDAP with SSL, set this to SSL.

DIRECTORY SERVER

Fully qualified domain name of the configuration store directory server host, such as opendj.example.com

DIRECTORY PORT

LDAP or LDAPS port number for the configuration store directory server, such as 389 or 636

DIRECTORY ADMIN PORT

Administration port number for the configuration store directory server, such as 4444

DIRECTORY JMX PORT

Java Management eXtension port number, such as 1689, used with the OpenDJ embedded configuration store

ROOT SUFFIX

Root suffix distinguished name (DN) for the configuration store, such as o=openam

DS DIRMGRDN

Distinguished name of the directory manager of the configuration store, such as cn=Directory Manager

DS DIRMGRPASSWD

Password for the directory manager of the configuration store

User Data Store Properties

These properties pertain to the directory server where OpenAM stores user profiles. If you do not include these properties, or you leave these properties commented out, then OpenAM uses the same directory server as it uses for the configuration store.

USERSTORE TYPE

The type of directory server used. Valid values include the following.

- LDAPv3ForOpenDS: ForgeRock OpenDJ or Sun OpenDS
- LDAPv3ForAD: Active Directory with host and port settings
- LDAPv3ForADDC: Active Directory with a Domain Name setting
- LDAPv3ForADAM: Active Directory Application Mode
- LDAPv3ForODSEE: Sun Java System Directory Server
- LDAPv3ForTivoli: IBM Tivoli Directory Server

USERSTORE SSL

To use LDAP without SSL, set this to SIMPLE. To use LDAP with SSL, set this to SSL.

USERSTORE DOMAINNAME

If USERSTORE_TYPE is LDAPv3ForADDC, you set this to the Active Directory Domain Name, such as ad.example.com, and then set only the USERSTORE_SSL, USERSTORE_MGRDN, and USERSTORE_PASSWD additional parameters. This lets Active Directory use DNS to retrieve service locations. Otherwise, do not use.

USERSTORE HOST

Fully qualified domain name of the user data store directory server, such as opendj.example.com

USERSTORE PORT

Port number of the user data store. Default for LDAP is 389, and for LDAP over SSL is 636.

USERSTORE SUFFIX

Root suffix distinguished name for the user data in the directory, such as dc=example,dc=com

USERSTORE MGRDN

Distinguished name of the directory manager of the user data store, such as cn=Directory Manager

USERSTORE PASSWD

Password for the directory manager of the user data store

Site Properties

These properties pertain when you configure multiple OpenAM servers in a site deployment, where a load balancer spreads request across multiple servers. Use the DS_EMB_REPL* and existingserverid properties only for the second and subsequent servers in a site configuration.

LB SITE NAME

The name of the OpenAM site

LB PRIMARY URL

The load balancer URL for the site, such as http://lb.example.com:80/openam.

LB SESSION HA SFO

Whether to enable session persistence and failover for the site. Default: false

DS EMB REPL FLAG

Enable use of the embedded configuration store by setting this parameter to embReplFlag, only if the DATA_STORE parameter is set to embedded. Use the other DS_EMB_REPL* parameters in this section to set up configuration store data replication.

DS EMB REPL REPLPORT1

Replication port number for the new OpenAM server you are installing, such as 58989

DS EMB REPL HOST2

Host name of an existing OpenAM server housing the configuration store directory server with which to replicate, such as openam1.example.com

DS EMB REPL ADMINPORT2

Administration port number for the configuration store directory server used by the existing OpenAM server, such as 4444

DS EMB REPL REPLPORT2

Replication port number for the configuration store directory server used by the existing OpenAM server, such as 50899

existingserverid

Full URL of the existing OpenAM server, such as http://serverl.example.com:8080/openam

4 Upgrade Configuration File

Base your configuration on the sampleconfiguration file delivered with OpenAM, and using the hints in this section, or the comments included in the file.

Upgrade Properties

SERVER URL

URL to the web container where OpenAM runs, such as http://openam.example.com:8080

DEPLOYMENT URI

URI where OpenAM is deployed on the web container, such as /openam

5 Examples

The following example shows a configuration file to install a server with an external user data store.

Server properties, AM_ENC_KEY="" means generate random key
SERVER_URL=http://openam.example.com:8080
DEPLOYMENT_URI=/openam
BASE_DIR=\$HOME/openam
locale=en_US
PLATFORM_LOCALE=en_US
AM_ENC_KEY=
ADMIN PWD=change3me

```
AMLDAPUSERPASSWD=secret12
COOKIE_DOMAIN=.example.com
# Embedded configuration data store
DATA STORE=embedded
DIRECTORY_SSL=SIMPLE
DIRECTORY_SERVER=openam.example.com
DIRECTORY PORT=50389
DIRECTORY ADMIN PORT=4444
DIRECTORY_JMX_PORT=1689
ROOT_SUFFIX=o=openam
DS DIRMGRDN=cn=Directory Manager
DS DIRMGRPASSWD=chang3me
# External OpenDJ based user data store
USERSTORE_TYPE=LDAPv3ForOpenDS
USERSTORE SSL=SIMPLE
#USERSTORE_DOMAINNAME=ad.example.com
USERSTORE_HOST=opendj.example.com
USERSTORE_PORT=389
USERSTORE_SUFFIX=dc=example,dc=com
USERSTORE_MGRDN=cn=Directory Manager
USERSTORE_PASSWD=secret12
# Uncomment to specify the site for the first server in a site configuration
#LB_SITE_NAME=lb
#LB_PRIMARY_URL=http://lb.example.com:80/openam
```

The following example shows a configuration file to install the second server in a site configuration.

```
# Server properties, AM_ENC_KEY from first server
SERVER_URL=http://server2.example.com:8080
DEPLOYMENT URI=/openam
BASE DIR=$HOME/openam
locale=en US
PLATFORM LOCALE=en US
AM_ENC_KEY=06QWwHP04os+zEz3Nqn/2daAYWyiFE32
ADMIN PWD=change3me
AMLDAPUSERPASSWD=secret12
COOKIE DOMAIN=.example.com
# Embedded configuration data store
DATA_STORE=embedded
DIRECTORY_SSL=SIMPLE
DIRECTORY_SERVER=server2.example.com
DIRECTORY_PORT=50389
DIRECTORY_ADMIN_PORT=4444
DIRECTORY_JMX_PORT=1689
ROOT SUFFIX=o=openam
DS DIRMGRDN=cn=Directory Manager
DS_DIRMGRPASSWD=chang3me
# External OpenDJ based user data store
USERSTORE_TYPE=LDAPv3ForOpenDS
USERSTORE_SSL=SIMPLE
#USERSTORE DOMAINNAME=ad.example.com
USERSTORE_HOST=opendj.example.com
USERSTORE PORT=389
USERSTORE SUFFIX=dc=example,dc=com
USERSTORE MGRDN=cn=Directory Manager
```

```
# Site properties
LB_SITE_NAME=lb
LB_PRIMARY_URL=http://lb.example.com:80/openam
DS_EMB_REPL_FLAG=embReplFlag
DS_EMB_REPL_REPLPORTI=58989
DS_EMB_REPL_HOST2=server1.example.com
DS_EMB_REPL_ADMINPORT2=4444
DS_EMB_REPL_REPLPORT2=50889
existingserverid=http://server1.example.com:8080/openam
```

The following example shows a configuration file to upgrade an OpenAM server.

```
SERVER_URL=https://openam.example.com:8080
DEPLOYMENT_URI=/openam
```

ssoadm

ssoadm — configure OpenAM core services

ssoadm

ssoadm [subcommand] [options]

1 Description

The **ssoadm** command provides a rich command-line interface for configuring OpenAM core services.

Also see the *Installation Guide* procedure, *To Set Up Administration Tools* for instructions on setting up the **ssoadm** command.

2 Global Options

The following global options are supported.

- --debug, -d Run in debug mode. Results sent to the debug file.
- --help, -? Print usage.

This command can also be used with subcommands as in **ssoadm** *subcommand* **--help**.

- --information, -0
 Print basic information about the tool.
- --locale, -l Name of the locale to display the results.
- --verbose, -v Run in verbose mode. Results sent to standard output.
- --version, -V Print the version of this tool.

3 Subcommands: By Category

This section lists subcommands by category. The subsequent section lists subcommands in alphabetical order with a short description.

See **ssoadm** *subcommand* **--help** for detailed options.

3.1 Agent Configuration

- add-agent-to-grp
- agent-remove-props
- create-agent
- create-agent-grp
- delete-agent-grps
- delete-agents
- list-agent-grp-members
- list-agent-grps
- list-agents
- remove-agent-from-grp
- show-agent
- show-agent-grp
- show-agent-membership
- show-agent-types
- update-agent
- update-agent-grp

3.2 Authentication Service Management

- add-auth-cfg-entr
- create-auth-cfg
- create-auth-instance
- delete-auth-cfgs
- delete-auth-instances
- get-auth-cfg-entr
- get-auth-instance
- list-auth-cfgs

- list-auth-instances
- register-auth-module
- unregister-auth-module
- update-auth-cfg-entr
- update-auth-cfg-props
- update-auth-instance

3.3 Data Store Management

- add-amsdk-idrepo-plugin
- create-datastore
- delete-datastores
- list-datastore-types
- list-datastores
- show-datastore
- update-datastore

3.4 Entitlements

- add-app-priv
- create-appl
- create-appl-type
- create-xacml
- delete-appl-types
- delete-appls
- delete-xacml
- list-appl-types
- list-appls
- list-xacml
- set-appl
- set-entitlement-conf

- show-app-priv
- show-appl
- show-entitlement-conf
- update-app-priv
- update-app-priv-resources
- update-app-priv-subjects

3.5 Federation Management

- add-cot-member
- create-cot
- create-metadata-templ
- delete-cot
- delete-entity
- do-bulk-federation
- export-entity
- import-bulk-fed-data
- import-entity
- list-cot-members
- list-cots
- list-entities
- remove-cot-member
- update-entity-keyinfo

3.6 Identity Management

- add-member
- add-privileges
- add-svc-identity
- create-identity
- delete-identities

- get-identity
- get-identity-svcs
- list-identities
- list-identity-assignable-svcs
- remove-member
- remove-privileges
- remove-svc-identity
- set-identity-attrs
- set-identity-svc-attrs
- show-identity-ops
- show-identity-svc-attrs
- show-identity-types
- show-members
- show-memberships
- show-privileges

3.7 Policy Management

- create-policies
- delete-policies
- list-policies
- update-policies

3.8 Realm Management

- add-svc-attrs
- add-svc-realm
- create-realm
- delete-realm
- delete-realm-attr
- get-realm

- get-realm-svc-attrs
- list-realm-assignable-svcs
- list-realms
- remove-svc-attrs
- remove-svc-realm
- set-realm-attrs
- set-svc-attrs
- set-realm-svc-attrs
- show-auth-modules
- show-data-types
- show-realm-svcs

3.9 Server Configuration

- add-site-members
- add-site-sec-urls
- clone-server
- create-server
- create-site
- delete-server
- delete-site
- export-server
- get-svrcfg-xml
- import-server
- list-server-cfg
- list-servers
- list-sites
- remove-server-cfg
- remove-site-members

- remove-site-sec-urls
- set-site-pri-url
- set-site-sec-urls
- set-svrcfg-xml
- show-site
- show-site-members
- update-server-cfg

3.10 Service Management

To translate settings applied in OpenAM console to service attributes for use with **ssoadm**, login to the OpenAM console as as amadmin and access the services page, such as http://openam.example.com:8080/openam/services.jsp.

- · add-attr-defs
- add-attrs
- add-plugin-interface
- add-sub-schema
- create-sub-cfg
- create-svc
- create-svrcfg-xml
- delete-attr
- · delete-sub-cfg
- delete-svc
- export-svc-cfg
- get-attr-defs
- get-revision-number
- import-svc-cfg
- remove-attr-choicevals
- · remove-attr-defs

- remove-sub-schema
- set-attr-any
- set-attr-bool-values
- set-attr-choicevals
- set-attr-defs
- set-attr-end-range
- set-attr-i18n-key
- set-attr-start-range
- set-attr-syntax
- set-attr-type
- set-attr-ui-type
- set-attr-validator
- set-attr-view-bean-url
- set-inheritance
- set-plugin-viewbean-url
- set-revision-number
- set-sub-cfg
- set-svc-i18n-key
- set-svc-view-bean-url
- update-svc

3.11 Other

- · add-res-bundle
- do-batch
- do-migration70
- list-res-bundle
- list-sessions
- remove-res-bundle

4 Subcommands: Alphabetical Order

The following subcommands are supported.

See also **ssoadm** *subcommand* --help.

4.1 ssoadm add-agent-to-grp

Add agents to a agent group.

Usage: ssoadm add-agent-to-grp --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--agentgroupname, -b
Name of agent group.
```

```
--agentnames, -s
Names of agents.
```

```
--password-file, -f
```

File name that contains password of administrator.

```
--realm, -e
Name of realm.
```

4.2 ssoadm add-amsdk-idrepo-plugin

Create AMSDK IdRepo Plug-in

Usage: ssoadm add-amsdk-idrepo-plugin --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--basedn, -b
```

Directory Server base distinguished name.

```
--bind-password-file, -m
File that contains password of bind password.
```

```
--binddn, -e
Directory Server bind distinguished name.
```

```
--directory-servers, -s
    directory servers <protocol>://<hostname>:<port>. Can have multiple
    entries.

--dsame-password-file, -x
    File that contains password of the dsameuser

--password-file, -f
    File name that contains password of administrator.

--puser-password-file, -p
    File that contains password of the puser

[--org, -o]
    Organization objects naming attribute (defaults to 'o')

[--user, -a]
    User objects naming attribute (defaults to 'uid')
```

4.3 ssoadm add-app-priv

Add an application privilege to delegate resources of a given application.

Usage: ssoadm add-app-priv --options [--global-options]

Options

```
--actions, -a
   Possible values are READ, MODIFY, DELEGATE, ALL
--adminid, -u
   Administrator ID of running the command.
--application, -t
   Application name
--name, -m
   Name for the this delegation
--password-file, -f
   File name that contains password of administrator.
--realm, -e
   Realm name
--subjects, -s
   Subject name
--subjecttype, -b
   Possible values are User or Group
```

```
[--description, -p]
```

Description for the this delegation.

```
[--resources, -r]
```

Resources to delegate, All resources in the applications will be delegated if this option is absent.

4.4 ssoadm add-attr-defs

Add default attribute values in schema.

```
Usage: ssoadm add-attr-defs --options [--global-options]
```

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

```
--schematype, -t
```

Type of schema.

--servicename, -s

Name of service.

```
[--attributevalues, -a]
```

Attribute values e.g. homeaddress=here.

```
[--datafile, -D]
```

Name of file that contains attribute values data.

```
[--subschemaname, -c]
```

Name of sub schema.

4.5 ssoadm add-attrs

Add attribute schema to an existing service.

```
Usage: ssoadm add-attrs --options [--global-options]
```

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--attributeschemafile, -F
   XML file containing attribute schema definition.
--password-file, -f
   File name that contains password of administrator.
--schematype, -t
   Schema Type.
--servicename, -s
   Service Name.
[--subschemaname, -c]
   Name of sub schema.
ssoadm add-auth-cfg-entr
Add authentication configuration entry
Usage: ssoadm add-auth-cfg-entr --options [--global-options]
Options
--adminid, -u
   Administrator ID of running the command.
--criteria, -c
   Criteria for this entry. Possible values are REQUIRED, OPTIONAL,
   SUFFICIENT, REQUISITE
--modulename, -o
   Module Name.
--name, -m
   Name of authentication configuration.
--password-file, -f
   File name that contains password of administrator.
--realm, -e
   Name of realm.
[--options, -t]
   Options for this entry.
[--position, -p]
   Position where the new entry is to be added. This is option is not set, entry
```

shall be added to the end of the list. If value of this option is 0, it will be

4.6

inserted to the front of the list. If value is greater of the length of the list, entry shall be added to the end of the list.

4.7 ssoadm add-cot-member

Add a member to a circle of trust.

```
Usage: ssoadm add-cot-member --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.

--cot, -t
Circle of Trust

--entityid, -y
Entity ID

--password-file, -f
File name that contains password of administrator.

[--realm, -e]
Realm where circle of trust resides
```

[--spec, -c]

Specify metadata specification, either wsfed, idff or saml2, defaults to saml2

4.8 ssoadm add-member

Add an identity as member of another identity

```
Usage: ssoadm add-member --options [--global-options]
```

```
    --adminid, -u
        Administrator ID of running the command.
    --idname, -i
        Name of identity.
    --idtype, -t
        Type of Identity
```

```
    --memberidname, -m
        Name of identity that is member.
    --memberidtype, -y
        Type of Identity of member such as User, Role and Group.
    --password-file, -f
        File name that contains password of administrator.
    --realm, -e
```

ssoadm add-plugin-interface

Name of realm.

Add Plug-in interface to service.

Usage: ssoadm add-plugin-interface --options [--global-options]

Options

4.9

```
    --adminid, -u
        Administrator ID of running the command.
    --i18nkey, -k
        Plug-in I18n Key.
    --interfacename, -i
        Name of interface.
    --password-file, -f
        File name that contains password of administrator.
    --pluginname, -g
        Name of Plug-in.
    --servicename, -s
        Name of service.
```

4.10 ssoadm add-plugin-schema

Add Plug-in schema to service.

Usage: ssoadm add-plugin-schema --options [--global-options]

Options

--adminid, -u
Administrator ID of running the command.

```
--classname, -c
Name of the Plugin Schema class implementation

--i18nkey, -k
Plug-in I18n Key.

--i18nname, -n
Plug-in I18n Name.

--interfacename, -i
Name of interface.

--password-file, -f
File name that contains password of administrator.

--pluginname, -g
Name of Plug-in.

--servicename, -s
Name of service.
```

4.11 ssoadm add-privileges

Add privileges to an identity. To add a privilege to all authenticated users, use the "All Authenticated Users" idname with "role" idtype.

Usage: ssoadm add-privileges --options [--global-options]

```
--adminid, -u
Administrator ID of running the command.

--idname, -i
Name of identity.

--idtype, -t
Type of Identity such as Role and Group.

--password-file, -f
File name that contains password of administrator.

--privileges, -g
Name of privileges to be added. Privilege names are AgentAdmin,
EntitlementRestAccess, FederationAdmin, LogAdmin, LogRead, LogWrite,
PolicyAdmin, PrivilegeRestAccess, PrivilegeRestReadAccess, RealmAdmin.

--realm, -e
Name of realm.
```

4.12 ssoadm add-res-bundle

Add resource bundle to data store.

```
Usage: ssoadm add-res-bundle --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--bundlefilename, -B
Resource bundle physical file name.
```

```
--bundlename, -b
Resource Bundle Name.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
[--bundlelocale, -o]
Locale of the resource bundle.
```

4.13 ssoadm add-site-members

Add members to a site.

```
Usage: ssoadm add-site-members --options [--global-options]
```

Options

```
--adminid, -u  Administrator \ ID \ of \ running \ the \ command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--servernames, -e
Server names, e.g. http://www.example.com:8080/fam
```

```
--sitename, -s
Site name, e.g. mysite
```

4.14 ssoadm add-site-sec-urls

Add Site Secondary URLs.

```
Usage: ssoadm add-site-sec-urls --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--secondaryurls, -a
Secondary URLs
```

```
--sitename, -s
Site name, e.g. mysite
```

4.15 ssoadm add-sub-schema

Add sub schema.

```
Usage: ssoadm add-sub-schema --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--filename, -F
Name of file that contains the schema
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--schematype, -t
Type of schema.
```

```
--servicename, -s
Name of service.
```

```
[--subschemaname, -c]
Name of sub schema.
```

4.16 ssoadm add-svc-attrs

Add service attribute values in a realm.

```
Usage: ssoadm add-svc-attrs --options [--global-options]
```

Options

```
--adminid, -u
   Administrator ID of running the command.
--password-file, -f
   File name that contains password of administrator.
--realm, -e
   Name of realm.
--servicename, -s
   Name of service.
[--attributevalues, -a]
   Attribute values to be added e.g. homeaddress=here.
[--datafile, -D]
   Name of file that contains attribute values to be added.
ssoadm add-svc-identity
Add Service to an identity
Usage: ssoadm add-svc-identity --options [--global-options]
Options
--adminid, -u
   Administrator ID of running the command.
--idname, -i
   Name of identity.
--idtype, -t
   Type of Identity such as User, Role and Group.
--password-file, -f
   File name that contains password of administrator.
--realm, -e
   Name of realm.
```

--servicename, -s Name of service.

4.17

```
[--attributevalues, -a]
   Attribute values e.g. homeaddress=here.
[--datafile, -D]
   Name of file that contains attribute values data.
```

4.18 ssoadm add-svc-realm

Add service to a realm.

```
Usage: ssoadm add-svc-realm --options [--global-options]
```

Options

```
-adminid, -u
    Administrator ID of running the command.
-password-file, -f
    File name that contains password of administrator.
-realm, -e
    Name of realm.
-servicename, -s
    Service Name.
[--attributevalues, -a]
    Attribute values e.g. homeaddress=here.
[--datafile, -D]
    Name of file that contains attribute values data.
```

4.19 ssoadm agent-remove-props

Remove agent's properties.

```
Usage: ssoadm agent-remove-props --options [--global-options]
```

```
    --adminid, -u
        Administrator ID of running the command.
    --agentname, -b
        Name of agent.
    --attributenames, -a
        properties name(s).
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm.
```

4.20 ssoadm clone-server

Clone a server instance.

```
Usage: ssoadm clone-server --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--cloneservername, -o
Clone server name
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--servername, -s
Server name
```

4.21 ssoadm create-agent

Create a new agent configuration.

```
Usage: ssoadm create-agent --options [--global-options]
```

```
--adminid, -u
Administrator ID of running the command.
```

```
--agentname, -b
Name of agent.
```

```
    --agenttype, -t
    Type of agent. Possible values: J2EEAgent, WebAgent, WSCAgent, WSPAgent, STSAgent, DiscoveryAgent, 2.2_Agent, SharedAgent, OAuth2Client
```

```
--password-file, -f
File name that contains password of administrator.
```

- --realm, -e Name of realm.
- [--agenturl, -g]

Agent URL. e.g. http://www.agent.example:8080/agent. WebAgent does not take URL with path. e.g. http://www.agent.example:8080. This option is valid for J2EEAgent and WebAgent. This parameter is required if the agent is created without datafile/attributes.

- [--attributevalues, -a]
 Properties e.g. sunIdentityServerDeviceKeyValue=https://
 agent.example.com:443/
- [--datafile, -D] Name of file that contains properties.
- [--serverurl, -s]
 Server URL. e.g. http://www.example.com:58080/openam. This option is valid for J2EEAgent and WebAgent. This parameter is required if the agent is created without datafile/attributes.

4.22 ssoadm create-agent-grp

Create a new agent group.

Usage: ssoadm create-agent-grp --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

- -agentgroupname, -bName of agent group.
- --agenttype, -t Type of agent group. e.g. J2EEAgent, WebAgent
- --password-file, -f File name that contains password of administrator.
- --realm, -e Name of realm.
- [--attributevalues, -a]
 Properties e.g. homeaddress=here.
- [--datafile, -D] Name of file that contains properties.

[--serverurl, -s]

Server URL. e.g. http://www.example.com:58080/openam. This option is valid for J2EEAgent and WebAgent.

4.23 ssoadm create-appl

Create application.

Usage: ssoadm create-appl --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--applicationtype, -t
Application type name

--name, -m

Application name

--password-file, -f

File name that contains password of administrator.

--realm, -e

Realm name

[--attributevalues, -a]

Attribute values e.g. applicationType=iPlanetAMWebAgentService.

[--datafile, -D]

Name of file that contains attribute values data. Mandatory attributes are resources, subjects, conditions and entitlementCombiner. Optional ones are actions, searchIndexImpl, saveIndexImpl, resourceComparator, subjectAttributeNames.

4.24 ssoadm create-appl-type

Create application type.

Usage: ssoadm create-appl-type --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

```
--name, -m
```

Application Type name

```
--password-file, -f
```

File name that contains password of administrator.

```
[--attributevalues, -a]
```

Application Type attribute values e.g. actions=enabled=true.

```
[--datafile, -D]
```

Name of file that contains attribute type values data. Mandatory attributes are actions, searchIndexImpl and saveIndexImpl. Optional are resourceComparator.

4.25 ssoadm create-auth-cfg

Create authentication configuration

Usage: ssoadm create-auth-cfg --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--name, -m
```

Name of authentication configuration.

```
--password-file, -f
```

File name that contains password of administrator.

```
--realm, -e
```

Name of realm.

4.26 ssoadm create-auth-instance

Create authentication instance

Usage: ssoadm create-auth-instance --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--authtype, -t
```

Type of authentication instance e.g. LDAP, DataStore.

```
    -name, -m
        Name of authentication instance.
    -password-file, -f
        File name that contains password of administrator.
    -realm, -e
        Name of realm.
```

4.27 ssoadm create-cot

Create circle of trust.

Usage: ssoadm create-cot --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.

--cot, -t
Circle of Trust

--password-file, -f
File name that contains password of administrator.

[--prefix, -p]
Prefix URL for idp discovery reader and writer URL.

[--realm, -e]
Realm where circle of trust resides

[--trustedproviders, -k]
Trusted Providers
```

4.28 ssoadm create-datastore

Create data store under a realm

Usage: ssoadm create-datastore --options [--global-options]

Options

--adminid, -u
Administrator ID of running the command.

```
Type of datastore. Use the list-datastore-types subcommand to get a list of
   supported datastore types.
--name, -m
   Name of datastore.
--password-file, -f
    File name that contains password of administrator.
--realm, -e
   Name of realm.
[--attributevalues, -a]
   Attribute values e.g.
   sunIdRepoClass=com.sun.identity.idm.plugins.files.FilesRepo.
[--datafile, -D]
   Name of file that contains attribute values data.
ssoadm create-identity
Create identity in a realm
Usage: ssoadm create-identity --options [--global-options]
Options
--adminid, -u
   Administrator ID of running the command.
--idname, -i
   Name of identity.
--idtype, -t
   Type of Identity such as User, Role and Group.
--password-file, -f
    File name that contains password of administrator.
```

Attribute values e.g. sunIdentityServerDeviceStatus=Active.

Name of file that contains attribute values data.

--datatype, -t

--realm. -e

Name of realm.

[--attributevalues, -a]

[--datafile, -D]

4.29

4.30 ssoadm create-metadata-templ

Create new metadata template.

Usage: ssoadm create-metadata-templ --options [--global-options]

Options

- --adminid, -u
 Administrator ID of running the command.
- --entityid, -y Entity ID
- --password-file, -f

File name that contains password of administrator.

[--affiecertalias, -K]

Affiliation encryption certificate alias

[--affiliation, -F]

Specify metaAlias for hosted affiliation. to be created. The format must be <realm name>/<identifier>

[--affimembers, -M]

Affiliation members

- [--affiownerid, -N]
 - Affiliation Owner ID
- [--affiscertalias, -J]
 Affiliation signing certificate alias
- [--attraecertalias, -G]

Attribute authority encryption certificate alias.

[--attrascertalias, -B]

Attribute authority signing certificate alias

[--attrauthority, -I]

Specify metaAlias for hosted attribute authority to be created. The format must be <realm name>/<identifier>.

[--attrqecertalias, -R]

Attribute query provider encryption certificate alias

[--attrqscertalias, -A]

Attribute query provider signing certificate alias

[--attrqueryprovider, -S]

Specify metaAlias for hosted attribute query provider to be created. The format must be <realm name>/<identifier>.

[--authnaecertalias, -E]

Authentication authority encryption certificate alias.

[--authnascertalias, -D]

Authentication authority signing certificate alias

[--authnauthority, -C]

Specify metaAlias for hosted authentication authority to be created. The format must be <realm name>/<identifier>.

[--extended-data-file, -x]

Specify file name for the extended metadata to be created. XML will be displayed on terminal if this file name is not provided.

[--identityprovider, -i]

Specify metaAlias for hosted identity provider to be created. The format must be <realm name>/<identifier>.

[--idpecertalias, -g]

Identity provider encryption certificate alias.

[--idpscertalias, -b]

Identity provider signing certificate alias

[--meta-data-file, -m]

Specify file name for the standard metadata to be created. XML will be displayed on terminal if this file name is not provided.

[--serviceprovider, -s]

Specify metaAlias for hosted service provider to be created. The format must be <realm name>/<identifier>.

[--specertalias, -r]

Service provider encryption certificate alias

[--spec, -c]

Specify metadata specification, either wsfed, idff or saml2, defaults to saml2

[--spscertalias, -a]

Service provider signing certificate alias

[--xacmlpdpecertalias, -i]

Policy decision point encryption certificate alias

[--xacmlpdpscertalias, -t]

Policy decision point signing certificate alias

[--xacmlpdp, -p]

Specify metaAlias for policy decision point to be created. The format must be <realm name>/<identifier>.

[--xacmlpepecertalias, -z]

Policy enforcement point encryption certificate alias

[--xacmlpepscertalias, -k]

Policy enforcement point signing certificate alias

[--xacmlpep, -e]

Specify metaAlias for policy enforcement point to be created. The format must be <realm name>/<identifier>.

4.31 ssoadm create-policies

Create policies in a realm.

Usage: ssoadm create-policies --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--password-file, -f

File name that contains password of administrator.

--realm, -e

Name of realm.

--xmlfile, -X

Name of file that contains policy XML definition.

4.32 ssoadm create-realm

Create realm.

Usage: ssoadm create-realm --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--password-file, -f

File name that contains password of administrator.

--realm, -e Name of realm to be created.

4.33 ssoadm create-server

Create a server instance.

Usage: ssoadm create-server --options [--global-options]

Options

- --adminid, -u
 Administrator ID of running the command.
- --password-file, -f File name that contains password of administrator.
- --serverconfigxml, -X Server Configuration XML file name.
- --servername, -s Server name, e.g. http://www.example.com:8080/fam
- [--attributevalues, -a]
 Attribute values e.g. homeaddress=here.
- [--datafile, -D]

 Name of file that contains attribute values data.

4.34 ssoadm create-site

Create a site.

Usage: ssoadm create-site --options [--global-options]

- --adminid, -u
 Administrator ID of running the command.
- --password-file, -f File name that contains password of administrator.
- --sitename, -s Site name, e.g. mysite

```
--siteurl, -i
Site's primary URL, e.g. http://www.example.com:8080
[--secondaryurls, -a]
Secondary URLs
```

4.35 ssoadm create-sub-cfg

Create a new sub configuration.

Usage: ssoadm create-sub-cfg --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--servicename, -s
Name of service.
```

```
--subconfigname, -g
Name of sub configuration.
```

```
[--attributevalues, -a]
Attribute values e.g. homeaddress=here.
```

```
[--datafile, -D]

Name of file that contains attribute values data.
```

```
[--priority, -p]
Priority of the sub configuration.
```

```
[--realm, -e]
```

Name of realm (Sub Configuration shall be added to global configuration if this option is not provided).

```
[--subconfigid, -b]
ID of parent configuration(Sub Configuration shall be added to root configuration if this option is not provided).
```

4.36 ssoadm create-svc

Create a new service in server.

Usage: ssoadm create-svc --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.

--password-file, -f
File name that contains password of administrator.

--xmlfile, -X
XML file(s) that contains schema.

[--continue, -c]
Continue adding service if one or more previous service cannot be added.
```

4.37 ssoadm create-svrcfg-xml

Create serverconfig.xml file. No options are required for flat file configuration data store.

Usage: ssoadm create-svrcfg-xml --options [--global-options]

```
--adminid, -u
   Administrator ID of running the command.
--password-file, -f
   File name that contains password of administrator.
[--basedn, -b]
   Directory Server base distinguished name.
[--dsadmin, -a]
   Directory Server administrator distinguished name
[--dshost, -t]
   Directory Server host name
[--dspassword-file, -x]
   File that contains Directory Server administrator password
[--dsport, -p]
   Directory Server port number
[--outfile, -ol
   File name where serverconfig XML is written.
```

4.38 ssoadm create-xacml

Create policies in a realm with XACML input.

Usage: ssoadm create-xacml --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

```
--realm, -e
```

Name of realm.

--xmlfile, -X

Name of file that contains policy XACML definition.

4.39 ssoadm delete-agent-grps

Delete agent groups.

Usage: ssoadm delete-agent-grps --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

```
--realm, -e
```

Name of realm.

```
[--agentgroupnames, -s]
```

Separate multiple agent group names with spaces.

```
[--file, -D]
```

File containing agent group names, with multiple group names separated by spaces.

4.40 ssoadm delete-agents

Delete agent configurations.

```
Usage: ssoadm delete-agents --options [--global-options]
```

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

```
--realm, -e
```

Name of realm.

```
[--agentnames, -s]
```

Separate multiple agent names with spaces.

```
[--file, -D]
```

File containing agent names, with multiple agent names separated by spaces.

4.41 ssoadm delete-appl-types

Delete application types.

Usage: ssoadm delete-appl-types --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--names, -m
```

Application Type names

```
--password-file, -f
```

File name that contains password of administrator.

4.42 ssoadm delete-appls

Delete applications.

Usage: ssoadm delete-appls --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

```
    -names, -m
        Application names
    -password-file, -f
        File name that contains password of administrator.
    -realm, -e
        Realm name
```

4.43 ssoadm delete-attr

Delete attribute schemas from a service

Usage: ssoadm delete-attr --options [--global-options]

Options

```
--adminid, -u
   Administrator ID of running the command.

--attributeschema, -a
   Name of attribute schema to be removed.

--password-file, -f
   File name that contains password of administrator.

--schematype, -t
   Type of schema.

--servicename, -s
   Name of service.

[--subschemaname, -c]
   Name of sub schema.
```

4.44 ssoadm delete-attr-def-values

Delete attribute schema default values.

Usage: ssoadm delete-attr-def-values --options [--global-options]

```
--adminid, -u
Administrator ID of running the command.
--attributeschema, -a
Name of attribute schema
```

```
    --defaultvalues, -e
        Default value(s) to be deleted
    --password-file, -f
        File name that contains password of administrator.
    --schematype, -t
        Type of schema.
    --servicename, -s
        Name of service.
    [--subschemaname, -c]
        Name of sub schema.
```

4.45 ssoadm delete-auth-cfgs

Delete authentication configurations

```
Usage: ssoadm delete-auth-cfgs --options [--global-options]
```

Options

```
    --adminid, -u
        Administrator ID of running the command.
    --names, -m
        Name of authentication configurations.
    --password-file, -f
        File name that contains password of administrator.
    --realm, -e
        Name of realm.
```

4.46 ssoadm delete-auth-instances

Delete authentication instances

Usage: ssoadm delete-auth-instances --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
--names, -m
```

Name of authentication instances.

```
--password-file, -f
File name that contains password of administrator.
```

--realm, -e Name of realm.

4.47 ssoadm delete-cot

Delete circle of trust.

Usage: ssoadm delete-cot --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--cot, -t
Circle of Trust
```

--password-file, -f

File name that contains password of administrator.

[--realm, -e]

Realm where circle of trust resides

4.48 ssoadm delete-datastores

Delete data stores under a realm

Usage: ssoadm delete-datastores --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--names, -m
```

Names of datastore.

```
--password-file, -f
```

File name that contains password of administrator.

```
--realm, -e
Name of realm.
```

4.49 ssoadm delete-entity

Delete entity.

```
Usage: ssoadm delete-entity --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.

--entityid, -y
Entity ID

--password-file, -f
File name that contains password of administrator.

[--extendedonly, -x]
Set to flag to delete only extended data.

[--realm, -e]
Realm where data resides

[--spec, -c]
Specify metadata specification, either wsfed, idff or saml2, defaults to saml2
```

4.50 ssoadm delete-identities

Delete identities in a realm

Usage: ssoadm delete-identities --options [--global-options]

```
    --adminid, -u
        Administrator ID of running the command.
    --idtype, -t
        Type of Identity such as User, Role and Group.
    --password-file, -f
        File name that contains password of administrator.
    --realm, -e
        Name of realm.
    [--file, -D]
        Name of file that contains the identity names to be deleted.
    [--idnames, -i]
        Names of identites.
```

4.51 ssoadm delete-policies

Delete policies from a realm.

Usage: ssoadm delete-policies --options [--global-options]

Options

```
--adminid, -uAdministrator ID of running the command.--password-file, -f
```

```
File name that contains password of administrator.
```

```
--realm, -e
Name of realm.
```

```
[--file, -D]
```

Name of file that contains the policy names to be deleted.

```
[--policynames, -p]
Names of policy to be deleted.
```

4.52 ssoadm delete-realm

Delete realm.

Usage: ssoadm delete-realm --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm to be deleted.
```

```
[--recursive, -r]
Delete descendent realms recursively.
```

4.53 ssoadm delete-realm-attr

Delete attribute from a realm.

```
Usage: ssoadm delete-realm-attr --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--attributename, -a
Name of attribute to be removed.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm.
```

```
--servicename, -s
Name of service.
```

4.54 ssoadm delete-server

Delete a server instance.

```
Usage: ssoadm delete-server --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--servername, -s
Server name, e.g. http://www.example.com:8080/fam
```

4.55 ssoadm delete-site

Delete a site.

```
Usage: ssoadm delete-site --options [--global-options]
```

Options

--adminid, -u
Administrator ID of running the command.

```
--password-file, -f
File name that contains password of administrator.
```

```
--sitename, -s
Site name, e.g. mysite
```

4.56 ssoadm delete-sub-cfg

Remove Sub Configuration.

```
Usage: ssoadm delete-sub-cfg --options [--global-options]
```

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

```
--servicename, -s
```

Name of service.

--subconfigname, -g

Name of sub configuration.

```
[--realm, -e]
```

Name of realm (Sub Configuration shall be added to global configuration if this option is not provided).

4.57 ssoadm delete-svc

Delete service from the server.

```
Usage: ssoadm delete-svc --options [--global-options]
```

Options

```
--adminid. -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

```
--servicename, -s
Service Name(s).
```

```
[--continue, -c]
    Continue deleting service if one or more previous services cannot be deleted.[--deletepolicyrule, -r]
    Delete policy rule.
```

4.58 ssoadm delete-xacml

Delete XACML policies from a realm.

Usage: ssoadm delete-xacml --options [--global-options]

Options

```
--adminid, -u  Administrator \ ID \ of \ running \ the \ command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm.
```

```
[--file, -D]
```

Name of file that contains the policy names to be deleted.

```
[--policynames, -p]
Names of policy to be deleted.
```

4.59 ssoadm do-batch

Do multiple requests in one command.

Usage: ssoadm do-batch --options [--global-options]

```
    --adminid, -u
        Administrator ID of running the command.
    --batchfile, -Z
        Name of file that contains commands and options.
    --password-file, -f
        File name that contains password of administrator.
    [--batchstatus, -b]
        Name of status file.
```

[--continue, -c]

Continue processing the rest of the request when preceeding request was erroneous.

4.60 ssoadm do-bulk-federation

Perform bulk federation.

Usage: ssoadm do-bulk-federation --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--metaalias, -m

Specify metaAlias for local provider.

--nameidmapping, -e

Name of file that will be created by this sub command. It contains remote user Id to name identifier. It shall be used by remote provider to update user profile.

--password-file, -f

File name that contains password of administrator.

--remoteentityid, -r

Remote entity Id

--useridmapping, -g File name of local to remote user Id mapping. Format <local-user-id>| <remote-user-id>

[--spec, -c]

Specify metadata specification, either idff or saml2, defaults to saml2

4.61 ssoadm do-migration70

Migrate organization to realm.

Usage: ssoadm do-migration70 --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

```
--entrydn, -e
Distinguished name of organization to be migrated.
```

--password-file, -f File name that contains password of administrator.

4.62 ssoadm embedded-status

Status of embedded store.

Usage: ssoadm embedded-status --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

--password-file, -f File name that contains password of administrator.

--port, -p Embedded store port

[--password, -w]
Embedded store password

4.63 ssoadm export-entity

Export entity.

Usage: ssoadm export-entity --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--entityid, -y
Entity ID
```

--password-file, -f File name that contains password of administrator.

[--extended-data-file, -x] Extended data

[--meta-data-file, -m] Metadata

```
[--realm, -e]
    Realm where data resides
[--sign, -g]
    Set this flag to sign the metadata
[--spec, -c]
    Specify metadata specification, either wsfed, idff or saml2, defaults to saml2
```

4.64 ssoadm export-server

Export a server instance.

Usage: ssoadm export-server --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.

--password-file, -f
File name that contains password of administrator.

--servername, -s
Server name

[--outfile, -o]
Filename where configuration was written.
```

4.65 ssoadm export-svc-cfg

Export service configuration.

Usage: ssoadm export-svc-cfg --options [--global-options]

```
--adminid, -u
Administrator ID of running the command.

--encryptsecret, -e
Secret key for encrypting password.

--password-file, -f
File name that contains password of administrator.

[--outfile, -o]
Filename where configuration was written.
```

4.66 ssoadm get-attr-choicevals

Get choice values of attribute schema.

Usage: ssoadm get-attr-choicevals --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.

--attributename, -a
Name of attribute.

--password-file, -f
File name that contains password of administrator.

--schematype, -t
Type of schema.

--servicename, -s
Name of service.

[--subschemaname, -c]
Name of sub schema.
```

4.67 ssoadm get-attr-defs

Get default attribute values in schema.

```
Usage: ssoadm get-attr-defs --options [--global-options]
```

```
    -adminid, -u
        Administrator ID of running the command.
    -password-file, -f
        File name that contains password of administrator.
    -schematype, -t
        Type of schema. One of dynamic, global, or organization (meaning realm).
    -servicename, -s
        Name of service.
    [--attributenames, -a]
        Attribute name(s).
```

```
[--subschemaname, -c]
Name of sub schema.
```

4.68 ssoadm get-auth-cfg-entr

Get authentication configuration entries

```
Usage: ssoadm get-auth-cfg-entr --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--name, -m
```

Name of authentication configuration.

```
--password-file, -f
```

File name that contains password of administrator.

```
--realm, -e
```

Name of realm.

4.69 ssoadm get-auth-instance

Get authentication instance values

```
Usage: ssoadm get-auth-instance --options [--global-options]
```

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--name, -m
```

Name of authentication instance.

```
--password-file, -f
```

File name that contains password of administrator.

```
--realm, -e
```

Name of realm.

4.70 ssoadm get-identity

Get identity property values

```
Usage: ssoadm get-identity --options [--global-options]
```

```
    --adminid, -u
        Administrator ID of running the command.
    --idname, -i
        Name of identity.
    --idtype, -t
        Type of Identity such as User, Role and Group.
```

--password-file, -f File name that contains password of administrator.

```
--realm, -e
Name of realm.
```

[--attributenames, -a]
Attribute name(s). All attribute values shall be returned if the option is not provided.

4.71 ssoadm get-identity-svcs

Get the service in an identity

```
Usage: ssoadm get-identity-svcs --options [--global-options]
```

Options

```
    --adminid, -u
        Administrator ID of running the command.
    --idname, -i
        Name of identity.
    --idtype, -t
        Type of Identity such as User, Role and Group.
    --password-file, -f
        File name that contains password of administrator.
    --realm, -e
        Name of realm.
```

4.72 ssoadm get-realm

Get realm property values.

```
Usage: ssoadm get-realm --options [--global-options]
```

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
```

File name that contains password of administrator.

```
--realm, -e
```

Name of realm.

--servicename, -s

Name of service.

4.73 ssoadm get-realm-svc-attrs

Get realm's service attribute values.

Usage: ssoadm get-realm-svc-attrs --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

```
--realm, -e
```

Name of realm.

--servicename, -s

Name of service.

4.74 ssoadm get-revision-number

Get service schema revision number.

Usage: ssoadm get-revision-number --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

```
--password-file, -f
File name that contains password of administrator.
```

```
--servicename, -s
Name of service.
```

4.75 ssoadm get-sub-cfg

Get sub configuration.

```
Usage: ssoadm get-sub-cfg --options [--global-options]
```

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

```
--servicename, -s
```

Name of service.

--subconfigname, -g

Name of sub configuration.

[--realm, -e]

Name of realm (Sub Configuration shall be added to global configuration if this option is not provided).

4.76 ssoadm get-svrcfg-xml

Get server configuration XML from centralized data store

```
Usage: ssoadm get-svrcfg-xml --options [--global-options]
```

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

--servername, -s

Server name, e.g. http://www.example.com:8080/fam

[--outfile, -o]

File name where serverconfig XML is written.

4.77 ssoadm import-bulk-fed-data

Import bulk federation data which is generated by 'do-bulk-federation' sub command.

Usage: ssoadm import-bulk-fed-data --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--bulk-data-file, -g

File name of bulk federation data which is generated by 'do-bulk-federation' sub command.

--metaalias, -m

Specify metaAlias for local provider.

--password-file, -f

File name that contains password of administrator.

[--spec, -c]

Specify metadata specification, either idff or saml2, defaults to saml2

4.78 ssoadm import-entity

Import entity.

Usage: ssoadm import-entity --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--password-file, -f

File name that contains password of administrator.

[--cot, -t]

Specify name of the Circle of Trust this entity belongs.

[--extended-data-file, -x]

Specify file name for the extended entity configuration to be imported.<web>Extended entity configuration to be imported.

```
[--meta-data-file, -m]
```

Specify file name for the standard metadata to be imported.<web>Standard metadata to be imported.

```
[--realm, -e]
```

Realm where entity resides.

```
[--spec, -c]
```

Specify metadata specification, either wsfed, idff or saml2, defaults to saml2

4.79 ssoadm import-server

Import a server instance.

Usage: ssoadm import-server --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--password-file, -f

File name that contains password of administrator.

--servername, -s Server name

--xmlfile, -X

XML file that contains configuration.

4.80 ssoadm import-svc-cfg

Import service configuration.

Usage: ssoadm import-svc-cfg --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--encryptsecret, -e

Secret key for decrypting password.

--password-file, -f

File name that contains password of administrator.

--xmlfile, -X XML file that contains configuration data.

4.81 ssoadm list-agent-grp-members

```
List agents in agent group.
```

Usage: ssoadm list-agent-grp-members --options [--global-options]

Options

```
--adminid, -u  Administrator \ ID \ of \ running \ the \ command.
```

```
--agentgroupname, -b Name of agent group.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm.
```

```
[--filter, -x]
Filter (Pattern).
```

4.82 ssoadm list-agent-grps

List agent groups.

```
Usage: ssoadm list-agent-grps --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm.

[--agenttype, -t]
Type of agent. e.g. J2EEAgent, WebAgent
```

[--filter, -x] Filter (Pattern).

4.83 ssoadm list-agents

```
List agent configurations.
```

```
Usage: ssoadm list-agents --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
--password-file, -f
File name that contains password of administrator.
--realm, -e
Name of realm.
[--agenttype, -t]
Type of agent. e.g. J2EEAgent, WebAgent
[--filter, -x]
Filter (Pattern).
```

4.84 ssoadm list-app-privs

List application privileges in a realm.

```
Usage: ssoadm list-app-privs --options [--global-options]
```

Options

```
    --adminid, -u
        Administrator ID of running the command.
    --password-file, -f
        File name that contains password of administrator.
    --realm, -e
        Realm name
```

4.85 ssoadm list-appl-types

List application types.

```
Usage: ssoadm list-appl-types --options [--global-options]
```

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

4.86 ssoadm list-appls

List applications in a realm.

```
Usage: ssoadm list-appls --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Realm name
```

4.87 ssoadm list-auth-cfgs

List authentication configurations

```
Usage: ssoadm list-auth-cfgs --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm.
```

4.88 ssoadm list-auth-instances

List authentication instances

```
Usage: ssoadm list-auth-instances --options [--global-options]
```

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
```

File name that contains password of administrator.

--realm, -e Name of realm.

4.89 ssoadm list-cot-members

List the members in a circle of trust.

Usage: ssoadm list-cot-members --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--cot, -t
```

Circle of Trust

--password-file, -f

File name that contains password of administrator.

```
[--realm, -e]
```

Realm where circle of trust resides

```
[--spec, -c]
```

Specify metadata specification, either wsfed, idff or saml2, defaults to saml2

4.90 ssoadm list-cots

List circles of trust.

Usage: ssoadm list-cots --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

```
[--realm, -e]
```

Realm where circle of trusts reside

4.91 ssoadm list-datastore-types

List the supported data store types

Usage: ssoadm list-datastore-types --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

4.92 ssoadm list-datastores

List data stores under a realm

Usage: ssoadm list-datastores --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

```
--realm, -e
```

Name of realm.

4.93 ssoadm list-entities

List entities under a realm.

Usage: ssoadm list-entities --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

```
--password-file, -f
File name that contains password of administrator.

[--realm, -e]
Realm where entities reside.

[--spec, -c]
```

Specify metadata specification, either wsfed, idff or saml2, defaults to saml2

4.94 ssoadm list-identities

List identities in a realm

Usage: ssoadm list-identities --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.

--filter, -x
Filter (Pattern).

--idtype, -t
Type of Identity such as User, Role and Group.

--password-file, -f
File name that contains password of administrator.

--realm, -e
Name of realm.
```

4.95 ssoadm list-identity-assignable-svcs

List the assignable service to an identity

Usage: ssoadm list-identity-assignable-svcs --options [--global-options]

```
    --adminid, -u
        Administrator ID of running the command.
    --idname, -i
        Name of identity.
    --idtype, -t
        Type of Identity such as User, Role and Group.
```

```
--password-file, -f
```

File name that contains password of administrator.

```
--realm, -e
```

Name of realm.

4.96 ssoadm list-policies

List policy definitions in a realm.

Usage: ssoadm list-policies --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--password-file, -f

File name that contains password of administrator.

--realm. -e

Name of realm.

[--namesonly, -n]

Returns only names of matching policies. Policies are not returned.

[--outfile, -ol

Filename where policy definition will be printed to. Definition will be printed in standard output if this option is not provided.

[--policynames, -p]

Names of policy. This can be an wildcard. All policy definition in the realm will be returned if this option is not provided.

4.97 ssoadm list-realm-assignable-svcs

List the assignable services to a realm.

Usage: ssoadm list-realm-assignable-svcs --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--password-file, -f

File name that contains password of administrator.

```
--realm, -e
Name of realm.
```

4.98 ssoadm list-realms

```
List realms by name.
```

```
Usage: ssoadm list-realms --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm where search begins.
```

```
[--filter, -x]
Filter (Pattern).
[--recursive, -r]
```

Search recursively

4.99 ssoadm list-res-bundle

List resource bundle in data store.

```
Usage: ssoadm list-res-bundle --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--bundlename, -b
Resource Bundle Name.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
[--bundlelocale, -o]
Locale of the resource bundle.
```

4.100 ssoadm list-server-cfg

List server configuration.

```
Usage: ssoadm list-server-cfg --options [--global-options]
```

```
--adminid, -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

--servername, -s

Server name, e.g. http://www.example.com:8080/fam or enter default to list default server configuration.

```
[--withdefaults, -w]
```

Set this flag to get default configuration.

4.101 ssoadm list-servers

List all server instances.

```
Usage: ssoadm list-servers --options [--global-options]
```

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

4.102 ssoadm list-sessions

List Sessions.

```
Usage: ssoadm list-sessions --options [--global-options]
```

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--host, -t
```

Host Name.

--password-file, -f

File name that contains password of administrator.

```
[--filter, -x]
   Filter (Pattern).
[--quiet, -q]
   Do not prompt for session invalidation.
```

4.103 ssoadm list-sites

List all sites.

Usage: ssoadm list-sites --options [--global-options]

Options

- --adminid, -u
 Administrator ID of running the command.
- --password-file, -f File name that contains password of administrator.

4.104 ssoadm list-xacml

export policies in realm as XACML.

Usage: ssoadm list-xacml --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--password-file, -f

File name that contains password of administrator.

--realm. -e

Name of realm.

[--namesonly, -n]

Returns only names of matching policies. Policies are not returned.

[--outfile, -o]

Filename where policy definition will be printed to. Definition will be printed in standard output if this option is not provided.

[--policynames, -p]

Names of policy. This can be a wildcard. All policy definition in the realm will be returned if this option is not provided.

4.105 ssoadm register-auth-module

Registers authentication module.

Usage: ssoadm register-auth-module --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--authmodule, -a
Java class name of authentication module.
```

```
--password-file, -f
File name that contains password of administrator.
```

4.106 ssoadm remove-agent-from-grp

Remove agents from a agent group.

Usage: ssoadm remove-agent-from-grp --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--agentgroupname, -b Name of agent group.
```

```
--agentnames, -s
Names of agents.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm.
```

4.107 ssoadm remove-app-priv-resources

Remove application privilege resources.

Usage: ssoadm remove-app-priv-resources --options [--global-options]

4.108

```
--adminid, -u
   Administrator ID of running the command.
--application, -t
   Application name
--name, -m
   Name for the this delegation
--password-file, -f
   File name that contains password of administrator.
--realm, -e
   Realm name
[--resources, -r]
   Resources to removed, All resources in the applications will be removed if
   this option is absent.
ssoadm remove-app-priv-subjects
Remove application privilege subjects.
Usage: ssoadm remove-app-priv-subjects --options [--global-options]
Options
--adminid, -u
   Administrator ID of running the command.
--name, -m
   Name for the this delegation
--password-file, -f
   File name that contains password of administrator.
--realm. -e
   Realm name
--subjects, -s
   Subject name
--subjecttype, -b
```

Possible values are User or Group

4.109 ssoadm remove-app-privs

Remove an application privileges.

```
Usage: ssoadm remove-app-privs --options [--global-options]
```

Options

```
    --adminid, -u
        Administrator ID of running the command.
    --names, -m
        Names of application privilege to be removed
    --password-file, -f
        File name that contains password of administrator.
    --realm, -e
        Realm name
```

4.110 ssoadm remove-attr-choicevals

Remove choice values from attribute schema.

```
Usage: ssoadm remove-attr-choicevals --options [--global-options]
```

```
--adminid, -u
   Administrator ID of running the command.

--attributename, -a
   Name of attribute.

--choicevalues, -k
   Choice values e.g. Inactive

--password-file, -f
   File name that contains password of administrator.

--schematype, -t
   Type of schema.

--servicename, -s
   Name of service.

[--subschemaname, -c]
   Name of sub schema.
```

4.111 ssoadm remove-attr-defs

Remove default attribute values in schema.

```
Usage: ssoadm remove-attr-defs --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.

--attributenames, -a
Attribute name(s).

--password-file, -f
File name that contains password of administrator.

--schematype, -t
Type of schema.

--servicename, -s
Name of service.

[--subschemaname, -c]
Name of sub schema.
```

4.112 ssoadm remove-cot-member

Remove a member from a circle of trust.

```
Usage: ssoadm remove-cot-member --options [--global-options]
```

```
    --adminid, -u
        Administrator ID of running the command.
    --cot, -t
        Circle of Trust
    --entityid, -y
        Entity ID
    --password-file, -f
        File name that contains password of administrator.
    [--realm, -e]
        Realm where circle of trust resides
```

[--spec, -c]
Specify metadata specification, either wsfed, idff or saml2, defaults to saml2

4.113 ssoadm remove-member

Remove membership of identity from another identity

Usage: ssoadm remove-member --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--idname, -i
```

Name of identity.

```
--idtype, -t
```

Type of Identity

--memberidname, -m

Name of identity that is member.

--memberidtype, -y

Type of Identity of member such as User, Role and Group.

--password-file, -f

File name that contains password of administrator.

--realm, -e

Name of realm.

4.114 ssoadm remove-plugin-schema

Add Plug-in interface to service.

Usage: ssoadm remove-plugin-schema --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--interfacename, -i

Name of interface.

--password-file, -f

File name that contains password of administrator.

```
--pluginname, -g
Name of Plug-in.
```

--servicename, -s Name of service.

4.115 ssoadm remove-privileges

Remove privileges from an identity

Usage: ssoadm remove-privileges --options [--global-options]

Options

```
--adminid, -u
```

Administrator ID of running the command.

```
--idname, -i
```

Name of identity.

--idtype, -t

Type of Identity such as Role and Group.

--password-file, -f

File name that contains password of administrator.

--privileges, -g

Name of privileges to be removed. Privilege names are AgentAdmin, EntitlementRestAccess, FederationAdmin, LogAdmin, LogRead, LogWrite, PolicyAdmin, PrivilegeRestAccess, PrivilegeRestReadAccess, RealmAdmin.

--realm, -e Name of realm.

4.116 ssoadm remove-res-bundle

Remove resource bundle from data store.

Usage: ssoadm remove-res-bundle --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--bundlename, -b

Resource Bundle Name.

```
--password-file, -f
File name that contains password of administrator.
```

[--bundlelocale, -o]
Locale of the resource bundle.

4.117 ssoadm remove-server-cfg

Remove server configuration.

Usage: ssoadm remove-server-cfg --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--propertynames, -a
Name of properties to be removed.
```

--servername, -s Server name, e.g. http://www.example.com:8080/fam or enter default to remove default server configuration.

4.118 ssoadm remove-site-members

Remove members from a site.

```
Usage: ssoadm remove-site-members --options [--global-options]
```

```
    --adminid, -u
        Administrator ID of running the command.
    --password-file, -f
        File name that contains password of administrator.
```

```
--servernames, -e
Server names, e.g. http://www.example.com:8080/fam
```

```
--sitename, -s
Site name, e.g. mysite
```

4.119 ssoadm remove-site-sec-urls

Remove Site Secondary URLs.

Usage: ssoadm remove-site-sec-urls --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--secondaryurls, -a
Secondary URLs
```

```
--sitename, -s
Site name, e.g. mysite
```

4.120 ssoadm remove-sub-schema

Remove sub schema.

Usage: ssoadm remove-sub-schema --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--schematype, -t
Type of schema.
```

```
--servicename, -s
Name of service.
```

```
--subschemanames, -a
Name(s) of sub schema to be removed.
```

```
[--subschemaname, -c]
Name of parent sub schema.
```

4.121 ssoadm remove-svc-attrs

Remove service attribute values in a realm.

```
Usage: ssoadm remove-svc-attrs --options [--global-options]
```

```
--adminid, -u
Administrator ID of running the command.

--password-file, -f
File name that contains password of administrator.

--realm, -e
Name of realm.

--servicename, -s
Name of service.

[--attributevalues, -a]
Attribute values to be removed e.g. homeaddress=here.

[--datafile, -D]
```

4.122 ssoadm remove-svc-identity

Remove Service from an identity

```
Usage: ssoadm remove-svc-identity --options [--global-options]
```

Name of file that contains attribute values to be removed.

```
    --adminid, -u
        Administrator ID of running the command.
    --idname, -i
        Name of identity.
    --idtype, -t
        Type of Identity such as User, Role and Group.
    --password-file, -f
        File name that contains password of administrator.
    --realm, -e
        Name of realm.
    --servicename, -s
        Name of service.
```

4.123 ssoadm remove-svc-realm

Remove service from a realm.

```
Usage: ssoadm remove-svc-realm --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm.
```

```
--servicename, -s
Name of service to be removed.
```

4.124 ssoadm set-appl

Set application attributes.

```
Usage: ssoadm set-appl --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--name, -m
Application name
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Realm name
```

[--attributevalues, -a]
Attribute values e.g. applicationType=iPlanetAMWebAgentService.

```
[--datafile, -D]
```

Name of file that contains attribute values data. Possible attributes are resources, subjects, conditions, actions, searchIndexImpl, saveIndexImpl, resourceComparator, subjectAttributeNames and entitlementCombiner.

4.125 ssoadm set-attr-any

Set any member of attribute schema.

```
Usage: ssoadm set-attr-any --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.

--any, -y
Attribute Schema Any value

--attributeschema, -a
Name of attribute schema

--password-file, -f
File name that contains password of administrator.

--schematype, -t
Type of schema.

--servicename, -s
Name of service.

[--subschemaname, -c]
Name of sub schema.
```

4.126 ssoadm set-attr-bool-values

Set boolean values of attribute schema.

```
Usage: ssoadm set-attr-bool-values --options [--global-options]
```

```
    --adminid, -u
        Administrator ID of running the command.
    --attributename, -a
        Name of attribute.
    --falsei18nkey, -j
        Internationalization key for false value.
```

```
--falsevalue, -z
   Value for false.
--password-file, -f
   File name that contains password of administrator.
--schematype, -t
   Type of schema.
--servicename, -s
   Name of service.
--truei18nkey, -k
   Internationalization key for true value.
--truevalue, -e
   Value for true.
[--subschemaname, -c]
   Name of sub schema.
ssoadm set-attr-choicevals
Set choice values of attribute schema.
Usage: ssoadm set-attr-choicevals --options [--global-options]
Options
--adminid, -u
   Administrator ID of running the command.
--attributename, -a
   Name of attribute.
--password-file, -f
   File name that contains password of administrator.
--schematype, -t
   Type of schema.
--servicename, -s
   Name of service.
[--add, -p]
   Set this flag to append the choice values to existing ones.
[--choicevalues, -k]
```

Choice value e.g. o102=Inactive.

4.127

```
[--datafile, -D]
```

Name of file that contains attribute values data.

```
[--subschemaname, -c]
Name of sub schema.
```

ssoadm set-attr-defs

Set default attribute values in schema.

```
Usage: ssoadm set-attr-defs --options [--global-options]
```

Options

4.128

```
--adminid, -u
```

Administrator ID of running the command.

```
--password-file, -f
```

File name that contains password of administrator.

```
--schematype, -t
```

Type of schema.

--servicename, -s

Name of service.

[--attributevalues, -a]

Attribute values e.g. homeaddress=here.

[--datafile, -D]

Name of file that contains attribute values data.

[--subschemaname, -c]

Name of sub schema.

4.129 ssoadm set-attr-end-range

Set attribute schema end range.

```
Usage: ssoadm set-attr-end-range --options [--global-options]
```

Options

```
--adminid, -u
```

Administrator ID of running the command.

--attributeschema, -a

Name of attribute schema

```
--password-file, -f
   File name that contains password of administrator.
--range, -r
   End range
--schematype, -t
   Type of schema.
--servicename. -s
   Name of service.
[--subschemaname, -c]
   Name of sub schema.
ssoadm set-attr-i18n-key
Set i18nKey member of attribute schema.
Usage: ssoadm set-attr-i18n-key --options [--global-options]
Options
--adminid, -u
   Administrator ID of running the command.
--attributeschema, -a
   Name of attribute schema
--i18nkey, -k
   Attribute Schema I18n Key
--password-file, -f
   File name that contains password of administrator.
--schematype, -t
   Type of schema.
--servicename, -s
   Name of service.
```

4.131 ssoadm set-attr-start-range

[--subschemaname, -c] Name of sub schema.

4.130

Set attribute schema start range.

```
Usage: ssoadm set-attr-start-range --options [--global-options]
```

```
--adminid, -u
Administrator ID of running the command.

--attributeschema, -a
Name of attribute schema

--password-file, -f
File name that contains password of administrator.

--range, -r
Start range

--schematype, -t
Type of schema.

--servicename, -s
Name of service.

[--subschemaname, -c]
Name of sub schema.
```

4.132 ssoadm set-attr-syntax

Set syntax member of attribute schema.

```
Usage: ssoadm set-attr-syntax --options [--global-options]
```

```
--adminid, -u
Administrator ID of running the command.

--attributeschema, -a
Name of attribute schema

--password-file, -f
File name that contains password of administrator.

--schematype, -t
Type of schema.

--servicename, -s
Name of service.
```

```
--syntax, -x
Attribute Schema Syntax
[--subschemaname, -c]
Name of sub schema.
```

4.133 ssoadm set-attr-type

Set type member of attribute schema.

```
Usage: ssoadm set-attr-type --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--attributeschema, -a
Name of attribute schema
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--schematype, -t
Type of schema.
```

```
--servicename, -s
Name of service.
```

```
--type, -p
Attribute Schema Type
```

```
[--subschemaname, -c]
Name of sub schema.
```

4.134 ssoadm set-attr-ui-type

Set UI type member of attribute schema.

```
Usage: ssoadm set-attr-ui-type --options [--global-options]
```

```
--adminid, -u
Administrator ID of running the command.
```

```
--attributeschema, -a
Name of attribute schema
```

```
    --password-file, -f
        File name that contains password of administrator.
    --schematype, -t
        Type of schema.
    --servicename, -s
        Name of service.
    --uitype, -p
        Attribute Schema UI Type
    [--subschemaname, -c]
        Name of sub schema.
```

4.135 ssoadm set-attr-validator

Set attribute schema validator.

Usage: ssoadm set-attr-validator --options [--global-options]

Options

```
--adminid, -u
   Administrator ID of running the command.

--attributeschema, -a
   Name of attribute schema

--password-file, -f
   File name that contains password of administrator.

--schematype, -t
   Type of schema.

--servicename, -s
   Name of service.

--validator, -r
   validator class name

[--subschemaname, -c]
```

4.136 ssoadm set-attr-view-bean-url

Name of sub schema.

Set properties view bean URL member of attribute schema.

Usage: ssoadm set-attr-view-bean-url --options [--global-options]

```
    -adminid, -u
        Administrator ID of running the command.
    -attributeschema, -a
        Name of attribute schema
    -password-file, -f
        File name that contains password of administrator.
    -schematype, -t
        Type of schema.
    -servicename, -s
        Name of service.
    -url, -r
        Attribute Schema Properties View Bean URL
    [--subschemaname, -c]
        Name of sub schema.
```

4.137 ssoadm set-entitlement-conf

Set entitlements service configuration

Usage: ssoadm set-entitlement-conf --options [--global-options]

Options

```
    --adminid, -u
        Administrator ID of running the command.
    --password-file, -f
        File name that contains password of administrator.
    [--attributevalues, -a]
        Attribute values e.g. evalThreadSize=4.
    [--datafile, -D]
        Name of file that contains attribute values data. Possible attributes are evalThreadSize, searchThreadSize, policyCacheSize and indexCacheSize.
```

4.138 ssoadm set-identity-attrs

Set attribute values of an identity

```
Usage: ssoadm set-identity-attrs --options [--global-options]
```

```
    --adminid, -u
        Administrator ID of running the command.
    --idname, -i
        Name of identity.
    --idtype, -t
        Type of Identity such as User, Role and Group.
    --password-file, -f
        File name that contains password of administrator.
    --realm, -e
        Name of realm.
    [--attributevalues, -a]
        Attribute values e.g. homeaddress=here.
    [--datafile, -D]
        Name of file that contains attribute values data.
```

4.139 ssoadm set-identity-svc-attrs

Set service attribute values of an identity

```
Usage: ssoadm set-identity-svc-attrs --options [--global-options]
```

```
    --adminid, -u
        Administrator ID of running the command.
    --idname, -i
        Name of identity.
    --idtype, -t
        Type of Identity such as User, Role and Group.
    --password-file, -f
        File name that contains password of administrator.
    --realm, -e
        Name of realm.
```

```
--servicename, -s
Name of service.

[--attributevalues, -a]
Attribute values e.g. homeaddress=here.

[--datafile, -D]
Name of file that contains attribute values data.
```

4.140 ssoadm set-inheritance

Set Inheritance value of Sub Schema.

Usage: ssoadm set-inheritance --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--inheritance, -r
Value of Inheritance.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--schematype, -t
Type of schema.
```

```
--servicename, -s
Name of service.
```

--subschemaname, -c Name of sub schema.

4.141 ssoadm set-plugin-viewbean-url

Set properties view bean URL of plug-in schema.

Usage: ssoadm set-plugin-viewbean-url --options [--global-options]

Options

--adminid, -u
Administrator ID of running the command.

```
--interfacename, -i
   Name of interface.
--password-file, -f
   File name that contains password of administrator.
--pluginname, -q
   Name of Plug-in.
--servicename, -s
   Name of service.
--url, -r
   Properties view bean URL.
ssoadm set-realm-attrs
Set attribute values of a realm.
Usage: ssoadm set-realm-attrs --options [--global-options]
Options
--adminid, -u
   Administrator ID of running the command.
--password-file, -f
   File name that contains password of administrator.
--realm, -e
   Name of realm.
--servicename, -s
```

$\begin{tabular}{ll} \hbox{$-$-append, $-$p$} \\ \hbox{Set this flag to append the values to existing ones.} \\ \end{tabular}$

Name of service.

[--attributevalues, -a]
Attribute values e.g. homeaddress=here.

```
[--datafile, -D]

Name of file that contains attribute values data.
```

4.143 ssoadm set-realm-svc-attrs

Set attribute values of a service that is assigned to a realm.

Usage: ssoadm set-realm-svc-attrs --options [--global-options]

4.142

```
-adminid, -u
Administrator ID of running the command.
-password-file, -f
File name that contains password of administrator.
-realm, -e
Name of realm.
-servicename, -s
Name of service.
[--append, -p]
Set this flag to append the values to existing ones.
[--attributevalues, -a]
Attribute values e.g. homeaddress=here.
[--datafile, -D]
Name of file that contains attribute values data.
```

4.144 ssoadm set-revision-number

Set service schema revision number.

```
Usage: ssoadm set-revision-number --options [--global-options]
```

Options

```
    --adminid, -u
        Administrator ID of running the command.
    --password-file, -f
        File name that contains password of administrator.
    --revisionnumber, -r
        Revision Number
    --servicename, -s
        Name of service.
```

4.145 ssoadm set-site-id

Set the ID of a site.

```
Usage: ssoadm set-site-id --options [--global-options]
```

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--siteid, -i
Site's ID, e.g. 10
```

--sitename, -s Site name, e.g. mysite

4.146 ssoadm set-site-pri-url

Set the primary URL of a site.

Usage: ssoadm set-site-pri-url --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--sitename, -s
Site name, e.g. mysite
```

--siteurl, -i Site's primary URL, e.g. http://site.www.example.com:8080

4.147 ssoadm set-site-sec-urls

Set Site Secondary URLs.

Usage: ssoadm set-site-sec-urls --options [--global-options]

Options

--adminid, -u
Administrator ID of running the command.

```
--password-file, -f
File name that contains password of administrator.
```

```
--secondaryurls, -a
Secondary URLs
```

--sitename, -s Site name, e.g. mysite

4.148 ssoadm set-sub-cfg

Set sub configuration.

```
Usage: ssoadm set-sub-cfg --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--operation, -o
Operation (either add/set/modify) to be performed on the sub configuration.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--servicename, -s
Name of service.
```

```
--subconfigname, -g
Name of sub configuration.
```

```
[--attributevalues, -a]
```

Attribute values e.g. homeaddress=here.

```
[--datafile, -D]
```

Name of file that contains attribute values data.

```
[--realm, -e]
```

Name of realm (Sub Configuration shall be added to global configuration if this option is not provided).

4.149 ssoadm set-svc-attrs

Set service attribute values in a realm.

Usage: ssoadm set-svc-attrs --options [--global-options]

```
-adminid, -u
Administrator ID of running the command.
-password-file, -f
File name that contains password of administrator.
-realm, -e
Name of realm.
-servicename, -s
Name of service.
[--attributevalues, -a]
Attribute values e.g. homeaddress=here.
[--datafile, -D]
Name of file that contains attribute values data.
```

4.150 ssoadm set-svc-i18n-key

Set service schema i18n key.

```
Usage: ssoadm set-svc-i18n-key --options [--global-options]
```

Options

```
    --adminid, -u
        Administrator ID of running the command.
    --i18nkey, -k
        I18n Key.
    --password-file, -f
        File name that contains password of administrator.
    --servicename, -s
        Name of service.
```

4.151 ssoadm set-svc-view-bean-url

Set service schema properties view bean URL.

```
Usage: ssoadm set-svc-view-bean-url --options [--global-options]
```

```
    --adminid, -u
        Administrator ID of running the command.
    --password-file, -f
        File name that contains password of administrator.
    --servicename, -s
        Name of service.
    --url, -r
        Service Schema Properties View Bean URL
```

4.152 ssoadm set-svrcfg-xml

Set server configuration XML to centralized data store

```
Usage: ssoadm set-svrcfg-xml --options [--global-options]
```

Options

```
    --adminid, -u
        Administrator ID of running the command.
    --password-file, -f
        File name that contains password of administrator.
    --servername, -s
        Server name, e.g. http://www.example.com:8080/fam
    --xmlfile, -X
        XML file that contains configuration.
```

4.153 ssoadm show-agent

Show agent profile.

Usage: ssoadm show-agent --options [--global-options]

Options

--adminid, -u
Administrator ID of running the command.

```
--agentname, -b
Name of agent.
--password-file, -f
File name that contains password of administrator.
--realm, -e
Name of realm.
[--inherit, -i]
Set this to inherit properties from parent group.
[--outfile, -o]
Filename where configuration is written to.
```

4.154 ssoadm show-agent-grp

Show agent group profile.

Usage: ssoadm show-agent-grp --options [--global-options]

Options

```
-adminid, -u
Administrator ID of running the command.
-agentgroupname, -b
Name of agent group.
-password-file, -f
File name that contains password of administrator.
-realm, -e
Name of realm.
[-outfile, -o]
Filename where configuration is written to.
```

4.155 ssoadm show-agent-membership

List agent's membership.

Usage: ssoadm show-agent-membership --options [--global-options]

Options

--adminid, -u
Administrator ID of running the command.

```
    --agentname, -b
        Name of agent.
    --password-file, -f
        File name that contains password of administrator.
    --realm, -e
        Name of realm.
```

4.156 ssoadm show-agent-types

Show agent types.

Usage: ssoadm show-agent-types --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

--password-file, -f File name that contains password of administrator.

4.157 ssoadm show-app-priv

Show application privilege.

```
Usage: ssoadm show-app-priv --options [--global-options]
```

Options

```
    --adminid, -u
        Administrator ID of running the command.
    --name, -m
        Name of application privilege
    --password-file, -f
        File name that contains password of administrator.
```

--realm, -e Realm name

4.158 ssoadm show-appl

Show application attributes.

```
Usage: ssoadm show-appl --options [--global-options]
```

```
--adminid, -u
Administrator ID of running the command.
--name, -m
Application name
--password-file, -f
```

--realm, -e Realm name

4.159 ssoadm show-appl-type

Show application type details.

```
Usage: ssoadm show-appl-type --options [--global-options]
```

File name that contains password of administrator.

Options

```
    --adminid, -u
        Administrator ID of running the command.
    --name, -m
        Application Type name
    --password-file, -f
        File name that contains password of administrator.
```

4.160 ssoadm show-auth-modules

Show the supported authentication modules in the system.

```
Usage: ssoadm show-auth-modules --options [--global-options]
```

```
    --adminid, -u
        Administrator ID of running the command.
    --password-file, -f
        File name that contains password of administrator.
```

4.161 ssoadm show-data-types

Show the supported data type in the system.

Usage: ssoadm show-data-types --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

4.162 ssoadm show-datastore

Show data store profile.

Usage: ssoadm show-datastore --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--name, -m
Name of datastore.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm.
```

4.163 ssoadm show-entitlement-conf

Display entitlements service configuration

Usage: ssoadm show-entitlement-conf --options [--global-options]

```
--adminid, -u
Administrator ID of running the command.
```

--password-file, -f File name that contains password of administrator.

4.164 ssoadm show-identity-ops

Show the allowed operations of an identity a realm

Usage: ssoadm show-identity-ops --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--idtype, -t
Type of Identity such as User, Role and Group.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm.
```

4.165 ssoadm show-identity-svc-attrs

Name of service.

Show the service attribute values of an identity

Usage: ssoadm show-identity-svc-attrs --options [--global-options]

```
    --adminid, -u
        Administrator ID of running the command.
    --idname, -i
        Name of identity.
    --idtype, -t
        Type of Identity such as User, Role and Group.
    --password-file, -f
        File name that contains password of administrator.
    --realm, -e
        Name of realm.
    --servicename, -s
```

4.166 ssoadm show-identity-types

Show the supported identity type in a realm

```
Usage: ssoadm show-identity-types --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm.
```

4.167 ssoadm show-members

Show the members of an identity. For example show the members of a role

```
Usage: ssoadm show-members --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--idname, -i
Name of identity.
```

```
--idtype, -t
```

Type of Identity such as User, Role and Group.

```
--membershipidtype, -m
Membership identity type.
```

```
    -password-file, -f
    File name that contains password of administrator.
```

```
--realm, -e
Name of realm.
```

4.168 ssoadm show-memberships

Show the memberships of an identity. For sample show the memberships of an user.

```
Usage: ssoadm show-memberships --options [--global-options]
```

```
--adminid, -u
   Administrator ID of running the command.

--idname, -i
   Name of identity.

--idtype, -t
   Type of Identity such as User, Role and Group.

--membershipidtype, -m
   Membership identity type.

--password-file, -f
   File name that contains password of administrator.

--realm, -e
   Name of realm.
```

4.169 ssoadm show-privileges

Show privileges assigned to an identity

```
Usage: ssoadm show-privileges --options [--global-options]
```

Options

```
    --adminid, -u
        Administrator ID of running the command.
    --idname, -i
        Name of identity.
    --idtype, -t
        Type of Identity such Role and Group.
    --password-file, -f
        File name that contains password of administrator.
    --realm, -e
        Name of realm.
```

4.170 ssoadm show-realm-svcs

Show services in a realm.

```
Usage: ssoadm show-realm-svcs --options [--global-options]
```

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--realm, -e
Name of realm.
```

```
[--mandatory, -y]
Include Mandatory services.
```

4.171 ssoadm show-site

Show site profile.

```
Usage: ssoadm show-site --options [--global-options]
```

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--sitename, -s
Site name, e.g. mysite
```

4.172 ssoadm show-site-members

Display members of a site.

```
Usage: ssoadm show-site-members --options [--global-options]
```

```
--adminid, -u
Administrator ID of running the command.
```

```
--password-file, -f
File name that contains password of administrator.
```

```
--sitename, -s
Site name, e.g. mysite
```

4.173 ssoadm unregister-auth-module

Unregisters authentication module.

Usage: ssoadm unregister-auth-module --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--authmodule, -a
Java class name of authentication module.
```

```
--password-file, -f
File name that contains password of administrator.
```

4.174 ssoadm update-agent

Update agent configuration.

Usage: ssoadm update-agent --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--agentname, -b
Name of agent.
```

```
--password-file, -f
```

 $File\ name\ that\ contains\ password\ of\ administrator.$

```
--realm, -e
Name of realm.
```

```
[--attributevalues, -a]
Properties e.g. homeaddress=here.
```

```
[--datafile, -D]
Name of file that contains properties.
```

```
[--set, -s]
Set this flag to overwrite properties values.
```

4.175 ssoadm update-agent-grp

Update agent group configuration.

Usage: ssoadm update-agent-grp --options [--global-options]

Options

```
--adminid, -u
Administrator ID of running the command.

--agentgroupname, -b
Name of agent group.

--password-file, -f
File name that contains password of administrator.

--realm, -e
Name of realm.

[--attributevalues, -a]
Properties e.g. homeaddress=here.

[--datafile, -D]
Name of file that contains properties.

[--set, -s]
Set this flag to overwrite properties values.
```

4.176 ssoadm update-app-priv

Update an application privilege.

Usage: ssoadm update-app-priv --options [--global-options]

```
--adminid, -u
Administrator ID of running the command.

--name, -m
Name for the this delegation

--password-file, -f
File name that contains password of administrator.

--realm, -e
Realm name
```

```
[--actions, -a]
    Possible values are READ, MODIFY, DELEGATE, ALL
[--description, -p]
    Description for the this delegation.
```

4.177 ssoadm update-app-priv-resources

Set application privilege resources.

Usage: ssoadm update-app-priv-resources --options [--qlobal-options]

Options

```
--adminid, -u
Administrator ID of running the command.
```

```
--application, -t
Application name
```

--name, -m

Name for the this delegation

--password-file, -f

File name that contains password of administrator.

--realm, -e Realm name

[--add, -p]

Resources are added to this application if this option is set. Otherwise, resources in the current application privilege will be overwritten.

[--resources, -r]

Resources to delegate, All resources in the applications will be delegated if this option is absent.

4.178 ssoadm update-app-priv-subjects

Set application privilege subjects.

Usage: ssoadm update-app-priv-subjects --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

```
--name, -m
```

Name for the this delegation

```
--password-file, -f
```

File name that contains password of administrator.

--realm, -e

Realm name

--subjects, -s

Subject name

--subjecttype, -b

Possible values are User or Group

[--add, -p]

Subjects are added to this application if this option is set. Otherwise, subjects in the current application privilege will be overwritten.

4.179 ssoadm update-auth-cfg-entr

Set authentication configuration entries

Usage: ssoadm update-auth-cfg-entr --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--name, -m

Name of authentication configuration.

--password-file, -f

File name that contains password of administrator.

--realm, -e

Name of realm.

[--datafile, -D]

Name of file that contains formatted authentication configuration entries in this format name|flag|options. option can be REQUIRED, OPTIONAL, SUFFICIENT, REQUISITE. e.g. myauthmodule|REQUIRED|my options.

[--entries, -a]

formatted authentication configuration entries in this format name|flag| options. option can be REQUIRED, OPTIONAL, SUFFICIENT, REQUISITE. e.g. myauthmodule|REQUIRED|my options.

4.180 ssoadm update-auth-cfg-props

Set authentication configuration properties

Usage: ssoadm update-auth-cfg-props --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--name, -m

Name of authentication configuration.

--password-file, -f

File name that contains password of administrator.

--realm, -e

Name of realm.

[--attributevalues, -a]

authentication configuration properties, valid configuration keys are: iplanet-am-auth-login-failure-url, iplanet-am-auth-login-success-url and iplanet-am-auth-post-login-process-class.

[--datafile, -D]

Name of file that contains authentication configuration properties.

4.181 ssoadm update-auth-instance

Update authentication instance values

Usage: ssoadm update-auth-instance --options [--global-options]

Options

--adminid, -u

Administrator ID of running the command.

--name, -m

Name of authentication instance.

--password-file, -f

File name that contains password of administrator.

--realm, -e

Name of realm.

```
[--attributevalues, -a]
   Attribute values e.g. homeaddress=here.
[--datafile, -D]
   Name of file that contains attribute values data.
```

4.182 ssoadm update-datastore

Update data store profile.

Usage: ssoadm update-datastore --options [--global-options]

Options

```
--adminid, -u
   Administrator ID of running the command.

--name, -m
   Name of datastore.

--password-file, -f
   File name that contains password of administrator.

--realm, -e
   Name of realm.

[--attributevalues, -a]
   Attribute values e.g.
   sunIdRepoClass=com.sun.identity.idm.plugins.files.FilesRepo.

[--datafile, -D]
```

4.183 ssoadm update-entity-keyinfo

Update XML signing and encryption key information in hosted entity metadata.

Usage: ssoadm update-entity-keyinfo --options [--global-options]

Name of file that contains attribute values data.

```
--adminid, -u
    Administrator ID of running the command.--entityid, -y
    Entity ID
```

```
--password-file, -f
File name that contains password of administrator.

[--idpecertalias, -g]
Identity provider encryption certificate alias.

[--idpscertalias, -b]
Identity provider signing certificate alias

[--realm, -e]
Realm where entity resides.

[--specertalias, -r]
Service provider encryption certificate alias

[--spec, -c]
Specify metadata specification, either wsfed, idff or saml2, defaults to saml2

[--spscertalias, -a]
Service provider signing certificate alias
```

4.184 ssoadm update-policies

Update policies in a realm.

Usage: ssoadm update-policies --options [--global-options]

Options

```
    --adminid, -u
        Administrator ID of running the command.
    --password-file, -f
        File name that contains password of administrator.
    --realm, -e
        Name of realm.
    --xmlfile, -X
        Name of file that contains policy XML definition.
```

4.185 ssoadm update-server-cfg

Update server configuration.

Usage: ssoadm update-server-cfg --options [--global-options]

```
    --adminid, -u
        Administrator ID of running the command.
    --password-file, -f
        File name that contains password of administrator.
    --servername, -s
        Server name, e.g. http://www.example.com:8080/fam or enter default to update default server configuration.
    [--attributevalues, -a]
        Attribute values e.g. homeaddress=here.
    [--datafile, -D]
        Name of file that contains attribute values data.
```

4.186 ssoadm update-svc

Update service.

--adminid, -u

updated.

Usage: ssoadm update-svc --options [--global-options]

Options

Administrator ID of running the command.

--password-file, -f
File name that contains password of administrator.

--xmlfile, -X
XML file(s) that contains schema.

[--continue, -c]

Continue updating service if one or more previous services cannot be

Chapter 1 Configuration Reference

This chapter covers OpenAM configuration properties accessible through the Configuration tab of the console, most of which can be set by using the **ssoadm** command. The chapter is organized to follow the OpenAM console layout.

1.1 Authentication Configuration

Under Configuration > Authentication you can configure authentication services globally using the same attributes you use to configure authentication modules per realm under Access Control > Realm Name > Authentication > Module Instances, and described in the Administration Guide chapter on Defining Authentication Services.

The primary difference is that when configuring services globally, you set the default values to be used when a module is configured further for a specific realm.

The Core Authentication module includes some fields under this tab that are not available through the realm changes under the Access Control tab. Because attributes set under the Configuration tab apply on a server level, the changes you make here will apply to all realms. Attributes set under the Access Control tab only apply to the realms that you specify. The Authentication table under the Configuration tab lists all existing types of modules available for configuration, including any customized modules you have added.

The following are the global fields you can configure for the Core Authentication module under the Configuration tab.

123

Pluggable Authentication Module Classes

Add class names for custom authentication modules to this list.

ssoadm attribute: iplanet-am-auth-authenticators

LDAP Connection Pool Size, Default LDAP Connection Pool Size

Sets a minimum and maximum number of LDAP connections in the pool for connecting to a directory server. When tuning for production, start with 10:65 (10 minimum, 65 maximum). Explicit settings for specific servers override the default.

This attribute is for LDAP and Membership authentication services only.

This connection pool is different than the SDK connection pool configured in serverconfig.xml.

ssoadm attributes: iplanet-am-auth-ldap-connection-pool-size, and iplanet-am-auth-ldap-connection-pool-default-size

LDAP Connection Pool Size, Default LDAP Connection Pool Size

Sets a minimum and maximum number of LDAP connections in the pool for connecting to a directory server. When tuning for production, start with 10:65 (10 minimum, 65 maximum). Explicit settings for specific servers override the default.

This attribute is for LDAP and Membership authentication services only.

This connection pool is different than the SDK connection pool configured in ${\sf serverconfig.xml.}$

ssoadm attributes: iplanet-am-auth-ldap-connection-pool-size, and iplanet-am-auth-ldap-connection-pool-default-size

Remote Auth Security

Require the authenticating application to send its SSOToken. This allows the Authentication Service to obtain the username and password associated with the application.

ssoadm attribute: sunRemoteAuthSecurityEnabled

Keep Post Process Objects for Logout Processing, Keep Authentication Module Objects for Logout Processing

When enabled, retain objects used to process authentication or post authentication operations in the user session until the user logs out.

ssoadm attributes: sunAMAuthKeepPostProcessInstances, and sunAMAuthKeepAuthModuleIntances

XUI Interface

When enabled, the initial login screen uses the XUI.

ssoadm attribute: openam-xui-interface-enabled

1.2 Console Configuration

Under Configuration > Console you can customize how the OpenAM console appears, and what character sets are used.

Administration

Administration includes both global and realm attributes.

ssoadm service name: iPlanetAMAdminConsoleService

Federation Management

Clear Enabled to disable federation functionality in OpenAM.

ssoadm attribute: iplanet-am-admin-console-liberty-enabled

Maximum Results Returned from Search

Use this attribute to restrict the maximum number of results found in a search, such as a search for user profiles. Increasing the value can negatively impact performance. On the other hand, the default maximum of 100 can explain why administrators unaware of this setting can be surprised not to see all the users they expect in search results.

ssoadm attribute: iplanet-am-admin-console-search-limit

Timeout for Search

Timeout in seconds for a console search. OpenAM returns an error if the search is not completed by the timeout.

ssoadm attribute: iplanet-am-admin-console-search-timeout

Search Return Attribute

List of LDAP attribute types to return in search results. OpenAM sorts users by the first attribute you specify. Use attributes that are actually present in user profiles.

ssoadm attribute: iplanet-am-admin-console-user-return-attribute

Maximum Items Displayed per Page

OpenAM shows a maximum of this many items in a console page before separating the page into multiple screens.

ssoadm attribute: iplanet-am-admin-console-paging-size

Prompt user for old password

If enabled, when the user edits her password in the user view, then OpenAM prompts her for the old password.

ssoadm attribute: iplanet-am-admin-console-password-reset-enabled

Globalization Settings

Globalization settings affect character sets and common name formats. See *Localization* for a list of supported locales.

ssoadm service name: iPlanetG11NSettings

Charsets Supported by Each Locale

This table lets you configure the order of supported character sets used for each supported locale. Change the settings only if the defaults are not appropriate.

ssoadm attribute: sun-identity-glln-settings-locale-charset-mapping

Charsets Aliases

Use this list to map between different character set names used in Java and in MIME.

ssoadm attribute: sun-identity-glln-settings-charset-alias-mapping

Auto Generated Common Name Format

Use this list to configure how OpenAM formats names shown in the console banner.

ssoadm attribute: sun-identity-glln-settings-common-name-format

1.3 System Configuration

Under Configuration > System, you can change OpenAM settings for server logging, monitoring, service URL naming, locale, cookie domain, and how OpenAM detects specific clients.

Client Detection

OpenAM can detect client user agents by their HTTP requests.

ssoadm service name: iPlanetAMClientDetection

Default Client Type

If no specific match is found for the client type, then this type is used. The default is genericHTML, suitable for supported browsers.

ssoadm attribute: iplanet-am-client-detection-default-client-type

Client Detection Class

The client detection plugin must implement the com.iplanet.services.cdm. ClientDetectionInterface. Client type is a name that uniquely identifies the client to OpenAM. The plugin scans HTTP requests to determine the client type.

ssoadm attribute: iplanet-am-client-detection-class

Enable Client Detection

If this is enabled, then OpenAM needs an appropriate client detection class implementation, and the authentication user interface must be appropriate for the clients detected.

ssoadm attribute: iplanet-am-client-detection-enabled

Logging

You configure global OpenAM logging settings on this page.

ssoadm service name: iPlanetAMLoggingService

Maximum Log Size

Sets the maximum log file size in bytes.

ssoadm attribute: iplanet-am-logging-max-file-size

Number of History Files

Sets the number of history files for each log that OpenAM keeps, including time-based histories. The previously live file is moved to be included in the history count, and a new log is created to serve as the live log file. Any log file in the history count that goes over the number specified here will be deleted. For time-based logs, a new set of logs will be created when OpenAM is started because of the time-based file names that are used.

ssoadm attribute: iplanet-am-logging-num-hist-file

Logfile Rotation Prefix

Set this if you want to add a prefix to log files governed by time-based log rotation.

ssoadm attribute: openam-logging-file-prefix

Logfile Rotation Suffix

Changing this if you want to change the suffix for log files governed by time-based log rotation. You can use SimpleDateFormat patterns. The default is -MM. dd.yy-kk.mm.

ssoadm attribute: openam-logging-file-suffix

Log File Location

This property is interpreted to determine the location of log files, taking either a file system location or a JDBC URL. The default is %BASE_DIR%/ %SERVER URI%/log/.

ssoadm attribute: iplanet-am-logging-location

Log Status

Set this to INACTIVE to disable the logging system.

ssoadm attribute: logstatus

Log Record Resolve Host Name

Enable this to have OpenAM perform a DNS host lookup to populate the host name field for log records. OpenAM requires DNS on the host where it runs. Enabling this feature increases the load on the logging system.

ssoadm attribute: resolveHostName

Logging Type

Set this to DB to log to a database. Default: File. If you choose DB then be sure to set the connection attributes correctly, including the JDBC driver to use.

ssoadm attribute: iplanet-am-logging-type

Database User Name

When logging to a database, set this to the user name used to connect to the database. If this attribute is incorrectly set, OpenAM performance suffers.

ssoadm attribute: iplanet-am-logging-db-user

Database User Password

When logging to a database, set this to the password used to connect to the database. If this attribute is incorrectly set, OpenAM performance suffers.

ssoadm attribute: iplanet-am-logging-db-password

Database Driver Name

When logging to a database, set this to the class name of the JDBC driver used to connect to the database. The default is for Oracle. OpenAM also works with the MySQL database driver.

ssoadm attribute: iplanet-am-logging-db-driver

Configurable Log Fields

Select the fields OpenAM includes in log messages using this attribute. By default all fields are included in log messages.

ssoadm attribute: iplanet-am-logging-logfields

Log Verification Frequency

When secure logging is enabled, set this to how often OpenAM verifies log file content (in seconds).

ssoadm attribute: iplanet-am-logging-verify-period-in-seconds

Log Signature Time

When secure logging is enabled, set this to how often OpenAM signs log file content (in seconds).

ssoadm attribute: iplanet-am-logging-signature-period-in-seconds

Secure Logging

Set this to 0N to enable the secure logging system whereby OpenAM digitally signs and verifies log files. You must also set up the Logging Certificate Store for this feature to function.

ssoadm attribute: iplanet-am-logging-security-status

Secure Logging Signing Algorithm

Set this to the algorithm used for digitally signing log records.

ssoadm attribute: iplanet-am-logging-secure-signing-algorithm

Logging Certificate Store Location

The secure logging system uses the certificate with alias Logger that it finds in the key store specified by this path. The default is %BASE_DIR%/%SERVER_URI %/Logger.jks.

ssoadm attribute: iplanet-am-logging-secure-certificate-store

Maximum Number of Records

Set this to the maximum number of records read from the logs through the Logging API.

ssoadm attribute: iplanet-am-logging-max-records

Number of Files per Archive

Set this to the number of files to be archived by the secure logging system.

ssoadm attribute: iplanet-am-logging-files-per-keystore

Buffer Size

The number of log messages buffered in memory before OpenAM flushes them to the log file or the database.

ssoadm attribute: iplanet-am-logging-buffer-size

DB Failure Memory Buffer Size

Set this to the maximum number of log records to hold in memory if the database to which records are logged is unavailable. If the value is less than Buffer Size, that value takes precedence.

ssoadm attribute: sun-am-logging-db-max-in-mem

Buffer Time

Set the time in seconds that OpenAM buffers log messages in memory before flushing the buffer when Time Buffering is ON. The default is 60 seconds.

ssoadm attribute: iplanet-am-logging-buffer-time-in-seconds

Time Buffering

Set this to OFF to cause OpenAM to write each log message separately rather than the default of holding messages in a memory buffer that OpenAM flushes periodically, as specified using the Buffer Time attribute.

ssoadm attribute: iplanet-am-logging-time-buffering-status

Logging Level

Set the log level for OpenAM. 0FF is equivalent to setting the status to TNACTIVE.

ssoadm attribute: sun-am-log-level

Monitoring

You enable OpenAM monitoring by using these attributes.

ssoadm service name: iPlanetAMMonitoringService

Monitoring Status

Enable monitoring using this attribute.

ssoadm attribute: iplanet-am-monitoring-enabled

Monitoring HTTP Port

Set the port number for the HTML monitoring interface.

ssoadm attribute: iplanet-am-monitoring-http-port

Monitoring HTTP interface status

Enable the HTML monitoring interface using this attribute.

ssoadm attribute: iplanet-am-monitoring-http-enabled

Monitoring HTTP interface authentication file path

Set this to path to indicate the file indicating the user name and password used to protect access to monitoring information. The default user name

password combination is demo and changeit. You can encode a new password using the ampasswordcommand.

ssoadm attribute: iplanet-am-monitoring-authfile-path

Monitoring RMI Port

Set the port number for the JMX monitoring interface.

ssoadm attribute: iplanet-am-monitoring-rmi-port

Monitoring RMI interface status

Enable the JMX monitoring interface using this attribute.

 ${\bf ssoadm} \ {\bf attribute: iplanet-am-monitoring-rmi-enabled}$

Monitoring SNMP Port

Set the port number for the SNMP monitoring interface.

ssoadm attribute: iplanet-am-monitoring-snmp-port

Monitoring SNMP interface status

Enable the SNMP monitoring interface using this attribute.

ssoadm attribute: iplanet-am-monitoring-snmp-enabled

Naming

You can configure URLs for service endpoints.

ssoadm service name: iPlanetAMNamingService

Profile Service URL

Set the endpoint used by the profile service.

This attribute is deprecated.

ssoadm attribute: iplanet-am-naming-profile-url

Session Service URL

Set the endpoint used by the session service.

ssoadm attribute: iplanet-am-naming-session-url

Logging Service URL

Set the endpoint used by the logging service.

ssoadm attribute: iplanet-am-naming-logging-url

Policy Service URL

Set the endpoint used by the policy service.

ssoadm attribute: iplanet-am-naming-policy-url Authentication Service URL Set the endpoint used by the authentication service. ssoadm attribute: iplanet-am-naming-auth-url SAML Web Profile/Artifact Service URL Set the SAML v1 endpoint. ssoadm attribute: iplanet-am-naming-samlawareservlet-url SAML SOAP Service URL Set the endpoint used by the SAML v1 SOAP service. ssoadm attribute: iplanet-am-naming-samlsoapreceiver-url SAML Web Profile/POST Service URL Set the SAML v1 Web Profile endpoint. ssoadm attribute: iplanet-am-naming-samlpostservlet-url SAML Assertion Manager Service URL Set the endpoint used by the SAML v1 assertion service. ssoadm attribute: iplanet-am-naming-samlassertionmanager-url Federation Assertion Manager Service URL Set the endpoint used by the ID-FF assertion manager service. **ssoadm** attribute: iplanet-am-naming-fsassertionmanager-url Security Token Manager URL Set the STS endpoint. ssoadm attribute: iplanet-am-naming-securitytokenmanager-url JAXRPC Endpoint URL Set the JAXRPC endpoint used by remote IDM/SMS APIs. **ssoadm** attribute: iplanet-am-naming-jaxrpc-url Identity Web Services Endpoint URL Set the endpoint for Identity WSDL services.

Identity REST Services Endpoint URL Set the endpoint used for Identity REST services.

ssoadm attribute: sun-naming-idsvcs-jaxws-url

ssoadm attribute: sun-naming-idsvcs-rest-url

Security Token Service Endpoint URL Set the STS endpoint.

ssoadm attribute: sun-naming-sts-url

Security Token Service MEX Endpoint URL Set the STS MEX endpoint.

ssoadm attribute: sun-naming-sts-mex-url

Platform

You can configure the default locale and list of cookie domains.

ssoadm service name: iPlanetAMPlatformService

Platform Locale

Set the fallback locale used when the user locale cannot be determined.

ssoadm attribute: iplanet-am-platform-locale

Cookie Domains

Set the list of domains into which OpenAM writes cookies. If you set multiple cookie domains, OpenAM still only sets the cookie in the domain the client uses to access OpenAM. You can also configure cross domain single sign on (CDSSO) to allow single sign on across multiple domains managed by your organization. See the *Administration Guide* chapter on *Configuring Cross-Domain Single Sign On* for details.

ssoadm attribute: iplanet-am-platform-cookie-domains

1.4 Global Configuration

Under Configuration > Global you can set defaults for a range of federation services, for password reset, for policy configuration, for session management, and for dynamic user attributes.

Common Federation Configuration

ssoadm service name: sunFAMFederationCommon

Datastore SPI implementation class
Used by the Federation system to access user profile attributes

ssoadm attribute: DatastoreClass

ConfigurationInstance SPI implementation class

Used by the Federation system to access service configuration

ssoadm attribute: ConfigurationClass

Logger SPI implementation class

Used by the Federation system to record log messages

ssoadm attribute: LoggerClass

SessionProvider SPI implementation class

Used by the Federation system to access the session service

ssoadm attribute: SessionProviderClass

Maximum allowed content length

Maximum number of bytes for Federation communications

ssoadm attribute: MaxContentLength

PasswordDecoder SPI implementation class

Used by the Federation system to decode passwords encoded by OpenAM

ssoadm attribute: PasswordDecoderClass

SignatureProvider SPI implementation class

Used by the Federation system digitally to sign SAML documents

ssoadm attribute: SignatureProviderClass

KeyProvider SPI implementation class

Used by the Federation system to access the Java key store

ssoadm attribute: KeyProviderClass

Check presence of certificates

If enabled, OpenAM checks that the partner's signing certificate presented in

the XML matches the certificate from the partner's metadata

ssoadm attribute: CheckCert

XML canonicalization algorithm

Algorithm used to render the canonical versions of XML documents

ssoadm attribute: CannonicalizationAlgorithm

XML signature algorithm

Algorithm used to sign XML documents

ssoadm attribute: SignatureAlgorithm

XML transformation algorithm

Algorithm used for XML transformations

ssoadm attribute: TransformationAlgorithm

SAML Error Page URL

OpenAM redirects users here when an error occurs in the SAML2 engine. Users are redirected to absolute URLs, whereas releative URLs are displayed within the request.

ssoadm attribute: SAMLErrorPageURL

SAML Error Page HTTP Binding

Set this either to HTTP-Redirect or to HTTP-POST.

ssoadm attribute: SAMLErrorPageHTTPBinding

Monitoring Agent Provider Class

Used by the Federation system to access the monitoring system

ssoadm attribute: MonAgentClass

Monitoring Provider Class for SAML1

Used by the SAMLv1 engine to access the monitoring system

ssoadm attribute: MonSAML1Class

Monitoring Provider Class for SAML2

Used by the SAML2 engine to access the monitoring system

ssoadm attribute: MonSAML2Class

Monitoring Provider Class for ID-FF

Used by the ID-FF engine to access the monitoring system

ssoadm attribute: MonIDFFClass

Dashboard Configuration

ssoadm service name: dashboardService

Dashboard Class Name

Identifies how to access the application, for example SAML2ApplicationClass

for a SAML 2.0 application

ssoadm attribute: dashboardClassName

Dashboard Name

The application name as it will appear to the administrator for configuring the dashboard

ssoadm attribute: dashboardName

Dashboard Display Name

The application name that displays on the dashboard client

ssoadm attribute: dashboardDisplayName

Dashboard Icon

The icon name that will be displayed on the dashboard client identifying the application

ssoadm attribute: dashboardIcon

Dashboard Login

The URL that takes the user to the application

ssoadm attribute: dashboardLogin

Available Dashboard Apps

List of application dashboard names available by default for realms with the Dashboard configured

ssoadm attribute: assignedDashboard

Email Service

ssoadm service name: ForgeRockSendEmailService

Email Message Implementation Class

Specifies the class that sends email notifications, such as those sent for user registration and forgotten passwords.

Default: org.forgerock.openam.services.email.MailServerImpl

ssoadm attribute: forgerockMailServerImplClassName

Mail Server Host Name

Specifies the fully qualified domain name of the SMTP mail server through which to send email notifications.

Default: smtp.gmail.com

ssoadm attribute: forgerockEmailServiceSMTPHostName

Mail Server Host Port

Specifies the port number for the SMTP mail server.

Default: 465

ssoadm attribute: forgerockEmailServiceSMTPHostPort

Mail Server Authentication Username

Specifies the user name for the SMTP mail server.

Default: forgerocksmtp

ssoadm attribute: forgerockEmailServiceSMTPUserName

Mail Server Authentication Password

Specifies the password for the SMTP user name.

ssoadm attribute: forgerockEmailServiceSMTPUserPassword

Mail Server Secure Connection

Specifies whether to connect to the SMTP mail server using SSL.

Default: use SSL (true)

ssoadm attribute: forgerockEmailServiceSMTPSSLEnabled

Email From Address

Specifies the address from which to send email notifications.

Default: no-reply@openam.org

ssoadm attribute: forgerockEmailServiceSMTPFromAddress

Email Attribute Name

Specifies the profile attribute from which to retrieve the end user's email address.

Default: mail

ssoadm attribute: openamEmailAttribute

Email Subject

Specifies a subject for notification messages. If you do not set this OpenAM does not set the subject for notification messages.

ssoadm attribute: forgerockEmailServiceSMTPSubject

Email Content

Specifies content for notification messages. If you do not set this OpenAM includes only the confirmation URL in the mail body.

ssoadm attribute: forgerockEmailServiceSMTPMessage

Liberty ID-FF Service Configuration

ssoadm service name: sunFAMIDFFConfiguration

Federation Cookie Name

Cookie name for Liberty ID-FF

ssoadm attribute: FedCookieName

IDP Proxy Finder SPI implementation class

Used by the ID-FF engine to find the IDP proxy

ssoadm attribute: IDPProxyFinderClass

Request cache cleanup interval

Seconds between times OpenAM cleans up the request cache

ssoadm attribute: RequestCacheCleanupInterval

Request cache timeout

Seconds cached requests remain valid

 ${\bf ssoadm} \ {\bf attribute:} \ {\bf RequestCacheTimeout}$

IDP Login URL

Login URL for the ID-FF IDP

ssoadm attribute: IDPLoginURL

XML signing on

If yes, require XML signing.

ssoadm attribute: XMLSigningOn

Liberty Interaction Service

ssoadm service name: sunFAMLibertyInteractionService

WSP to redirect user for interaction **ssoadm** attribute: WSPWillRedirect

WSP to redirect user for interaction for data **ssoadm** attribute: WSPWillRedirectForData

WSP's expected duration for interaction **ssoadm** attribute: WSPRedirectTime

WSP to enforce that returnToURL must be SSL ssoadm attribute: WSPWillEnforceHttpsCheck

WSP to enforce return to host be the same as request host **ssoadm** attribute: WSPWillEnforceReturnToHostEqualsRequestHost

HTML style sheet location

ssoadm attribute: HTMLStyleSheetLocation

WML style sheet location

ssoadm attribute: WMLStyleSheetLocation

WSP interaction URL

ssoadm attribute: WSPRedirectHandlerURL

WSP interaction URL if behind load balancer ssoadm attribute: LBWSPRedirectHandler

List of interaction URLs of WSP cluster (site) behind the load balancer **ssoadm** attribute: TrustedWspRedirectHandlers

Interaction Configuration Class

ssoadm attribute: InteractionConfigClass

Options for WSC to participate in interaction **ssoadm** attribute: WSCSpecifiedInteractionChoice

WSC to include userInteractionHeader

ssoadm attribute: WSCWillIncludeUserInteractionHeader

WSC to redirect user for interaction ssoadm attribute: WSCWillRedirect

WSC's expected duration for interaction **ssoadm** attribute: WSCSpecifiedMaxInteractionTime

WSC to enforce that redirection URL must be SSL ssoadm attribute: WSCWillEnforceHttpsCheck

Multi-Federation Protocol

ssoadm service name: sunMultiFederationProtocol

Single Logout Handler List

List of logout handlers used for each different federation protocol

ssoadm attribute: SingleLogoutHandlerList

OAuth2 Provider Configuration

ssoadm service name: OAuth2Provider

Authorization Code Lifetime

Lifetime of OAuth 2.0 authorization code in seconds.

ssoadm attribute: forgerock-oauth2-provider-authorization-code-lifetime

Refresh Token Lifetime

Lifetime of OAuth 2.0 refresh token in seconds.

ssoadm attribute: forgerock-oauth2-provider-refresh-token-lifetime

Access Token Lifetime

Lifetime of OAuth 2.0 access token in seconds.

ssoadm attribute: forgerock-oauth2-provider-access-token-lifetime

Issue Refresh Tokens

Whether to issue a refresh token when returning an access token.

ssoadm attribute: forgerock-oauth2-provider-issue-refresh-token

Scope Implementation Class

Name of class on OpenAM classpath implementing scopes.

ssoadm attribute: forgerock-oauth2-provider-scope-implementation-class

Response Type Plugins

List of plugins that handle the valid response_type values. OAuth 2.0 clients pass response types as parameters to the OAuth 2.0 Authorization end point (/oauth2/authorize) to indicate which grant type is requested from the provider. For example, the client passes code when requesting an authorization code, and token when requesting an access token.

Values in this list take the form response-type|plugin-class-name.

Defaults: code|org.forgerock.restlet.ext.oauth2.flow.responseTypes. CodeResponseType, id_token|org.forgerock.restlet.ext.oauth2.flow.responseTypes, token|org.forgerock.restlet.ext.oauth2.flow.responseTypes. TokenResponseType

ssoadm attribute: forgerock-oauth2-provider-response-type-map-class

User Profile Attribute(s) the Resource Owner is Authenticated On Names of profile attributes that resource owners use to log in. The default is uid, and you can add others such as mail.

ssoadm attribute: forgerock-oauth2-provider-authentication-attributes

Shared Consent Attribute Name

Name of a multi-valued attribute on resource owner profiles where OpenAM can save authorization consent decisions. When the resource owner chooses to save the decision to authorize access for a client application, then OpenAM updates the resource owner's profile to avoid having to prompt the resource owner to grant authorization when the client issues subsequent authorization requests.

ssoadm attribute: forgerock-oauth2-provider-saved-consent-attribute

JSON Web Key URL

The URL where the OpenID Connect provider's JSON Web Key can be retrieved.

ssoadm attribute: forgerock-oauth2-provider-jkws-uri

ID Token Signing Algorithms supported

Algorithms supported to sign OpenID Connect id tokens.

ssoadm attribute: forgerock-oauth2-provider-id-token-signing-algorithmssupported

Supported Claims

List of claims supported by the OpenID Connect /oauth2/userinfo endpoint.

ssoadm attribute: forgerock-oauth2-provider-supported-claims

Password Reset

Realm Attributes

See the *Administration Guide* chapter on *Configuring Password Reset* for details.

Policy Configuration

You can change global policy configuration, and the defaults per realm.

ssoadm service name: iPlanetAMPolicyConfigService

Resource Comparator

OpenAM uses resource comparators to match resources specified in policy rules. When setting comparators on the command line, separate fields with | characters.

ssoadm attribute: iplanet-am-policy-config-resource-comparator

Continue Evaluation on Deny Decision

If no, then OpenAM stops evaluating policy as soon as it reaches a deny decision.

ssoadm attribute: iplanet-am-policy-config-continue-evaluation-on-denydecision

Advices Handleable by OpenAM

Lists advice names for which policy agents redirect users to OpenAM for further authentication and authorization

ssoadm attribute: sun-am-policy-config-advices-handleable-by-am

Realm Alias Referrals

If yes, then OpenAM allows creation of policies for HTTP and HTTPS resources whose FQDN matches the DNS alias for the realm even when no referral policy exists.

ssoadm attribute: sun-am-policy-config-org-alias-mapped-resources-enabled

Primary LDAP Server

Configuration directory server host:port that OpenAM searches for policy information

ssoadm attribute: iplanet-am-policy-config-ldap-server

LDAP Base DN

Base DN for policy searches

ssoadm attribute: iplanet-am-policy-config-ldap-base-dn

LDAP Users Base DN

Base DN for LDAP Users subject searches

ssoadm attribute: iplanet-am-policy-config-ldap-users-base-dn

OpenAM Roles Base DN

Base DN for OpenAM Roles searches

ssoadm attribute: iplanet-am-policy-config-is-roles-base-dn

LDAP Bind DN

Bind DN to connect to the directory server for policy information

ssoadm attribute: iplanet-am-policy-config-ldap-bind-dn

LDAP Bind Password

Bind password to connect to the directory server for policy information

ssoadm attribute: iplanet-am-policy-config-ldap-bind-password

LDAP Organization Search Filter

Search filter to match organization entries

ssoadm attribute: iplanet-am-policy-config-ldap-organizations-searchfilter

LDAP Organization Search Scope

Search scope to find organization entries

ssoadm attribute: iplanet-am-policy-config-ldap-organizations-search-scope

LDAP Groups Search Filter

Search filter to match group entries

ssoadm attribute: iplanet-am-policy-config-ldap-groups-search-filter

LDAP Groups Search Scope

Search scope to find group entries

ssoadm attribute: iplanet-am-policy-config-ldap-groups-search-scope

LDAP Users Search Filter

Search filter to match user entries

ssoadm attribute: iplanet-am-policy-config-ldap-users-search-filter

LDAP Users Search Scope

Search scope to find user entries

ssoadm attribute: iplanet-am-policy-config-ldap-users-search-scope

LDAP Roles Search Filter

Search filter to match nsRole definition entries

ssoadm attribute: iplanet-am-policy-config-ldap-roles-search-filter

LDAP Roles Search Scope

Search scope to find nsRole definition entries

ssoadm attribute: iplanet-am-policy-config-ldap-roles-search-scope

OpenAM Roles Search Scope

Search scope to find OpenAM roles entries

ssoadm attribute: iplanet-am-policy-config-is-roles-search-scope

LDAP Organization Search Attribute

Naming attribute for organization entries

 ${\bf ssoadm} \ {\bf attribute: iplanet-am-policy-config-ldap-organizations-search-attribute}$

LDAP Groups Search Attribute

Naming attribute for group entries

ssoadm attribute: iplanet-am-policy-config-ldap-groups-search-attribute

LDAP Users Search Attribute

Naming attribute for user entries

ssoadm attribute: iplanet-am-policy-config-ldap-users-search-attribute

LDAP Roles Search Attribute

Naming attribute for nsRole definition entries

ssoadm attribute: iplanet-am-policy-config-ldap-roles-search-attribute

Maximum Results Returned from Search

Search limit for LDAP searches

ssoadm attribute: iplanet-am-policy-config-search-limit

Search Timeout

Seconds after which OpenAM returns an error for an incomplete search

ssoadm attribute: iplanet-am-policy-config-search-timeout

LDAP SSL/TLS

If enabled, OpenAM connects securely to the directory server. This requires that you install the directory server certificate.

ssoadm attribute: iplanet-am-policy-config-ldap-ssl-enabled

LDAP Connection Pool Minimum Size

Minimum number of connections in the pool

ssoadm attribute: iplanet-am-policy-config-connection_pool_min_size

LDAP Connection Pool Maximum Size

Maximum number of connections in the pool

ssoadm attribute: iplanet-am-policy-config-connection pool max size

Selected Policy Subjects

Lists subjects available for policy definition in realms

ssoadm attribute: iplanet-am-policy-selected-subjects

Selected Policy Conditions

Lists conditions available for policy definition in realms

ssoadm attribute: iplanet-am-policy-selected-conditions

Selected Policy Referrals

Lists referral types available for policy definition in realms

ssoadm attribute: iplanet-am-policy-selected-referrals

Subjects Result Time to Live

Maximum minutes OpenAM caches a subject result for evaluating policy requests. A value of 0 prevents OpenAM from caching subject evaluations for policy decisions.

Default: 10

ssoadm attribute: iplanet-am-policy-config-subjects-result-ttl

User Alias

If enabled, OpenAM can evaluate policy for remote users aliased to local users.

ssoadm attribute: iplanet-am-policy-config-user-alias-enabled

Selected Response Providers

Lists available response providers available for policy definition

ssoadm attribute: sun-am-policy-selected-responseproviders

Selected Dynamic Response Attributes

Lists dynamic response attributes available for policy definition

ssoadm attribute: sun-am-policy-dynamic-response-attributes

REST Security

ssoadm service name: RestSecurity

The order of options that appear in the console may vary depending on whether you are running from a new installation or an upgrade of OpenAM.

Self-Registration for Users

If enabled, new users can sign up using a REST API client.

Default: not enabled

ssoadm attribute: forgerockRESTSecuritySelfRegistrationEnabled

Self-Registration Token LifeTime (seconds)

Maximum life time for the token allowing user self-registration using the REST API.

Default: 900 (seconds)

ssoadm attribute: forgerockRESTSecuritySelfRegTokenTTL

Self-Registration Confirmation Email URL

This page handles the HTTP GET request when the user clicks the link sent by email in the confirmation request.

Default: deployment-base-url/XUI/confirm.html where deployment-base-url is something like https://openam.example.com:8443/openam

ssoadm attribute: forgerockRESTSecuritySelfRegConfirmationUrl

Forgot Password for Users

If enabled, users can assign themselves a new password using a REST API client.

Default: not enabled

ssoadm attribute: forgerockRESTSecurityForgotPasswordEnabled

Forgot Password Token LifeTime (seconds)

Maximum life time for the token allowing user to process a forgotten password using the REST API.

Default: 900 (seconds)

ssoadm attribute: forgerockRestSecurityForgotPassTokenTTL

Forgot Password Confirmation Email URL

This page handles the HTTP GET request when the user clicks the link sent by email in the confirmation request.

Default: deployment-base-url/XUI/confirm.html where deployment-base-url is something like https://openam.example.com:8443/openam

ssoadm attribute: forgerockRESTSecurityForgotPassConfirmationUrl

SAMLv2 Service Configuration

ssoadm service name: sunFAMSAML2Configuration

Cache cleanup interval

Seconds between cache cleanup operations

ssoadm attribute: CacheCleanupInterval

Attribute name for Name ID information

User entry attribute to store name identifier information

ssoadm attribute: NameIDInfoAttribute

Attribute name for NAME ID information key
User entry attribute to store the name identifier key

ssoadm attribute: NameIDInfoKeyAttribute

Cookie domain for IDP Discovery Service Specifies the cookie domain for the IDP discovery service

ssoadm attribute: IDPDiscoveryCookieDomain

Cookie type for IDP Discovery Service Indicates whether to use PERSISTENT or SESSION cookies

ssoadm attribute: IDPDiscoveryCookieType

URL scheme for IDP Discovery Service Indicates whether to use HTTP or HTTPS

ssoadm attribute: IDPDiscoveryURLScheme

XML Encryption SPI implementation class
Used by the SAML2 engine to encrypt and decrypt documents

ssoadm attribute: XMLEncryptionClass

Include xenc:EncryptedKey Inside ds:KeyInfo Element
 ssoadm attribute: EncryptedKeyInKeyInfo

XML Signing SPI implementation class
Used by the SAML2 engine to sign documents

ssoadm attribute: XMLSigningClass

XML Signing Certificate Validation
If enabled, then validate certificates used to sign documents.

ssoadm attribute: SigningCertValidation

CA Certificate Validation
If enabled, then validate CA certificates.

ssoadm attribute: CACertValidation

Enable SAMLv2 failover
If enabled, the OpenAM can failover requests to another instance.

ssoadm attribute: failOverEnabled

Buffer length to decompress request The size is specified in bytes.

 ${\bf ssoadm}$ attribute: bufferLength

SAMLv2 SOAP Binding

ssoadm service name: sunfmSAML2SOAPBindingService

Request Handler List

List of handlers to deal with SAML2 requests bound to SOAP. The key for a request handler is the meta alias, whereas the class indicates the name of the class that implements the handler.

ssoadm attribute: sunSAML2RequestHandlerList

Security Token Service

ssoadm service name: sunFAMSTSService

Issuer

Specifies the name of the security token service

ssoadm attribute: stsIssuer

End Point

Specifies the STS service endpoint

ssoadm attribute: stsEndPoint

Lifetime for Security Token

Milliseconds the security token remains valid

ssoadm attribute: stslifetime

Certificate Alias Name

Specifies the alias for the signing certificate

ssoadm attribute: stsCertAlias

STS End User Token Plugin class

Specifies the class that converts end user tokens

ssoadm attribute: com.sun.identity.wss.sts.clientusertoken

Security Mechanism

Lists credentials used to secure the token, and credentials OpenAM accepts in the incoming request

ssoadm attribute: SecurityMech

Authentication Chain

Specifies the authentication chain OpenAM applies for incoming requests for authenticated security tokens

ssoadm attribute: AuthenticationChain

User Credential

User name and password shared secrets to validate UserName tokens in incoming requests

ssoadm attribute: UserCredential

Detect Message Replay

If yes, then OpenAM checks for and rejects replayed messages.

ssoadm attribute: DetectMessageReplay

Detect User Token Replay

If yes, then OpenAM checks for and rejects replayed user tokens.

ssoadm attribute: DetectUserTokenReplay

Is Request Signature Verified

If yes, then OpenAM verifies signatures on incoming requests.

ssoadm attribute: isRequestSign

Is Response Signed Enabled

If yes, then OpenAM signs the selected parts of the response.

ssoadm attribute: isResponseSign

Signing Reference Type

Specifies the reference type used to sign the response. One of DirectReference, KeyldentifierRef, or X509IssuerSerialRef.

ssoadm attribute: SigningRefType

Is Request Decrypted

If yes, then OpenAM decrypts the selected parts of the request.

ssoadm attribute: isRequestEncrypt

Is Response Encrypted

If yes, then OpenAM encrypts responses.

ssoadm attribute: isResponseEncrypt

Encryption Algorithm

Specifies the algorithm used to encrypt responses

ssoadm attribute: EncryptionAlgorithm

Private Key Alias

Alias for the private key used to sign responses and decrypt requests

ssoadm attribute: privateKeyAlias

Private Key Type

Type of private key. One of publicKey, symmetricKey, or noProofKey.

ssoadm attribute: privateKeyType

Public Key Alias of Web Service Client

Alias for the certificate used to verify request signatures and encrypt responses

ssoadm attribute: publicKeyAlias

Kerberos Domain Server

Specifies the FQDN of the KDC

ssoadm attribute: KerberosDomainServer

Kerberos Domain

Specifies the domain name of the KDC

ssoadm attribute: KerberosDomain

Kerberos Service Principal

Specifies the Kerberos principal who owns the generated token. Use the format HTTP/host.domain@kdc-domain.

ssoadm attribute: KerberosServicePrincipal

Kerberos Key Tab File

Specifies the key tab file used to issue the token

ssoadm attribute: KerberosKeyTabFile

Is Verify Kerberos Signature

If yes, then OpenAM requires signed Kerberos tokens.

ssoadm attribute: isVerifyKrbSignature

SAML Attribute Mapping

Lists attribute mappings for generated assertions

This attribute applies when OpenAM acts as a WSP, receiving a SAML token or assertion generated by another STS.

ssoadm attribute: SAMLAttributeMapping

NameID Mapper

Specifies the NameID mapper for generated assertions

This attribute applies when OpenAM acts as a WSP, receiving a SAML token or assertion generated by another STS.

ssoadm attribute: NameIDMapper

Should Include Memberships

If yes, then OpenAM requires generated assertions include user memberships.

This attribute applies when OpenAM acts as a WSP, receiving a SAML token or assertion generated by another STS.

ssoadm attribute: includeMemberships

Attribute Namespace

Specifies the namespace for generated assertions

This attribute applies when OpenAM acts as a WSP, receiving a SAML token or assertion generated by another STS.

ssoadm attribute: AttributeNamespace

Trusted Issuers

Lists issuers OpenAM can trust to send security tokens

ssoadm attribute: trustedIssuers

Trusted IP Addresses

Lists issuer IP address that OpenAM can trust to send security tokens

ssoadm attribute: trustedIPAddresses

Session

ssoadm service name: iPlanetAMSessionService

Secondary Configuration Instance

When session failover is configured, you can set up additional configurations for connecting to the session repository here.

Maximum Number of Search Results

Maximum number of results from a session search

ssoadm attribute: iplanet-am-session-max-session-list-size

Timeout for Search

Seconds after which OpenAM sees an incomplete search as having failed

ssoadm attribute: iplanet-am-session-session-list-retrieval-timeout

Enable Property Change Notifications

If on, then OpenAM notifies other applications participating in SSO when a session property in the Notification Properties list changes.

ssoadm attribute: iplanet-am-session-property-change-notification

Enable Ouota Constraints

If on, then OpenAM allows you to set constraints on user sessions.

ssoadm attribute: iplanet-am-session-enable-session-constraint

Read Timeout for Quota Constraint

Milliseconds after which OpenAM considers a search for live session count as having failed if quota constraints are enabled

ssoadm attribute: iplanet-am-session-constraint-max-wait-time

Resulting behavior if session quota exhausted

You can either set the next expiring session to be destroyed,
DESTROY_NEXT_EXPIRING, the oldest session to be destroyed,
DESTROY_OLDEST_SESSION, all previous sessions to be destroyed,
DESTROY_OLD SESSIONS, or deny the new session creation request, DENY ACCESS.

ssoadm attribute: iplanet-am-session-constraint-resulting-behavior

Deny user login when session repository is down

This attribute takes effect when quota constraints are enabled.

ssoadm attribute: iplanet-am-session-deny-login-if-db-is-down

Notification Properties

Lists session properties for which OpenAM can send notifications upon modification

ssoadm attribute: iplanet-am-session-notification-property-list

DN Restriction Only Enabled

If enabled, OpenAM does not perform DNS lookups when checking restrictions in cookie hijacking mode.

ssoadm attribute: iplanet-am-session-dnrestrictiononly

Enable Session Trimming

If yes, then OpenAM stores only a limited set of session properties after session timeout and before session purging.

ssoadm attribute: iplanet-am-session-enable-session-trimming

Session Timeout Handler implementations

Lists plugin classes implementing session timeout handlers

ssoadm attribute: openam-session-timeout-handler-list

Maximum Session Time

Maximum minutes a session can remain valid before OpenAM requires the user to authenticate again

ssoadm attribute: iplanet-am-session-max-session-time

Maximum Idle Time

Maximum minutes a session can remain idle before OpenAM requires the user to authenticate again

ssoadm attribute: iplanet-am-session-max-idle-time

Maximum Caching Time

Maximum minutes before OpenAM refreshes a session that has been cached

ssoadm attribute: iplanet-am-session-max-caching-time

Active User Sessions

Maximum number of concurrent sessions OpenAM allows a user to have

ssoadm attribute: iplanet-am-session-quota-limit

User

ssoadm service name: iPlanetAMUserService

User Preferred Timezone

Time zone for accessing OpenAM console

ssoadm attribute: preferredtimezone

Administrator DN Starting View

Specifies the DN for the initial screen when the OpenAM administrator successfully logs in to the OpenAM console

ssoadm attribute: iplanet-am-user-admin-start-dn

Default User Status

Inactive users cannot authenticate, though OpenAM stores their profiles.

Default: Active

ssoadm attribute: iplanet-am-user-login-status

1.5 Servers and Sites Configuration

Under Configuration > Servers and Sites you can manage server defaults, configuration for OpenAM server instances, and site configurations when using multiple OpenAM server instances.

To change inherited settings that appear read only for a server, click Default Server Settings on the Servers and Sites tab page to access and adjust the defaults, or change the Inheritance Settings for a specific server.

After changing server configurations, restart OpenAM or the web application container where OpenAM runs for the changes to take effect.

Servers > General

The General tab lets you access the settings to inherit, set the site for the server, and also set system, debug, and mail server attributes.

Parent Site

Select the site from the list. You must first create at least one site.

Base installation directory

OpenAM writes the configuration data and logs here.

property: com.iplanet.services.configpath

Default Locale

The locale used when none is requested.

property: com.iplanet.am.locale

Notification URL

The notification service endpoint.

property: com.sun.identity.client.notification.url

XMI. Validation

If on, then OpenAM validates XML documents that it parses.

property: com.iplanet.am.util.xml.validating

Debug Level

Set the log level shared across components for debug logging.

property: com.iplanet.services.debug.level

Merge Debug Files

If on, then OpenAM writes all debug log messages to a single file, debug.out. By default, OpenAM writes a debug log per component.

property: com.iplanet.services.debug.mergeall

Debug Directory

File system directory where OpenAM writes debug logs.

property: com.iplanet.services.debug.directory

Mail Server Host Name

SMTP host name for email sent by OpenAM.

property: com.iplanet.am.smtphost

Mail Server Port Number

SMTP port number for email sent by OpenAM.

property: com.iplanet.am.smtpport

Servers > Security

Most security settings are inherited by default.

Password Encryption Key

Encryption key for decrypting stored passwords

Example: TF1Aue9c63bWTTY4mmZJeFYubJbNiSE3

property: am.encryption.password

Authentication Service Shared Secret

Shared secret for application authentication

Example: AQICQ7QMKN5TSt1fpyFZBMZ8hRwkYkkrUaFk

property: com.iplanet.am.service.secret

Encryption class

Default class used to handle encryption

Default: com.iplanet.services.util.JCEEncryption

property: com.iplanet.security.encryptor

Secure Random Factory Class

The default implementation uses pure Java, rather than JSS.

Default: com.iplanet.am.util.SecureRandomFactoryImpl

property: com.iplanet.security.SecureRandomFactorImpl

Platform Low Level Comm. Max. Content Length

Maximum content length for an HTTP request

Default: 16384

property: com.iplanet.services.comm.server.pllrequest.maxContentLength

Client IP Address Check

If yes, then OpenAM checks client IP addresses when creating and validating SSO tokens.

Default: No

property: com.iplanet.am.clientIPCheckEnabled

Cookie Name

Cookie name OpenAM uses to set a session handler ID during authentication.

Default: iPlanetDirectoryPro

property: com.iplanet.am.cookie.name

Secure Cookie

If yes, then OpenAM sets the cookie in secure mode such that the browser only returns the cookie if a secure protocol such as HTTPS is used.

Default: No

property: com.iplanet.am.cookie.secure

Encode Cookie Value

If yes, then OpenAM URL encodes cookie values.

Default: No

property: com.iplanet.am.cookie.encode

Keystore File

Path to OpenAM key store file

Default: Path to keystore.jks, located in the directory that holds the OpenAM configuration.

Example: ~/openam/openam/keystore.jks

property: com.sun.identity.saml.xmlsig.keystore

Keystore Password File

Path to password file for key store

Default: Path to .storepass, located in the directory that holds the OpenAM configuration.

Example: ~/openam/openam/.storepass

property: com.sun.identity.saml.xmlsig.storepass

Private Key Password File

Path to password file for OpenAM private key

Default: Path to .keypass, located in the directory that holds the $\ensuremath{\mathsf{OpenAM}}$ configuration.

Example: ~/openam/openam/.keypass

property: com.sun.identity.saml.xmlsig.keypass

Certificate Alias

Alias for OpenAM certificate stored in key store

Not set by default

property: com.sun.identity.saml.xmlsig.certalias

CRL: LDAP server host name

Directory server host name where the certificate revocation list (CRL) is cached

Not set by default

property: com.sun.identity.crl.cache.directory.host

CRL: LDAP server port number

Directory server port number where the certificate revocation list is cached

Not set by default

property: com.sun.identity.crl.cache.directory.port

CRL: SSL/TLS Enabled

If yes, then connect securely when accessing the CRL cache directory server

Default: No

property: com.sun.identity.crl.cache.directory.ssl CRL: LDAP server bind user name Bind DN to access CRL cache directory server Not set by default property: com.sun.identity.crl.cache.directory.user CRL: LDAP server bind password Bind password to access CRL cache directory server Not set by default property: com.sun.identity.crl.cache.directory.password CRL: LDAP search base DN Base DN under which to search for CRL Not set by default property: com.sun.identity.crl.cache.directory.searchlocs **CRL**: Search Attributes DN component of issuer's subject DN used to retrieve the CRL Not set by default property: com.sun.identity.crl.cache.directory.searchattr OCSP: Check Enabled If yes, then OpenAM runs Online Certificate Status Protocol (OCSP) checks. Default: Yes property: com.sun.identity.authentication.ocspCheck Responder URL URL for OCSP responder Not set by default property: com.sun.identity.authentication.ocsp.responder.url Certificate Nickname Nickname for OCSP responder certificate Not set by default

property: com.sun.identity.authentication.ocsp.responder.nickname

FIPS Mode

If yes, then OpenAM runs in Federal Information Processing Standards mode.

Default: No

property: com.sun.identity.security.fipsmode

Servers > Session

Session settings are inherited by default.

Maximum Sessions

Maximum concurrent sessions OpenAM permits

property: com.iplanet.am.session.maxSessions

Invalidate Session Max Time

Minutes after which invalid sessions are removed from the session table

property: com.iplanet.am.session.invalidsessionmaxtime

Sessions Purge Delay

Minutes OpenAM delays session purging

property: com.iplanet.am.session.purgedelay

Logging Interval

Seconds OpenAM delays between logging sessions statistics

property: com.iplanet.am.stats.interval

State

Whether to write statistics to a file, to the console, or to turn recording off

property: com.iplanet.services.stats.state

Directory

Path to statistics logs directory

property: com.iplanet.services.stats.directory

Enable Host Lookup

If yes, then OpenAM performs host lookup during session logging.

property: com.sun.am.session.enableHostLookUp

Notification Pool Size

Number of threads in the notification pool

property: com.iplanet.am.notification.threadpool.size

Notification Thread Pool Threshold

Maximum number of tasks in the queue for serving notification threads

property: com.iplanet.am.notification.threadpool.threshold

Case Insensitive client DN comparison

If yes, then OpenAM distinguished name comparison is case insensitive.

property: com.sun.am.session.caseInsensitiveDN

Servers > SDK

Most SDK settings are inherited.

Enable Datastore Notification

If yes, then OpenAM uses datastore notification. Otherwise, OpenAM uses inmemory notification.

property: com.sun.identity.sm.enableDataStoreNotification

Enable Directory Proxy

If yes, then OpenAM accounts for the use of a directory proxy to access the directory server.

property: com.sun.identity.sm.ldap.enableProxy

Notification Pool Size

Service management notification thread pool size

property: com.sun.identity.sm.notification.threadpool.size

Number of retries for Event Service connections

Maximum number of attempts to reestablish Event Service connections

property: com.iplanet.am.event.connection.num.retries

Delay between Event Service connection retries

Milliseconds between attempts to reestablish Entry Service connections

property: com.iplanet.am.event.connection.delay.between.retries

Error codes for Event Service connection retries

LDAP error codes for which OpenAM retries rather than returning failure

property: com.iplanet.am.event.connection.ldap.error.codes.retries

Idle Time Out

Minutes after which OpenAM reestablishes idle persistent search connections

property: com.sun.am.event.connection.idle.timeout

Disabled Event Service Connection

Persistent search connections OpenAM can disable

property: com.sun.am.event.connection.disable.list

Number of retries for LDAP Connection

Maximum number of attempts to reestablish LDAP connections

property: com.iplanet.am.ldap.connection.num.retries

Delay between LDAP connection retries

Milliseconds between attempts to reestablish LDAP connections

property: com.iplanet.am.ldap.connection.delay.between.retries

Error Codes for LDAP connection retries

LDAP error codes for which OpenAM retries rather than returning failure

property: com.iplanet.am.ldap.connection.ldap.error.codes.retries

SDK Caching Max. Size

Cache size used if SDK caching is enabled

property: com.iplanet.am.sdk.cache.maxSize

SDK Replica Retries

Maximum number of attempts to retrieve entries returned as not found

property: com.iplanet.am.replica.num.retries

Delay between SDK Replica Retries

Milliseconds between attempts to retrieve entries through the SDK

property: com.iplanet.am.replica.delay.between.retries

Cache Entry Expiration Enabled

If no, then cache entries expire based on User Entry Expiration Time

property: com.iplanet.am.sdk.cache.entry.expire.enabled

User Entry Expiration Time

Minutes user entries remain valid after modification. When OpenAM accesses a user entry that has expired, it rereads the entry from the directory server.

property: com.iplanet.am.sdk.cache.entry.user.expire.time

Default Entry Expiration Time

Minutes non-user entries remain valid after modification

property: com.iplanet.am.sdk.cache.entry.default.expire.time

Servers > Directory Configuration

Use this tab to change connection settings and add additional LDAP configuration directory server instances.

Minimum Connection Pool

Set the minimum number of connections in the pool.

Maximum Connection Pool

Set the maximum number of connections in the pool.

Bind DN

Set the bind DN to connect to the configuration directory servers.

Bind Password

Set the bind password to connect to the configuration directory servers.

Servers > CTS

The Core Token Service (CTS) does not need to be configured in the same LDAP storage as the external or embedded user store. The CTS can instead be configured on its own external directory server. There are some specific requirements for indexing and replication which need to be accounted for. In particular, WAN replication is an important consideration which needs to be handled carefully for optimum performance.

You may also choose to set advanced properties related to token size, including com.sun.identity.session.repository.enableEncryption, com.sun.identity.session.repository.enableCompression, and com.sun.identity.session.repository.enableAttributeCompression.For more information, identify these variables in the following section: Servers > Advanced.

Default Token Store

If selected, CTS tokens are stored in the same external or embedded datastore as is used on an OpenAM configuration store. If you use the default token store, you can only configure the Root Suffix. Associated with the Directory Configuration tab associated with individual servers.

External Token Store

If you use OpenDJ, you can separate the CTS from the configuration on different external servers. On the external CTS server, you can also configure token schema and indexes.

Root Suffix

For either the default or external token stores, enter the base DN for CTS storage information in LDAP format, such as dc=cts, dc=forgerock, dc=com. The Root Suffix would be a database that can be maintained and replicated separately from the standard user datastore.

SSL/TLS Enabled

Access the directory service using StartTLS or LDAPS.

Directory Name

The hostname of the external server.

Port

Specifies the TCP/IP port number used for communication to to external datastore, such as 389 for LDAP.

Login Id

Specifies the user, in DN format, needed to authenticate. The user needs sufficient privileges to read and write to the root suffix of the external datastore.

Password

Specifies the password associated with the Login Id.

Max Connections

Notes the maximum number of remote connections to the external datastore.

Heartbeat

Specifies how often OpenAM should send a heartbeat request to the directory server to ensure that the connection does not remain idle, in seconds. Default: 10.

Servers > Advanced

Use this page to set advanced properties directly. A partial list of advanced properties follows.

For a list of inherited advanced properties, see the table under the Advanced tab for Default Server Settings.

com.iplanet.am.cookie.c66Encode Properly URL encode session tokens.

Default: true

com.iplanet.am.cookie.timeToLive
 iplanetDirectoryPro cookie lifetime if persistent, in hours

Default: 24

com.iplanet.am.daemons

Modules for which to open daemons at OpenAM startup.

Default: securid

com.iplanet.am.directory.ssl.enabled

Whether to connect to the configuration directory server over LDAPS.

Default: false

com.iplanet.am.installdir

OpenAM Configuration and log file location.

Default: ~/openam/server-uri, such as ~/openam/openam

com.iplanet.am.jssproxy.checkSubjectAltName

When using JSS, check whether the name values in the SubjectAltName certificate match the server FQDN.

Default: false

com.iplanet.am.jssproxy.resolveIPAddress

When using JSS, check that the IP address of the server resolves to the host name.

Default: false

com.iplanet.am.jssproxy.SSLTrustHostList

When using JSS, comma-separated list of server FQDNs to trust if they match the certificate CN, even if the domain name is not correct.

com.iplanet.am.jssproxy.trustAllServerCerts

When using JSS, set to true to trust whatever certificate is presented without checking.

Default: true

com.iplanet.am.lbcookie.name

Used with sticky load balancers that can inspect the cookie value.

Default: amlbcookie

com.iplanet.am.lbcookie.value

Used with sticky load balancers that can inspect the cookie value. Set this property to a unique value if your load balancer requires it. Restart OpenAM for the change to take effect.

Default: 01

com.iplanet.am.pcookie.name Persistent cookie name.

Default: DProPCookie

com.iplanet.am.profile.host

Not used

Default: server-host, such as openam.example.com

com.iplanet.am.profile.port

Not used

Default: server-port, such as 8080 or 8443

com.iplanet.am.session.agentSessionIdleTime

Time in minutes after which a policy agent session expires.

Default: 0, meaning never time out. Range is 0-30 (minutes).

com.iplanet.am.session.client.polling.enable

Whether client applications such as policy agents poll for configuration changes. If false, then OpenAM notifies clients about changes.

Default: false

com.iplanet.am.session.client.polling.period

If client applications poll for changes, number of seconds between polls.

Default: 180

com.iplanet.am.session.failover.cluster.stateCheck.period

Time in milliseconds between health checks of other servers in the same site.

Default: 1000

com.iplanet.am.session.failover.cluster.stateCheck.timeout

Socket timeout in milliseconds for health checks of other servers in the same

site.

Default: 1000

com.iplanet.am.session.httpSession.enabled

Create an HttpSession for users on successful authentication.

Default: true

com.iplanet.security.SSLSocketFactoryImpl

SSL socket factory implementation used by OpenAM.

Default: com.sun.identity.shared.ldap.factory.JSSESocketFactory, uses a pure Java provider

com.iplanet.services.cdc.invalidGotoStrings;

Strings that OpenAM rejects as values in goto query string parameters.

Default: <,>javascript:,javascript%3a,%3c,%3e

com.sun.embedded.replicationport

Replication port for embedded OpenDJ directory server.

Default: 8989

com.sun.embedded.sync.servers

Whether to replicate data between embedded directory servers.

Default: on

com.sun.identity.am.cookie.check

Whether to check for cookie support in the user agent, and if not to return an error.

Default: false

com.sun.identity.appendSessionCookieInURL

Whether to append the session cookie to URL for a zero page session.

Default: true

com.sun.identity.auth.cookieName

Cookie used by the OpenAM authentication service to handle the authentication process.

Default: AMAuthCookie

com.sun.identity.authentication.client.ipAddressHeader

Set the name of the HTTP header that OpenAM can examine to learn the client IP address when requests go through a proxy or load balancer. (When requests go through an HTTP proxy or load balancer, checking the IP address on the request alone returns the address of the proxy or load balancer rather than that of the client.) OpenAM must be able to trust the proxy or load balancer to set the client IP address correctly in the header specified.

Example: com.sun.identity.authentication.client.ipAddressHeader=X-Forwarded-For

com.sun.identity.authentication.multiple.tabs.used

Whether to allow users to open many browser tabs to the login page at the same time without encountering an error.

Default: false

com.sun.identity.authentication.setCookieToAllDomains
 Whether to allow multiple cookie domains.

Default: true

com.sun.identity.authentication.special.users

List of special users always authenticated against the local directory server.

Default: cn=dsameuser,ou=DSAME Users,dc=openam,dc=forgerock,dc=org| cn=amService-UrlAccessAgent,ou=DSAME Users,dc=openam,dc=forgerock,dc=org

com.sun.identity.authentication.super.user OpenAM privileged administrator user.

Default: uid=amAdmin,ou=People,dc=openam,dc=forgerock,dc=org

com.sun.identity.authentication.uniqueCookieName
When cookie hijacking protection is configured, name of the cookie holding
the URL to the OpenAM server that authenticated the user.

Default: sunIdentityServerAuthNServer

com.sun.identity.client.notification.url
Notification service endpoint for clients such as policy agents.

Default: server-protocol://server-host:server-port/server-uri/ notificationservice, such as https://openam.example.com:8443/openam/ notificationservice

com.sun.identity.common.systemtimerpool.size Number of threads in the shared system timer pool used to schedule operations such as session timeout.

Default: 3

com.sun.identity.cookie.httponly

When set to true, mark cookies as HTTPOnly to prevent scripts and third-party programs from accessing the cookies.

Default: false

com.sun.identity.enableUniqueSSOTokenCookie
If true, then OpenAM is using protection against cookie hijacking.

Default: false

 ${\tt com.sun.identity.jss.donotInstallAtHighestPriority} \\ Whether JSS should take priority over other providers.$

Default: true

com.sun.identity.monitoring
Whether monitoring is active for OpenAM.

Default: off

com.sun.identity.monitoring.local.conn.server.url URL for local connection to the monitoring service.

Default: service: jmx:rmi://

com.sun.identity.password.deploymentDescriptor Internal property used by OpenAM.

Default: *server-uri*, such as openam

com.sun.identity.policy.Policy.policy_evaluation_weights
Weights of the cost of evaluating policy subjects, rules, and conditions.
Evaluation is in order of heaviest weight to lightest weight.

Default: 10:10:10, meaning evaluation of rules, then conditions, then subjects

com.sun.identity.policy.resultsCacheMaxSize
Maximum number of policy decisions OpenAM caches.

Default: 10000

com.sun.identity.server.fqdnMap Enables virtual hosts, partial hostname and IP address. Maps invalid or virtual name keys to valid FQDN values for proper redirection.

To map myserver to myserver.example.com, set com.sun.identity.server.fqdnMap[myserver]=myserver.example.com.

com.sun.identity.session.repository.enableEncryption Enables tokens to be encrypted when stored.

Multi-instance deployments require consistent use of this property, which should be done under the Servers and Sites > Default Server Settings > Advanced.

The am.encryption.pwd property must also be the same for all deployed instances. The am.encryption.pwd is under Servers and Sites > Server > Security > Password Encryption Key. You will need to verify that all servers have the same setting for this property as the default server.

Default: false

com.sun.identity.urlchecker.dorequest

Whether to perform an HTTP GET on com.sun.identity.urlchecker.targeturl as a health check against another server in the same site. If false, then OpenAM only checks the Socket connection, and does not perform an HTTP GET.

If each OpenAM server runs behind a reverse proxy, then setting this property to true means the health check actually runs against the OpenAM instance, rather than checking only the Socket to the reverse proxy.

Default: false

com.sun.identity.urlchecker.targeturl

URL to monitor when com.sun.identity.urlchecker.dorequest is set to true.

Default: URL to the /openam/namingservice endpoint on the remote server

com.sun.identity.security.checkcaller

Whether to perform a Java security permissions check for OpenAM.

Default: false

com.sun.identity.session.repository.enableEncryption For CTS token encryption, if desired.

Default: false

com.sun.identity.session.repository.enableCompression For GZip-based compression of CTS tokens, if desired.

Default: false

com.sun.identity.session.repository.enableAttributeCompression
 For additional compression of CTS token JSON binaries, beyond GZip, if
 desired.

Default: false

com.sun.identity.sm.cache.ttl

When service configuration caching time-to-live is enabled, this sets the time to live in minutes.

Default: 30

com.sun.identity.sm.cache.ttl.enable

If service configuration caching is enabled, whether to enable a time-to-live for cached configuration.

Default: false

com.sun.identity.sm.flatfile.root dir

File system directory to hold file-based representation of OpenAM configuration.

Default: ~/openam/server-uri/sms such as ~/openam/openam/sms

com.sun.identity.sm.sms object class name

Class used to read and write OpenAM service configuration entries in the directory.

Default: com.sun.identity.sm.ldap.SMSEmbeddedLdapObject

com.sun.identity.url.readTimeout

Used to set the read timeout in milliseconds for HTTP and HTTPS connections to other servers.

Default: 30000

com.sun.identity.urlchecker.dorequest

Allows the OpenAM ClusterStateService to work with HTTPS endpoints.

Default: true

com.sun.identity.urlconnection.useCache

Whether to cache documents for HTTP and HTTPS connections to other servers.

Default: false

com.sun.identity.webcontainer

Name of the web container to correctly set character encoding, if necessary.

Default: WEB CONTAINER

console.privileged.users

Used to assigned privileged console access to particular users. Set to a | separated list of users' Universal IDs, such as console.privileged. users=uid=demo,ou=user,dc=openam,dc=forgerock,dc=org|uid=demo2,ou=user,dc=openam,dc=forgerock,dc=org.

openam.auth.destroy_session_after_upgrade

Where to destroy the old session after a session is successfully upgraded.

Default: true

openam.auth.distAuthCookieName

Cookie used by the OpenAM distributed authentication service to handle the authentication process.

Default: AMDistAuthCookie

openam.auth.session property upgrader

Class that controls which session properties are copied during session upgrade, where default is to copy all properties to the upgraded session.

Default: org.forgerock.openam.authentication.service. DefaultSessionPropertyUpgrader

openam.auth.version.header.enabled

The X-DSAMEVersion http header provides detailed information about the version of OpenAM currently running on the system, including the build and date/time of the build. OpenAM will need to be restarted once this property is enabled.

Default: false

openam.authentication.ignore goto during logout

Whether to ignore the goto query string parameter on logout, instead displaying the logout page.

Default: false

openam.cdm.default.charset

Character set used for globalization.

Default: UTF-8

openam.forbidden.to.copy.headers

Comma-separated list of HTTP headers not to copy when the distributed authentication server forwards a request to another distributed authentication server.

Default: connection

openam.forbidden.to.copy.request.headers

Comma-separated list of HTTP headers not to copy when the distributed authentication server forwards a request to another distributed authentication server.

Default: connection

openam.retained.http.headers

Comma-separated list of HTTP headers to copy to the forwarded response when the server forwards a request to another server.

Requests are forwarded when the server receiving the request is not the server that originally initiated authentication. The server that originally initiated authentication is identified by a cookie.

When the distributed authentication service (DAS) is in use, then the cookie is the AMDistAuthCookie that identifies the DAS server by its URL.

When authentication is done directly on OpenAM, then the cookie is the AMAuthCookie that holds a session ID that identifies the OpenAM server.

On subsequent requests the server receiving the request checks the cookie. If the cookie identifies another server, the current server forwards the request to that server.

If a header such as Cache-Control has been included in the list of values for the property openam.retained.http.request.headers and the header must also be copied to the response, then add it to the list of values for this property.

Example: openam.retained.http.headers=X-DSAMEVersion,Cache-Control

Default: X-DSAMEVersion

openam.retained.http.request.headers

Comma-separated list of HTTP headers to copy to the forwarded request when the server forwards a request to another server.

Requests are forwarded when the server receiving the request is not the server that originally initiated authentication. The server that originally initiated authentication is identified by a cookie.

When the distributed authentication service (DAS) is in use, then the cookie is the AMDistAuthCookie that identifies the DAS server by its URL.

When authentication is done directly on OpenAM, then the cookie is the AMAuthCookie that holds a session ID that identifies the OpenAM server.

On subsequent requests the server receiving the request checks the cookie. If the cookie identifies another server, the current server forwards the request to that server.

When configuring the distributed authentication service, or when a reverse proxy is set up to provide the client IP address in the X-Forwarded-For header, if your deployment includes multiple OpenAM servers, then this property must be set to include the header.

Example: openam.retained.http.request.headers=X-DSAMEVersion,X-Forwarded-For

OpenAM copies the header when forwarding a request to the authoritative server where the client originally began the authentication process, so that the authoritative OpenAM server receiving the forwarded request can determine the real client IP address.

In order to retain headers to return in the response to the OpenAM server that forwarded the request, use the property openam.retained.http.headers.

Servers and Sites Configuration

Default: X-DSAMEVersion

openam.session.allow_persist_am_cookie

If true users can extend the lifetime of the iplanetDirectoryPro cookie to com.iplanet.am.cookie.timeToLive on a per-session basis, by using the query string parameter openam.session.persist am cookie=Yes.

openam.session.case.sensitive.uuid

Whether universal user IDs are considered case sensitive when matching them.

Default: false

openam.session.persist am cookie

If true extend the lifetime of the iplanetDirectoryPro cookie to com.iplanet. am.cookie.timeToLive.

Default: false

openam.session.useLocalSessionsInMultiServerMode

This property is for use in multi-server deployments where session failover is not available. If true, calculate session quotas per server. In other words, if the session quota is 5 sessions and users can access up to 4 servers, they can have a maximum of 20 (5*4) sessions.

Default: false

opensso.protocol.handler.pkgs

If the web application containers sets java.protocol.handler.pkgs, then set this property to com.sun.identity.protocol.

org.forgerock.embedded.dsadminport

Administration port for embedded OpenDJ directory server.

Default: 4444

org.forgerock.openam.authentication.accountExpire.days

Days until account expiration set after successful authentication by the account expiration post authentication plugin.

Default: 30

securidHelper.ports

Port on which SecurID daemon listens.

Default: 58943

ssoadm.disabled

Set to false to enable ssoadm.jsp.

Servers and Sites Configuration

Default: true

Sites

Sites involve multiple OpenAM servers working together to provide services. You can use sites with load balancers and session failover to configure pools of servers capable of responding to client requests in highly available fashion.

Primary URL

Set the primary entry point to the site, such as the URL to the load balancer for the site configuration.

Secondary URLs

Set alternate entry points to the site. Used when session failover is configured.

Assigned Servers

Shows the list of OpenAM servers in the site.

Chapter 2 Log Files and Messages

This chapter gives information about the different log files and messages for OpenAM.

2.1 Log Files

This section describes the different OpenAM log files.

Administrative Log Files

Administrative logs record information on OpenAM events. You can adjust the amount of detail in the administrative logs under Configuration > System > Logging.

amAdmin.access

Contains log data about actions conducted by users logged in as amAdmin

amAdmin.error

Contains log data about errors encountered for users logged in as amAdmin

amAuthentication.access

Contains log data for when users log into and out of OpenAM, including failed authentications

amAuthentication.error

Contains \log data about errors encountered when users \log and out of OpenAM

175

amConsole.access

Contains data about actions run as the administrator in the console, including changes to realms and policies

amConsole.error

Contains data on errors encountered during administrator sessions

amPasswordReset.access

Contains data about password resets

amPolicv.access

Contains data about authorization actions permitted by policies, including policy creation, removal, or modification

amPolicy.error

Contains data on errors encountered during actions related to the policy

amPolicyDelegation.access

Contains data about actions as part of the policy delegation, including any changes to the delegation

amRemotePolicy.access

Contains data about policies accessed remotely

amSSO.access

Contains data about user sessions, including times of access, session time outs, and session creation/termination

CoreToken.access

Contains data about actions run against the core token

CoreToken.error

Contains data on errors encountered regarding the core token

COT.access

Contains data about the circle of trust

COT.error

Contains data on errors encountered for the circle of trust

Entitlement.access

Contains data about entitlement actions or changes

Federation.access

Contains data about federation events

Federation.error

Contains data on errors encountered while executing actions for federation

IDFF.access

Contains data about federation actions, including the creation of authentication domains or the hosted providers

IDFF.error

Contains data on errors encountered during federation actions

Liberty.access

Contains data about actions run for the federation Liberty schema

Liberty.error

Contains data on errors encountered for the federation Liberty schema

OAuth2Provider.access

Contains data about actions for the OAuth 2.0 provider

OAuth2Provider.error

Contains data about errors encountered by the OAuth 2.0 provider

SAML2.access

Contains data about SAML 2 actions, including changes to assertions, artifacts, response, and requests

SAML2.error

Contains data about errors encountered during SAML 2 actions

SAML.access

Contains data about SAML actions, including changes to assertions, artifacts, response, and requests

SAML.error

Contains data about errors encountered during SAML actions

ssoadm.access

Contains data about actions completed for SSO as admin

WebServicesSecurity.access

Contains data about activity for Web Services Security

WebServicesSecurity.error

Contains data on errors encountered by Web Services Security

WSFederation.access

Contains data about activity for WS Federation, including changes and access information

WSFederation.error

Contains data on errors encountered during WS Federation

Debug Log Files

Debug logs provide information that can help you troubleshoot. You can adjust the amount of detail in the debug logs under Configuration > System > Logging.

Authentication

Contains information about problems encountered during user authentication, including authentication services, framework, modules, callbacks, JAAS, and API

Configuration

Contains information about problems with the OpenAM configuration

CoreSystem

Contains information about problems specific to your core deployment of OpenAM that are not part of the authentication process or part of your current configuration, including core infrastructure services, PLL, cookies, naming, logging, and upgrades

Entitlement

Contains information about problems specific to entitlement

Federation

Contains information about problems specific to federation, including federated SSO, the federation protocols (SAML, SAML 2.0, ID-FF, and WS-Federation), metadata, hub, and circles of trust

IdRepo

Contains information about problems specific to the identity repository, including datastores and plugins

Policy

Contains information about problems specific to the policies you have setup, including policy framework, their subjects, conditions, resource attributes, plugins, and API

Session

Contains information about problems specific to OpenAM sessions, including session framework, management SSOToken, failover, and API

WebServices

Contains information about problems specific to Web Services, including STS and Identity Services

2.2 Log Messages

This section describes OpenAM log messages.

OpenAM logs the following COT messages.

INVALID COT NAME

ID: COT-1

Level: INFO

Description: Invalid circle of trust name.

Data: Realm or organization name, Circle of Trust Name

Triggers: Accessing the circle of trust.

Actions: Check the name and retry accessing the circle of trust.

CONFIG_ERROR_MODIFY_COT_DESCRIPTOR

ID: COT-2

Level: INFO

Description: Configuration error modifying the circle of trust.

Data: Error message, Name of the circle of trust, Realm or organization name

Triggers: Modifying the circle of trust.

Actions: Check COT debug, fmCOT, for more detailed error message.

CONFIG ERROR GET ALL COT DESCRIPTOR

ID: COT-3

Level: INFO

Description: Error retreiving all circle of trusts.

Data: Error message, Realm or organization name

Triggers: Getting all circle of trust.

Actions: Check configuration; check debug for more detailed error message.

NO COT NAME CREATE COT DESCRIPTOR

ID: COT-4

Level: INFO

Description: Invalid name, error creating the circle of trust.

Data: Realm or organization name

Triggers: Creating the circle of trust.

Actions: Check the name to create circle of trust descriptor.

COT EXISTS CREATE COT DESCRIPTOR

 $\overline{\text{ID}}$: COT- $\overline{5}$

Level: INFO

Description: Circle of Trust exists.

Data: Name of the circle of trust, Realm or organization name

Triggers: Creating the circle of trust.

Actions: Create Circle of Trust with a unique name.

INVALID COT TYPE

ID: COT-6

Level: INFO

Description: Circle of Trust Type is invalid

Data: Realm or organization name, Circle of Trust Type

Triggers: Creating the circle of trust.

Actions: The values for Circle of Trust type are IDFF , SAML2. Create Circle

of Trust using either of these values.

CONFIG_ERROR_CREATE_COT_DESCRIPTOR

ID: COT-7

Level: INFO

Description: Configuration error while creating circle of trust.

Data: Error message, Entity ID, Realm or organization name

Triggers: Create circle of trust.

Actions: Check the fmCOT debug file for detailed errors.

COT DESCRIPTOR CREATED

ID: COT-8

Level: INFO

Description: Circle of trust created.

Data: Name of the circle of trust, Realm or organization name

Triggers: Creating the circle of trust.

NULL_COT_NAME_ADD_COT_DESCRIPTOR

ID: COT-9

Level: INFO

Description: Circle of Trust name is null, error adding to circle of trust.

Data: Realm or organization name

Triggers: Adding to the circle of trust.

Actions: Check the name of the circle of trust.

NULL ENTITYID ADD COT DESCRIPTOR

ID: COT-10

Level: INFO

Description: Entity Identifier is null, cannot add entity to circle of trust

Data: Realm or organization name

Triggers: Adding to the circle of trust.

Actions: Check the value of entity id.

CONFIG ERROR ADD COT MEMBER

ID: COT-11

Level: INFO

Description: Error adding entity to the circle of trust.

Data: Error message, Name of the circle of trust, Entity Id, Realm or

organization name

Triggers: Adding entity to circle of trust.

Actions: Check COT debug for more detailed error message.

NO COT NAME REMOVE COT MEMBER

ID: COT-12

Level: INFO

Description: Null circle of trust name.

Data: Realm or organization name

Log Messages

Triggers: Removing member from the circle of trust.

Actions: Check the name of the circle of trust.

NULL ENTITYID REMOVE COT MEMBER

ID: COT-13

Level: INFO

Description: Null entity identifier.

Data: Name of the circle of trust, Realm or organization name

Triggers: Removing member from the circle of trust.

Actions: Check the value of the entity identifier.

CONFIG ERROR REMOVE COT MEMBER

ID: COT-14

Level: INFO

Description: Error while removing entity from the circle of trust.

Data: Error message, Name of the circle of trust, Entity Id, Realm or

organization name

Triggers: Removing entity identifier from the circle of trust.

Actions: Check COT debug for more detailed error message.

NULL_COT_NAME_LIST_COT ID: COT-15

Level: INFO

Description: Null circle of trust name.

Data: Realm or organization name

Triggers: Listing entities in Circle of Trust

Actions: Check the name of the circle of trust.

CONFIG_ERROR_LIST_COT_MEMBER

ID: COT-16

Level: INFO

Description: Error listing providers in the circle of trust.

Data: Error message, Name of the circle of trust, Realm or organization name

Triggers: Listing providers in the circle of trust.

Actions: Check COT debug for more detailed error message.

CONFIG ERROR DELETE COT DESCRIPTOR

ID: COT-17

Level: INFO

Description: Error while deleting the circle of trust.

Data: Error message, Name of the circle of trust, Realm or organization name

Triggers: Deleting the circle of trust.

Actions: Check COT debug for more detailed error message.

INVALID_NAME_ERROR_DELETE_COT_DESCRIPTOR

ID: COT-18

Level: INFO

Description: Invalid name, cannot delete circle of trust.

Data: Circle of Trust Name, Realm or organization name

Triggers: Deleting the circle of trust.

Actions: Check the circle of trust name and retry deletion.

HAS ENTITIES DELETE COT DESCRIPTOR

ID: COT-19

Level: INFO

Description: Cannot delete circle of trust which has entities.

Data: Circle of Trust Name, Realm or organization name

Triggers: Deleting the circle of trust.

Actions: Remove all entities from the circle of trust and retry deletion.

INVALID_COT_TYPE DELETE COT DESCRIPTOR

ID: COT-20

Level: INFO

Description: Invalid type cannot delete circle of trust.

Log Messages

Data: Realm or organization name, Circle of Trust Name, Circle of Trust Type

Triggers: Deleting the circle of trust.

Actions: Specify correct Circle of Trust type and retry delete.

COT DESCRIPTOR DELETED

ID: COT-21

Level: INFO

Description: Circle of trust deleted.

Data: Name of the circle of trust, Realm or organization name

Triggers: Deleting the circle of trust.

COT FROM CACHE

ID: COT-22

Level: FINE

Description: Retrieved the circle of trust from cache.

Data: Name of the circle of trust, Realm or organization name

Triggers: Retreived the circle of trust from cache.

CONFIG ERROR GET COT DESCRIPTOR

ID: COT-23

Level: INFO

Description: Error while getting the circle of trust from data store.

Data: Error message, Name of the circle of trust, Realm or organization name

Triggers: Retreiving the circle of trust

Actions: Check configuration; check debug for more detailed error message.

CONFIG ERROR RETREIVE COT

ID: COT-24

Level: INFO

Description: Error determining an entity is in a circle of trust.

Data: Error message, Name of the circle of trust, ID of an entity, Realm or organization name

Log Messages

Triggers: Determining an entity is in a circle of trust.

Actions: Check debug for more detailed error message.

COT DESCRIPTOR RETRIEVED

ID: COT-25

Level: INFO

Description: Retrieved the circle of trust descriptor.

Data: Name of the circle of trust, Realm or organization name

Triggers: Retrieving the circle of trust under a realm.

OpenAM logs the following IDFF messages.

WRITE ACCOUNT FED INFO

ID: IDFF-14

Level: INFO

Description: Write Account Federation Info

Data: user DN, federation info key, federation info value

Triggers: Acccount Federation Info with key was added to user

REMOVE ACCOUNT FED INFO

ID: IDFF-15

Level: INFO

Description: Remove Account Federation Info

Data: user DN, provider id, existing federation info key

Triggers: Account federation info with key and provider ID was removed from

user

CREATE ASSERTION

ID: IDFF-16

Level: FINER

Description: Create Assertion

Data: assertion id or string

Triggers: Assertion Created

LOGOUT_REQUEST_PROCESSING_FAILED

ID: IDFF-18

Level: INFO

Description: Logout Request processing failed.

Data: message

Triggers: Logout Request processing failed

TERMINATION REQUEST PROCESSING FAILED

ID: IDFF-19

Level: INFO

Description: Termination request processing failed

Data: message

Triggers: Termination request processing failed

FAILED_SOAP_URL_END_POINT CREATION

ID: ĪDFF-20

Level: INFO

Description: Failed in creating SOAP URL End point.

Data: soap end point url

Triggers: Failed in creating SOAP URL End point

MISMATCH AUTH TYPE AND PROTOCOL

ID: IDFF-21

Level: INFO

Description: Mismatched AuthType and the protocol (based on SOAPUrl).

Data: protocol, authentication type

Triggers: AuthType and the protocol (based on SOAPUrl) do not match.

WRONG AUTH TYPE

ID: IDFF-22

Level: INFO

Description: Wrong Authentication type

Data: authentication type

Triggers: Wrong Authentication type

SOAP_RECEIVER_URL

ID: IDFF-23

Level: FINER

Description: SAML SOAP Receiver URL

Data: soap url

Triggers: SAML SOAP Receiver URL

INVALID SOAP RESPONSE

ID: IDFF-24

Level: INFO

Description: SOAP Response is Invalid

Data: message

Triggers: SOAP Response is Invalid.

INVALID_ASSERTION

ID: IDFF-25

Level: INFO

Description: Assertion is invalid

Data: message

Triggers: This Assertion is invalid

 $SINGLE_SIGNON_FAILED$

ID: IDFF-26

Level: INFO

Description: Single SignOn Failed

Data: message

Triggers: Single SignOn Failed

ACCESS_GRANTED_REDIRECT_TO

ID: IDFF-27

Log Messages

Level: INFO

Description: Redirect to URL after granting access.

Data: redirect url

Triggers: Redirecting to URL after granting access.

MISSING_AUTHN_RESPONSE

ID: IDFF-28 Level: INFO

Description: Authentication Response is missing

Data: message

Triggers: Authentication Response not found

ACCOUNT_FEDERATION_FAILED

ID: IDFF-29

Level: INFO

Description: Account Federation Failed

Data: message

Triggers: Account Federation Failed

FAILED_SSO_TOKEN_GENERATION ID: IDFF-30

Level: INFO

Description: SSOToken Generation Failed

Data: message

Triggers: Failed to generate SSOToken

INVALID AUTHN RESPONSE

ID: IDFF-31

Level: INFO

Description: Authentication Response is invalid

Data: invalid authentication response

Triggers: Authentication Response is invalid

AUTHN_REQUEST_PROCESSING_FAILED

ID: ĪDFF-32

Level: INFO

Description: Authentication Request processing failed

Data: message

Triggers: Authentication Request processing failed.

SIGNATURE VERIFICATION FAILED

ID: IDFF-33

Level: INFO

Description: Signature Verification Failed.

Data: message

Triggers: Signature Verification Failed.

CREATE SAML RESPONSE

ID: IDFF-34

Level: INFO

Description: Created SAML Response

Data: sending saml response to remote server's IP address, saml response or

response ID and InResponseTo ID

Triggers: Created SAML Response

REDIRECT_TO

ID: IDFF-35

Level: FINER

Description: Redirect URL

Data: redirect url

Triggers: Redirect to:

COMMON DOMAIN META DATA NOT FOUND

ID: IDFF-36

Level: INFO

Description: Common Domain Service Information not found

Data: message

Triggers: Common Domain Service Information not found.

PROVIDER NOT TRUSTED

ID: IDFF-37

Level: INFO

Description: Provider is not trusted

Data: provider id

Triggers: Provider is not trusted.

INVALID AUTHN REQUEST

ID: IDFF-38

Level: INFO

Description: Authentication Request is invalid

Data: message

Triggers: Authentication Request is invalid

USER ACCOUNT FEDERATION INFO NOT FOUND

ID: IDFF-39

Level: INFO

Description: Account Federation Information not found for user

Data: user name

Triggers: Account Federation Information not found for user:

USER NOT FOUND

ID: IDFF-40

Level: INFO

Description: User not found.

Data: user name

Triggers: User not found.

LOGOUT PROFILE NOT SUPPORTED

ID: IDFF-41

Level: INFO

Description: Logout profile not supported.

Data: logout profile

Triggers: Logout profile not supported.

Actions: Verify metadata is correct.

LOGOUT SUCCESS

ID: IDFF-42

Level: INFO

Description: Logout is successful.

Data: user name

Triggers: Logout is successful.

LOGOUT REDIRECT FAILED

ID: IDFF-43

Level: INFO

Description: Logout failed to redirect due to incorrect URL.

Data: message

Triggers: Logout failed to redirect due to incorrect URL.

LOGOUT FAILED REQUEST IMPROPER

ID: IDFF-44

Level: INFO

Description: Logout request not formed properly.

Data: user name

Triggers: Logout request not formed properly.

LOGOUT_FAILED_INVALID_HANDLER

ID: IDFF-45

Level: INFO

Description: Failed to get Pre/Logout handler.

Data: logout url

Triggers: Failed to get Pre/Logout handler.

 $LOGOUT_FAILED$

ID: IDFF-46

Level: INFO

Description: Single logout failed.

Data: user name

Triggers: Single logout failed.

REGISTRATION_FAILED_SP_NAME_IDENTIFIER

ID: IDFF-47

Level: INFO

Description: Failed to create SPProvidedNameIdentifier.

Data: message

Triggers: Failed to create SPProvidedNameIdentifier.

INVALID SIGNATURE

ID: IDFF-48

Level: INFO

Description: Invalid Signature.

Data: message

Triggers: Invalid Signature.

TERMINATION FAILED

ID: IDFF-49

Level: INFO

Description: Federation Termination failed.

Data: user name

Triggers: Federation Termination failed. Cannot update account.

TERMINATION SUCCESS

ID: IDFF-50

Level: INFO

Description: Federation Termination succeeded.

Data: userDN

Triggers: Federation Termination succeeded. User account updated.

INVALID RESPONSE

ID: IDFF-51

Level: INFO

Description: Response is Invalid

Data: saml response

Triggers: SAML Response is Invalid.

INVALID PROVIDER

ID: IDFF-52

Level: INFO

Description: Invalid Provider Registration.

Data: provider id, Realm or Organization Name

Triggers: Invalid Provider.

ERROR GET IDFF META INSTANCE

ID: IDFF-61

Level: INFO

Description: Error getting Configuration instance.

Data: message

Triggers: Trying to initialize IDFF Metadata configuration.

Actions: Check if the Data Repository has the IDFFMetaData Service. If it is not present then it wil need to be loading using the FM Administration command. Check the Administration Guide on how to load services.

NULL ENTITY DESCRIPTOR

ID: IDFF-62

Level: INFO

Description: EntityDescriptor is null.

Data: message

Triggers: Trying to create EntityDescriptor.

Actions: Pass a valid non-null EntityDescriptorElement object to the IDFFMetaManager:createEntityDescriptor method.

NULL_ENTITY_ID ID: IDFF-63

Level: INFO

Description: Entity Identifier in the EntityDescriptor is null.

Data: message

Triggers: Trying to create, modify, retrieve or delete EntityDescriptor or extended Entity Config.

Actions: The EntityDescriptor Element passed should have the Entity Identifier , this is the "providerID" attribute in the IDFF MetaData schema.

CREATE ENTITY SUCCEEDED

ID: IDFF-64

Level: INFO

Description: Creating of Entity Descriptor succeeded.

Data: Entity ID, Realm or Organization Name

Triggers: EntityDescriptor is stored in the data repository.

CREATE ENTITY FAILED

ID: IDFF-65

Level: INFO

Description: Storing of IDFF Meta Data in the repository failed.

Data: Entity ID, Realm or Organization Name

Triggers: Trying to create EntityDescriptor.

Actions: Check the IDFF Meta Data Debug "libIDFFMeta" for specific errors. Check if the data repository exists and is accessible. Check if the IDFF Meta Data Service exists in the data repository.

UNSUPPORTED OPERATION

ID: IDFF-66

Level: INFO

Description: Unsupported operation.

Data: message

Triggers: Trying to create, modify or delete EntityDescriptor or extended EntityConfig.

Actions: Check the System Configuration Implementation to find out how IDFF Meta Data can be stored in the repository.

INVALID ENTITY DESCRIPTOR

ID: IDFF-67

Level: INFO

Description: The EntityDescriptor object is not valid.

Data: Entity ID, Realm or Organization Name

Triggers: Trying to retrieve or modify EntityDescriptor.

Actions: Check the EntityDescriptor Element is valid and follows the IDFF Standard Meta Data Schema Description.

GET ENTITY FAILED

ID: IDFF-68

Level: INFO

Description: Retrieval of Entity Configuration failed.

Data: Entity ID, Realm or Organization Name

Triggers: EntityDescriptor is retrieved.

Actions: Check if the entity identifier is correct.

GET ENTITY SUCCEEDED

ID: IDFF-69

Level: INFO

Description: Retrieval of Entity Descriptor succeeded.

Data: Entity ID, Realm or Organization Name

Triggers: Entity Configuration is returned to the requester.

SET ENTITY FAILED

ID: IDFF-70

Level: INFO

Description: Storing of Entity Configuration failed.

Data: Entity ID, Realm or Organization Name

Triggers: Trying to modify IDFF Standard Meta data.

Actions: Check if the entity identifier is correct.; Check if the data repository exists and is accessible.

SET ENTITY SUCCEEDED

ID: IDFF-71

Level: INFO

Description: Modifying Entity Descriptor succeeded.

Data: Entity ID, Realm or Organization Name

Triggers: Entity Descriptor is modified in the data repository.

DELETE ENTITY SUCCEEDED

ID: IDFF-72

Level: INFO

Description: Deleting of IDFF Standard Meta Data succeeded.

Data: Entity ID, Realm or Organization Name

Triggers: IDFF Standard Meta data for the entity is deleted in the data

repository.

DELETE_ENTITY FAILED

ID: IDFF-73

Level: INFO

Description: Deleting of Standard Metadata for entity identifier failed.

Data: Entity ID, Realm or Organization Name

Triggers: Trying to delete IDFF Standard Meta data for the entity.

Actions: Check if the entity identifier is correct.; Check if the data repository

exists and is accessible

NULL ENTITY CONFIG

ID: IDFF- $7\overline{4}$

Log Messages

Level: INFO

Description: Extended Entity Configuration is null.

Data: message

Triggers: Trying to create IDFF extended Meta data.

Actions: Check the validity of the extended entity configuration.

ENTITY_CONFIG_NOT_FOUND

ID: IDFF-75

Level: INFO

Description: Entity Configuration could not be found.

Data: Entity ID, Realm or Organization Name

Triggers: Trying to create IDFF extended Meta data.

Actions: Check the validity of the entity configuration.

ENTITY CONFIG EXISTS

ID: IDFF-76

Level: INFO

Description: Creation of Extended Entity Configuration failed since it already exists.

Data: Entity ID, Realm or Organization Name

Triggers: Trying to create IDFF extended Meta data.

Actions: Cannot create entity configuration if it already exists. If new attributes are to be set in the extended entity configuration then use the setConfiguration method or delete the existing entity configuration and then try create again.

GET ENTITY CONFIG FAILED

ID: IDFF-77

Level: INFO

Description: Failed to get entity configuration.

Data: Entity ID, Realm or Organization Name

Triggers: Trying to retrieve IDFF extended Meta data.

Actions: Check the IDFF Meta Data Debug "libIDFFMeta" for specific errors.

GET ENTITY CONFIG SUCCEEDED

ID: IDFF-78

Level: INFO

Description: Retrieval of Entity Configuration succeeded.

Data: Entity ID, Realm or Organization Name

Triggers: Entity Configuration is retrieved from the data repository

SET_ENTITY_CONFIG_SUCCEEDED

ID: IDFF-79

Level: INFO

Description: Extended Entity Configuration was modified.

Data: Entity ID, Realm or Organization Name

Triggers: Extended Entity Configuration is modified in the data repository

SET ENTITY CONFIG FAILED

ID: IDFF-80

Level: INFO

Description: Failed to modify Extended Entity Configuration.

Data: Entity ID, Realm or Organization Name

Triggers: Extended Entity Configuration is modified in the data repository

Actions: Check the IDFF Meta Data Debug "libIDFFMeta" for specific errors.

CREATE ENTITY CONFIG SUCCEEDED

ID: IDFF-81

Level: INFO

Description: Extended Entity Configuration was created.

Data: Entity ID, Realm or Organization Name

Triggers: Extended Entity Configuration is stored in the data repository

CREATE ENTITY CONFIG FAILED

ID: IDFF-82

Level: INFO

Description: Storing of IDFF Extended Configuration in the repository failed.

Data: Entity ID, Realm or Organization Name

Triggers: Trying to create Extended Entity Configuration.

Actions: Check the IDFF Meta Data Debug "libIDFFMeta" for specific errors.; Check if the data repository exists and is accessible.; Check if the IDFF Meta Data Service exists in the data repository.

INVALID ENTITY CONFIG

ID: IDFF-83

Level: INFO

Description: The Extended Entity Configuration is invalid.

Data: Entity ID, Realm or Organization Name

Triggers: Trying to create, modify or retrieve Extended Entity Configuration.

Actions: Check the Extended Entity Configuration is valid and retry creating the entity config.

GET_ALL_ENTITIES_SUCCEEDED

ID: IDFF-84

Level: INFO

Description: Retrieve all Entity Descriptors succeeded.

Data: message

Triggers: Retrieve all Entity Descriptors

GET ALL ENTITIES FAILED

ID: IDFF-85

Level: INFO

Description: Failed to get all Entity Descriptors.

Data: message

Triggers: Retrieve all Entity Descriptors

Actions: Check the IDFF Meta Data Debug "libIDFFMeta" for specific errors.; Check if the data repository exists and is accessible.; Check if the IDFF Meta Data Service exists in the data repository.

GET_ENTITY_NAMES_SUCCEEDED

ID: IDFF-86

Level: INFO

Description: Retrieve names of all Entities.

Data: message

Triggers: Retrieve names of all Entities.

GET ENTITY NAMES FAILED

ID: IDFF-87

Level: INFO

Description: Failed to get names for all Entities.

Data: message

Triggers: Retrieving names of all Entities.

Actions: Check the IDFF Meta Data Debug "libIDFFMeta" for specific errors.; Check if the data repository exists and is accessible.; Check if the IDFF Meta Data Service exists in the data repository.

GET_HOSTED_ENTITIES_SUCCEEDED

ID: IDFF-88

Level: INFO

Description: Retrieve all hosted Entities succeeded.

Data: message

Triggers: Retrieving all hosted Entities.

GET HOSTED ENTITIES FAILED

ID: IDFF-89

Level: INFO

Description: Failed to get all hosted Entities.

Data: message

Triggers: Retrieving all hosted Entities.

Actions: Check the IDFF Meta Data Debug "libIDFFMeta" for specific errors.; Check if the data repository exists and is accessible.; Check if the IDFF Meta Data Service exists in the data repository.

GET_REMOTE_ENTITIES_SUCCEEDED

ID: IDFF-90

Level: INFO

Description: Retrieval of all remote Entities succeeded.

Data: message

Triggers: Retrieve all remote Entities.

GET REMOTE ENTITIES FAILED

ID: IDFF-91

Level: INFO

Description: Failed to get all remote Entities.

Data: message

Triggers: Retrieving all remote Entities.

Actions: Check the IDFF Meta Data Debug "libIDFFMeta" for specific errors.; Check if the data repository exists and is accessible.; Check if the IDFF Meta

Data Service exists in the data repository.

GET_HOSTED_SERVICE_PROVIDERS_SUCCEEDED

ID: IDFF-92

Level: INFO

Description: Retrieval of all hosted services providers succeeded.

Data: message

Triggers: Retrieving all hosted services providers.

GET REMOTE SERVICE PROVIDERS SUCCEEDED

ID: IDFF-93

Level: INFO

Description: Retrieval of all remote services providers succeeded.

Data: message

Triggers: Retrieve all remote services providers.

GET HOSTED IDENTITY PROVIDERS SUCCEEDED

ID: IDFF-94

Log Messages

Level: INFO

Description: Retrieval of all hosted identity providers succeeded.

Data: message

Triggers: Retrieve all hosted identity providers.

GET_REMOTE_IDENTITY_PROVIDERS_SUCCEEDED

ID: IDFF-95

Level: INFO

Description: Retrieval of all remote identity providers succeeded.

Data: message

Triggers: Retrieve all remote identity providers.

IS AFFILIATE MEMBER SUCCEEDED

ID: IDFF-96

Level: INFO

Description: Checking Affiliation member succeeded.

Data: Entity ID, Affiliation ID, Realm or Organization Name

Triggers: Checks if the provider is a member of the Affiliation.

NO_ENTITY_CONFIG_TO_DELETE ID: IDFF-97

Level: INFO

Description: No entity configuration to delete.

Data: Entity ID, Realm or Organization Name

Triggers: Delete Entity Configuration.

Actions: Check the entityID to make sure the Entity Configuration does exist.

DELETE_ENTITY_CONFIG FAILED

ID: IDFF-98

Level: INFO

Description: Failed to delete entity configuration.

Data: Entity ID, Realm or Organization Name

Triggers: Delete Entity Configuration.

Actions: Check the IDFF Meta Data Debug "libIDFFMeta" for specific errors.; Check if the data repository exists and is accessible.; Check if the IDFF Meta Data Service exists in the data repository.

DELETE ENTITY CONFIG SUCCEEDED

ID: IDFF-99

Level: INFO

Description: Entity configuration deleted successfully.

Data: Entity ID, Realm or Organization Name

Triggers: Delete Entity Configuration.

ENTITY DOES NOT EXISTS

ID: IDFF-100

Level: INFO

Description: Entity does not exist.

Data: Entity ID, Realm or Organization Name

Triggers: Delete Entity Descriptor.

Actions: Check to make sure you have the right entity ID.; Check if the data repository exists and is accessible.; Check if the IDFF Meta Data Service exists in the data repository.

CREATE_AUTHN_RESPONSE

ID: IDFF-101

Level: INFO

Description: Created Authn Response

Data: saml response or response ID and InResponseTo ID

Triggers: Created SAML Response

SENT AUTHN RESPONSE

ID: IDFF-102

Level: INFO

Description: Sent Authn Response

Data: Service provider's assertion consumer service URL, response ID and InResponseTo ID

Triggers: Sent Authn Response

OpenAM logs the following LIBERTY messages.

AS Abort

ID: LIBERTY-1

Level: INFO

Description: Unable to process SASL Request

Data: message id, authentication mechanism, authorization id, advisory

authentication id

Triggers: Unable to process SASL Request.

AS OK

ID: LIBERTY-2

Level: INFO

Description: SASL Response Ok

Data: message id, authentication mechanism, authorization id, advisory

authentication id

Triggers: SASL Response Ok.

AS Continue

ID: LIBERTY-3

Level: INFO

Description: Return SASL Authenticaton Response

Data: message id, authentication mechanism, authorization id, advisory

authentication id

Triggers: Returned SASL Response, continue Authentication.

DS Lookup Failure

ID: LIBERTY-4

Level: INFO

Description: User not found in Data store

Data: user name

Triggers: User not found in Data store

DS_Lookup_Success ID: LIBERTY-5

Level: INFO

Description: User found in Data Store

Data: user name

Triggers: User found in Data Store

DS_Update_Failure ID: LIBERTY-6

Level: INFO

Description: Cannot locate user from resourceID

Data: resourceID

Triggers: Cannot locate user from resourceID

DS_Update_Success ID: LIBERTY-7

Level: INFO

Description: Successfully updated user profile

Data: user name

Triggers: Successfully updated user profile

PP_Query_Failure ID: LIBERTY-8

Level: INFO

Description: UnAuthorized. Failed to Query Personal Profile Service

Data: resource id

Triggers: Failed to Query Personal Profile Service

PP_Interaction_Failure

ID: LIBERTY-9

Level: INFO

Log Messages

Description: Interaction Failed

Data: resource id

Triggers: Interaction with Personal Profile Service Failed

 $PP_Query_Success$

ID: LIBERTY-10

Level: INFO

Description: Successfully queried PP Service

Data: resource id

Triggers: Personal Profile Service Query Succeeded

 $PP_Modify_Failure$

ID: LIBERTY-11

Level: INFO

Description: Modify Failure

Data: resource id

Triggers: Failed to modify Personal Profile Service

PP_Modify_Success

ID: LIBERTY-12

Level: INFO

Description: Modify Success

Data: resource id

Triggers: Personal Profile Service Successfully modified.

 $PP_Interaction_Success$

ID: LIBERTY-13

Level: INFO

Description: Interaction Successful

Data: successful interaction message

Triggers: Successful interaction with Personal Profile Service

 $IS_Sending_Message$

ID: LIBERTY-14

Level: INFO

Description: Sending Message

Data: request message id

Triggers: Sending SOAP Request Message to WSP.

IS_Returning_Response_Message

ID: LIBERTY-15

Level: INFO

Description: Returning Response Message

Data: response message id, request message id

Triggers: Returning Response Message for SOAP Request.

 $IS_Resending_Message$

ID: LIBERTY-16

Level: INFO

Description: Resending Message

Data: message id

Triggers: Resending SOAP Request Message to WSP

IS Redirected User Agent

ID: LIBERTY-17

Level: INFO

Description: Interaction manager redirecting user agent to interaction

service

Data: request message id

Triggers: Interaction manager redirecting user agent to interaction service

IS Returning Response Element

ID: LIBERTY-18

Level: INFO

Description: Interaction manager returning response element

Data: message id, reference message id, cache entry status

Triggers: Interaction manager returning response element

 $IS_Presented_Query_To_User_Agent$

ID: LIBERTY-19

Level: INFO

Description: Interaction query presented to user agent

Data: message id

Triggers: Interaction query presented to user agent

IS Collected Response From User Agent

ID: LIBERTY-20

Level: INFO

Description: User agent responded to interaction query

Data: message id

Triggers: User agent responded to interaction query

IS Redirected User Agent Back

ID: LIBERTY-21

Level: INFO

Description: User agent redirected back to SP

Data: message id

Triggers: User agent redirected back to SP

WS Success

ID: LIBERTY-22

Level: INFO

Description: Webservices Success

Data: message id, handler key

Triggers: Webservices success.

WS Failure

ID: LIBERTY-23

Level: INFO

Description: Webservices Failure

Data: error message

Triggers: Webservices Failure.

OpenAM logs the following SAML2 messages.

INVALID SP

ID: SAML2-1

Level: INFO

Description: Invalid Service Provider Identifier

Data: Service Provider Entity Identifier

Triggers: Invalid Service Provider, cannot process request

Actions: Check the Service Provider Name.

INVALID IDP

ID: SAML2-2

Level: INFO

Description: Invalid Identity Provider Identifier

Data: Identity Provider Entity Identifier

Triggers: Invalid Identity Provider, cannot process request

Actions: Check the Identity Provider Name.

SP METADATA ERROR

ID: SAML2-3

Level: INFO

Description: Unable to retreive Service Provider Metadata.

Data: Service Provider Entity Identifier

Triggers: Cannot retrieve Service Provider Metadata

Actions: Check the Data Store is accessible .; Check the Realm name.; Check

the Service Provider Entity Identifier.

IDP METADATA ERROR

ID: SAML2-4

Level: INFO

Description: Unable to retrieve Identity Provider Metadata.

Data: Identity Provider Entity Identifier

Triggers: Cannot retreive Identity Provider Metadata

Actions: Check the Data Store is accessible .; Check the Realm name.; Check the Identity Provider Entity Identifier.

SSO_NOT_FOUND

ID: SAML2-5

Level: INFO

Description: Unable to retrieve SingleSignOnService URL.

Data: Identity Provider Entity Identifier

Triggers: Error retreiving SingleSignOnService URL.

Actions: Check the Data Store is accessible .; Check the Realm name.; Check the Identity Provider Entity Identifier.

REDIRECT_TO_SP

ID: SAML2-6

Level: INFO

Description: Redirecting to SingleSignOnService

Data: SingleSignOnService URL

Triggers: Sending Authentication Request by redirecting to Single SignOn Service URL.

RESPONSE NOT FOUND FROM CACHE

ID: SAML2-7

Level: INFO

Description: Unable to retrieve Response using Response ID after local login.

Data: Response ID

Triggers: Response doesn't exist in the SP cache.

Actions: Check the SP cache clean up interval configuration.

MISSING_ARTIFACT

ID: SAML2-8

Level: INFO

Description: Unable to retrieve Artifact from HTTP Request.

Triggers: SAMLart is missing from HTTP Request

Actions: Check with sender.; Check web container server log.

RECEIVED ARTIFACT

ID: SAML2-9

Level: INFO

Description: Received Artifact from HTTP Request.

Data: Artifact value

Triggers: Received Artifact from HTTP Request in the process of Single Sign

On using Artifact Profile.

IDP NOT FOUND

ĪD: SĀML2-10

Level: INFO

Description: Unable to find Identity Provider Entity ID based on the SourceID

in Artifact.

Data: Artifact value, Realm or organization name

Triggers: No matching Identity Provider Entity ID found in meta data

configuration.

Actions: Check if Identity Provider's meta data is loaded.

IDP META NOT FOUND

ID: SAML2-11

Level: INFO

Description: Unable to load Identity Provider's meta data.

Data: Realm or organization name, Identity Provider Entity ID

Triggers: Unable to load Identity Provider's meta data.

Actions: Check Identity Provider Entity ID.; Check Realm or organization

name.; Check if the identity provider's meta is loaded.

ARTIFACT_RESOLUTION_URL_NOT_FOUND

ID: SAML2-12

Level: INFO

Description: Unable to find Identity Provider's Artifact resolution service

URL.

Data: Identity Provider Entity ID

Triggers: Artifact resolution service URL is not defined in Identity Provider's

metadata.

Actions: Check Identity Provider's meta data.

CANNOT_CREATE_ARTIFACT_RESOLVE

ID: SAML2-13

Level: INFO

Description: Unable to create ArtifactResolve.

Data: Hosted Service Provider Entity ID, Artifact value

Triggers: Error when creating ArtifactResolve instance.

Actions: Check implementation of ArtifactResolve.

CANNOT GET SOAP RESPONSE

ID: SAML2-14

Level: INFO

Description: Unable to obtain response from SOAP communication with Identity Provider's artifact resolution service.

Data: Hosted Service Provider Entity ID, Identity Provider's Artifact Resolution Service URL

Triggers: Error in SOAP communication.

Actions: Check Identity Provider's Artifact Resolution Service URL.; Check SOAP message authentication requirements for Identity Provider's Artifact Resolution Service.

GOT RESPONSE FROM ARTIFACT

ID: SAML2-15

Level: INFO

Description: Obtained response using artifact profile.

Data: Hosted Service Provider Entity ID, Remote Identity Provider Entity ID, Artifact value, Response xml String if the log level was set to LL_FINE at run time

Triggers: Single Sign On using Artifact Profile.

SOAP ERROR

ID: SAML2-16

Level: INFO

Description: Unable to obtain Artifact Response due to SOAP error.

Data: Identity Provider Entity ID

Triggers: Error in SOAP communication.

Actions: Check configuration for Identity Provider

SOAP FAULT

ID: SAML2-17

Level: INFO

Description: Received SOAP Fault instead of Artifact Response.

Data: Identity Provider Entity ID

Triggers: Error in Identity Provider's Artifact Resolution.

Actions: Check Identity Provider; Check debug file for detailed fault info.

TOO MANY ARTIFACT RESPONSE

ID: SAML2-18

Level: INFO

Description: Received too many Artifact Response.

Data: Identity Provider Entity ID

Triggers: Identity Provider sent more than one Artifact Response in

SOAPMessage.

Actions: Check Identity Provider

CANNOT INSTANTIATE ARTIFACT RESPONSE

ID: SAML2-19

Log Messages

Description: Unable to instantiate Artifact Response.

Data: Identity Provider Entity ID

Triggers: Error while instantiating Artifact Response.

Actions: Check Identity Provider; Check debug message for detailed error.

MISSING ARTIFACT RESPONSE

ID: SAML2-20

Level: INFO

Description: Unable to obtain Artifact Response from SOAP message.

Data: Identity Provider Entity ID

Triggers: No ArtifactResponse is included in SOAPMessage.

Actions: Check Identity Provider

ARTIFACT RESPONSE INVALID SIGNATURE

ID: SAML2-21

Level: INFO

Description: Unable to verify signature on Artifact Response.

Data: Identity Provider Entity ID

Triggers: Error while trying to verify signature on ArtifactResponse.

Actions: Check configuration for Identity Provider; Check debug file for

detailed info

ARTIFACT RESPONSE INVALID INRESPONSETO

ID: SAML2-22

Level: INFO

Description: Invalid InResponseTo attribute in Artifact Response.

Data: Identity Provider Entity ID

Triggers: InResponseTo attribute in Artifact Response is missing or doesn't

match with Artifact Resolve ID.

Actions: Check with Identity Provider

ARTIFACT RESPONSE INVALID ISSUER

ID: SAML2-23

Level: INFO

Description: Invalid Issuer in Artifact Response.

Data: Identity Provider Entity ID

Triggers: Issuer in Artifact Response is missing or doesn't match with

Identity Provider Entity ID.

Actions: Check with Identity Provider

ARTIFACT RESPONSE INVALID STATUS CODE

ID: SAML2-24

Level: INFO

Description: Invalid status code in Artifact Response.

Data: Identity Provider Entity ID, Status code if the log level was set to

LL FINE at runtime

Triggers: Status in Artifact Response is missing or status code is not Success.

Actions: Check with Identity Provider

CANNOT INSTANTIATE RESPONSE ARTIFACT

ID: SAML2-25

Level: INFO

Description: Unable to instantiate Respones from Artifact Response.

Data: Identity Provider Entity ID

Triggers: Error occurred while instantiating Response.

Actions: Check debug file for detailed error.

MISSING_SAML RESPONSE FROM POST

ID: SAML2-26

Level: INFO

Description: SAML Response is missing from http post.

Triggers: Parameter SAMLResponse is missing from http POST.

CANNOT INSTANTIATE RESPONSE POST

ID: SAML2-27

Log Messages

Description: Unable to instantiate Response from POST.

Triggers: Error occurred while instantiating Response.

Actions: Check debug file for more info

CANNOT_DECODE_RESPONSE

ID: SAML2-28

Level: INFO

Description: Unable to decode Response.

Triggers: Error occurred while decoding Response.

Actions: Check debug file for more info

GOT_RESPONSE_FROM POST

ID: SAML2-29

Level: INFO

Description: Obtained response using POST profile.

Data: Response xml String if the log level was set to LL FINE at runtime

Triggers: Single Sign On using POST Profile.

FED INFO WRITTEN

ID: SAML2-30

Level: INFO

Description: Written federation info.

Data: Username, NameIDInfo value string if the log level was set to LL FINE

at runtime

Triggers: Federation is done.

REDIRECT TO IDP

ID: SAML2-31

Level: INFO

Description: Redirect request to IDP.

Data: redirection url

Triggers: Single logout.

NO_ACS_URL ID: SAML2-32

Level: INFO

Description: Unable to find Assertion Consumer Service URL.

Data: meta alias

Triggers: Single Sign On.

NO RETURN BINDING

ID: SAML2-33

Level: INFO

Description: Unable to find return binding.

Data: meta alias

Triggers: Single Sign On.

POST_TO_TARGET_FAILED

ID: SAML2-34

Level: INFO

Description: Unable to post the response to target.

Data: Assertion Consumer Service URL

Triggers: Single Sign On with POST binding.

CANNOT CREATE ARTIFACT

ID: SAML2-35

Level: INFO

Description: Unable to create an artifact.

Data: IDP entity ID

Triggers: Single Sign On with Artifact binding.

RECEIVED_AUTHN_REQUEST

ID: SAML2-36

Level: INFO

Description: Received AuthnRequest.

Data: SP entity ID, IDP meta alias, authnRequest xml string

Triggers: Single Sign On.

POST_RESPONSE ID: SAML2-37

Level: INFO

Description: Post response to SP.

Data: SP entity ID, IDP meta alias, response xml string

Triggers: Single Sign On with POST binding.

SEND ARTIFACT

ID: SAML2-38

Level: INFO

Description: Send an artifact to SP.

Data: IDP entity ID, IDP realm, redirect URL

Triggers: Single Sign On with Artifact binding.

INVALID SOAP MESSAGE

ID: SAML2-39

Level: INFO

Description: Encounter invalid SOAP message in IDP.

Data: IDP entity ID

Triggers: Single Sign On with Artifact binding.

ARTIFACT RESPONSE

ID: SAML2-40

Level: INFO

Description: The artifact response being sent to SP.

Data: IDP entity ID, artifact string, artifact response

Triggers: Single Sign On with Artifact binding.

GOT ENTITY DESCRIPTOR

ID: SAML2-41

Level: FINE

Description: Entity descriptor obtained.

Data: Entity ID, Realm or organization name

Triggers: Obtain entity descriptor.

INVALID_REALM_GET_ENTITY_DESCRIPTOR

ID: SAML2-42

Level: INFO

Description: Invaid realm while getting entity descriptor.

Data: Realm or organization name

Triggers: Obtain entity descriptor.

Actions: Check the Realm name.

GOT INVALID ENTITY DESCRIPTOR

ID: SAML2-43

Level: INFO

Description: Obtained invalid entity descriptor.

Data: Entity ID, Realm or organization name

Triggers: Obtain entity descriptor.

Actions: Delete invalid entity descriptor and import it again.

CONFIG_ERROR_GET_ENTITY_DESCRIPTOR

ID: $\overline{SAML2-44}$

Level: INFO

Description: Configuration error while getting entity descriptor.

Data: Error message, Entity ID, Realm or organization name

Triggers: Obtain entity descriptor.

Actions: Check debug message for detailed error.

NO_ENTITY_ID_SET_ENTITY_DESCRIPTOR

ID: SAML2-45

Log Messages

Description: No entity ID while setting entity descriptor.

Data: Realm or organization name

Triggers: Set entity descriptor.

Actions: Set entity ID in entity descriptor.

INVALID_REALM_SET_ENTITY_DESCRIPTOR

ID: SAML2-46

Level: INFO

Description: Invaid realm while setting entity descriptor.

Data: Realm or organization name

Triggers: Set entity descriptor.

Actions: Check the Realm name.

NO ENTITY DESCRIPTOR SET ENTITY DESCRIPTOR

ID: SAML2-47

Level: INFO

Description: Entity descriptor doesn't exist while setting entity descriptor.

Data: Entity ID, Realm or organization name

Triggers: Set entity descriptor.

Actions: Create entity descriptor before set.

SET ENTITY DESCRIPTOR

ĪD: SAMLZ-48

Level: INFO

Description: Entity descriptor was set.

Data: Entity ID, Realm or organization name

Triggers: Set entity descriptor.

CONFIG_ERROR_SET_ENTITY_DESCRIPTOR

ID: SAML2-49

Level: INFO

Description: Configuration error while setting entity descriptor.

Data: Error message, Entity ID, Realm or organization name

Triggers: Set entity descriptor.

Actions: Check debug message for detailed error.

SET INVALID ENTITY DESCRIPTOR

ID: SAML2-50

Level: INFO

Description: Invalid entity descriptor to set.

Data: Entity ID, Realm or organization name

Triggers: Set entity descriptor.

Actions: Check entity descriptor if it follows the schema.

NO ENTITY ID CREATE ENTITY DESCRIPTOR

ID: SAML2-51

Level: INFO

Description: No entity ID while creating entity descriptor.

Data: Realm or organization name

Triggers: Create entity descriptor.

Actions: Set entity ID in entity descriptor.

INVALID REALM CREATE ENTITY DESCRIPTOR

ID: SAML2-52

Level: INFO

Description: Invaid realm while creating entity descriptor.

Data: Realm or organization name

Triggers: Create entity descriptor.

Actions: Check the Realm name.

ENTITY DESCRIPTOR EXISTS

ID: SAML2-53

Level: INFO

Description: Entity descriptor exists while creating entity descriptor.

Log Messages

Data: Entity ID, Realm or organization name

Triggers: Create entity descriptor.

Actions: Delete existing entity descriptor first.

ENTITY DESCRIPTOR CREATED

ID: SAML2-54

Level: INFO

Description: Entity descriptor was created.

Data: Entity ID, Realm or organization name

Triggers: Create entity descriptor.

CONFIG ERROR CREATE ENTITY DESCRIPTOR

ID: SAML2-55

Level: INFO

Description: Configuration error while creating entity descriptor.

Data: Error message, Entity ID, Realm or organization name

Triggers: Create entity descriptor.

Actions: Check debug message for detailed error.

CREATE INVALID ENTITY DESCRIPTOR

ID: SAML2-56

Level: INFO

Description: Invalid entity descriptor to create.

Data: Entity ID, Realm or organization name

Triggers: Create entity descriptor.

Actions: Check entity descriptor if it follows the schema.

INVALID REALM DELETE ENTITY DESCRIPTOR

ID: SAML2-57

Level: INFO

Description: Invaid realm while deleting entity descriptor.

Data: Realm or organization name

Triggers: Delete entity descriptor.

Actions: Check the Realm name.

NO ENTITY DESCRIPTOR DELETE ENTITY DESCRIPTOR

ID: SAML2-58

Level: INFO

Description: Entity descriptor doesn't exist while deleting entity descriptor.

Data: Entity ID, Realm or organization name

Triggers: Delete entity descriptor.

ENTITY DESCRIPTOR DELETED

ID: SAML2-59

Level: INFO

Description: Entity descriptor was deleted.

Data: Entity ID, Realm or organization name

Triggers: Delete entity descriptor.

CONFIG ERROR DELETE ENTITY DESCRIPTOR

ID: SAML2-60

Level: INFO

Description: Configuration error while deleting entity descriptor.

Data: Error message, Entity ID, Realm or organization name

Triggers: Delete entity descriptor.

Actions: Check debug message for detailed error.

GOT ENTITY CONFIG

ID: SAML2-61

Level: FINE

Description: Entity config obtained.

Data: Entity ID, Realm or organization name

Triggers: Obtain entity config.

INVALID REALM GET ENTITY CONFIG

ID: SAML2-62

Level: INFO

Description: Invaid realm while getting entity config.

Data: Realm or organization name

Triggers: Obtain entity config.

Actions: Check the Realm name.

GOT_INVALID_ENTITY_CONFIG

ID: SAML2-63

Level: INFO

Description: Obtained invalid entity config.

Data: Entity ID, Realm or organization name

Triggers: Obtain entity config.

Actions: Delete invalid entity config and import it again.

CONFIG ERROR GET ENTITY CONFIG

ID: SAML2-64

Level: INFO

Description: Configuration error while getting entity config.

Data: Error message, Entity ID, Realm or organization name

Triggers: Obtain entity config.

Actions: Check debug message for detailed error.

NO_ENTITY_ID_SET_ENTITY_CONFIG

ID: SAML2-65

Level: INFO

Description: No entity ID while setting entity config.

Data: Realm or organization name

Triggers: Set entity config.

Actions: Set entity ID in entity config.

INVALID REALM SET ENTITY CONFIG

ID: SAML2-66

Level: INFO

Description: Invaid realm while setting entity config.

Data: Realm or organization name

Triggers: Set entity config.

Actions: Check the Realm name.

NO_ENTITY_DESCRIPTOR_SET_ENTITY_CONFIG

ID: SAML2-67

Level: INFO

Description: Entity config doesn't exist while setting entity config.

Data: Entity ID, Realm or organization name

Triggers: Set entity config.

Actions: Create entity descriptor before set entity config.

SET ENTITY CONFIG

ĪD: SAML2-68

Level: INFO

Description: Entity config was set.

Data: Entity ID, Realm or organization name

Triggers: Set entity config.

CONFIG ERROR SET ENTITY CONFIG

ID: SAML2-69

Level: INFO

Description: Configuration error while setting entity config.

Data: Error message, Entity ID, Realm or organization name

Triggers: Set entity config.

Actions: Check debug message for detailed error.

SET INVALID ENTITY CONFIG

ID: SAML2-70

Description: Invalid entity config to set.

Data: Entity ID, Realm or organization name

Triggers: Set entity config.

Actions: Check entity config if it follows the schema.

NO_ENTITY_ID_CREATE_ENTITY_CONFIG

ID: SAML2-71

Level: INFO

Description: No entity ID while creating entity config.

Data: Realm or organization name

Triggers: Create entity config.

Actions: Set entity ID in entity config.

INVALID REALM CREATE ENTITY CONFIG

ID: SAML2-72

Level: INFO

Description: Invaid realm while creating entity config.

Data: Realm or organization name

Triggers: Create entity config.

Actions: Check the Realm name.

NO ENTITY DESCRIPTOR CREATE ENTITY CONFIG

ID: SAML2-73

Level: INFO

Description: Entity config doesn't exist while creating entity config.

Data: Entity ID, Realm or organization name

Triggers: Create entity config.

Actions: Create entity descriptor before create entity config.

ENTITY_CONFIG_EXISTS

ID: SAML2-74

Log Messages

Description: Entity config exists while creating entity config.

Data: Entity ID, Realm or organization name

Triggers: Create entity config.

Actions: Delete existing entity config first.

ENTITY_CONFIG_CREATED

ID: SAML2-75

Level: INFO

Description: Entity config was created.

Data: Entity ID, Realm or organization name

Triggers: Create entity config.

CONFIG ERROR CREATE ENTITY CONFIG

ID: SAML2-76

Level: INFO

Description: Configuration error while creating entity config.

Data: Error message, Entity ID, Realm or organization name

Triggers: Create entity config.

Actions: Check debug message for detailed error.

CREATE INVALID ENTITY CONFIG

ID: SAML2-77

Level: INFO

Description: Invalid entity config to create.

Data: Entity ID, Realm or organization name

Triggers: Create entity config.

Actions: Check entity config if it follows the schema.

INVALID REALM DELETE ENTITY CONFIG

ID: SAML2-78

Level: INFO

Description: Invaid realm while deleting entity config.

Data: Realm or organization name

Triggers: Delete entity config.

Actions: Check the Realm name.

NO ENTITY CONFIG DELETE ENTITY CONFIG

ID: SAML2-79

Level: INFO

Description: Entity config doesn't exist while deleting entity config.

Data: Entity ID, Realm or organization name

Triggers: Delete entity config.

Actions: Check debug message for detailed error.

ENTITY_CONFIG_DELETED

ID: SAML2-80

Level: INFO

Description: Entity config was deleted.

Data: Entity ID, Realm or organization name

Triggers: Delete entity config.

CONFIG ERROR DELETE ENTITY CONFIG

ID: SAML2-81

Level: INFO

Description: Configuration error while deleting entity config.

Data: Error message, Entity ID, Realm or organization name

Triggers: Delete entity config.

Actions: Check debug message for detailed error.

INVALID REALM GET ALL HOSTED ENTITIES

ID: SAML2-82

Level: INFO

Description: Invaid realm while getting all hosted entities.

Data: Realm or organization name

Triggers: Get all hosted entities.

Actions: Check the Realm name.

CONFIG ERROR GET ALL HOSTED ENTITIES

ID: SAML2-83

Level: INFO

Description: Configuration error while getting all hosted entities.

Data: Error message, Realm or organization name

Triggers: Get all hosted entities.

Actions: Check debug message for detailed error.

GOT ALL HOSTED ENTITIES

ID: SAML2-84

Level: FINE

Description: Obtained all hosted entities.

Data: Error message, Realm or organization name

Triggers: Get all hosted entities.

INVALID REALM GET ALL REMOTE ENTITIES

ID: SAML2-85

Level: INFO

Description: Invaid realm while getting all remote entities.

Data: Realm or organization name

Triggers: Get all remote entities.

Actions: Check the Realm name.

CONFIG ERROR GET ALL REMOTE ENTITIES

ID: SAML2-86

Level: INFO

Description: Configuration error while getting all remote entities.

Data: Error message, Realm or organization name

Triggers: Get all remote entities.

Actions: Check debug message for detailed error.

GOT_ALL_REMOTE_ENTITIES

ID: SAML2-87

Level: FINE

Description: Obtained all remote entities.

Data: Error message, Realm or organization name

Triggers: Get all remote entities.

INVALID INRESPONSETO RESPONSE

ID: SAML2-88

Level: INFO

Description: InResponseTo attribute in Response is invalid.

Data: Response ID

Triggers: Service Provider received a Response for Single Sign On.

Actions: Check debug message for detailed error.

INVALID ISSUER RESPONSE

ID: SAML2-89

Level: INFO

Description: Issuer in Response is invalid.

Data: Hosted Entity ID, Name of Realm or organization, Response ID

Triggers: Issuer in Response is not configured or not trusted by the hosted

provider

Actions: Check configuration.

WRONG_STATUS_CODE

ID: SAML2-90

Level: INFO

Description: Status code in Response was not Success.

Data: Response ID, Status code (if log level is set to LL FINE)

Triggers: Service provider received a Response with wrong Status code. Most

likely an error occurred at Identity Provider.

Actions: Check the status code. Contact Identity Provider if needed.

ASSERTION NOT ENCRYPTED

ID: SAML2-91

Level: INFO

Description: Assertion in Response was not encrypted.

Data: Response ID

Triggers: Service provider requested the assertion in Response to be encrypted, but it received a Response with unencrypted assertion(s).

Actions: Check configuration. Notify Identity Provider regarding the requirement.

MISSING ASSERTION

ID: SAML2-92

Level: INFO

Description: Response had no Assertion.

Data: Response ID

Triggers: Service provider received a Response for Single Sign On, but the response contained no Assertion.

Actions: Check error code of the Response. Notify Identity Provider if needed.

INVALID ISSUER ASSERTION

ID: SAML2-93

Level: INFO

Description: Issuer in Assertion is not valid.

Data: Assertion ID

Triggers: Issuer in Assertion for single sign on was not configured at service

provider, or not trusted by the service provider.

Actions: Check configuration

MISMATCH ISSUER ASSERTION

ID: SAML2-94

Description: Issuer in Assertion didn't match the Issuer in Response or other Assertions in the Response.

Data: Assertion ID

Triggers: Service provider received Response which had mismatch Issuer inside the Assertion it contained.

Actions: Check debug message

INVALID SIGNATURE ASSERTION

ID: SAML2-95

Level: INFO

Description: Assertion is not signed or signature is not valid.

Data: Assertion ID

Triggers: Service provider requested the Assertion to be signed but the assertion received was not; or the signature on the Assertion received was not valid.

Actions: Check configuration; check debug for more detailed error message.

MISSING_SUBJECT_COMFIRMATION DATA

ID: SAML2-96

Level: INFO

Description: SubjectConfirmationData had no Subject.

Data: Assertion ID

Triggers: Service provider received an Assertion whose

SubjectConfirmationData had no Subject.

Actions: Check debug for the Assertion received. Contact Identity Provider if needed.

MISSING RECIPIENT

ID: SAML2-97

Level: INFO

Description: SubjectConfirmationData had no Recipient.

Data: Assertion ID

Triggers: Service provider received an Assertion whose

SubjectConfirmationData had no Recipient.

Actions: Check debug for the Assertion received. Contact Identity Provider if needed.

WRONG_RECIPIENT

ID: SAML2-98

Level: INFO

Description: Service Provider is not the intended recipient.

Data: Assertion ID

Triggers: Service provider received an Assertion. But the provider is not the intended recipient of the Assertion.

Actions: Check debug for the Assertion received. Check meta data. Contact Identity Provider if needed.

INVALID_TIME_SUBJECT_CONFIRMATION_DATA

ID: SAML2-99

Level: INFO

Description: Time in SubjectConfirmationData of the Assertion is invalid.

Data: Assertion ID

Triggers: The assertion service provider received had expired timewise.

Actions: Synchronize the time between service provider and identity provider. Increase the time skew attribute for the service provider in its entity config.

CONTAINED NOT BEFORE

ID: SAML2-100

Level: INFO

Description: SubjectConfirmationData of the Assertion had NotBefore.

Data: Assertion ID

Triggers: The assertion service provider received had NotBefore.

Actions: Check debug for the Assertion received. Contact identity provider if needed.

WRONG_INRESPONSETO_ASSERTION

ID: SAML2-101

Level: INFO

Description: Assertion contained wrong InResponseTo attribute.

Data: Assertion ID

Triggers: InResponseTo in Assertion is different from the one in Response. Or Assertion didn't contain InResponseTo, but Response did.

Actions: Check debug for the Assertion received. Contact identity provider if needed.

MISSING CONDITIONS

ID: SAML2-102

Level: INFO

Description: Assertion contained no Conditions.

Data: Assertion ID

Triggers: Conditions is missing from the Single Sign On Assertion.

Actions: Check debug for the Assertion received. Contact identity provider if needed.

MISSING AUDIENCE RESTRICTION

ID: SAML2-103

Level: INFO

Description: Assertion contained no AudienceRestriction.

Data: Assertion ID

Triggers: AudienceRestriction is missing from the Single Sign On Assertion.

Actions: Check debug for the Assertion received. Contact identity provider if needed.

WRONG_AUDIENCE

ID: SAML2-104

Level: INFO

Description: Assertion contained wrong Audience.

Data: Assertion ID

Triggers: This service provider was not the intended audience of the single sign on assertion.

Actions: Check debug for the Assertion received. Check meta data. Contact identity provider if needed.

FOUND AUTHN ASSERTION

ID: SAML2-105

Level: INFO

Description: Found authentication assertion in the Response.

Data: Assertion ID, Subject if the log level was set to LL FINE, SesionIndex if

any

Triggers: Both the Response and Assertion(s) inside the Response are valid.

INVALID SSOTOKEN

ID: SAML2-106

Level: INFO

Description: Invalid SSOToken found in Request.

Data: SSOToken value

Triggers: Initiate Single Logout without SSOToken.

MISSING ENTITY

ID: SAML2-107

Level: INFO

Description: No entity ID is specified in Request.

Data: EntityID value

Triggers: Initiate Request without EntityID.

Actions: Specify EntityID parameter in request URL.

MISSING_META_ALIAS

ID: SAML2-108

Level: INFO

Description: No metaAlias is specified in Request.

Data: MetaAlias value

Triggers: Initiate Request without metaAlias.

Actions: Specify metaAlias parameter in request URL.

REDIRECT_TO_AUTH ID: SAML2-109

Level: INFO

Description: Redirect request to authentication page.

Data: URL to Authentication page

Triggers: Initiate Request without SSOToken.

CANNOT DECODE REQUEST

ID: SAML2-110

Level: INFO

Description: Can not decode URL encoded Query parameter.

Data: URL encoded Query parameter

Triggers: Initiate to decode incorrectly URL encoded Query parameter.

CANNOT INSTANTIATE MNI RESPONSE

ID: SAML2-111

Level: INFO

Description: Can not instantiate MNI Response with input xml.

Data: Input XML string for MNI Response

Triggers: Initiate parse MNI Response with incorrect XML string.

CANNOT INSTANTIATE MNI REQUEST

ID: SAML2-112

Level: INFO

Description: Can not instantiate MNI Request with input XML.

Data: Input XML string for MNI Request

Triggers: Initiate parse MNI Request with incorrect XML string.

CANNOT INSTANTIATE SLO RESPONSE

ID: SAML2-113

Level: INFO

Description: Can not instantiate SLO Response with input XML.

Data: Input XML string for SLO Response

Triggers: Initiate parse SLO Response with incorrect XML string.

CANNOT_INSTANTIATE_SLO_REQUEST

ID: SAML2-114

Level: INFO

Description: Can not instantiate SLO Request with input XML.

Data: Input XML string for SLO Request

Triggers: Initiate parse SLO Request with incorrect XML string.

MNI REQUEST INVALID SIGNATURE

 $\overline{\text{ID}}$: SAML2- $\overline{1}15$

Level: INFO

Description: Can not varify signature in MNI Request.

Data: MNI Request with signature

Triggers: Sinature in MNI Request is incorrect.

MNI RESPONSE INVALID SIGNATURE

ID: SAML2-116

Level: INFO

Description: Can not valify signature in MNI Response.

Data: MNI Response with signature

Triggers: Sinature in MNI Response is incorrect.

SLO_REQUEST_INVALID SIGNATURE

ĪD: SAML2-117

Level: INFO

Description: Can not valify signature in SLO Request.

Data: SLO Request with signature

Triggers: Sinature in SLO Request is incorrect.

SLO RESPONSE INVALID SIGNATURE

ID: SAML2-118

Log Messages

Level: INFO

Description: Can not valify signature in SLO Response.

Data: SLO Response with signature

Triggers: Sinature in SLO Response is incorrect.

NAMEID INVALID ENCRYPTION

ID: SAML2-119

Level: INFO

Description: Can not decrypt EncryptedID.

Data: Exception message

Triggers: Decrypt the incorrectly encrypted EncryptedID.

INVALID MNI RESPONSE

ID: SAML2-120

Level: INFO

Description: MNI Response has error status.

Data: Status message

Triggers: Requested MNI Request caused problem.

INVALID SLO RESPONSE

ID: SAML2-121

Level: INFO

Description: SLO Response has error status.

Data: Status message

Triggers: Requested SLO Request caused problem.

MISSING ENTITY ROLE

ID: SAML2-122

Level: INFO

Description: Entity Role is not specified in the request.

Data: Entity Role value

Triggers: Initiate request without Role value.

Actions: Specify Entity Role parameter in the request.

INVALID ISSUER REQUEST

ID: SAML2-123

Level: INFO

Description: Issuer in Request is invalid.

Data: Hosted Entity ID, Name of Realm or organization, Request ID

Triggers: Issuer in Request is not configured or not trusted by the hosted

provider

Actions: Check configuration.

INVALID REALM GET ALL ENTITIES

ID: SAML2-124

Level: INFO

Description: Invaid realm while getting all entities.

Data: Realm or organization name

Triggers: Get all entities.

Actions: Check the Realm name.

CONFIG ERROR GET ALL ENTITIES

ID: SAML2-125

Level: INFO

Description: Configuration error while getting all entities.

Data: Error message, Realm or organization name

Triggers: Get all entities.

Actions: Check debug message for detailed error.

GOT ALL ENTITIES

ID: SAML2-126

Level: FINE

Description: Obtained all entities.

Data: Realm or organization name

Triggers: Get all entities.

INVALID_PEP_ID ID: SAML2-127

Level: INFO

Description: Invalid Policy Enforcement Point (PEP) Identifier.

Data: PEP Identifier

Triggers: Cannot retrieve PEP Metadata

Actions: Provide valid PEP Identifier and retry.

INVALID_PDP_ID ID: SAML2-128

Level: INFO

Description: Invalid Policy Decision Point (PDP) Identifier.

Data: PDP Identifier

Triggers: Cannot retrieve PDP Metadata

Actions: Provide valid PDP Identifier and retry.

NULL_PDP_SIGN_CERT_ALIAS

ID: SAML2-129

Level: INFO

Description: Certificate Alias is null, cannot sign the message.

Data: The realm from which the metadata was retreived., Entity Identifier for

the Policy Decision Point.

Triggers: Cannot sign the message.

Actions: Check the entity's metadata to verify the certificate alias is correct.

NULL_PEP_SIGN_CERT_ALIAS

ID: SAML2-130

Level: INFO

Description: Certificate Alias is null, cannot retreive the certificate.

Data: The realm from which the metadata was retreived., Entity Identifier for the Policy Enforcement Point.

Triggers: Cannot validate the signature in the request message.

Actions: Check the entity's metadata to verify the certificate alias is correct.

INVALID SIGNATURE QUERY

ID: SAML2-131

Level: INFO

Description: Invalid Signature in Query Request.

Data: The realm from which the metadata was retreived., Entity Identifier for the Policy Decision Point., Cert Alias used to retrieve certificate from keystore.

Triggers: Cannot process the request, server will send back error to the Requester.

Actions: Check the entity's metadata to verify the certificate alias is correct.; Check the certificate in the keystore for its existance and validity.

INVALID_ISSUER_IN_PEP_REQUEST

ID: SAML2-132

Level: INFO

Description: Issuer in Request is invalid.

Data: Name of Realm or organization, Identity of the Issuer, Hosted Entity Identifier

Triggers: Issuer in Request is not configured or not trusted by the hosted provider therefore Query will fail.

Actions: Check the hosted entity configuration attribute cotlist to make sure the issuer identifier is in the list.

PEP METADATA ERROR

ĪD: SAML2-133

Level: INFO

Description: Unable to retreive Policy Enforcement Point (PEP) Metadata.

Data: PEP Provider Entity Identifier

Triggers: Cannot retrieve PEP Provider Metadata

Actions: Check the Data Store is accessible .; Check the PEP Provider Entity Identifier.

PDP_METADATA_ERROR

ID: SAML2-134

Level: INFO

Description: Unable to retrieve Policy Decision Point (PDP) Metadata.

Data: PDP Provider Entity Identifier

Triggers: Cannot retreive PDP Provider Metadata

Actions: Check the Data Store is accessible .; Check the PDP Provider Entity Identifier.

ASSERTION FROM PDP NOT ENCRYPTED

ID: SAML 2-135

Level: INFO

Description: Assertion in Response not encrypted.

Data: Identity of the Issuer, Response ID

Triggers: Policy Enforcement Point (PEP) Provider requested the assertion in Response to be encrypted, but it received a Response with unencrypted assertion(s).

Actions: Check PEP metadata published to the PDP. Notify Policy Decision Point (PDP) Provider regarding the requirement.

MISSING ASSERTION IN PDP RESPONSE

ID: SAML2-136

Level: INFO

Description: Response has no Assertion.

Data: Identity of Issuer, Response ID

Triggers: Policy Enforcement Point (PEP) Provider received a Response with no Assertion.

Actions: Check error code of the Response. Notify Policy Decision Point (PDP) Provider to check for errors or possible misconfiguration.

INVALID_ISSUER_IN_ASSERTION_FROM_PDP

ID: SAML2-137

Description: Issuer in Assertion is not valid.

Data: Assertion Issuer, Assertion ID

Triggers: Issuer in Assertion was not configured at Policy Enforcement Point (PEP) provider, or not trusted by the PEP provider.

Actions: Check the configuration.

MISMATCH ISSUER IN ASSERTION FROM PDP

ID: SAML2-138

Level: INFO

Description: Issuer in Assertion doesn't match the Issuer in Response.

Data: Issuer Identifier in the Resposnse, Issuer Identity in the Assertion

Triggers: Error condition, Response will not be accepted.

Actions: Check the Policy Decision Point instance to debug the cause of the problem.

INVALID SIGNATURE ASSERTION FROM PDP

ID: SAML2-139

Level: INFO

Description: Assertion is not signed or signature is not valid.

Data: Issuer Identity in the Assertion, Assertion ID

Triggers: Policy Enforcement Point (PEP) provider requested the Assertion to be signed but the assertion received was not; or the signature on the Assertion received was not valid.

Actions: Check PEP metadata configuration.; Check debug for more detailed error message.

REQUEST MESSAGE

ID: SAML2-140

Level: FINE

Description: Request message from Query Requester

Data: policy decision point entity descriptor, SAMLv2 Query Request

Message

Triggers: SAMLv2 SOAP Query

VALID_SIGNATURE_QUERY

ID: SAML2-141

Level: INFO

Description: Valid Signature in Query Request.

Data: The realm from which the metadata was retreived., Entity Identifier for the Policy Decision Point., Cert Alias used to retrieve certificate from keystore.

Triggers: The Request will be processed.

SUCCESS FED SSO

ID: SAML2-142

Level: INFO

Description: Successful federation/Single Sign On.

Data: user id, NameID value

Triggers: Successful federation/Single Sign On.

$SAE_IDP_SUCCESS$

ĪD: SAML2-143

Level: INFO

Description: SAE IDP succeeded.

Data: SAE attributes

Triggers: SAE IDP succeeded.

SAE IDP ERROR

ID: SAML2-144

Level: INFO

Description: SAE IDP failed.

Data: Error message, SAE attributes

Triggers: SAE IDP failed.

SAE IDP ERROR NODATA

ID: SAML2-145

Log Messages

Description: SAE_IDP invoked without attributes.

Data: Error message

Triggers: SAE IDP invoked without attributes.

Actions: Add SAE attributes to request.

SAE IDP AUTH

ID: SAML2-146

Level: INFO

Description: SAE_IDP delegated to Auth.

Data: SAE attributes

Triggers: SAE IDP invoked but no user session.

SAE_SP_SUCCESS

ID: SAML2-147

Level: INFO

Description: SAE SP succeeded.

Data: SAE attributes

Triggers: SAE SP succeeded.

SAE_SP ERROR

ID: SAML2-148

Level: INFO

Description: SAE SP failed.

Data: Error message

Triggers: SAE SP failed.

SEND ECP RESPONSE

ID: SAML2-149

Level: INFO

Description: Send a response to ECP.

Data: Identity Provider Entity Identifier, Realm or organization name, Assertion Consumer Service URL, SOAP message string if the log level was set to LL FINE at run time

Triggers: Received AuthnRequest.

SEND_ECP_RESPONSE_FAILED

ID: SAML2-150

Level: INFO

Description: Unable to send a response to ECP.

Data: Identity Provider Entity Identifier, Realm or organization name,

Assertion Consumer Service URL

Triggers: Send a response to ECP.

CANNOT INSTANTIATE SOAP MESSAGE ECP

ID: SAML2-151

Level: INFO

Description: Unable to instantiate a SOAP message sent from ECP.

Data: Service Provider Entity Identifier

Triggers: Received a response from ECP.

RECEIVE SOAP FAULT ECP

ID: SAML2-152

Level: INFO

Description: Received a SOAP fault from ECP.

Data: Service Provider Entity Identifier

Triggers: Received a response from ECP.

CANNOT INSTANTIATE SOAP MESSAGE ECP

ID: SAML2-153

Level: INFO

Description: Unable to instantiate a SAML Response sent from ECP.

Data: Service Provider Entity Identifier

Triggers: Received a response from ECP.

ECP ASSERTION NOT SIGNED

ID: SAML2-154

Level: INFO

Description: Assertion received from ECP is not signed.

Data: Identity Provider Entity Identifier

Triggers: Received a response from ECP.

ECP ASSERTION INVALID SIGNATURE

ID: SAML2-155

Level: INFO

Description: Assertion received from ECP has invalid signature.

Data: Identity Provider Entity Identifier

Triggers: Assertion signature verification.

RECEIVED_AUTHN_REQUEST_ECP

ID: SAML2-156

Level: INFO

Description: Received AuthnRequest from ECP.

Data: Service Provider Entity Identifier, IDP meta alias, authnRequest xml

string

Triggers: Single Sign On.

RECEIVED HTTP REQUEST ECP

ID: SAML2-157

Level: INFO

Description: Received HTTP request from ECP.

Data: Service Provider Entity Identifier, Realm or organization name

Triggers: ECP accessed SP Resource.

SEND ECP PAOS REQUEST

ID: SAML2-158

Level: INFO

Description: Send a PAOS request to ECP.

Data: Service Provider Entity Identifier, Realm or organization name, SOAP

message string if the log level was set to LL FINE at run time

Triggers: Received HTTP request from ECP.

SEND ECP PAOS REQUEST FAILED

ID: SAML2-159

Level: INFO

Description: Unable to send a PAOS request to ECP.

Data: Service Provider Entity Identifier, Realm or organization name

Triggers: Send a PAOS request to ECP.

SUCCESS FED TERMINATION

ID: SAML2-160

Level: INFO

Description: Federation termination succeeded.

Data: user id

Triggers: Federation termination succeeded.

SUCCESS NEW NAMEID

ID: SAML2-161

Level: INFO

Description: New name identifier succeeded.

Data: user id

Triggers: New name identifier succeeded.

UNKNOWN PRINCIPAL

ID: SAML2-162

Level: INFO

Description: Unknown princial in manage name ID request.

Data: Manage Name ID request XML

Triggers: Unable to find old name id in the management name id request.

UNABLE TO TERMINATE

ID: SAML2-163

Level: INFO

Description: Unable to terminate federation.

Data: user id

Triggers: Unable to terminate federation.

POST RESPONSE INVALID SIGNATURE

ID: SAML2-164

Level: INFO

Description: Unable to verify signature in Single Sign-On Response using

POST binding.

Data: Identity Provider Entity ID

Triggers: Error while trying to verify signature in Response.

Actions: Check Identity Provider metadata; Check debug file for detailed info

BINDING NOT SUPPORTED

ID: SAML2-165

Level: INFO

Description: Binding is not supported.

Data: Provider Entity ID, Name of binding that is not supported

Triggers: Hosted provider received data from unsupported binding endpoint.

Actions: Check Provider metadata; Check debug file for detailed info

SP SSO FAILED

ID: SAML2-166

Level: INFO

Description: Single Sign-On Failed at Service Provider.

Data: Hosted Service Provider Entity ID, Error message, Response received

from IDP if the log level was set to LL FINE at run time

Triggers: Single Sign On failed

Actions: Check debug file for detailed info

INVALID REALM FOR SESSION

ID: SAML2-167

Level: INFO

Description: Invalid realm for the user trying to get an assertion from the IdP.

Data: Realm of the authenticated user, Realm where the IdP is defined, Entity Id of the SP, IP Address of the requester, SAML2 Authentication Request

Triggers: Single Sign On failed

Actions: Check debug file for detailed info

OpenAM logs the following SAML messages.

ASSERTION CREATED

ID: SAML-1

Level: INFO

Description: New assertion created

Data: message id, Assertion ID or Assertion if log level is LL FINER

Triggers: Browser Artifact Profile; Browser POST Profile; Create Assertion Artifact; Authentication Query; Attribute Query; Authorization Decision Query

ASSERTION ARTIFACT CREATED

ID: SAML-2

Level: INFO

Description: New assertion artifact created

Data: message id, Assertion Artifact, ID of the Assertion corresponding to the

Artifact

Triggers: Browser Artifact Profile; Creating Assertion Artifact

ASSERTION ARTIFACT REMOVED

ID: SAML-3

Level: FINE

Description: Assertion artifact removed from map

Data: message id, Assertion Artifact

Triggers: SAML Artifact Query; Assertion artifact expires

ASSERTION REMOVED

ID: SAML-4

Level: FINE

Log Messages

Description: Assertion removed from map

Data: message id, Assertion ID

Triggers: SAML Artifact Query; Assertion expires

ASSERTION ARTIFACT VERIFIED

ID: SAML-5

Level: INFO

Description: Access right by assertion artifact verified

Data: message id, Assertion Artifact

Triggers: SAML Artifact Query

AUTH PROTOCOL MISMATCH

ID: SAML-6

Level: INFO

Description: Authentication type configured and the actual SOAP protocol do not match.

1100 111400111

Data: message id

Triggers: SAML SOAP Query

Actions: Login to console, go to Federation, then SAML, edit the Trusted Partners Configuration, check the selected Authentication Type field, make sure it matches the protocol specified in SOAP URL field.

INVALID AUTH TYPE

ID: SAML-7

Level: INFO

Description: Invalid authentication type

Data: message id

Triggers: SAML SOAP Query

Actions: Login to console, go to Federation, then SAML, edit the Trusted Partners Configuration, select one of the values for Authentication Type field, then save.

SOAP RECEIVER URL

ID: SAML-8

Level: FINE

Description: Remote SOAP receiver URL

Data: message id, SOAP Receiver URL

Triggers: SAML SOAP Query

NO_ASSERTION_IN_RESPONSE

ID: SAML-9

Level: INFO

Description: No assertion present in saml response

Data: message id, SAML Response

Triggers: SAML Artifact Query

Actions: Contact remote partner on what's wrong

MISMATCHED ASSERTION AND ARTIFACT

ID: SAML-10

Level: INFO

Description: Number of assertions in SAML response does not equal to

number of artifacts in SAML request.

Data: message id, SAML Response

Triggers: SAML Artifact Query

Actions: Contact remote partner on what's wrong

ARTIFACT TO SEND

ID: SAML-11

Level: INFO

Description: Artifact to be sent to remote partner

Data: message id, SAML Artifact

Triggers: SAML Artifact Query

WRONG_SOAP_URL

ID: SAML-12

Level: INFO

Log Messages

Description: Wrong SOAP URL in trusted partner configuration

Data: message id

Triggers: SAML Artifact Query

Actions: Login to console, go to Federation, then SAML, edit the Trusted Partners Configuration, enter value for SOAP URL field, then save.

SAML ARTIFACT QUERY

ID: SAML-13

Level: FINE

Description: SAML Artifact Query SOAP request

Data: message id, SAML Artifact Query message

Triggers: SAML Artifact Query

NO REPLY FROM SOAP RECEIVER

ID: SAML-14

Level: INFO

Description: No reply from remote SAML SOAP Receiver

Data: message id

Triggers: SAML Artifact Query

Actions: Check remote partner on what's wrong

REPLIED SOAP MESSAGE

ID: SAML-15

Level: FINE

Description: SAML Artifact Query response

Data: message id, SAML Artifact Query response message

Triggers: SAML Artifact Query

NULL SAML RESPONSE

ID: SAML-16

Level: INFO

Description: No SAML response inside SOAP response

Data: message id

Triggers: SAML Artifact Query

Actions: Check remote partner on what's wrong

INVALID RESPONSE SIGNATURE

ID: SAML-17

Level: INFO

Description: XML signature for SAML response is not valid

Data: message id

Triggers: SAML Artifact Query

Actions: Check remote partner on what's wrong on XML digital signature

ERROR RESPONSE STATUS

ID: SAML-18

Level: INFO

Description: Error in getting SAML response status code

Data: message id

Triggers: SAML Artifact Query

Actions: Check remote partner on what's wrong on response status code

MISSING_TARGET ID: SAML-19

ID: SAML-18

Level: INFO

Description: TARGET parameter is missing from the request

Data: message id

Triggers: SAML Artifact Profile; SAML POST Profile

Actions: Add "TARGET=target url" as query parameter in the request

REDIRECT TO URL

ID: SAML-20

Level: INFO

Description: Redirection URL in SAML artifact source site

Data: message id, target, redirection URL, SAML response message in case of POST profile and log level is LL FINER

Triggers: SAML Artifact Profile source; SAML POST Profile source

TARGET_FORBIDDEN

ID: SAML-21

Level: INFO

Description: The specified target site is forbidden

Data: message id, target URL

Triggers: SAML Artifact Profile source; SAML POST Profile source

Actions: TARGET URL specified in the request is not handled by any trusted partner, check your TARGET url, make sure it matches one of the Target URL configured in trusted partner sites

FAILED TO CREATE SSO TOKEN

ID: SAML-22

Level: INFO

Description: Failed to create single-sign-on token

Data: message id

Triggers: SAML Artifact Profile destination; SAML POST Profile destination

Actions: Authentication component failed to create SSO token, please check authentication log and debug for more details

ACCESS GRANTED

ID: SAML-23

Level: INFO

Description: Single sign on successful, access to target is granted

Data: message id, Response message in case of POST profile and log levele is

LL FINER or higher

Triggers: SAML Artifact Profile destination; SAML POST Profile destination

NULL PARAMETER

ID: SAML-24

Level: INFO

Log Messages

Description: Null servlet request or response

Data: message id

Triggers: SAML Artifact Profile; SAML POST Profile

Actions: Check web container error log for details

MISSING RESPONSE

ID: SAML-25

Level: INFO

Description: Missing SAML response in POST body

Data: message id

Triggers: SAML POST Profile destination

Actions: Check with remote SAML partner to see why SAML response object

is missing from HTTP POST body

RESPONSE MESSAGE ERROR

ID: SAML-26

Level: INFO

Description: Error in response message

Data: message id

Triggers: SAML POST Profile destination

Actions: Unable to convert encoded POST body attribute to SAML Response object, check with remote SAML partner to see if there is any error in the SAML response create, for example, encoding error, invalid response sub-

element etc.

INVALID RESPONSE

ID: SAML-27

Level: INFO

Description: Response is not valid

Data: message id

Triggers: SAML POST Profile destination

Actions: recipient attribute in SAML response does not match this site's POST

profile URL; Response status code is not success

SOAP_MESSAGE_FACTORY_ERROR

ID: SAML-28

Level: INFO

Description: Failed to get an instance of the message factory

Data: message id

Triggers: SAML SOAP Receiver init

Actions: Check your SOAP factory property (javax.xml.soap.MessageFactory)

to make sure it is using a valid SOAP factory implementation

UNTRUSTED SITE

ID: SAML-29

Level: INFO

Description: Received Request from an untrusted site

Data: message id, Remote site Hostname or IP Address

Triggers: SAML SOAP Queries

Actions: Login to console, go to Federation, then SAML service, edit the Trusted Partners Configuration, check the Host List field, make sure remote host/IP is one the values. In case of SSL with client auth, make sure Host List contains the client certificate alias of the remote site.

INVALID REQUEST

ID: SAML-30

Level: INFO

Description: Invalid request from remote partner site

Data: message id and request hostname/IP address, return response

Triggers: SAML SOAP Queries

Actions: Check with administrator of remote partner site

SOAP REQUEST MESSAGE

ID: SAML-31

Level: FINE

Description: Request message from partner site

Data: message id and request hostname/IP address, request xml

Triggers: SAML SOAP Queries

BUILD RESPONSE ERROR

ID: SAML-32

Level: INFO

Description: Failed to build response due to internal server error

Data: message id

Triggers: SAML SOAP Queries

Actions: Check debug message to see why it is failing, for example, cannot

create response status, major/minor version error, etc.

SENDING RESPONSE

ID: SAML-33

Level: INFO

Description: Sending SAML response to partner site

Data: message id, SAML response or response id

Triggers: SAML SOAP Queries

SOAP FAULT ERROR

ID: SAML-34

Level: INFO

Description: Failed to build SOAP fault response body

Data: message id

Triggers: SAML SOAP Queries

Actions: Check debug message to see why it is failing, for example, unable to

create SOAP fault, etc.

OpenAM logs the following WSFederation messages.

INVALID SIGNATURE ASSERTION

ID: WSFederation-1

Level: INFO

Description: Assertion is not signed or signature is not valid.

Data: Assertion or assertion ID, Realm or organization name, Assertion issuer

Triggers: Service provider requested the Assertion to be signed but the assertion received was not; or the signature on the Assertion received was not valid.

Actions: Check configuration; check debug for more detailed error message.

MISSING CONDITIONS NOT ON OR AFTER

ID: WSFederation-2

Level: INFO

Description: Assertion conditions are missing notOnOrAfter attribute.

Data: Assertion or assertion ID

Triggers: The Conditions element of the assertion is missing its notOnOrAfter

attribute.

Actions: Check the assertion. Contact Identity Provider if needed.

ASSERTION EXPIRED

ID: WSFederation-3

Level: INFO

Description: Assertion has expired.

Data: Assertion or assertion ID, Assertion notOnOrAfter time, Time skew in seconds. Current time

seconds, Current time

Triggers: The current time is after the assertion's notOnOrAfter time plus the time skew.

Actions: Synchronize server clocks. Contact Identity Provider if needed.

MISSING_CONDITIONS_NOT_BEFORE

ID: WSFederation-4

Level: INFO

Description: Assertion conditions are missing notBefore attribute.

Data: Assertion or assertion ID

Triggers: The Conditions element of the assertion is missing its notBefore

attribute.

Actions: Check the assertion. Contact Identity Provider if needed.

ASSERTION NOT YET VALID

ID: WSFederation-5

Level: INFO

Description: Assertion not yet valid.

Data: Assertion or assertion ID, Assertion notBefore time, Time skew in

seconds, Current time

Triggers: The current time is before the assertion's notBefore time minus the

time skew.

Actions: Synchronize server clocks. Contact Identity Provider if needed.

MISSING WRESULT

ID: WSFederation-6

Level: INFO

Description: WS-Federation response is missing wresult.

Data: WS-Federation response

Triggers: The WS-Federation response is missing its wresult parameter.

Actions: Check the response. Contact Identity Provider if needed.

MISSING WCTX

ID: WSFederation-7

Level: INFO

Description: WS-Federation response is missing wctx.

Data: WS-Federation response

Triggers: The WS-Federation response is missing its wctx parameter.

Actions: Check the response. Contact Identity Provider if needed.

INVALID WRESULT

ID: WSFederation-8

Level: INFO

Description: WS-Federation response is invalid.

Data: WS-Federation response

Triggers: The WS-Federation response is not a valid

RequestSecurityTokenResponse element.

Actions: Check the response. Contact Identity Provider if needed.

CONFIG_ERROR_GET_ENTITY_CONFIG

ID: WSFederation-9

Level: INFO

Description: Configuration error while getting entity config.

Data: Error message, MetaAlias, Realm or organization name

Triggers: Obtain entity config.

Actions: Check debug message for detailed error.

CANT FIND SP ACCOUNT MAPPER

ID: WSFederation-10

Level: INFO

Description: Can't find SP Account Mapper.

Data: Error message, Account mapper class name

Triggers: Cannot get class object for SP account mapper class.

Actions: Check the configuration. Ensure that SP account mapper class name is correct and that the account mapper class is on the classpath.

CANT CREATE SP ACCOUNT MAPPER

ID: WSFederation-11

Level: INFO

Description: Can't create SP Account Mapper.

Data: Error message, Account mapper class name

Triggers: Cannot create SP account mapper object.

Actions: Check the configuration. Ensure that SP account mapper class name is correct and that the account mapper class is on the classpath.

CANT_CREATE SESSION

ID: WSFederation-12

Level: INFO

Description: Can't create session for user.

Data: Error message, Realm or organization name, User name, Auth level

Triggers: Cannot create session for user.

Actions: Check the configuration. Ensure that SP account mapper is finding a user in the local store.

SSO SUCCESSFUL

ID: WSFederation-13

Level: INFO

Description: Single sign-on completed successfully.

Data: wctx, Assertion or assertion ID, Realm or organization name, User ID, Authentication Level, Target URL

Triggers: Successful WS-Federation RP Signin Response.

UNTRUSTED ISSUER

ID: WSFederation-14

Level: INFO

Description: Assertion issuer is not trusted by this service provider.

Data: Assertion or assertion ID, Realm or organization name, Service provider ID, Target URL

Triggers: Cannot create session for user.

Actions: Check the configuration. Ensure that SP account mapper is finding a user in the local store.

MISSING SUBJECT

ID: WSFederation-15

Level: INFO

Description: Assertion does not contain a subject element.

Data: Assertion or assertion ID

Triggers: Assertion does not contain a subject element.

Actions: Check the assertion. Contact Identity Provider if needed.

GOT FEDERATION

ID: WSFederation-16

Level: FINE

Description: Federation obtained.

Data: Federation ID, Realm or organization name

Triggers: Obtain federation.

GOT INVALID ENTITY DESCRIPTOR

ID: WSFederation-17

Level: INFO

Description: Obtained invalid entity descriptor.

Data: Entity ID, Realm or organization name

Triggers: Obtain entity descriptor.

Actions: Delete invalid entity descriptor and import it again.

CONFIG ERROR GET ENTITY DESCRIPTOR

ID: WSFederation-18

Level: INFO

Description: Configuration error while getting entity descriptor.

Data: Error message, Entity ID, Realm or organization name

Triggers: Obtain entity descriptor.

Actions: Check debug message for detailed error.

SET ENTITY DESCRIPTOR

ID: WSFederation-19

Level: INFO

Description: Entity descriptor was set.

Data: Entity ID, Realm or organization name

Triggers: Set entity descriptor.

CONFIG ERROR SET ENTITY DESCRIPTOR

ID: WSFederation-20

Level: INFO

Description: Configuration error while setting entity descriptor.

Data: Error message, Entity ID, Realm or organization name

Triggers: Set entity descriptor.

Actions: Check debug message for detailed error.

SET INVALID ENTITY DESCRIPTOR

ID: WSFederation-21

Level: INFO

Description: Invalid entity descriptor to set.

Data: Entity ID, Realm or organization name

Triggers: Set entity descriptor.

Actions: Check entity descriptor if it follows the schema.

ENTITY_DESCRIPTOR_CREATED

ID: WSFederation-22

Level: INFO

Description: Entity descriptor was created.

Data: Entity ID, Realm or organization name

Triggers: Create entity descriptor.

CONFIG ERROR CREATE ENTITY DESCRIPTOR

ID: WSFederation-23

Level: INFO

Description: Configuration error while creating entity descriptor.

Data: Error message, Entity ID, Realm or organization name

Triggers: Create entity descriptor.

Actions: Check debug message for detailed error.

CREATE INVALID ENTITY DESCRIPTOR

ID: WSFederation-24

Level: INFO

Description: Invalid entity descriptor to create.

Data: Entity ID, Realm or organization name

Triggers: Create entity descriptor.

Actions: Check entity descriptor if it follows the schema.

ENTITY DESCRIPTOR DELETED

ID: WSFederation-25

Level: INFO

Description: Entity descriptor was deleted.

Data: Entity ID, Realm or organization name

Triggers: Delete entity descriptor.

CONFIG ERROR DELETE ENTITY DESCRIPTOR

ID: WSFederation-26

Level: INFO

Description: Configuration error while deleting entity descriptor.

Data: Error message, Entity ID, Realm or organization name

Triggers: Delete entity descriptor.

Actions: Check debug message for detailed error.

GOT ENTITY CONFIG

ID: WSFederation-27

Level: FINE

Description: Entity config obtained.

Data: Entity ID, Realm or organization name

Triggers: Obtain entity config.

GOT INVALID ENTITY CONFIG

ID: WSFederation-28

Level: INFO

Description: Obtained invalid entity config.

Data: Entity ID, Realm or organization name

Triggers: Obtain entity config.

Actions: Delete invalid entity config and import it again.

CONFIG ERROR GET ENTITY CONFIG

ID: WSFederation-29

Level: INFO

Description: Configuration error while getting entity config.

Data: Error message, Entity ID, Realm or organization name

Triggers: Obtain entity config.

Actions: Check debug message for detailed error.

NO ENTITY ID SET ENTITY CONFIG

ID: WSFederation-30

Level: INFO

Description: No entity ID while setting entity config.

Data: Realm or organization name

Triggers: Set entity config.

Actions: Set entity ID in entity config.

SET_ENTITY_CONFIG

ID: WSFederation-31

Level: INFO

Description: Entity config was set.

Data: Entity ID, Realm or organization name

Triggers: Set entity config.

CONFIG ERROR SET ENTITY CONFIG

ID: WSFederation-32

Level: INFO

Description: Configuration error while setting entity config.

Data: Error message, Entity ID, Realm or organization name

Triggers: Set entity config.

Actions: Check debug message for detailed error.

SET INVALID ENTITY CONFIG

ID: WSFederation-33

Level: INFO

Description: Invalid entity config to set.

Data: Entity ID, Realm or organization name

Triggers: Set entity config.

Actions: Check entity config if it follows the schema.

NO ENTITY ID CREATE ENTITY CONFIG

ID: WSFederation-34

Level: INFO

Description: No entity ID while creating entity config.

Data: Realm or organization name

Triggers: Create entity config.

Actions: Set entity ID in entity config.

NO ENTITY DESCRIPTOR CREATE ENTITY CONFIG

ID: WSFederation-35

Level: INFO

Description: Entity config doesn't exist while creating entity config.

Data: Entity ID, Realm or organization name

Triggers: Create entity config.

Actions: Create entity descriptor before create entity config.

ENTITY_CONFIG_EXISTS

ID: WSFederation-36

Level: INFO

Description: Entity config exists while creating entity config.

Data: Entity ID, Realm or organization name

Triggers: Create entity config.

Actions: Delete existing entity config first.

ENTITY CONFIG CREATED

ID: WSFederation-37

Level: INFO

Description: Entity config was created.

Data: Entity ID, Realm or organization name

Triggers: Create entity config.

CONFIG ERROR CREATE ENTITY CONFIG

ID: WSFederation-38

Level: INFO

Description: Configuration error while creating entity config.

Data: Error message, Entity ID, Realm or organization name

Triggers: Create entity config.

Actions: Check debug message for detailed error.

CREATE INVALID ENTITY CONFIG

ID: WSFederation-39

Level: INFO

Description: Invalid entity config to create.

Data: Entity ID, Realm or organization name

Triggers: Create entity config.

Actions: Check entity config if it follows the schema.

NO ENTITY CONFIG DELETE ENTITY CONFIG

ID: WSFederation-40

Level: INFO

Description: Entity config doesn't exist while deleting entity config.

Data: Entity ID, Realm or organization name

Triggers: Delete entity config.

Actions: Check debug message for detailed error.

ENTITY CONFIG DELETED

ID: WSFederation-41

Level: INFO

Description: Entity config was deleted.

Data: Entity ID, Realm or organization name

Triggers: Delete entity config.

CONFIG ERROR DELETE ENTITY CONFIG

ID: WSFederation-42

Level: INFO

Description: Configuration error while deleting entity config.

Data: Error message, Entity ID, Realm or organization name

Triggers: Delete entity config.

Actions: Check debug message for detailed error.

CONFIG ERROR GET ALL HOSTED ENTITIES

ID: WSFederation-43

Level: INFO

Description: Configuration error while getting all hosted entities.

Data: Error message, Realm or organization name

Triggers: Get all hosted entities.

Actions: Check debug message for detailed error.

GOT ALL HOSTED ENTITIES

ID: WSFederation-44

Level: FINE

Description: Obtained all hosted entities.

Data: Realm or organization name

Triggers: Get all hosted entities.

CONFIG ERROR GET ALL REMOTE ENTITIES

ID: WSFederation-45

Level: INFO

Description: Configuration error while getting all remote entities.

Data: Error message, Realm or organization name

Triggers: Get all remote entities.

Actions: Check debug message for detailed error.

GOT ALL REMOTE ENTITIES

ID: WSFederation-46

Level: FINE

Description: Obtained all remote entities.

Data: Error message, Realm or organization name

Triggers: Get all remote entities.

CONFIG ERROR GET ALL ENTITIES

ID: WSFederation-47

Level: INFO

Description: Configuration error while getting all entities.

Data: Error message, Realm or organization name

Triggers: Get all entities.

Actions: Check debug message for detailed error.

GOT ALL ENTITIES

ID: WSFederation-48

Level: FINE

Description: Obtained all entities.

Data: Realm or organization name

Triggers: Get all entities.

ASSERTION CREATED

ID: WSFederation-49

Level: INFO

Description: Assertion created successfully.

Data: Assertion or assertion ID

Triggers: Creation of WS-Federation IdP Signin Response.

NO ACS URL

ID: WSFederation-50

Level: INFO

Description: Could not find an Assertion Consumer Service URL.

Data: Realm or organization name, Service provider ID, Reply URL

Triggers: No ACS URL in configuration.; ACS URL provided in request not found in configuration.

iouna in configuration.

Actions: Check configuration for service provider.

SLO SUCCESSFUL

ID: WSFederation-51

Level: INFO

Description: Single logout completed successfully.

Data: Reply URL

Triggers: Successful single logout.

OpenAM logs the following WebServicesSecurity messages.

UNSUPPORTED TOKEN TYPE

ID: WebServicesSecurity-1

Level: INFO

Description: Unsupported Token Type sent to STS for Security Token

creation.

Data: Token Type sent by client to STS

Triggers: Invalid or unsupported token type sent by client to STS.

Actions: Check the Token Type sent by client to STS.

CREATED SAML11 ASSERTION

ID: WebServicesSecurity-2

Level: INFO

Description: Successfully created SAML 1.1 assertion by STS.

Data: Assertion ID, Issuer of this SAML assertion, Service Provider for which this Assertion is created or applies to, Confirmation Method, Token Type, Key Type

Triggers: Valid parameters sent by client to STS to create SAML assetion.

CREATED_SAML20_ASSERTION

ID: WebServicesSecurity-3

Level: INFO

Description: Successfully created SAML 2.0 assertion by STS.

Data: Assertion ID, Issuer of this SAML assertion, Service Provider for which this Assertion is created or applies to, Confirmation Method, Token Type, Key Type

Triggers: Valid parameters sent by client to STS to create SAML assetion.

ERROR SIGNING SAML ASSERTION

ID: WebServicesSecurity-4

Level: INFO

Description: Error during signing SAML assertion by STS.

Data: Actual Error message

Triggers: Problem in STS's Certificate or Private key.

Actions: Check the certificate of STS.; Check the Private Key of STS.

ERROR CREATING SAML11 ASSERTION

ID: WebServicesSecurity-5

Level: INFO

Description: Error during creation of SAML 1.1 Assertion by STS.

Data: Actual Error message

Triggers: Invalid parameters sent to create SAML 1.1 Assertion.

Actions: Check all the parameters sent to create SAML 1.1 Assertion.

ERROR_CREATING_SAML20_ASSERTION

ID: WebServicesSecurity-6

Level: INFO

Description: Error during creation of SAML 2.0 Assertion by STS.

Data: Actual Error message

Triggers: Invalid parameters sent to create SAML 2.0 Assertion.

Actions: Check all the parameters sent to create SAML 2.0 Assertion.

IDENTITY SUBJECT NAME

ID: WebServicesSecurity-7

Level: INFO

Description: Security token being created for this Identity.

Data: Subject or Identity of the token

ATTR MAP FOR SP

ID: WebServicesSecurity-8

Level: INFO

Description: Security token being created with this Attribute Map for Service

Provider.

Data: Attribute Map required by Service Provider

Triggers: Service Provider needs Attributes to be populated in Security

token.

SUCCESS VALIDATE REQUEST

ID: WebServicesSecurity-9

Level: INFO

Description: Successfully validated the incoming SOAP request.

Data: Provider name to identify the STS service or WSP profile, Security

Mechanism or authentication token sent by client

REQUEST_TO BE VALIDATED

ID: WebServicesSecurity-10

Level: FINE

Description: Incoming SOAP request to be validated.

Data: Complete SOAP request

RESPONSE TO BE SECURED

ID: WebServicesSecurity-11

Level: FINE

Description: Outgoing SOAP response to be secured.

Data: Complete SOAP response

SUCCESS SECURE RESPONSE

ID: WebServicesSecurity-12

Level: INFO

Description: Successfully secured the outgoing SOAP response.

Data: Provider name to identify the STS service or WSP profile

REQUEST TO BE SECURED

ID: WebServicesSecurity-13

Level: FINE

Description: Outgoing SOAP request to be secured.

Data: Complete SOAP request

SUCCESS SECURE REQUEST

ID: WebServicesSecurity-14

Level: INFO

Description: Successfully secured the outgoing SOAP request.

Data: Provider name to identify the STS client or WSC profile, Security

Mechanism or authentication token sent by client

RESPONSE TO BE VALIDATED

ID: WebServicesSecurity-15

Level: FINE

Description: Incoming SOAP response to be validated.

Data: Complete SOAP response

SUCCESS VALIDATE RESPONSE

ID: WebServicesSecurity-16

Level: INFO

Description: Successfully validated the incoming SOAP response.

Data: Provider name to identify the STS client or WSC profile

AUTHENTICATION FAILED

ID: WebServicesSecurity-17

Level: INFO

Description: Authentication of the incoming SOAP request failed at server or WSP.

Data: Security Mechanism or Security token sent by client

Triggers: Invalid Security Mechanism or Security token sent by client.

Actions: Check Security Mechanism or Security token sent by client.

ERROR PARSING SOAP HEADERS

ID: WebServicesSecurity-18

Level: INFO

Description: Error in parsing SOAP headers from incoming SOAP request.

Data: Actual error message

Triggers: Client has sent incorrect SOAP headers.

Actions: Check SOAP headers.

ERROR ADDING SECURITY HEADER

ID: WebServicesSecurity-19

Level: INFO

Description: Error in adding Security header in outgoing SOAP request.

Data: Actual error message

Triggers: Error in adding namespaces or creating Security Header element.

Actions: Check namespaces and Secuirty Header.

SIGNATURE VALIDATION FAILED

ID: WebServicesSecurity-20

Level: INFO

Description: Signature validation failed in incoming SOAP request / response.

Data: Actual error message

Triggers: Error in signing request / response by client / server.

Actions: Check keystore and certificate used for signing.

UNABLE TO SIGN

ID: WebServicesSecurity-21

Level: INFO

Description: Unable to sign SOAP request or response.

Data: Actual error message

Triggers: Error in retrieving certificate from the keystore.

Actions: Check keystore configuration and certificate used for signing.;

Check debug file for detailed info.

UNABLE TO ENCRYPT

ID: WebServicesSecurity-22

Level: INFO

Description: Unable to encrypt SOAP request or response.

Data: Actual error message

Triggers: Error in retrieving certificate from the keystore.

Actions: Check keystore configuration and certificate used for encryption.;

Check debug file for detailed info.

UNABLE TO DECRYPT

ID: WebServicesSecurity-23

Level: INFO

Description: Unable to decrypt SOAP request or response.

Data: Actual error message

Triggers: Error in retrieving certificate from the keystore.

Actions: Check keystore configuration and certificate used for decryption.;

Check debug file for detailed info.

SUCCESS RETRIEVING TOKEN FROM STS

ID: WebServicesSecurity-24

Level: INFO

Description: Successfully retrieved Security Token from STS service.

Data: Web Service Provider end point for which Security Token being generated, Security Token Service end point to which STS client talks to, Security Token Service MEX end point address, End user credential (if "null"

then the Identity of the generated Security token is Web Service Client, else it is owned by Authenticated End user), Key Type, Token Type

Triggers: All the required input data parameters are correct.

ERROR_RETRIEVING_TOKEN_FROM_STS

ID: WebServicesSecurity-25

Level: INFO

Description: Error in retrieving Security Token from STS service.

Data: Actual error message

Triggers: Some or more required input data parameters are not correct.

Actions: Check all the required input data parameters.; Check debug file for detailed error.

ERROR RETRIEVING TOKEN FROM STS

ID: WebServicesSecurity-26

Level: SEVERE

Description: Error in retrieving Security Token from STS service.

Data: Actual error message

Triggers: Some or more required input data parameters are not correct.

Actions: Check all the required input data parameters.; Check debug file for detailed error.

ERROR CREATING SAML11 ASSERTION

ID: WebServicesSecurity-27

Level: SEVERE

Description: Error during creation of SAML 1.1 Assertion by STS.

Data: Actual Error message

Triggers: Invalid parameters sent to create SAML 1.1 Assertion.

Actions: Check all the parameters sent to create SAML 1.1 Assertion.; Check debug file for detailed error.

ERROR CREATING SAML20 ASSERTION

ID: WebServicesSecurity-28

Level: SEVERE

Description: Error during creation of SAML 2.0 Assertion by STS.

Data: Actual Error message

Triggers: Invalid parameters sent to create SAML 2.0 Assertion.

Actions: Check all the parameters sent to create SAML 2.0 Assertion.; Check debug file for detailed error.

OpenAM logs the following AUTHENTICATION messages.

LOGIN SUCCESS

ID: AUTHENTICATION-100

Level: INFO

Description: Authentication is Successful

Data: message, no session

Triggers: User authenticated with valid credentials

LOGIN SUCCESS USER

ID: AUTHENTICATION-101

Level: INFO

Description: User based authentication is successful

Data: message, authentication type, user name, no session

Triggers: User authenticated with valid credentials

LOGIN SUCCESS ROLE

ID: AUTHENTICATION-102

Level: INFO

Description: Role based authentication is successful

Data: message, authentication type, role name, no session

Triggers: User belonging to role authenticated with valid credentials

LOGIN SUCCESS SERVICE

ID: AUTHENTICATION-103

Level: INFO

Description: Service based authentication is successful

Data: message, authentication type, service name, no session

Triggers: User authenticated with valid credentials to a configured service under realm

LOGIN SUCCESS LEVEL

ID: AUTHENTICATION-104

Level: INFO

Description: Authentication level based authentication is successful

Data: message, authentication type, authentication level value, no session

Triggers: User authenticated with valid credentials to one or more authentication modules having authentication level value greater than or equal to specified authentication level

LOGIN SUCCESS MODULE INSTANCE

ID: AUTHENTICATION-105

Level: INFO

Description: Module based authentication is successful

Data: message, authentication type, module name, no session

Triggers: User authenticated with valid credentials to authentication module under realm

LOGIN FAILED

ID: AUTHENTICATION-200

Level: INFO

Description: Authentication Failed

Data: error message

Triggers: Incorrect/invalid credentials presented; User locked out/not active

Actions: Enter correct/valid credentials to required authentication module

LOGIN FAILED INVALIDPASSWORD

ID: AUTHENTICATION-201

Level: INFO

Description: Authentication Failed

Data: error message

Triggers: Invalid credentials entered.

Actions: Enter the correct password.

LOGIN_FAILED_NOCONFIG

ID: AUTHENTICATION-202

Level: INFO

Description: Authentication Failed

Data: error message

Triggers: Named Configuration (Auth Chain) does not exist.

Actions: Create and configure a named config for this org.

LOGIN FAILED NOUSERPROFILE

ID: AUTHENTICATION-203

Level: INFO

Description: Authentication Failed

Data: error message

Triggers: No user profile found for this user.

Actions: User does not exist in the datastore plugin configured and hence

configure the datastore plugin for this realm/org correctly.

$LOGIN_FAILED_USERINACTIVE$

ID: AUTHENTICATION-204

Level: INFO

Description: Authentication Failed

Data: error message

Triggers: This user is not active.

Actions: Activate the user.

LOGIN_FAILED_LOCKEDOUT

ID: AUTHENTICATION-205

Level: INFO

Description: Authentication Failed

Data: error message

Triggers: Max number of failure attempts exceeded. User is Locked out.

Actions: Contact system administrator.

LOGIN_FAILED_ACCOUNTEXPIRED

ID: AUTHENTICATION-206

Level: INFO

Description: Authentication Failed

Data: error message

Triggers: User account has expired.

Actions: Contact system administrator.

LOGIN_FAILED_LOGINTIMEOUT

ID: AUTHENTICATION-207

Level: INFO

Description: Authentication Failed

Data: error message

Triggers: Login timed out.

Actions: Try to login again.

LOGIN_FAILED_MODULEDENIED

ID: AUTHENTICATION-208

Level: INFO

Description: Authentication Failed

Data: error message

Triggers: Authentication module is denied.

Actions: Configure this module or use some other module.

LOGIN FAILED MAXSESSIONREACHED

ID: AUTHENTICATION-209

Level: INFO

Description: Authentication Failed

Data: error message

Triggers: Limit for maximum number of allowed session has been reached.

Actions: Logout of a session or increase the limit.

LOGIN_FAILED_INVALIDDOMAIN

ID: AUTHENTICATION-210

Level: INFO

Description: Authentication Failed

Data: error message

Triggers: Org/Realm does not exists.

Actions: Use a valid Org/Realm.

LOGIN_FAILED_ORGINACTIVE

ID: AUTHENTICATION-211

Level: INFO

Description: Authentication Failed

Data: error message

Triggers: Org/Realm is not active.

Actions: Activate the Org/Realm.

LOGIN_FAILED_SESSIONCREATEERROR

ID: AUTHENTICATION-212

Level: INFO

Description: Authentication Failed

Data: error message

Triggers: Cannot create a session.

Actions: Ensure that session service is configured and maxsession is not

reached.

LOGIN FAILED USER

ID: AUTHENTICATION-213

Level: INFO

Description: User based authentication failed

Data: error message, authentication type, user name

Triggers: No authentication configuration (chain of one or more authentication modules) configured for user; Incorrect/invalid credentials presented; User locked out/not active

Actions: Configure authentication configuration (chain of one or more authentication modules) for user; Enter correct/valid credentials to required authentication module

LOGIN FAILED USER INVALIDPASSWORD

ID: AUTHENTICATION-214

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, user name

Triggers: User based Auth. Invalid credentials entered.

Actions: Enter the correct password.

LOGIN_FAILED_USER_NOCONFIG

ID: AUTHENTICATION-215

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, user name

Triggers: Named Configuration (Auth Chain) does not exist for this user

Actions: Create and configure a named config for this user

LOGIN FAILED USER NOUSERPROFILE

ID: AUTHENTICATION-216

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, user name

Triggers: User based Auth. No user profile found for this user.

Actions: User does not exist in the datastore plugin configured and hence configure the datastore plugin for this realm/org correctly.

LOGIN_FAILED_USER_USERINACTIVE ID: AUTHENTICATION-217

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, user name

Triggers: User based Auth. This user is not active.

Actions: Activate the user.

LOGIN FAILED USER LOCKEDOUT

ID: AUTHENTICATION-218

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, user name

Triggers: User based Auth. Max number of failure attempts exceeded. User is

Locked out.

Actions: Contact system administrator.

LOGIN FAILED USER ACCOUNTEXPIRED

ID: AUTHENTICATION-219

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, user name

Triggers: User based Auth. User account has expired.

Actions: Contact system administrator.

LOGIN_FAILED_USER_LOGINTIMEOUT

ID: AUTHENTICATION-220

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, user name

Triggers: User based Auth. Login timed out.

Actions: Try to login again.

LOGIN FAILED USER MODULEDENIED

ID: AUTHENTICATION-221

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, user name

Triggers: User based Auth. Authentication module is denied.

Actions: Configure this module or use some other module.

LOGIN FAILED USER MAXSESSIONREACHED

ID: AUTHENTICATION-222

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, user name

Triggers: User based auth. Limit for maximum number of allowed session has

been reached.

Actions: Logout of a session or increase the limit.

LOGIN_FAILED_USER_INVALIDDOMAIN

ID: AUTHENTICATION-223

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, user name

Triggers: User based auth. Org/Realm does not exists.

Actions: Use a valid Org/Realm.

LOGIN FAILED USER ORGINACTIVE

ID: AUTHENTICATION-224

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, user name

Triggers: User based auth. Org/Realm is not active.

Actions: Activate the Org/Realm.

LOGIN_FAILED_USER_SESSIONCREATEERROR

ID: AUTHENTICATION-225

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, user name

Triggers: User based auth. Cannot create a session.

Actions: Ensure that session service is configured and maxsession is not

reached.

LOGIN FAILED ROLE

ID: AUTHENTICATION-226

Level: INFO

Description: Role based authentication failed

Data: error message, authentication type, role name

Triggers: No authentication configuration (chain of one or more authentication modules) configured for role; Incorrect/invalid credentials presented; User does not belong to this role; User locked out/not active

Actions: Configure authentication configuration (chain of one or more authentication modules) for role; Enter correct/valid credentials to required authentication module; Assign this role to the authenticating user

$LOGIN_FAILED_ROLE_INVALIDPASSWORD$

ID: AUTHENTICATION-227

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, role name

Triggers: Role based Auth. Invalid credentials entered.

Actions: Enter the correct password.

LOGIN_FAILED_ROLE_NOCONFIG

ID: AUTHENTICATION-228

Description: Authentication Failed

Data: error message, authentication type, role name

Triggers: Named Configuration (Auth Chain) does not exist for this role.

Actions: Create and configure a named config for this role.

LOGIN FAILED ROLE NOUSERPROFILE

ID: AUTHENTICATION-229

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, role name

Triggers: Role based Auth. No user profile found for this user.

Actions: User does not exist in the datastore plugin configured and hence configure the datastore plugin for this realm/org correctly.

LOGIN FAILED ROLE USERINACTIVE

ID: AUTHENTICATION-230

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, role name

Triggers: Role based Auth. This user is not active.

Actions: Activate the user.

LOGIN FAILED ROLE LOCKEDOUT

ID: AUTHENTICATION-231

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, role name

Triggers: Role based Auth. Max number of failure attempts exceeded. User is

Locked out.

Actions: Contact system administrator.

LOGIN_FAILED_ROLE_ACCOUNTEXPIRED ID: AUTHENTICATION-232

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, role name

Triggers: Role based Auth. User account has expired.

Actions: Contact system administrator.

LOGIN FAILED ROLE LOGINTIMEOUT

ID: AUTHENTICATION-233

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, role name

Triggers: Role based Auth. Login timed out.

Actions: Try to login again.

LOGIN FAILED ROLE MODULEDENIED

ID: AUTHENTICATION-234

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, role name

Triggers: Role based Auth. Authentication module is denied.

Actions: Configure this module or use some other module.

LOGIN FAILED ROLE MAXSESSIONREACHED

ID: AUTHENTICATION-235

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, role name

Triggers: Role based auth. Limit for maximum number of allowed session has

been reached.

Actions: Logout of a session or increase the limit.

$LOGIN_FAILED_ROLE_INVALIDDOMAIN$

ID: AUTHENTICATION-236

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, role name

Triggers: Role based auth. Org/Realm does not exists.

Actions: Use a valid Org/Realm.

LOGIN FAILED ROLE ORGINACTIVE

ID: AUTHENTICATION-237

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, role name

Triggers: Role based auth. Org/Realm is not active.

Actions: Activate the Org/Realm.

LOGIN FAILED ROLE SESSIONCREATEERROR

ID: AUTHENTICATION-238

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, role name

Triggers: Role based auth. Cannot create a session.

Actions: Ensure that session service is configured and maxsession is not

reached.

LOGIN FAILED ROLE USERNOTFOUND

ID: AUTHENTICATION-239

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, role name

Triggers: Role based auth. User does not belong to this role.

Actions: Add the user to this role.

LOGIN FAILED SERVICE

ID: AUTHENTICATION-240

Level: INFO

Description: Service based authentication failed

Data: error message, authentication type, service name

Triggers: No authentication configuration (chain of one or more authentication modules) configured for service; Incorrect/invalid credentials presented; User locked out/not active

Actions: Configure authentication configuration (chain of one or more authentication modules) for service; Enter correct/valid credentials to required authentication module

$LOGIN_FAILED_SERVICE_INVALIDPASSWORD$

ID: AUTHENTICATION-241

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, service name

Triggers: Service based Auth. Invalid credentials entered.

Actions: Enter the correct password.

LOGIN FAILED SERVICE NOCONFIG

ID: AUTHENTICATION-242

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, service name

Triggers: Named Configuration (Auth Chain) does not exist with this service

name.

Actions: Create and configure a named config.

LOGIN FAILED SERVICE NOUSERPROFILE

ID: AUTHENTICATION-243

Description: Authentication Failed

Data: error message, authentication type, service name

Triggers: Service based Auth. No user profile found for this user.

Actions: User does not exist in the datastore plugin configured and hence configure the datastore plugin for this realm/org correctly.

LOGIN FAILED SERVICE USERINACTIVE

ID: AUTHENTICATION-244

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, service name

Triggers: Service based Auth. This user is not active.

Actions: Activate the user.

LOGIN FAILED SERVICE LOCKEDOUT

ID: AUTHENTICATION-245

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, service name

Triggers: Service based Auth. Max number of failure attempts exceeded.

User is Locked out.

Actions: Contact system administrator.

LOGIN FAILED SERVICE ACCOUNTEXPIRED

ID: AUTHENTICATION-246

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, service name

Triggers: Service based Auth. User account has expired.

Actions: Contact system administrator.

LOGIN_FAILED_SERVICE_LOGINTIMEOUT ID: AUTHENTICATION-247

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, service name

Triggers: Service based Auth. Login timed out.

Actions: Try to login again.

LOGIN FAILED SERVICE MODULEDENIED

ID: AUTHENTICATION-248

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, service name

Triggers: Service based Auth. Authentication module is denied.

Actions: Configure this module or use some other module.

LOGIN FAILED SERVICE NOSERVICE

ID: AUTHENTICATION-249

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, service name

Triggers: Service based Auth. Service does not exist.

Actions: Please use only valid Service.

LOGIN FAILED_SERVICE_MAXSESSIONREACHED

ID: AUTHENTICATION-250

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, service name

 $\label{thm:continuous} \mbox{Triggers: Service based auth. Limit for maximum number of allowed session}$

has been reached.

Actions: Logout of a session or increase the limit.

LOGIN_FAILED_SERVICE_INVALIDDOMAIN

ID: AUTHENTICATION-251

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, service name

Triggers: Service based auth. Org/Realm does not exists.

Actions: Use a valid Org/Realm.

LOGIN FAILED SERVICE ORGINACTIVE

ID: AUTHENTICATION-252

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, service name

Triggers: Service based auth. Org/Realm is not active.

Actions: Activate the Org/Realm.

LOGIN FAILED SERVICE SESSIONCREATEERROR

ID: AUTHENTICATION-253

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, service name

Triggers: Service based auth. Cannot create a session.

Actions: Ensure that session service is configured and maxsession is not

reached.

LOGIN FAILED LEVEL

ID: AUTHENTICATION-254

Level: INFO

Description: Authentication level based authentication failed

Data: error message, authentication type, authentication level value

Triggers: There are no authentication module(s) having authentication level value greater than or equal to specified authentication level; Incorrect/invalid credentials presented to one or more authentication modules having authentication level greater than or equal to specified authentication level; User locked out/not active

Actions: Configure one or more authentication modules having authentication level value greater than or equal to required authentication level; Enter correct/valid credentials to one or more authentication modules having authentication level greater than or equal to specified authentication level

LOGIN FAILED LEVEL INVALIDPASSWORD

ID: AUTHENTICATION-255

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, authentication level value

Triggers: Level based Auth. Invalid credentials entered.

Actions: Enter the correct password.

LOGIN_FAILED_LEVEL_NOCONFIG

ID: AUTHENTICATION-256

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, authentication level value

Triggers: Level based Auth. No Auth Configuration available.

Actions: Create an auth configuration.

LOGIN FAILED LEVEL NOUSERPROFILE

ID: AUTHENTICATION-257

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, authentication level value

Triggers: Level based Auth. No user profile found for this user.

Actions: User does not exist in the datastore plugin configured and hence configure the datastore plugin for this realm/org correctly.

LOGIN_FAILED_LEVEL_USERINACTIVE

ID: AUTHENTICATION-258

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, authentication level value

Triggers: Level based Auth. This user is not active.

Actions: Activate the user.

LOGIN FAILED LEVEL LOCKEDOUT

ID: AUTHENTICATION-259

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, authentication level value

Triggers: Level based Auth. Max number of failure attempts exceeded. User

is Locked out.

Actions: Contact system administrator.

LOGIN FAILED LEVEL ACCOUNTEXPIRED

ID: AUTHENTICATION-260

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, authentication level value

Triggers: Level based Auth. User account has expired.

Actions: Contact system administrator.

LOGIN FAILED LEVEL LOGINTIMEOUT

ID: AUTHENTICATION-261

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, authentication level value

Triggers: Level based Auth. Login timed out.

Actions: Try to login again.

LOGIN FAILED LEVEL MODULEDENIED

ID: AUTHENTICATION-262

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, authentication level value

Triggers: Level based Auth. Authentication module is denied.

Actions: Configure this module or use some other module.

LOGIN FAILED LEVEL INCORRECTLEVEL

ID: AUTHENTICATION-263

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, authentication level value

Triggers: Level based Auth. Invalid Authg Level.

Actions: Please specify valid auth level.

LOGIN FAILED LEVEL MAXSESSIONREACHED

ID: AUTHENTICATION-264

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, authentication level value

Triggers: Level based auth. Limit for maximum number of allowed session

has been reached.

Actions: Logout of a session or increase the limit.

LOGIN_FAILED_LEVEL_INVALIDDOMAIN

ID: AUTHENTICATION-265

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, authentication level value

Triggers: Level based auth. Org/Realm does not exists.

Actions: Use a valid Org/Realm.

LOGIN FAILED LEVEL ORGINACTIVE

ID: AUTHENTICATION-266

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, authentication level value

Triggers: Level based auth. Org/Realm is not active.

Actions: Activate the Org/Realm.

LOGIN FAILED LEVEL SESSIONCREATEERROR

ID: AUTHENTICATION-267

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, authentication level value

Triggers: Level based auth. Cannot create a session.

Actions: Ensure that session service is configured and maxsession is not reached.

LOGIN FAILED MODULE INSTANCE

ID: AUTHENTICATION-268

Level: INFO

Description: Module based authentication failed

Data: error message, authentication type, module name

 $Triggers: Module \ is \ not \ registered/configured \ under \ realm; \ Incorrect/invalid$

credentials presented; User locked out/not active

Actions: Register/configure authentication module under realm; Enter

correct/valid credentials to authentication module

LOGIN_FAILED_MODULE_INSTANCE_INVALIDPASSWORD

ID: AUTHENTICATION-269

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, module name

Triggers: Module based Auth. Invalid credentials entered.

Actions: Enter the correct password.

LOGIN FAILED MODULE INSTANCE NOUSERPROFILE

ID: AUTHENTICATION-270

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, module name

Triggers: Module based Auth. No user profile found for this user.

Actions: User does not exist in the datastore plugin configured and hence configure the datastore plugin for this realm/org correctly.

LOGIN_FAILED_MODULE_INSTANCE_USERINACTIVE ID: AUTHENTICATION-271

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, module name

Triggers: Module based Auth. This user is not active.

Actions: Activate the user.

LOGIN FAILED MODULE INSTANCE LOCKEDOUT

ID: AUTHENTICATION-272

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, module name

Triggers: Module based Auth. Max number of failure attempts exceeded.

User is Locked out.

Actions: Contact system administrator.

LOGIN FAILED MODULE INSTANCE ACCOUNTEXPIRED

ID: AUTHENTICATION-273

Description: Authentication Failed

Data: error message, authentication type, module name

Triggers: Module based Auth. User account has expired.

Actions: Contact system administrator.

LOGIN_FAILED_MODULE_INSTANCE_LOGINTIMEOUT ID: AUTHENTICATION-274

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, module name

Triggers: Module based Auth. Login timed out.

Actions: Try to login again.

LOGIN_FAILED_MODULE_INSTANCE_MODULEDENIED ID: AUTHENTICATION-275

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, module name

Triggers: Module based Auth. Authentication module is denied.

Actions: Configure this module or use some other module.

LOGIN_FAILED_MODULE_INSTANCE_MAXSESSIONREACHED ID: AUTHENTICATION-276

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, module name

 $\label{thm:continuous} \mbox{Triggers: Module based auth. Limit for maximum number of allowed session}$

has been reached.

Actions: Logout of a session or increase the limit.

LOGIN_FAILED_MODULE_INSTANCE_INVALIDDOMAIN ID: AUTHENTICATION-277

Description: Authentication Failed

Data: error message, authentication type, module name

Triggers: Module based auth. Org/Realm does not exists.

Actions: Use a valid Org/Realm.

LOGIN_FAILED_MODULE_INSTANCE_ORGINACTIVE

ID: AUTHENTICATION-278

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, module name

Triggers: Module based auth. Org/Realm is not active.

Actions: Activate the Org/Realm.

LOGIN_FAILED_MODULE_INSTANCE_SESSIONCREATEERROR

ID: AUTHENTICATION-279

Level: INFO

Description: Authentication Failed

Data: error message, authentication type, module name

Triggers: Module based auth. Cannot create a session.

Actions: Ensure that session service is configured and maxsession is not

reached.

LOGOUT

ID: AUTHENTICATION-300

Level: INFO

Description: User logout is Successful

Data: message

Triggers: User logged out

LOGOUT USER

ID: AUTHENTICATION-301

Description: User logout is successful from user based authentication

Data: message, authentication type, user name

Triggers: User logged out

LOGOUT ROLE

ID: AUTHENTICATION-302

Level: INFO

Description: User logout is successful from role based authentication

Data: message, authentication type, role name

Triggers: User belonging to this role logged out

LOGOUT SERVICE

ID: AUTHENTICATION-303

Level: INFO

Description: User logout is successful from service based authentication

Data: message, authentication type, service name

Triggers: User logged out of a configured service under realm

LOGOUT LEVEL

ID: AUTHENTICATION-304

Level: INFO

 $Description: User\ logout\ is\ successful\ from\ authentication\ level\ based$

authentication

Data: message, authentication type, authentication level value

Triggers: User logged out of one or more authentication modules having authentication level value greater than or equal to specified authentication

level

LOGOUT MODULE INSTANCE

ID: AUTHENTICATION-305

Level: INFO

Description: User logout is successful from module based authentication

Data: message, authentication type, module name

Triggers: User logged out of authentication module under realm

CHANGE USER PASSWORD FAILED

ID: AUTHENTICATION-306

Level: INFO

Description: Change user password failed

Data: error message, authentication type, user name

Triggers: Change user password in authentication screen due to directory

server password policy.

Actions: Enter password which meets directory server password policy

CHANGE USER PASSWORD SUCCEEDED

ID: AŪTHENTICATION-307

Level: INFO

Description: Changing user password succeeded

Data: message

Triggers: Change user password in authentication screen due to directory

server password policy.

CREATE USER PROFILE FAILED

ID: AUTHENTICATION-308

Level: INFO

Description: Create user password failed

Data: error message, user name

Triggers: Create new user in Membership module

Actions: Make sure password entered meets directory server password policy

OpenAM logs the following AMCLI messages.

ATTEMPT LOGIN

ID: AMCLI-1

Level: INFO

Description: Attempt to login to execute the commandline.

Data: user ID

Triggers: Run the Commandline tool.

SUCCEED_LOGIN

ID: AMCLI-2

Level: INFO

Description: Login to execute the commandline.

Data: user ID

Triggers: Run the Commandline tool.

FAILED LOGIN

ID: AMCLI-3

Level: INFO

Description: Failed to login.

Data: user ID, error message

Triggers: Run the Commandline tool.

Actions: Check your user ID and password.; Look under debug file for more

information.

ATTEMPT_LOAD_SCHEMA

ID: AMCLI-20

Level: INFO

Description: Attempt to load schema to data store.

Data: XML file name

Triggers: Load Schema through Commandline interface.

SUCCESS LOAD SCHEMA

ID: AMCLI-21

Level: INFO

Description: Schema is loaded to data store.

Data: XML file name

Triggers: Load Schema through Commandline interface.

FAILED LOAD SCHEMA

ID: ĀMCLI-22

Level: SEVERE

Description: Schema is not loaded to data store.

Data: XML file name, error message

Triggers: Load Schema through Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_DELETE_SERVICE

ID: AMCLI-30

Level: INFO

Description: Attempt to delete service from data store.

Data: service name

Triggers: Delete Service through Commandline interface.

SUCCESS DELETE SERVICE

ID: AMCLI-31

Level: INFO

Description: Deleted service from data store.

Data: service name

Triggers: Delete Service through Commandline interface.

FAILED DELETE SERVICE

ID: AMCLI-32

Level: SEVERE

Description: Schema is not loaded to data store.

Data: service name, error message

Triggers: Delete Service Schema through Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_ADD_ATTRIBUTE_SCHEMA

ID: AMCLI-40

Description: Attempt to attribute schema to an existing service.

Data: service name, schema type, XML file name

Triggers: Add attribute schema through Commandline interface.

SUCCESS_ADD_ATTRIBUTE SCHEMA

ID: AMCLI-41

Level: INFO

Description: Added attribute schema to existing service.

Data: service name, schema type, XML file name

Triggers: Add attribute schema through Commandline interface.

FAILED_ADD_ATTRIBUTE_SCHEMA ID: AMCLI-42

Level: SEVERE

Description: Attribute schema is not added to existing service.

Data: service name, schema type, XML file name, error message

Triggers: Add attribute schema through Commandline interface.

Actions: Check the service name, schema type and XML file.; Look under debug file for more information.

ATTEMPT ADD RESOURCE BUNDLE

ID: AMCLI-50

Level: INFO

Description: Attempt to add resource bundle to data store.

Data: resource bundle name, file name, locale

Triggers: Add Resource Bundle through Commandline interface.

SUCCEED ADD RESOURCE BUNDLE

ID: AMCLI-51

Level: INFO

Description: Resource bundle is added to data store.

Data: resource bundle name, file name, locale

Triggers: Add Resource Bundle through Commandline interface.

FAILED ADD RESOURCE BUNDLE

ID: AMCLI-52

Level: SEVERE

Description: Failed to add resource bundle to data store.

Data: resource bundle name, file name, locale, error message

Triggers: SDK for adding resource bundle failed.

Actions: Look under debug file for more information.

ATTEMPT_GET_RESOURCE_BUNDLE

ID: AMCLI-60

Level: INFO

Description: Attempt to get resource bundle from data store.

Data: resource bundle name, locale

Triggers: Get Resource Bundle through Commandline interface.

SUCCEED_GET_RESOURCE_BUNDLE

ID: AMCLI-61

Level: INFO

Description: Resource bundle retrieved from data store.

Data: resource bundle name, locale

Triggers: Get Resource Bundle through Commandline interface.

FAILED GET RESOURCE BUNDLE

ID: AMCLI-62

Level: SEVERE

Description: Failed to get resource bundle from data store.

Data: resource bundle name, locale, error message

Triggers: SDK for getting resource bundle failed.

Actions: Look under debug file for more information.

ATTEMPT_DELETE_RESOURCE_BUNDLE ID: AMCLI-70

Level: INFO

Description: Attempt to delete resource bundle from data store.

Data: resource bundle name, locale

Triggers: Delete Resource Bundle through Commandline interface.

SUCCEED DELETE RESOURCE BUNDLE

ID: AMCLI-71

Level: INFO

Description: Resource bundle deleted from data store.

Data: resource bundle name, locale

Triggers: Delete Resource Bundle through Commandline interface.

FAILED_DELETE_RESOURCE_BUNDLE

ID: AMCLI-72

Level: SEVERE

Description: Failed to delete resource bundle from data store.

Data: resource bundle name, locale, error message

Triggers: SDK for deleting resource bundle failed.

Actions: Look under debug file for more information.

ATTEMPT SESSION DESTROY

ID: AMCLI-100

Level: INFO

Description: Attempt to destroy Session destroyed

Data: name of user

Triggers: Administrator invalidates session via Commandline interface.

SUCCEED SESSION DESTROY

ID: AMCLI-101

Level: INFO

Log Messages

Description: Session destroyed

Data: name of user

Triggers: Administrator invalidates session via Commandline interface.

FAILED SESSION DESTROY

ID: AMCLI-102

Level: SEVERE

Description: Failed to destroy session

Data: name of user, error message

Triggers: Session cannot be destroyed.

Actions: Look under debug file for more information.

ATTEMPT_MIGRATION ENTRY

ID: AMCLI-1000

Level: INFO

Description: Attempt to migration organization to realm/

Data: distinguished name of organization

Triggers: Migration Commandline interface.

SUCCEED_MIGRATION_ENTRY ID: AMCLI-1001

Level: INFO

Description: Migration completed.

Data: distinguished name of organization

Triggers: Migration Commandline interface.

ATTEMPT DELETE REALM

ID: AMCLI-2000

Level: INFO

Description: Attempt to delete realm/

Data: name of realm, recursive

Triggers: Delete realm command through Commandline interface.

SUCCEED_DELETE_REALM ID: AMCLI-2001

Level: INFO

Description: Realm deleted.

Data: name of realm, recursive

Triggers: Delete realm command through Commandline interface.

FAILED DELETE REALM

ID: AMCLI-2002

Level: INFO

Description: Failed to delete realm.

Data: name of realm, recursive, error message

Triggers: Delete realm command through Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT CREATE REALM

ID: AMCLI-2010

Level: INFO

Description: Attempt to create realm/

Data: name of realm

Triggers: Create realm command through Commandline interface.

SUCCEED CREATE REALM

ID: AMCLI-2011

Level: INFO

Description: Realm created.

Data: name of realm

Triggers: Create realm command through Commandline interface.

FAILED CREATE REALM

ID: AMCLI-2012

Level: INFO

Log Messages

Description: Failed to create realm.

Data: name of realm, error message

Triggers: Create realm command through Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SEARCH_REALM

ID: AMCLI-3020

Level: INFO

Description: Attempt to search for realms by name.

Data: name of realm, search pattern, recursive

Triggers: Search realms command through Commandline interface.

SUCCEED_SEARCH_REALM

ID: AMCLI-3021

Level: INFO

Description: Completed searching for realms.

Data: name of realm, search pattern, recursive

Triggers: Search realms command through Commandline interface.

FAILED SEARCH REALM

ID: AMCLI-3022

Level: INFO

Description: Search for realms failed.

Data: name of realm, search pattern, recursive, error message

Triggers: Search realms command through Commandline interface.

Actions: Look under debug file for more information.

$ATTEMPT_GET_ASSIGNABLE_SERVICES_OF_REALM$

ID: AMCLI-2020

Level: INFO

Description: Attempt to get assignable services of realm.

Data: name of realm

Log Messages

Triggers: Execute get assignable services of realm Commandline interface.

SUCCEED_GET_ASSIGNABLE_SERVICES_OF_REALM

ID: AMCLI-2021

Level: INFO

Description: Assignable services command is serviced.

Data: name of realm

Triggers: Execute get assignable services of realm Commandline interface.

FAILED_GET_ASSIGNABLE_SERVICES_OF_REALM

ID: AMCLI-2022

Level: INFO

Description: Unable to get assignable services of realm.

Data: name of realm, error message

Triggers: Execute get assignable services of realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_GET_ASSIGNED_SERVICES_OF_REALM

ID: AMCLI-2030

Level: INFO

Description: Attempt to get services assigned to a realm.

Data: name of realm, include mandatory services

Triggers: Execute get services assigned to realm Commandline interface.

SUCCEED GET ASSIGNED SERVICES OF REALM

ID: AMCLI-2031

Level: INFO

Description: Assignable services command is serviced.

Data: name of realm, include mandatory services

Triggers: Execute get services assigned to realm Commandline interface.

FAILED_GET_ASSIGNED_SERVICES_OF_REALM

ID: AMCLI-2032

Description: Unable to get services assigned to realm.

Data: name of realm, include mandatory services, error message

Triggers: Execute get services assigned to realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_ASSIGN_SERVICE TO REALM

ID: AMCLI-2040

Level: INFO

Description: Attempt to assign service to a realm.

Data: name of realm, name of service

Triggers: Execute assign service to realm Commandline interface.

SUCCEED_ASSIGN_SERVICE_TO_REALM

ID: AMCLI-2041

Level: INFO

Description: Service is assigned to realm.

Data: name of realm, name of service

Triggers: Execute assign service to realm Commandline interface.

FAILED ASSIGN SERVICE TO REALM

ID: AMCLI-2042

Level: INFO

Description: Unable to assign service to realm.

Data: name of realm, name of service, error message

Triggers: Execute assign service to realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT UNASSIGN SERVICE FROM REALM

ID: AMCLI-2050

Level: INFO

Description: Attempt to unassign service from a realm.

Data: name of realm, name of service

Triggers: Execute unassign service from realm Commandline interface.

SUCCEED_UNASSIGN_SERVICE_FROM_REALM

ID: AMCLI-2051

Level: INFO

Description: Service is unassigned from realm.

Data: name of realm, name of service

Triggers: Execute unassign service from realm Commandline interface.

FAILED UNASSIGN SERVICE FROM REALM

ID: AMCLI-2052

Level: INFO

Description: Unable to unassign service from realm.

Data: name of realm, name of service, error message

Triggers: Execute unassign service from realm Commandline interface.

Actions: Look under debug file for more information.

$ATTEMPT_GET_REALM_SERVICE_ATTR_VALUES$

ID: AMCLI-2060

Level: INFO

Description: Attempt to get service attribute values from a realm.

Data: name of realm, name of service

Triggers: Execute get service attribute values from realm Commandline

interface.

SUCCEED_GET_REALM_SERVICE_ATTR VALUES

ID: AMCLI-2061

Level: INFO

Description: Service attribute values of realm is returneed.

Data: name of realm, name of service

Triggers: Execute get service attribute values from realm Commandline interface.

FAILED GET REALM SERVICE ATTR VALUES

ID: AMCLI-2062

Level: INFO

Description: Unable to get service attribute values of realm.

Data: name of realm, name of service, error message

Triggers: Execute get service attribute values from realm Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT_REMOVE_REALM_ATTRIBUTE

ID: AMCLI-2070

Level: INFO

Description: Attempt to remove attribute from a realm.

Data: name of realm, name of service, name of attribute

Triggers: Execute remove attribute from realm Commandline interface.

SUCCEED_REMOVE_REALM_ATTRIBUTE

ID: AMCLI-2071

Level: INFO

Description: Attribute of realm is removed.

Data: name of realm, name of service, name of attribute

Triggers: Execute remove attribute from realm Commandline interface.

FAILED REMOVE REALM ATTRIBUTE

ID: AMCLI-2072

Level: INFO

Description: Unable to remove attribute from realm.

Data: name of realm, name of service, name of attribute, error message

Triggers: Execute remove attribute from realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_MODIFY_SERVICE_REALM ID: AMCLI-2080

Level: INFO

Description: Attempt to modify service of realm.

Data: name of realm, name of service

Triggers: Execute modify service of realm Commandline interface.

SUCCEED MODIFY SERVICE REALM

ID: AMCLI-2081

Level: INFO

Description: Attribute of realm is modified.

Data: name of realm, name of service

Triggers: Execute modify service of realm Commandline interface.

FAILED_MODIFY_SERVICE_REALM

ID: AMCLI-2082

Level: INFO

Description: Unable to modify service of realm.

Data: name of realm, name of service, error message

Triggers: Execute modify service of realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT ADD ATTR VALUES REALM

ID: AMCLI-2090

Level: INFO

Description: Attempt to add attribute value to realm.

Data: name of realm, name of service, name of attribute

Triggers: Execute add attribute values to realm Commandline interface.

SUCCEED ADD ATTR VALUES REALM

ID: AMCLI-2091

Level: INFO

Description: Attribute values is added to realm.

Data: name of realm, name of service, name of attribute

Triggers: Execute add attribute values to realm Commandline interface.

FAILED ADD ATTR VALUES REALM

ID: AMCLI-2092

Level: INFO

Description: Unable to add attribute values to realm.

Data: name of realm, name of service, name of attribute, error message

Triggers: Execute add attribute values to realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SET_ATTR_VALUES_REALM

ID: AMCLI-2100

Level: INFO

Description: Attempt to set attribute value to realm.

Data: name of realm, name of service

Triggers: Execute set attribute values to realm Commandline interface.

SUCCEED_SET_ATTR_VALUES_REALM ID: AMCLI-2101

Level: INFO

Description: Attribute values is set to realm.

Data: name of realm, name of service

Triggers: Execute set attribute values to realm Commandline interface.

FAILED SET ATTR VALUES REALM

ID: AMCLI-2102

Level: INFO

Description: Unable to set attribute values to realm.

Data: name of realm, name of service, error message

Triggers: Execute set attribute values to realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_REMOVE_SCHEMA_ATTR_DEFAULTS

ID: AMCLI-2110

Level: INFO

Description: Attempt to remove schema attribute defaults.

Data: name of service, schema type, name of sub schema, name of attribute

Triggers: Execute remove schema attribute defaults Commandline interface.

SUCCEED REMOVE SCHEMA ATTR DEFAULTS

ID: AMCLI-2111

Level: INFO

Description: Schema attribute defaults is removed.

Data: name of service, schema type, name of sub schema, name of attribute

Triggers: Execute remove schema attribute defaults Commandline interface.

FAILED REMOVE SCHEMA ATTR DEFAULTS

ID: AMCLI-2112

Level: INFO

Description: Unable to remove schema attribute defaults.

Data: name of service, schema type, name of sub schema, name of attribute,

error message

Triggers: Execute remove schema attribute defaults Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT ADD SCHEMA ATTR DEFAULTS

ID: AMCLI-2120

Level: INFO

Description: Attempt to add schema attribute defaults.

Data: name of service, schema type, name of sub schema, name of attribute

Triggers: Execute add schema attribute defaults Commandline interface.

${\tt SUCCEED_ADD_SCHEMA_ATTR_DEFAULTS}$

ID: AMCLI-2121

Description: Schema attribute defaults is added.

Data: name of service, schema type, name of sub schema, name of attribute

Triggers: Execute add schema attribute defaults Commandline interface.

FAILED ADD SCHEMA ATTR DEFAULTS

ID: AMCLI-2122

Level: INFO

Description: Unable to add schema attribute defaults.

Data: name of service, schema type, name of sub schema, name of attribute,

error message

Triggers: Execute add schema attribute defaults Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_GET_SCHEMA_ATTR_DEFAULTS

ID: AMCLI-2130

Level: INFO

Description: Attempt to get schema attribute defaults.

Data: name of service, schema type, name of sub schema

Triggers: Execute get schema attribute defaults Commandline interface.

SUCCEED GET SCHEMA ATTR DEFAULTS

ID: AMCLI-2131

Level: INFO

Description: Schema attribute defaults is returned.

Data: name of service, schema type, name of sub schema

Triggers: Execute get schema attribute defaults Commandline interface.

FAILED GET SCHEMA ATTR DEFAULTS

ID: AMCLI-2132

Level: INFO

Description: Unable to get schema attribute defaults.

Data: name of service, schema type, name of sub schema, error message

Triggers: Execute get schema attribute defaults Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SET_SCHEMA_ATTR DEFAULTS

ID: AMCLI-2140

Level: INFO

Description: Attempt to set schema attribute defaults.

Data: name of service, schema type, name of sub schema

Triggers: Execute set schema attribute defaults Commandline interface.

SUCCEED SET SCHEMA ATTR DEFAULTS

ID: AMCLI-2141

Level: INFO

Description: Schema attribute defaults is set.

Data: name of service, schema type, name of sub schema

Triggers: Execute set schema attribute defaults Commandline interface.

FAILED SET SCHEMA ATTR DEFAULTS

ID: AMCLI-2142

Level: INFO

Description: Unable to set schema attribute defaults.

Data: name of service, schema type, name of sub schema, error message

Triggers: Execute set schema attribute defaults Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_ADD_ATTRIBUTE_SCHEMA_CHOICE_VALUES

ID: AMCLI-2150

Level: INFO

Description: Attempt to add choice value to attribute schema.

Data: name of service, schema type, name of sub schema, name of attribute schema

Triggers: Execute add attribute schema choice values Commandline interface.

SUCCEED_ADD_ATTRIBUTE_SCHEMA_CHOICE_VALUES

ID: AMCLI-2151

Level: INFO

Description: Choice values are added.

Data: name of service, schema type, name of sub schema, name of attribute schema

Triggers: Execute add attribute schema choice values Commandline interface.

FAILED ADD ATTRIBUTE SCHEMA CHOICE VALUES

ID: AMCLI-2152

Level: INFO

Description: Unable to add choice value to attribute schema.

Data: name of service, schema type, name of sub schema, name of attribute schema, error message

Triggers: Execute add attribute schema choice values Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT GET ATTRIBUTE SCHEMA CHOICE VALUES

ID: AMCLI-2155

Level: INFO

Description: Attempt to get choice value to attribute schema.

Data: name of service, schema type, name of sub schema, name of attribute schema

Triggers: Execute get attribute schema choice values Commandline interface.

${\tt SUCCEED_GET_ATTRIBUTE_SCHEMA_CHOICE_VALUES}$

ID: AMCLI-2156

Level: INFO

Description: Choice values are listed.

Data: name of service, schema type, name of sub schema, name of attribute schema

Triggers: Execute get attribute schema choice values Commandline interface.

FAILED GET ATTRIBUTE SCHEMA CHOICE VALUES

ID: ĀMCLĪ-2157

Level: INFO

Description: Unable to get choice value to attribute schema.

Data: name of service, schema type, name of sub schema, name of attribute schema, error message

Triggers: Execute get attribute schema choice values Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT REMOVE ATTRIBUTE SCHEMA CHOICE VALUE

ID: AMCLI-2160

Level: INFO

Description: Attempt to remove choice value from attribute schema.

Data: name of service, schema type, name of sub schema, name of attribute schema

Triggers: Execute remove attribute schema choice values Commandline interface.

SUCCEED REMOVE ATTRIBUTE SCHEMA CHOICE VALUE

ID: AMCLI-2161

Level: INFO

Description: Choice value is removed.

Data: name of service, schema type, name of sub schema, name of attribute schema

Triggers: Execute remove attribute schema choice values Commandline interface.

FAILED REMOVE ATTRIBUTE SCHEMA CHOICE VALUE ID: AMCLI-2162

Level: INFO

Description: Unable to remove choice value to attribute schema.

Data: name of service, schema type, name of sub schema, name of attribute schema, error message

Triggers: Execute remove attribute schema choice values Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_MODIFY_ATTRIBUTE_SCHEMA_TYPE

ID: AMCLI-2170

Level: INFO

Description: Attempt to modify attribute schema type.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema type

Triggers: Execute modify attribute schema type Commandline interface.

SUCCEED MODIFY ATTRIBUTE SCHEMA TYPE

ID: AMCLI-2171

Level: INFO

Description: Attribute schema type is modified.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema type

Triggers: Execute modify attribute schema type Commandline interface.

FAILED MODIFY ATTRIBUTE SCHEMA TYPE

ID: **ĀMCLI-2172**

Level: INFO

Description: Unable to modify attribute schema type.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema type, error message

Triggers: Execute modify attribute schema type Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_MODIFY_ATTRIBUTE_SCHEMA_UI_TYPE

ID: AMCLI-2180

Description: Attempt to modify attribute schema UI type.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema UI type

Triggers: Execute modify attribute schema UI type Commandline interface.

SUCCEED MODIFY ATTRIBUTE SCHEMA UI TYPE

ID: AMCLI-2181

Level: INFO

Description: Attribute schema UI type is modified.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema UI type

Triggers: Execute modify attribute schema UI type Commandline interface.

FAILED MODIFY ATTRIBUTE SCHEMA UI TYPE

ID: AMCLI-2182

Level: INFO

Description: Unable to modify attribute schema UI type.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema UI type, error message

Triggers: Execute modify attribute schema UI type Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_MODIFY_ATTRIBUTE_SCHEMA_SYNTAX

ID: AMCLI-2190

Level: INFO

Description: Attempt to modify attribute schema syntax.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema syntax

Triggers: Execute modify attribute schema syntax Commandline interface.

SUCCEED_MODIFY_ATTRIBUTE_SCHEMA_SYNTAX

ID: AMCLI-2191

Level: INFO

Description: Attribute schema syntax is modified.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema syntax

Triggers: Execute modify attribute schema syntax Commandline interface.

FAILED MODIFY ATTRIBUTE SCHEMA SYNTAX

ID: AMCLI-2192

Level: INFO

Description: Unable to modify attribute schema syntax.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema syntax, error message

Triggers: Execute modify attribute schema syntax Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT MODIFY ATTRIBUTE SCHEMA I18N KEY

ID: AMCLI-2200

Level: INFO

Description: Attempt to modify attribute schema i18n Key.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema i18n Key

Triggers: Execute modify attribute schema i18n Key Commandline interface.

SUCCEED_MODIFY_ATTRIBUTE_SCHEMA_I18N_KEY

ID: AMCLI-2201

Level: INFO

Description: Attribute schema i18n Key is modified.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema i18n Key

Triggers: Execute modify attribute schema i18n Key Commandline interface.

FAILED MODIFY ATTRIBUTE SCHEMA I18N KEY

ID: AMCLI-2202

Level: INFO

Description: Unable to modify attribute schema i18n Key.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema i18n Key, error message

Triggers: Execute modify attribute schema i18n Key Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_MODIFY_ATTRIBUTE_SCHEMA_PROPERTIES_VIEW_BEAN_URL ID: AMCLI-2210

Level: INFO

Description: Attempt to modify attribute schema properties view bean URL.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema properties view bean URL

Triggers: Execute modify attribute schema properties view bean URL Commandline interface.

SUCCEED_MODIFY_ATTRIBUTE_SCHEMA_PROPERTIES_VIEW_BEAN_URL ID: AMCLI-2211

Level: INFO

 $Description: Attribute \ schema \ properties \ view \ bean \ URL \ is \ modified.$

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema properties view bean URL

Triggers: Execute modify attribute schema properties view bean URL Commandline interface.

FAILED_MODIFY_ATTRIBUTE_SCHEMA_PROPERTIES_VIEW_BEAN_URL ID: AMCLI-2212

Level: INFO

Description: Unable to modify attribute schema properties view bean URL.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema properties view bean URL, error message

Triggers: Execute modify attribute schema properties view bean URL Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_MODIFY_ATTRIBUTE_SCHEMA_ANY ID: AMCLI-2220

Description: Attempt to modify attribute schema any value.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema any

Triggers: Execute modify attribute schema any Commandline interface.

SUCCEED MODIFY ATTRIBUTE SCHEMA ANY

ID: AMCLI-2221

Level: INFO

Description: Attribute schema any value is modified.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema any

Triggers: Execute modify attribute schema any Commandline interface.

FAILED MODIFY ATTRIBUTE SCHEMA ANY

ID: AMCLI-2222

Level: INFO

Description: Unable to modify attribute schema any value.

Data: name of service, schema type, name of sub schema, name of attribute schema, attribute schema any, error message

Triggers: Execute modify attribute schema any Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_REMOVE_ATTRIBUTE_SCHEMA_DEFAULT_VALUE

ID: AMCLI-2230

Level: INFO

Description: Attempt to remove attribute schema default value.

Data: name of service, schema type, name of sub schema, name of attribute schema, default value to be removed

Triggers: Execute remove attribute schema default values Commandline interface.

SUCCEED_REMOVE_ATTRIBUTE_SCHEMA_DEFAULT_VALUE ID: AMCLI-2231

Description: Attribute schema default value is removed.

Data: name of service, schema type, name of sub schema, name of attribute schema, default value to be removed

Triggers: Execute remove attribute schema default values Commandline interface.

FAILED_REMOVE_ATTRIBUTE_SCHEMA_DEFAULT_VALUE

ID: AMCLI-2232

Level: INFO

Description: Unable to remove attribute schema default value.

Data: name of service, schema type, name of sub schema, name of attribute schema, default value to be removed, error message

Triggers: Execute remove attribute schema default values Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT SET ATTRIBUTE SCHEMA VALIDATOR

ID: AMCLI-2240

Level: INFO

Description: Attempt to set attribute schema validator.

Data: name of service, schema type, name of sub schema, name of attribute schema, validator

Triggers: Execute set attribute schema validator Commandline interface.

SUCCEED_SET_ATTRIBUTE_SCHEMA_VALIDATOR

ID: AMCLI-2241

Level: INFO

Description: Attribute schema validator is set.

Data: name of service, schema type, name of sub schema, name of attribute schema, validator

Triggers: Execute set attribute schema validator Commandline interface.

$FAILED_SET_ATTRIBUTE_SCHEMA_VALIDATOR$

ID: AMCLI-2242

Description: Unable to set attribute schema validator.

Data: name of service, schema type, name of sub schema, name of attribute schema, validator, error message

Triggers: Execute set attribute schema validator Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SET_ATTRIBUTE_SCHEMA_START_RANGE

ID: AMCLI-2250

Level: INFO

Description: Attempt to set attribute schema start range.

Data: name of service, schema type, name of sub schema, name of attribute schema, start range

Triggers: Execute set attribute schema start range Commandline interface.

SUCCEED SET ATTRIBUTE SCHEMA START RANGE

ID: AMCLI-2251

Level: INFO

Description: Attribute schema start range is set.

Data: name of service, schema type, name of sub schema, name of attribute schema, start range

Triggers: Execute set attribute schema start range Commandline interface.

FAILED_SET_ATTRIBUTE_SCHEMA_START_RANGE

ID: ĀMCLI-2252

Level: INFO

Description: Unable to set attribute schema start range.

Data: name of service, schema type, name of sub schema, name of attribute schema, start range, error message

Triggers: Execute set attribute schema start range Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SET_ATTRIBUTE_SCHEMA_END_RANGE

ID: AMCLI-2250

Description: Attempt to set attribute schema end range.

Data: name of service, schema type, name of sub schema, name of attribute schema, end range

Triggers: Execute set attribute schema end range Commandline interface.

SUCCEED SET ATTRIBUTE SCHEMA END RANGE

ID: AMCLI-2251

Level: INFO

Description: Attribute schema end range is set.

Data: name of service, schema type, name of sub schema, name of attribute schema, end range

Triggers: Execute set attribute schema end range Commandline interface.

FAILED SET ATTRIBUTE SCHEMA END RANGE

ID: AMCLI-2252

Level: INFO

Description: Unable to set attribute schema end range.

Data: name of service, schema type, name of sub schema, name of attribute schema, end range, error message

Triggers: Execute set attribute schema end range Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT SET SERVICE SCHEMA I18N KEY

ID: AMCLI-2260

Level: INFO

Description: Attempt to set service schema i18n key.

Data: name of service, i18n key

Triggers: Execute set service schema i18n key Commandline interface.

SUCCEED SET SERVICE SCHEMA I18N KEY

ID: AMCLI-2261

Level: INFO

Description: Service schema i18n key is set.

Data: name of service, i18n key

Triggers: Execute set service schema i18n key Commandline interface.

FAILED SET SERVICE SCHEMA I18N KEY

ID: AMCLI-2262

Level: INFO

Description: Unable to set service schema i18n key.

Data: name of service, i18n key, error message

Triggers: Execute set service schema i18n key Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SET_SERVICE_SCHEMA_PROPERTIES_VIEW_BEAN_URL

ID: AMCLI-2270

Level: INFO

Description: Attempt to set service schema properties view bean URL.

Data: name of service, properties view bean URL

Triggers: Execute set service schema properties view bean URL Commandline interface.

${\tt SUCCEED_SET_SERVICE_SCHEMA_PROPERTIES_VIEW_BEAN_URL}$

ID: AMCLI-2271

Level: INFO

Description: Service schema properties view bean URL is set.

Data: name of service, properties view bean URL

Triggers: Execute set service schema properties view bean URL Commandline interface.

$FAILED_SET_SERVICE_SCHEMA_PROPERTIES_VIEW_BEAN_URL$

ID: AMCLI-2272

Level: INFO

Description: Unable to set service schema properties view bean URL.

Data: name of service, properties view bean URL, error message

Triggers: Execute set service schema properties view bean URL Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT SET SERVICE REVISION NUMBER

ID: AMCLI-2280

Level: INFO

Description: Attempt to set service revision number.

Data: name of service, revision number

Triggers: Execute set service revision number Commandline interface.

SUCCEED SET SERVICE REVISION NUMBER

ID: AMCLI-2281

Level: INFO

Description: Service revision number is set.

Data: name of service, revision number

Triggers: Execute set service revision number Commandline interface.

FAILED SET SERVICE REVISION NUMBER

ID: AMCLI-2282

Level: INFO

Description: Unable to set service revision number.

Data: name of service, revision number, error message

Triggers: Execute set service revision number Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_GET_SERVICE_REVISION NUMBER

ID: AMCLI-2290

Level: INFO

Description: Attempt to get service revision number.

Data: name of service

Triggers: Execute get service revision number Commandline interface.

SUCCEED_GET_SERVICE_REVISION_NUMBER

ID: AMCLI-2291

Level: INFO

Description: Service revision number is returned.

Data: name of service

Triggers: Execute get service revision number Commandline interface.

FAILED GET SERVICE REVISION NUMBER

ID: AMCLI-2292

Level: INFO

Description: Unable to get service revision number.

Data: name of service, error message

Triggers: Execute get service revision number Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT REMOVE ATTRIBUTE SCHEMA

ID: AMCLI-2300

Level: INFO

Description: Attempt to remove attribute schema.

Data: name of service, schema type, name of sub schema, name of attribute schema

Triggers: Execute remove attribute schema Commandline interface.

SUCCEED REMOVE ATTRIBUTE SCHEMA

ID: AMCLI-2301

Level: INFO

Description: Attribute schema is removed.

Data: name of service, schema type, name of sub schema, name of attribute

schema

Triggers: Execute remove attribute schema Commandline interface.

FAILED REMOVE ATTRIBUTE_SCHEMA

ID: AMCLI-2302

Description: Unable to remove attribute schema.

Data: name of service, schema type, name of sub schema, name of attribute

schema, error message

Triggers: Execute remove attribute schema Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT ADD SUB CONFIGURATION

ID: AMCLI-2310

Level: INFO

Description: Attempt to add sub configuration.

Data: name of sub configuration, name of service

Triggers: Execute add sub configuration Commandline interface.

SUCCEED ADD SUB CONFIGURATION

ID: AMCLI-2311

Level: INFO

Description: Sub configuration is added.

Data: name of sub configuration, name of service

Triggers: Execute add sub configuration Commandline interface.

FAILED ADD SUB CONFIGURATION

ID: AMCLI-2312

Level: INFO

Description: Unable to add sub configuration.

Data: name of sub configuration, name of service, error message

Triggers: Execute add sub configuration Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_ADD_SUB_CONFIGURATION TO REALM

ID: AMCLI-2320

Level: INFO

Description: Attempt to add sub configuration to realm.

Data: name of realm, name of sub configuration, name of service

Triggers: Execute add sub configuration Commandline interface.

SUCCEED ADD SUB CONFIGURATION TO REALM

ID: AMCLI-2321

Level: INFO

Description: Sub configuration is added to realm.

Data: name of realm, name of sub configuration, name of service

Triggers: Execute add sub configuration Commandline interface.

FAILED ADD SUB CONFIGURATION TO REALM

ID: AMCLI-2322

Level: INFO

Description: Unable to add sub configuration.

Data: name of realm, name of sub configuration, name of service, error

message

Triggers: Execute add sub configuration Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_DELETE_SUB_CONFIGURATION ID: AMCLI-2330

Level: INFO

Description: Attempt to delete sub configuration.

Data: name of sub configuration, name of service

Triggers: Execute delete sub configuration Commandline interface.

SUCCEED DELETE SUB CONFIGURATION

ID: AMCLI-2331

Level: INFO

Description: Sub configuration is deleted.

Data: name of sub configuration, name of service

Triggers: Execute delete sub configuration Commandline interface.

FAILED_ADELETE_SUB_CONFIGURATION

ID: AMCLI-2332

Level: INFO

Description: Unable to delete sub configuration.

Data: name of sub configuration, name of service, error message

Triggers: Execute delete sub configuration Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_DELETE_SUB_CONFIGURATION_TO_REALM

ID: AMCLI-2340

Level: INFO

Description: Attempt to delete sub configuration from realm.

Data: name of realm, name of sub configuration, name of service

Triggers: Execute delete sub configuration Commandline interface.

SUCCEED DELETE SUB CONFIGURATION TO REALM

ID: AMCLI-2341

Level: INFO

Description: Sub configuration is deleted from realm.

Data: name of realm, name of sub configuration, name of service

Triggers: Execute delete sub configuration Commandline interface.

FAILED DELETE SUB CONFIGURATIONT TO REALM

ID: AMCLI-2342

Level: INFO

Description: Unable to delete sub configuration.

Data: name of realm, name of sub configuration, name of service, error

message

Triggers: Execute delete sub configuration Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_ADD_SUB_SCHEMA ID: AMCLI-2350

Level: INFO

Description: Attempt to add sub schema.

Data: name of service, schema type, name of sub schema

Triggers: Execute add sub schema Commandline interface.

SUCCEED_ADD_SUB_SCHEMA

ID: AMCLI-2351

Level: INFO

Description: Sub schema is added.

Data: name of service, schema type, name of sub schema

Triggers: Execute add sub schema Commandline interface.

FAILED_ADD_SUB_SCHEMA

ID: AMCLI-2352

Level: INFO

Description: Unable to add sub schema.

Data: name of service, schema type, name of sub schema, error message

Triggers: Execute add sub schema configurations Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT REMOVE SUB SCHEMA

ID: AMCLI-2360

Level: INFO

Description: Attempt to remove sub schema.

Data: name of service, schema type, name of parent sub schema, name of sub

schema

Triggers: Execute remove sub schema Commandline interface.

SUCCEED REMOVE SUB SCHEMA

ID: AMCLI-2361

Description: Sub schema is removed.

Data: name of service, schema type, name of parent sub schema, name of sub

schema

Triggers: Execute remove sub schema Commandline interface.

FAILED REMOVE SUB SCHEMA

ID: AMCLI-2362

Level: INFO

Description: Unable to remove sub schema.

Data: name of service, schema type, name of parent sub schema, name of sub

schema, error message

Triggers: Execute remove sub schema configurations Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT MODIFY INHERITANCE SUB SCHEMA

ID: AMCLI-2370

Level: INFO

Description: Attempt to modify inheritance of sub schema.

Data: name of service, schema type, name of sub schema

Triggers: Execute modify inheritance of sub schema Commandline interface.

SUCCEED MODIFY INHERITANCE SUB SCHEMA

ID: AMCLI-2371

Level: INFO

Description: Sub schema is modified.

Data: name of service, schema type, name of sub schema

Triggers: Execute modify inheritance of sub schema Commandline interface.

FAILED MODIFY INHERITANCE SUB SCHEMA

ID: AMCLI-2372

Level: INFO

Description: Unable to modify sub schema.

Data: name of service, schema type, name of sub schema, error message

Triggers: Execute modify inheritance of sub schema configurations Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_MODIFY_SUB_CONFIGURATION

ID: AMCLI-2380

Level: INFO

Description: Attempt to modify sub configuration.

Data: name of sub configuration, name of service

Triggers: Execute modify sub configuration Commandline interface.

SUCCEED_MODIFY_SUB_CONFIGURATION

ID: AMCLI-2381

Level: INFO

Description: Sub configuration is modified.

Data: name of sub configuration, name of service

Triggers: Execute modify sub configuration Commandline interface.

FAILED MODIFY SUB CONFIGURATION

ID: AMCLI-2382

Level: INFO

Description: Unable to modify sub configuration.

Data: name of sub configuration, name of service, error message

Triggers: Execute modify sub configuration Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT GET SUB CONFIGURATION

ID: AMCLI-2383

Level: INFO

Description: Attempt to retrieve sub configuration.

Data: name of sub configuration, name of service

Triggers: Execute get sub configuration Commandline interface.

SUCCEED GET SUB CONFIGURATION

ID: AMCLI-2384

Level: INFO

Description: Sub configuration is retrieved.

Data: name of sub configuration, name of service

Triggers: Execute get sub configuration Commandline interface.

FAILED GET SUB CONFIGURATION

ID: AMCLI-2385

Level: INFO

Description: Unable to retrieve sub configuration.

Data: name of sub configuration, name of service, error message

Triggers: Execute get sub configuration Commandline interface.

Actions: Look under debug file for more information.

$ATTEMPT_MODIFY_SUB_CONFIGURATION_IN_REALM$

ID: AMCLI-2390

Level: INFO

Description: Attempt to modify sub configuration in realm.

Data: name of realm, name of sub configuration, name of service

Triggers: Execute modify sub configuration Commandline interface.

${\tt SUCCEED_MODIFY_SUB_CONFIGURATION_IN_REALM}$

ID: AMCLI-2391

Level: INFO

Description: Sub configuration is modified.

Data: name of realm, name of sub configuration, name of service

Triggers: Execute modify sub configuration Commandline interface.

$FAILED_MODIFY_SUB_CONFIGURATION_IN_REALM$

ID: AMCLI-2392

Description: Unable to modify sub configuration in realm.

Data: name of realm, name of sub configuration, name of service, error

message

Triggers: Execute modify sub configuration Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_GET_SUB_CONFIGURATION_IN_REALM ID: AMCLI-2393

Level: INFO

Description: Attempt to retrieve sub configuration in realm.

Data: name of realm, name of sub configuration, name of service

Triggers: Execute get sub configuration Commandline interface.

SUCCEED_GET_SUB_CONFIGURATION_IN_REALM

ID: AMCLI-2394

Level: INFO

Description: Sub configuration is retrieved.

Data: name of realm, name of sub configuration, name of service

Triggers: Execute get sub configuration Commandline interface.

FAILED GET SUB CONFIGURATION IN REALM

ID: AMCLI-2395

Level: INFO

Description: Unable to retrieve sub configuration in realm.

Data: name of realm, name of sub configuration, name of service, error

message

Triggers: Execute get sub configuration Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_ADD PLUGIN INTERFACE

ID: AMCLI-2400

Level: INFO

Description: Attempt to add Plug-in interface to service.

Data: name of service, name of plugin

Triggers: Execute add Plug-in interface Commandline interface.

SUCCEED ADD PLUGIN INTERFACE

ID: AMCLI-2401

Level: INFO

Description: Plug-in interface is added.

Data: name of service, name of plugin

Triggers: Execute add Plug-in interface Commandline interface.

FAILED ADD PLUGIN INTERFACE

ID: AMCLI-2402

Level: INFO

Description: Unable to add Plug-in interface to service.

Data: name of service, name of plugin, error message

Triggers: Execute add Plug-in interface Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SET_PLUGIN_SCHEMA_PROP_VIEWBEAN_URL

ID: AMCLI-2410

Level: INFO

Description: Attempt to set Plug-in schema's properties view bean.

Data: name of service, name of plugin

Triggers: Execute set Plug-in schema's properties view bean Commandline

interface.

SUCCEED_SET_PLUGIN_SCHEMA_PROP_VIEWBEAN_URL

ID: AMCLI-2411

Level: INFO

Description: Plug-in schema's properties view bean is set.

Data: name of service, name of plugin

Triggers: Execute set Plug-in schema's properties view bean Commandline interface.

FAILED SET PLUGIN SCHEMA PROP VIEWBEAN URL

ID: AMCLI-2412

Level: INFO

Description: Unable to set Plug-in schema's properties view bean.

Data: name of service, name of plugin, error message

Triggers: Execute set Plug-in schema's properties view bean Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT_CREATE_POLICY_IN_REALM ID: AMCLI-2420

Level: INFO

Description: Attempt to create policies under realm.

Data: name of realm

Triggers: Execute create policies under realm Commandline interface.

SUCCEED_CREATE_POLICY IN REALM

ID: AMCLI-2421

Level: INFO

Description: Policies are created.

Data: name of realm

Triggers: Execute create policies under realm Commandline interface.

FAILED CREATE POLICY IN REALM

ID: AMCLI-2422

Level: INFO

Description: Unable to create policies under realm.

Data: name of realm, error message

Triggers: Execute create policies under realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_DELETE_POLICY_IN_REALM ID: AMCLI-2430

Level: INFO

Description: Attempt to delete policy in realm.

Data: name of realm, name of policy

Triggers: Execute delete policy in realm Commandline interface.

SUCCEED DELETE POLICY IN REALM

ID: AMCLI-2431

Level: INFO

Description: Policy is deleted.

Data: name of realm, name of policy

Triggers: Execute delete policy in realm Commandline interface.

FAILED DELETE POLICY IN REALM

ID: AMCLI-2432

Level: INFO

Description: Unable to delete policy under realm.

Data: name of realm, name of policy, error message

Triggers: Execute delete policy under realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT TO GET POLICY NAMES IN REALM

ID: AMCLI-2433

Level: INFO

Description: Attempt to get policy names in realm.

Data: name of realm

Triggers: Execute get policy names in realm Commandline interface.

GOT POLICY NAMES IN REALM

ID: AMCLI-2434

Level: INFO

Description: Got policy names in realm.

Data: name of realm

Triggers: Execute get policy names in realm Commandline interface.

FAILED GET POLICY NAMES IN REALM

ID: AMCLI-2435

Level: INFO

Description: Unable to get policy names in realm.

Data: name of realm

Triggers: Execute get policy names in realm Commandline interface.

ATTEMPT GET POLICY IN REALM

ID: AMCLI-2440

Level: INFO

Description: Attempt to get policy definition in realm.

Data: name of realm, name of policy

Triggers: Execute get policy definition in realm Commandline interface.

SUCCEED_GET_POLICY_IN REALM

ID: AMCLI-2441

Level: INFO

Description: Policy definition is returned.

Data: name of realm, name of policy

Triggers: Execute get policy definition in realm Commandline interface.

FAILED GET POLICY IN REALM

ID: AMCLI-2442

Level: INFO

Description: Unable to get policy definition under realm.

Data: name of realm, name of policy, error message

Triggers: Execute get policy definition under realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_CREATE_IDENTITY ID: AMCLI-2450

Level: INFO

Description: Attempt to create an identity in realm.

Data: name of realm, identity type, name of identity

Triggers: Execute create identity in realm Commandline interface.

SUCCEED CREATE IDENTITY

ID: AMCLI-2451

Level: INFO

Description: Identity is created.

Data: name of realm, identity type, name of identity

Triggers: Execute create identity in realm Commandline interface.

FAILED CREATE IDENTITY

ID: AMCLI-2452

Level: INFO

Description: Unable to create identity in realm.

Data: name of realm, identity type, name of identity, error message

Triggers: Execute create identity in realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT DELETE IDENTITY

ID: AMCLI-2460

Level: INFO

Description: Attempt to delete an identity in realm.

Data: name of realm, identity type, name of identity

Triggers: Execute delete identity in realm Commandline interface.

SUCCEED DELETE IDENTITY

ID: AMCLI-2461

Level: INFO

Log Messages

Description: Identity is deleted.

Data: name of realm, identity type, name of identity

Triggers: Execute delete identity in realm Commandline interface.

FAILED DELETE IDENTITY

ID: AMCLI-2462

Level: INFO

Description: Unable to delete identity in realm.

Data: name of realm, identity type, name of identity, error message

Triggers: Execute delete identity in realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SEARCH_IDENTITIES

ID: AMCLI-2470

Level: INFO

Description: Attempt to search identities in realm.

Data: name of realm, identity type, search pattern

Triggers: Execute search identities in realm Commandline interface.

SUCCEED SEARCH IDENTITIES

ID: AMCLI-2471

Level: INFO

Description: Search Result is returned.

Data: name of realm, identity type, search pattern

Triggers: Execute search identities in realm Commandline interface.

FAILED SEARCH IDENTITIES

ID: AMCLI-2472

Level: INFO

Description: Unable to search identities in realm.

Data: name of realm, identity type, search pattern, error message

Triggers: Execute search identities in realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT GET ALLOWED OPS

ID: AMCLI-2480

Level: INFO

Description: Attempt to get the allowed operation of an identity type in realm.

Data: name of realm, identity type

Triggers: Execute get the allowed operation of an identity type in realm

Commandline interface.

SUCCEED_GET_ALLOWED OPS

ID: AMCLI-2481

Level: INFO

Description: Allowed operations are returned.

Data: name of realm, identity type

Triggers: Execute get the allowed operation of an identity type in realm

Commandline interface.

FAILED GET ALLOWED OPS

ID: AMCLI-2482

Level: INFO

Description: Unable to get the allowed operation of an identity type in realm.

Data: name of realm, identity type, error message

Triggers: Execute get the allowed operation of an identity type in realm

Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT GET SUPPORTED IDTYPES

ID: AMCLI-2490

Level: INFO

Description: Attempt to get the supported identity type in realm.

Data: name of realm

Triggers: Execute get the supported identity type in realm Commandline

interface.

SUCCEED_GET_SUPPORTED_IDTYPES

ID: AMCLI-2491

Level: INFO

Description: Allowed identity types are returned.

Data: name of realm

Triggers: Execute get the supported identity type in realm Commandline

interface.

FAILED GET SUPPORTED IDTYPES

ID: AMCLI-2492

Level: INFO

Description: Unable to get the supported identity type in realm.

Data: name of realm, error message

Triggers: Execute get the supported identity type in realm Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT GET ASSIGNABLE SERVICES

ID: AMCLI-2500

Level: INFO

Description: Attempt to get the assignable services of an identity.

Data: name of realm, name of identity type, name of identity

Triggers: Execute get the assignable services of an identity Commandline

interface.

SUCCEED GET ASSIGNABLE SERVICES

ID: AMCLI-2501

Level: INFO

Description: Assignable services are returned.

Data: name of realm, name of identity type, name of identity

Triggers: Execute get the assignable services of an identity Commandline

interface.

FAILED_GET_ASSIGNABLE_SERVICES

ID: AMCLI-2502

Level: INFO

Description: Unable to get the assignable services of an identity.

Data: name of realm, name of identity type, name of identity, error message

Triggers: Execute get the assignable services of an identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT GET ASSIGNED SERVICES

ID: AMCLI-2510

Level: INFO

Description: Attempt to get the assigned services of an identity.

Data: name of realm, name of identity type, name of identity

Triggers: Execute get the assigned services of an identity Commandline interface.

SUCCEED GET ASSIGNED SERVICES

ID: AMCLI-2511

Level: INFO

Description: Assigned services are returned.

Data: name of realm, name of identity type, name of identity

Triggers: Execute get the assigned services of an identity Commandline interface.

FAILED GET ASSIGNED SERVICES

ID: AMCLI-2512

Level: INFO

Description: Unable to get the assigned services of an identity.

Data: name of realm, name of identity type, name of identity, error message

Triggers: Execute get the assigned services of an identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IDREPO GET SERVICE ATTRIBUTES

ID: AMCLI-2520

Level: INFO

Description: Attempt to get service attribute values of an identity.

Data: name of realm, name of identity type, name of identity, name of service

Triggers: Execute get the service attribute values of an identity Commandline interface.

SUCCEED_IDREPO_GET_SERVICE_ATTRIBUTES

ID: AMCLI-2521

Level: INFO

Description: Service attribute values are returned.

Data: name of realm, name of identity type, name of identity, name of service

Triggers: Execute get the service attribute values of an identity Commandline interface.

FAILED IDREPO GET SERVICE ATTRIBUTES

ID: AMCLI-2522

Level: INFO

Description: Unable to get the service attribute values of an identity.

Data: name of realm, name of identity type, name of identity, name of service, error message

Triggers: Execute get the service attribute values of an identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IDREPO GET ATTRIBUTES

ID: AMCLI-2530

Level: INFO

Description: Attempt to get attribute values of an identity.

Data: name of realm, name of identity type, name of identity

Triggers: Execute get the attribute values of an identity Commandline interface.

SUCCEED IDREPO GET ATTRIBUTES

ID: AMCLI-2531

Level: INFO

Description: Attribute values are returned.

Data: name of realm, name of identity type, name of identity

Triggers: Execute get the attribute values of an identity Commandline

interface.

FAILED IDREPO GET ATTRIBUTES

ID: AMCLI-2532

Level: INFO

Description: Unable to get the attribute values of an identity.

Data: name of realm, name of identity type, name of identity, error message

Triggers: Execute get the attribute values of an identity Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT IDREPO GET MEMBERSHIPS

ID: AMCLI-2540

Level: INFO

Description: Attempt to get memberships of an identity.

Data: name of realm, name of identity type, name of identity, name of

membership identity type

Triggers: Execute get the memberships of an identity Commandline interface.

SUCCEED IDREPO GET MEMBERSHIPS

ID: AMCLI-2541

Level: INFO

Description: Memberships are returned.

Data: name of realm, name of identity type, name of identity, name of $\ensuremath{\mathsf{I}}$

membership identity type

Triggers: Execute get the memberships of an identity Commandline interface.

FAILED_IDREPO_GET_MEMBERSHIPS

ID: AMCLI-2542

Level: INFO

Description: Unable to get the memberships of an identity.

Data: name of realm, name of identity type, name of identity, name of

membership identity type, error message

Triggers: Execute get the memberships of an identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IDREPO GET MEMBERS

ID: AMCLI-2550

Level: INFO

Description: Attempt to get members of an identity.

Data: name of realm, name of identity type, name of identity, name of

membership identity type

Triggers: Execute get the members of an identity Commandline interface.

SUCCEED IDREPO GET MEMBERS

ID: AMCLI-2551

Level: INFO

Description: Members are returned.

Data: name of realm, name of identity type, name of identity, name of

membership identity type

Triggers: Execute get the members of an identity Commandline interface.

FAILED IDREPO GET MEMBERS

ID: AMCLI-2552

Level: INFO

Description: Unable to get the members of an identity.

Data: name of realm, name of identity type, name of identity, name of

membership identity type, error message

Triggers: Execute get the members of an identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_IDREPO_IS_MEMBER

ID: AMCLI-2560

Level: INFO

Description: Attempt to determine if an identity is a member of another identity.

Data: name of realm, name of identity type, name of identity, name of member identity type, name of member identity

Triggers: Execute determine if an identity is a member of another identity Commandline interface.

SUCCEED IDREPO IS MEMBER

ID: AMCLI-2561

Level: INFO

Description: Membership is determined.

Data: name of realm, name of identity type, name of identity, name of member identity type, name of member identity

Triggers: Execute determine if an identity is a member of another identity Commandline interface.

FAILED IDREPO IS MEMBER

ID: AMCLI-2562

Level: INFO

Description: Unable to determine the membership of an identity of another.

Data: name of realm, name of identity type, name of identity, name of member identity type, name of member identity, error message

Triggers: Execute determine if an identity is a member of another identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IDREPO IS ACTIVE

ID: AMCLI-2570

Level: INFO

Description: Attempt to determine if an identity is active.

Data: name of realm, name of identity type, name of identity

Triggers: Execute determine if an identity is active Commandline interface.

SUCCEED IDREPO IS ACTIVE

ID: AMCLI-2571

Level: INFO

Description: Active status of identity is determined.

Data: name of realm, name of identity type, name of identity

Triggers: Execute determine if an identity is active Commandline interface.

FAILED IDREPO IS ACTIVE

ID: AMCLI-2572

Level: INFO

Description: Unable to determine if an identity is active.

Data: name of realm, name of identity type, name of identity, error message

Triggers: Execute determine if an identity is a active Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IDREPO ADD MEMBER

ID: AMCLI-2580

Level: INFO

Description: Attempt to make an identity a member of another identity.

Data: name of realm, name of identity type, name of identity, name of member identity type, name of member identity

Triggers: Execute make an identity a member of another identity Commandline interface.

SUCCEED IDREPO ADD MEMBER

ID: AMCLI-2581

Level: INFO

Description: Membership is set.

Data: name of realm, name of identity type, name of identity, name of member identity type, name of member identity

Triggers: Execute make an identity a member of another identity Commandline interface.

FAILED IDREPO ADD MEMBER

ID: AMCLI-2582

Level: INFO

Description: Unable to add member of an identity to another.

Data: name of realm, name of identity type, name of identity, name of member identity type, name of member identity, error message

Triggers: Execute make an identity a member of another identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IDREPO REMOVE MEMBER

ID: AMCLI-2590

Level: INFO

Description: Attempt to remove membership an identity from another identity.

Data: name of realm, name of identity type, name of identity, name of member identity type, name of member identity

Triggers: Execute remove membership an identity from another identity Commandline interface.

SUCCEED IDREPO REMOVE MEMBER

ID: AMCLI-2591

Level: INFO

Description: Membership is removed.

Data: name of realm, name of identity type, name of identity, name of member identity type, name of member identity

Triggers: Execute remove membership an identity from another identity Commandline interface.

FAILED_IDREPO_REMOVE_MEMBER

ID: AMCLI-2592

Description: Unable to remove membership of an identity.

Data: name of realm, name of identity type, name of identity, name of member identity type, name of member identity, error message

Triggers: Execute remove membership an identity from another identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IDREPO ASSIGN SERVICE

ID: AMCLI-2600

Level: INFO

Description: Attempt to assign service to an identity.

Data: name of realm, identity type, name of identity, name of service

Triggers: Execute assign service to an identity Commandline interface.

SUCCEED IDREPO ASSIGN SERVICE

ID: AMCLI-2601

Level: INFO

Description: Service is assigned to an identity.

Data: name of realm, identity type, name of identity, name of service

Triggers: Execute assign service to an identity Commandline interface.

FAILED IDREPO ASSIGN SERVICE

ID: AMCLI-2602

Level: INFO

Description: Unable to assign service to an identity.

Data: name of realm, identity type, name of identity, name of service, error

message

Triggers: Execute assign service to an identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IDREPO UNASSIGN SERVICE

ID: AMCLI-2610

Description: Attempt to unassign service from an identity.

Data: name of realm, identity type, name of identity, name of service

Triggers: Execute unassign service from an identity Commandline interface.

SUCCEED IDREPO UNASSIGN SERVICE

ID: AMCLI-2611

Level: INFO

Description: Service is unassigned from an identity.

Data: name of realm, identity type, name of identity, name of service

Triggers: Execute unassign service from an identity Commandline interface.

FAILED_IDREPO_UNASSIGN_SERVICE

ID: AMCLI-2612

Level: INFO

Description: Unable to unassign service to an identity.

Data: name of realm, identity type, name of identity, name of service, error

message

Triggers: Execute unassign service from an identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IDREPO MODIFY SERVICE

ID: AMCLI-2620

Level: INFO

Description: Attempt to modify service attribute values of an identity.

Data: name of realm, identity type, name of identity, name of service

Triggers: Execute modify service attribute values of an identity Commandline interface.

SUCCEED IDREPO MODIFY SERVICE

ID: AMCLI-2621

Level: INFO

Description: Service attribute values are modified.

Data: name of realm, identity type, name of identity, name of service

Triggers: Execute modify service attribute values of an identity Commandline interface.

FAILED_IDREPO_MODIFY_SERVICE

ID: AMCLI-2622

Level: INFO

Description: Unable to modify service attribute values of an identity.

Data: name of realm, identity type, name of identity, name of service, error

message

Triggers: Execute modify service attribute values of an identity Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT_IDREPO_SET_ATTRIBUTE_VALUES

ID: AMCLI-2630

Level: INFO

Description: Attempt to set attribute values of an identity.

Data: name of realm, identity type, name of identity

Triggers: Execute set attribute values of an identity Commandline interface.

SUCCEED_IDREPO_SET ATTRIBUTE VALUES

ID: AMCLI-2631

Level: INFO

Description: Attribute values are modified.

Data: name of realm, identity type, name of identity

Triggers: Execute set attribute values of an identity Commandline interface.

FAILED IDREPO SET ATTRIBUTE VALUES

ID: AMCLI-2632

Level: INFO

Description: Unable to set attribute values of an identity.

Data: name of realm, identity type, name of identity, error message

Triggers: Execute set attribute values of an identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IDREPO GET PRIVILEGES

ID: AMCLI-2640

Level: INFO

Description: Attempt to get privileges of an identity.

Data: name of realm, identity type, name of identity

Triggers: Execute get privileges of an identity Commandline interface.

SUCCEED IDREPO GET PRIVILEGES

ID: AMCLI-2641

Level: INFO

Description: Privileges are returned.

Data: name of realm, identity type, name of identity

Triggers: Execute get privileges of an identity Commandline interface.

FAILED IDREPO GET PRIVILEGES

ID: AMCLI-2642

Level: INFO

Description: Unable to get privileges of an identity.

Data: name of realm, identity type, name of identity, error message

Triggers: Execute get privileges of an identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IDREPO ADD PRIVILEGES

ID: AMCLI-2650

Level: INFO

Description: Attempt to add privileges to an identity.

Data: name of realm, identity type, name of identity

Triggers: Execute add privileges to an identity Commandline interface.

SUCCEED IDREPO ADD PRIVILEGES

ID: AMCLI-2651

Level: INFO

Description: Privileges are added.

Data: name of realm, identity type, name of identity

Triggers: Execute add privileges to an identity Commandline interface.

FAILED_IDREPO_ADD_PRIVILEGES

ID: AMCLI-2652

Level: INFO

Description: Unable to add privileges to an identity.

Data: name of realm, identity type, name of identity, error message

Triggers: Execute add privileges to an identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IDREPO REMOVE PRIVILEGES

ID: AMCLI-2660

Level: INFO

Description: Attempt to remove privileges from an identity.

Data: name of realm, identity type, name of identity

Triggers: Execute remove privileges from an identity Commandline interface.

SUCCEED IDREPO REMOVE PRIVILEGES

ID: AMCLI-2661

Level: INFO

Description: Privileges are removed.

Data: name of realm, identity type, name of identity

Triggers: Execute remove privileges from an identity Commandline interface.

FAILED IDREPO REMOVE PRIVILEGES

ID: AMCLI-2662

Level: INFO

Description: Unable to remove privileges from an identity.

Data: name of realm, identity type, name of identity, error message

Triggers: Execute remove privileges from an identity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SET_ATTRIBUTE_SCHEMA_BOOLEAN_VALUES

ID: AMCLI-2670

Level: INFO

Description: Attempt to set boolean values to attribute schema.

Data: name of service, schema type, name of sub schema, name of attribute schema

Triggers: Execute set attribute schema boolean values Commandline interface.

SUCCEED SET ATTRIBUTE SCHEMA BOOLEAN VALUES

ID: AMCLI-2671

Level: INFO

Description: Boolean values are set.

Data: name of service, schema type, name of sub schema, name of attribute schema

Triggers: Execute set attribute schema boolean values Commandline interface.

FAILED_SET_ATTRIBUTE_SCHEMA_BOOLEAN_VALUES

ID: AMCLI-2672

Level: INFO

Description: Unable to set boolean values to attribute schema.

Data: name of service, schema type, name of sub schema, name of attribute schema, error message

Triggers: Execute set attribute schema boolean values Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT LIST AUTH INSTANCES

ID: AMCLI-2680

Description: Attempt to list authentication instances.

Data: name of realm

Triggers: Execute list authentication instances Commandline interface.

SUCCEEDED LIST AUTH INSTANCES

ID: AMCLI-2681

Level: INFO

Description: List authentication instances succeeded.

Data: name of realm

Triggers: Execute list authentication instances Commandline interface.

FAILED LIST AUTH INSTANCES

ID: AMCLI-2682

Level: INFO

Description: Failed to list authentication instances.

Data: name of realm

Triggers: Execute list authentication instances Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_CREATE_AUTH_INSTANCE ID: AMCLI-2690

Level: INFO

Description: Attempt to create authentication instance.

Data: name of realm, name of authentication instance, type of authentication

instance

Triggers: Execute create authentication instance Commandline interface.

SUCCEEDED CREATE AUTH INSTANCE

ID: AMCLI-2691

Level: INFO

Description: Authentication instance created.

Data: name of realm, name of authentication instance, type of authentication

instance

Triggers: Execute create authentication instance Commandline interface.

FAILED CREATE AUTH INSTANCE

ID: AMCLI-2692

Level: INFO

Description: Failed to create authentication instance.

Data: name of realm, name of authentication instance, type of authentication

instance

Triggers: Execute create authentication instance Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT DELETE AUTH INSTANCES

ID: AMCLI-2700

Level: INFO

Description: Attempt to delete authentication instances.

Data: name of realm, name of authentication instances

Triggers: Execute delete authentication instance Commandline interface.

SUCCEEDED DELETE AUTH INSTANCES

ID: AMCLI-2701

Level: INFO

Description: Authentication instances are deleted.

Data: name of realm, name of authentication instances

Triggers: Execute delete authentication instances Commandline interface.

FAILED DELETE AUTH INSTANCES

ID: AMCLI-2702

Level: INFO

Description: Failed to delete authentication instance.

Data: name of realm, name of authentication instances

Triggers: Execute delete authentication instances Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_UPDATE_AUTH_INSTANCE ID: AMCLI-2710

Level: INFO

Description: Attempt to update authentication instance.

Data: name of realm, name of authentication instance

Triggers: Execute update authentication instance Commandline interface.

SUCCEEDED UPDATE AUTH INSTANCE

ID: AMCLĪ-2711

Level: INFO

Description: Authentication instance is updated.

Data: name of realm, name of authentication instance

Triggers: Execute update authentication instance Commandline interface.

FAILED_UPDATE_AUTH_INSTANCE

ID: AMCLI-2712

Level: INFO

Description: Failed to update authentication instance.

Data: name of realm, name of authentication instance

Triggers: Execute update authentication instance Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT GET AUTH INSTANCE

ID: AMCLI-2710

Level: INFO

Description: Attempt to get authentication instance.

Data: name of realm, name of authentication instance

Triggers: Execute get authentication instance Commandline interface.

SUCCEEDED GET AUTH INSTANCE

ID: AMCLĪ-2711

Description: Authentication instance profile is displayed.

Data: name of realm, name of authentication instance

Triggers: Execute get authentication instance Commandline interface.

FAILED GET AUTH INSTANCE

ID: AMCLI-2712

Level: INFO

Description: Failed to get authentication instance.

Data: name of realm, name of authentication instance

Triggers: Execute get authentication instance Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT LIST AUTH CONFIGURATIONS

ID: AMCLI-2720

Level: INFO

Description: Attempt to list authentication configurations.

Data: name of realm

Triggers: Execute list authentication configurations Commandline interface.

SUCCEEDED_LIST_AUTH_CONFIGURATIONS

ID: AMCLĪ-272Ī

Level: INFO

Description: List authentication configurations succeeded.

Data: name of realm

Triggers: Execute list authentication configurations Commandline interface.

FAILED LIST AUTH CONFIGURATIONS

ID: AMCLI-2722

Level: INFO

Description: Failed to list authentication configurations.

Data: name of realm

Triggers: Execute list authentication configurations Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_CREATE_AUTH_CONFIGURATION

ID: AMCLI-2730

Level: INFO

Description: Attempt to create authentication configuration.

Data: name of realm, name of authentication configuration

Triggers: Execute create authentication configuration Commandline

interface.

SUCCEEDED CREATE AUTH CONFIGURATION

ID: AMCLĪ-2731

Level: INFO

Description: Authentication configuration created.

Data: name of realm, name of authentication configuration

 ${\bf Triggers: Execute\ create\ authentication\ configuration\ Commandline}$

interface.

FAILED_CREATE_AUTH_CONFIGURATION

ID: AMCLI-2732

Level: INFO

Description: Failed to create authentication configuration.

Data: name of realm, name of authentication configuration

Triggers: Execute create authentication configuration Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT DELETE AUTH CONFIGURATIONS

ID: AMCLI-2740

Level: INFO

Description: Attempt to delete authentication configurations.

Data: name of realm, name of authentication configurations

Triggers: Execute delete authentication configurations Commandline

interface.

${\tt SUCCEEDED_DELETE_AUTH_CONFIGURATIONS}$

ID: AMCLĪ-2741

Level: INFO

Description: Authentication configurations are deleted.

Data: name of realm, name of authentication configurations

Triggers: Execute delete authentication configurations Commandline interface.

FAILED DELETE AUTH CONFIGURATIONS

ID: AMCLI-2742

Level: INFO

Description: Failed to delete authentication instance.

Data: name of realm, name of authentication configurations

Triggers: Execute delete authentication configurations Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT GET AUTH CONFIG ENTRIES

ID: AMCLI-2750

Level: INFO

Description: Attempt to get authentication configuration entries.

Data: name of realm, name of authentication configuration

Triggers: Execute get authentication configuration entries Commandline interface.

SUCCEEDED GET AUTH CONFIG ENTRIES

ID: AMCLI-2751

Level: INFO

Description: Authentication instance configuration entries are displayed.

Data: name of realm, name of authentication configuration

Triggers: Execute get authentication configuration entries Commandline interface.

FAILED_GET_AUTH_CONFIG_ENTRIES

ID: AMCLI-2752

Level: INFO

Description: Failed to get authentication configuration entries.

Data: name of realm, name of authentication configuration

Triggers: Execute get authentication configuration entries Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT SET AUTH CONFIG ENTRIES

ID: AMCLI-2760

Level: INFO

Description: Attempt to set authentication configuration entries.

Data: name of realm, name of authentication configuration

 $Triggers: Execute \ set \ authentication \ configuration \ entries \ Command line$

interface.

SUCCEEDED SET AUTH CONFIG ENTRIES

ID: AMCLĪ-2761

Level: INFO

Description: Authentication instance configuration entries are displayed.

Data: name of realm, name of authentication configuration

Triggers: Execute set authentication configuration entries Commandline

interface.

FAILED SET AUTH CONFIG ENTRIES

ID: AMCLI-2762

Level: INFO

Description: Failed to set authentication configuration entries.

Data: name of realm, name of authentication configuration

Triggers: Execute set authentication configuration entries Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT LIST DATASTORES

ID: AMCLI-2770

Level: INFO

Description: Attempt to list datastores.

Data: name of realm

Triggers: Execute list datastores Commandline interface.

SUCCEEDED LIST DATASTORES

ID: AMCLĪ-277Ī

Level: INFO

Description: List datastores succeeded.

Data: name of realm

Triggers: Execute list datastores Commandline interface.

FAILED LIST DATASTORES

ID: ĀMCLĪ-2772

Level: INFO

Description: Failed to list datastores.

Data: name of realm, error message

Triggers: Execute list datastores Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT CREATE DATASTORE

ID: AMCLI-2780

Level: INFO

Description: Attemp to create datastore.

Data: name of realm, name of datastore, type of datastore

Triggers: Execute create datastore Commandline interface.

SUCCEEDED CREATE DATASTORE

ID: AMCLĪ-2781

Log Messages

Description: Create datastore succeeded.

Data: name of realm, name of datastore, type of datastore

Triggers: Execute create datastore Commandline interface.

FAILED CREATE DATASTORE

ID: AMCLI-2782

Level: INFO

Description: Failed to create datastore.

Data: name of realm, name of datastore, type of datastore

Triggers: Execute create datastore Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT DELETE DATASTORES

ID: AMCLI-2790

Level: INFO

Description: Attempt to delete datastores.

Data: name of realm, names of datastore

Triggers: Execute delete datastores Commandline interface.

SUCCEEDED_DELETE_DATASTORES ID: AMCLI-2791

Level: INFO

Description: Delete datastores succeeded.

Data: name of realm, names of datastore

Triggers: Execute delete datastores Commandline interface.

FAILED DELETE DATASTORES

ID: AMCLI-2792

Level: INFO

Description: Failed to delete datastores.

Data: name of realm, names of datastore

Triggers: Execute delete datastore Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT UPDATE DATASTORE

ID: AMCLI-2800

Level: INFO

Description: Attempt to update datastore profile.

Data: name of realm, name of datastore

Triggers: Execute update datastore Commandline interface.

SUCCEEDED UPDATE DATASTORE

ID: AMCLI-2801

Level: INFO

Description: Update datastore succeeded.

Data: name of realm, name of datastore

Triggers: Execute update datastore Commandline interface.

FAILED UPDATE DATASTORE

ID: AMCLI-2802

Level: INFO

Description: Failed to update datastore.

Data: name of realm, name of datastore, error message

Triggers: Execute update datastore Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IMPORT SM CONFIG DATA

ID: AMCLI-2900

Level: INFO

Description: Attempt to import service management configuration data.

Data: name of file

Triggers: Execute export configuration data Commandline interface.

SUCCEEDED IMPORT SM CONFIG DATA

ID: AMCLI-2901

Level: INFO

Description: Import service management configuration data succeeded.

Data: name of file

Triggers: Execute export configuration data Commandline interface.

FAILED_IMPORT_SM_CONFIG_DATA

ID: AMCLI-2902

Level: INFO

Description: Failed to import service management configuration data.

Data: name of file, error message

Triggers: Execute export configuration data Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT EXPORT SM CONFIG DATA

ID: AMCLI-3000

Level: INFO

Description: Attempt to export service management configuration data.

Data: name of file

Triggers: Execute export configuration data Commandline interface.

SUCCEEDED IMPORT SM CONFIG DATA

ID: AMCLĪ-3001

Level: INFO

Description: Export service management configuration data succeeded.

Data: name of file

Triggers: Execute export configuration data Commandline interface.

FAILED_EXPORT_SM_CONFIG_DATA

ID: AMCLI-3002

Level: INFO

Description: Failed to export service management configuration data.

Data: name of file, error message

Triggers: Execute export configuration data Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_CREATE_SERVERCONFIG XML

ID: AMCLI-3010

Level: INFO

Description: Attempt to create server configuration xml.

Data: name of file

Triggers: Execute create server configuration xml Commandline interface.

SUCCEEDED CREATE SERVERCONFIG XML

ID: AMCLĪ-3011

Level: INFO

Description: Create server configuration xml succeeded.

Data: name of file

Triggers: Execute create server configuration xml Commandline interface.

FAILED CREATE SERVERCONFIG XML

ID: AMCLI-3012

Level: INFO

Description: Failed to create server configuration xml.

Data: name of file, error message

Triggers: Execute create server configuration xml Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT REALM REMOVE SERVICE ATTR VALUES

ID: AMCLI-3020

Level: INFO

Description: Attempt to remove service attribute values of realm.

Data: name of realm, name of service

Triggers: Execute remove service attribute values of realm Commandline interface.

$SUCCEED_REALM_REMOVE_SERVICE_ATTR_VALUES$

ID: AMCLI-3021

Level: INFO

Description: Service attribute values of realm are removed.

Data: name of realm, name of service

Triggers: Execute remove service attribute values of realm Commandline interface.

FAILED REALM REMOVE SERVICE ATTR VALUES

ID: AMCLI-3022

Level: INFO

Description: Unable to remove service attribute values of realm.

Data: name of realm, name of service, error message

Triggers: Execute remove service attribute values of realm Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT REALM ADD SERVICE ATTR VALUES

ID: AMCLI-3030

Level: INFO

Description: Attempt to add service attribute values of realm.

Data: name of realm, name of service

Triggers: Execute add service attribute values of realm Commandline interface.

SUCCEED REALM ADD SERVICE ATTR VALUES

ID: AMCLI-3031

Level: INFO

Description: Service attribute values of realm are added.

Data: name of realm, name of service

 $Triggers: \ Execute \ add \ service \ attribute \ values \ of \ realm \ Command line$

interface.

FAILED_REALM_ADD_SERVICE_ATTR_VALUES

ID: ĀMCLI-3032

Level: INFO

Description: Unable to add service attribute values of realm.

Data: name of realm, name of service, error message

Triggers: Execute add service attribute values of realm Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT LIST SERVER CONFIG

ID: AMCLI-3040

Level: INFO

Description: Attempt to list server configuration.

Data: name of server

Triggers: Execute list server configuration Commandline interface.

SUCCEED LIST SERVER CONFIG

ID: AMCLI-3041

Level: INFO

Description: Server configuration is displayed.

Data: name of server

Triggers: Execute list server configuration Commandline interface.

FAILED LIST SERVER CONFIG

ID: AMCLI-3042

Level: INFO

Description: Unable to list server configuration.

Data: name of server, error message

Triggers: Execute list server configuration Commandline interface.

Actions: Check if servername is correct.; Look under debug file for more information.

ATTEMPT_UPDATE_SERVER_CONFIG ID: AMCLI-3050

Level: INFO

Description: Attempt to update server configuration.

Data: name of server

Triggers: Execute update server configuration Commandline interface.

SUCCEED UPDATE SERVER CONFIG

ID: AMCLI-3051

Level: INFO

Description: Server configuration is updated.

Data: name of server

Triggers: Execute update server configuration Commandline interface.

FAILED_UPDATE_SERVER_CONFIG

ID: AMCLI-3052

Level: INFO

Description: Unable to update server configuration.

Data: name of server, error message

Triggers: Execute update server configuration Commandline interface.

Actions: Check if servername is correct.; Look under debug file for more

information.

ATTEMPT_REMOVE_SERVER_CONFIG

ID: AMCLI-3060

Level: INFO

Description: Attempt to remove server configuration.

Data: name of server

Triggers: Execute remove server configuration Commandline interface.

SUCCEED REMOVE SERVER CONFIG

ID: AMCLI-3061

Log Messages

Description: Server configuration is removed.

Data: name of server

Triggers: Execute remove server configuration Commandline interface.

FAILED REMOVE SERVER CONFIG

ID: AMCLI-3062

Level: INFO

Description: Remove server configuration.

Data: name of server, error message

Triggers: Execute remove server configuration Commandline interface.

Actions: Check if servername is correct.; Look under debug file for more

information.

ATTEMPT_CREATE_SERVER

ID: AMCLI-3070

Level: INFO

Description: Attempt to create server.

Data: name of server

Triggers: Execute create server Commandline interface.

SUCCEED_CREATE_SERVER ID: AMCLI-3071

Level: INFO

Description: Server is created.

Data: name of server

Triggers: Execute create server Commandline interface.

FAILED CREATE SERVER

ID: AMCLI-3072

Level: INFO

Description: Unable to create server.

Data: name of server, error message

Triggers: Execute create server Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT DELETE SERVER

ID: AMCLI-3080

Level: INFO

Description: Attempt to delete server.

Data: name of server

Triggers: Execute delete server Commandline interface.

SUCCEED_DELETE_SERVER

ID: AMCLI-3081

Level: INFO

Description: Server is deleted.

Data: name of server

Triggers: Execute delete server Commandline interface.

FAILED DELETE SERVER

ID: AMCLI-3082

Level: INFO

Description: Unable to delete server.

Data: name of server, error message

Triggers: Execute delete server Commandline interface.

Actions: Check the name of the server.; Look under debug file for more

information.

ATTEMPT LIST SERVERS

ID: AMCLI-3090

Level: INFO

Description: Attempt to list servers.

Triggers: Execute list servers Commandline interface.

SUCCEED LIST SERVERS

ID: AMCLI-3091

Level: INFO

Description: Servers are displayed.

Triggers: Execute list servers Commandline interface.

FAILED LIST SERVERS

ID: AMCLI-3092

Level: INFO

Description: Unable to list servers.

Data: error message

Triggers: Execute list servers Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_CREATE_SITE

ID: AMCLI-3100

Level: INFO

Description: Attempt to create site.

Data: name of site, primary URL of site

Triggers: Execute create site Commandline interface.

SUCCEED_CREATE_SITE ID: AMCLI-3101

Level: INFO

Description: Site is created.

Data: name of site, primary URL of site

Triggers: Execute create site Commandline interface.

FAILED CREATE SITE

ID: AMCLI-3102

Level: INFO

Description: Unable to create site.

Data: name of site, primary URL of site, error message

Triggers: Execute create site Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT LIST SITES

ID: AMCLI-3110

Level: INFO

Description: Attempt to list sites.

Triggers: Execute list sites Commandline interface.

SUCCEED LIST SITES

ID: AMCLI-3111

Level: INFO

Description: Sites are displayed.

Triggers: Execute list sites Commandline interface.

FAILED LIST SITES

ID: AMCLI-3112

Level: INFO

Description: Unable to list sites.

Data: error message

Triggers: Execute list sites Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SHOW_SITE_MEMBERS ID: AMCLI-3120

Level: INFO

Description: Attempt to show site members.

Data: name of site

Triggers: Execute show site members Commandline interface.

SUCCEED_SHOW_SITE_MEMBERS

ID: AMCLI-3121

Level: INFO

Description: Site members are displayed.

Data: name of site

Triggers: Execute show site members Commandline interface.

FAILED SHOW SITE MEMBERS

ID: AMCLI-3122

Level: INFO

Description: Unable to show site members.

Data: name of site, error message

Triggers: Execute show site members Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_ADD_SITE_MEMBERS

ID: AMCLI-3130

Level: INFO

Description: Attempt to add members to site.

Data: name of site

Triggers: Execute add members to site Commandline interface.

SUCCEED ADD SITE MEMBERS

ID: AMCLI-3131

Level: INFO

Description: Members are added to site.

Data: name of site

Triggers: Execute add members to site Commandline interface.

FAILED ADD SITE MEMBERS

ID: AMCLI-3132

Level: INFO

Description: Unable to add members to site.

Data: name of site, error message

Triggers: Execute add members to site Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_REMOVE_SITE_MEMBERS ID: AMCLI-3140

Level: INFO

Description: Attempt to remove members from site.

Data: name of site

Triggers: Execute remove members from site Commandline interface.

SUCCEED REMOVE SITE MEMBERS

ID: AMCLI-3141

Level: INFO

Description: Members are removed from site.

Data: name of site

Triggers: Execute remove members from site Commandline interface.

FAILED_REMOVE_SITE_MEMBERS

ID: AMCLI-3142

Level: INFO

Description: Unable to remove members from site.

Data: name of site, error message

Triggers: Execute remove members from site Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT DELETE SITE

ID: AMCLI-3150

Level: INFO

Description: Attempt to delete site.

Data: name of site

Triggers: Execute delete site Commandline interface.

SUCCEED_DELETE_SITE

ID: AMCLI-3151

Description: Site is deleted.

Data: name of site

Triggers: Execute delete site Commandline interface.

FAILED DELETE SITE

ID: AMCLI-3152

Level: INFO

Description: Unable to delete members from site.

Data: name of site, error message

Triggers: Execute delete site Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SET_SITE_PRIMARY_URL

ID: AMCLI-3160

Level: INFO

Description: Attempt to set site primary URL.

Data: name of site, primary URL of site

Triggers: Execute set site primary URL Commandline interface.

SUCCEED_SET_SITE_PRIMARY_URL ID: AMCLI-3161

Level: INFO

Description: Site primary URL is set.

Data: name of site, primary URL of site

Triggers: Execute set site primary URL Commandline interface.

FAILED SET SITE PRIMARY URL

ID: AMCLI-3162

Level: INFO

Description: Unable to set site primary URL.

Data: name of site, primary URL of site, error message

Triggers: Execute set site primary URL Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT SHOW SITE

ID: AMCLI-3170

Level: INFO

Description: Attempt to show site profile.

Data: name of site

Triggers: Execute show site profile Commandline interface.

SUCCEED SHOW SITE

ID: AMCLI-3171

Level: INFO

Description: Site profile is displayed.

Data: name of site

Triggers: Execute show site profile Commandline interface.

FAILED_SHOW_SITE

ID: ĀMCLI-3172

Level: INFO

Description: Unable to show site profile.

Data: name of site, error message

Triggers: Execute show site profile Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SET_SITE_FAILOVER URLS

ID: AMCLI-3180

Level: INFO

Description: Attempt to set site failover URLs.

Data: name of site

Triggers: Execute set site failover URLs Commandline interface.

SUCCEED_SET_SITE_FAILOVER_URLS

ID: AMCLI-3181

Level: INFO

Description: Site failover URLs are set.

Data: name of site

Triggers: Execute set site failover URLs Commandline interface.

FAILED_SET_SITE_FAILOVER_URLS

ID: AMCLI-3182

Level: INFO

Description: Unable to set site failover URLs.

Data: name of site, error message

Triggers: Execute set site failover URLs Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT ADD SITE FAILOVER URLS

ID: AMCLI-3190

Level: INFO

Description: Attempt to add site failover URLs.

Data: name of site

Triggers: Execute add site failover URLs Commandline interface.

SUCCEED ADD SITE FAILOVER URLS

ID: AMCLI-3191

Level: INFO

Description: Site failover URLs are added.

Data: name of site

Triggers: Execute add site failover URLs Commandline interface.

FAILED ADD SITE FAILOVER URLS

ID: AMCLI-3192

Level: INFO

Description: Unable to add site failover URLs.

Data: name of site, error message

Triggers: Execute add site failover URLs Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT REMOVE SITE FAILOVER URLS

ID: AMCLI-3200

Level: INFO

Description: Attempt to remove site failover URLs.

Data: name of site

Triggers: Execute remove site failover URLs Commandline interface.

SUCCEED_REMOVE_SITE_FAILOVER_URLS

ID: AMCLI-3201

Level: INFO

Description: Site failover URLs are removed.

Data: name of site

Triggers: Execute remove site failover URLs Commandline interface.

FAILED REMOVE SITE FAILOVER URLS

ID: AMCLI-3202

Level: INFO

Description: Unable to remove site failover URLs.

Data: name of site, error message

Triggers: Execute remove site failover URLs Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT CLONE SERVER

ID: AMCLI-3210

Level: INFO

Description: Attempt to clone server.

Data: name of server, name of cloned server

Triggers: Execute clone server Commandline interface.

SUCCEED_CLONE_SERVER ID: AMCLI-3211

Level: INFO

Description: Server is cloned.

Data: name of server, name of cloned server

Triggers: Execute clone server Commandline interface.

FAILED CLONE SERVER

ID: AMCLI-3212

Level: INFO

Description: Unable to clone server.

Data: name of server, name of cloned server, error message

Triggers: Execute clone server Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_EXPORT SERVER

ID: AMCLI-3220

Level: INFO

Description: Attempt to export server.

Data: name of server

Triggers: Execute export server Commandline interface.

SUCCEED EXPORT SERVER

ID: AMCLI-3221

Level: INFO

Description: Server is cloned.

Data: name of server

Triggers: Execute export server Commandline interface.

FAILED EXPORT SERVER

ID: AMCLI-3222

Log Messages

Description: Unable to export server.

Data: name of server, error message

Triggers: Execute export server Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_IMPORT_SERVER

ID: AMCLI-3230

Level: INFO

Description: Attempt to import server configuration.

Data: name of server

Triggers: Execute import server configuration Commandline interface.

SUCCEED_IMPORT_SERVER

ID: AMCLI-3231

Level: INFO

Description: Server configuration is imported.

Data: name of server

Triggers: Execute import server configuration Commandline interface.

FAILED IMPORT SERVER

ID: ĀMCLI-3232

Level: INFO

Description: Unable to import server configuration.

Data: name of server, error message

Triggers: Execute import server configuration Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_GET_SUPPORTED_DATA_TYPES

ID: AMCLI-5000

Level: INFO

Description: Attempt to get the supported data types.

Triggers: Execute get the supported data type Commandline interface.

SUCCEED_GET_SUPPORTED_DATA_TYPES ID: AMCLI-5001

Level: INFO

Description: The supported data types are retrieved.

Triggers: Execute add service attribute values Commandline interface.

FAILED GET SUPPORTED DATA TYPES

ID: AMCLI-5002

Level: INFO

Description: Unable to get the supported data types.

Data: error message

Triggers: Execute get the supported data types Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_CREATE_AGENT

ID: AMCLI-4000

Level: INFO

Description: Attempt to create an agent.

Data: realm, agent type, name of agent

Triggers: Execute create agent Commandline interface.

SUCCEED CREATE AGENT

ID: AMCLI-4001

Level: INFO

Description: Agent is created.

Data: realm, agent type, name of agent

Triggers: Execute create agent Commandline interface.

FAILED CREATE AGENT

ID: AMCLI-4002

Level: INFO

Description: Unable to create agent.

Log Messages

Data: realm, agent type, name of agent, error message

Triggers: Execute create agent Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT DELETE AGENTS

ID: AMCLI-4010

Level: INFO

Description: Attempt to delete agents.

Data: name of realm, name of agents

Triggers: Execute delete agents Commandline interface.

SUCCEED DELETE AGENTS

ID: AMCLI-4011

Level: INFO

Description: Agents are deleted.

Data: name of realm, name of agents

Triggers: Execute delete agents Commandline interface.

FAILED DELETE AGENTS

ID: AMCLI-4012

Level: INFO

Description: Unable to delete agents.

Data: name of realm, name of agents, error message

Triggers: Execute delete agents Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT UPDATE AGENT

ID: AMCLI-4020

Level: INFO

Description: Attempt to set attribute values of an agent.

Data: name of realm, name of agent

Triggers: Execute update agent Commandline interface.

SUCCEED_UPDATE_AGENT ID: AMCLI-4021

Level: INFO

Description: Agent profile is modified.

Data: name of realm, name of agent

Triggers: Execute update agent Commandline interface.

FAILED UPDATE AGENT

ID: AMCLI-4022

Level: INFO

Description: Unable to update an agent.

Data: name of realm, name of agent, error message

Triggers: Execute update agent Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT LIST AGENTS

ID: AMCLI-4030

Level: INFO

Description: Attempt to list agents.

Data: name of realm, agent type, search pattern

Triggers: Execute list agents Commandline interface.

SUCCEED LIST AGENTS

ID: AMCLI-4031

Level: INFO

Description: Search Result is returned.

Data: name of realm, agent type, search pattern

Triggers: Execute list agents Commandline interface.

FAILED LIST AGENTS

ID: AMCLI-4032

Level: INFO

Description: Unable to list agents.

Data: name of realm, agent type, search pattern, error message

Triggers: Execute list agents Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT SHOW AGENT

ID: AMCLI-4040

Level: INFO

Description: Attempt to get attribute values of an agent.

Data: name of realm, name of agent

Triggers: Execute get the attribute values of an agent Commandline

interface.

SUCCEED SHOW AGENT

ID: AMCLI-4041

Level: INFO

Description: Attribute values are returned.

Data: name of realm, name of agent

Triggers: Execute get the attribute values of an agent Commandline

interface.

FAILED SHOW AGENT

ID: AMCLI-4042

Level: INFO

Description: Unable to get the attribute values of an agent.

Data: name of realm, name of agent, error message

Triggers: Execute get the attribute values of an agent Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT_CREATE_AGENT_GROUP

ID: AMCLI-4050

Level: INFO

Log Messages

Description: Attempt to create an agent group.

Data: realm, agent type, name of agent group

Triggers: Execute create agent group Commandline interface.

SUCCEED CREATE AGENT GROUP

ID: AMCLI-4051

Level: INFO

Description: Agent group is created.

Data: realm, agent type, name of agent group

Triggers: Execute create agent group Commandline interface.

FAILED CREATE AGENT GROUP

ID: AMCLI-4052

Level: INFO

Description: Unable to create agent group.

Data: realm, agent type, name of agent group, error message

Triggers: Execute create agent group Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_DELETE_AGENT_GROUPS ID: AMCLI-4060

Level: INFO

Description: Attempt to delete agent groups.

Data: name of realm, name of agent groups

Triggers: Execute delete agent groups Commandline interface.

SUCCEED DELETE AGENT GROUPS

ID: AMCLI-4061

Level: INFO

Description: Agent groups are deleted.

Data: name of realm, name of agent groups

Triggers: Execute delete agent groups Commandline interface.

FAILED_DELETE_AGENT_GROUPS

ID: AMCLI-4062

Level: INFO

Description: Unable to delete agent groups.

Data: name of realm, name of agent groups, error message

Triggers: Execute delete agent groups Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT LIST AGENT GROUPS

ID: AMCLI-4070

Level: INFO

Description: Attempt to list agent groups.

Data: name of realm, agent type, search pattern

Triggers: Execute list agent groups Commandline interface.

SUCCEED LIST AGENT GROUPS

ID: AMCLI-4071

Level: INFO

Description: Search Result is returned.

Data: name of realm, agent type, search pattern

Triggers: Execute list agent groups Commandline interface.

FAILED LIST AGENT GROUPS

ID: AMCLI-4072

Level: INFO

Description: Unable to list agent groups.

Data: name of realm, agent type, search pattern, error message

Triggers: Execute list agent groups Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT ADD AGENT TO GROUP

ID: AMCLI-4080

Level: INFO

Description: Attempt to add agent to group.

Data: name of realm, name of agent group, name of agent

Triggers: Execute add agents to group Commandline interface.

SUCCEED_ADD_AGENT_TO_GROUP

ID: AMCLI-4081

Level: INFO

Description: Agent is added to group.

Data: name of realm, name of agent group, name of agent

Triggers: Execute add agent to group Commandline interface.

FAILED ADD AGENT TO GROUP

ID: AMCLI-4082

Level: INFO

Description: Unable to add agent to group.

Data: name of realm, name of agent group, name of agent, error message

Triggers: Execute add agent to group Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT REMOVE AGENT FROM GROUP

ID: AMCLI-4090

Level: INFO

Description: Attempt to remove agent from group.

Data: name of realm, name of agent group, name of agent

Triggers: Execute remove agent from group Commandline interface.

SUCCEED REMOVE AGENT FROM GROUP

ID: AMCLI-4091

Level: INFO

Description: Agent is removed to group.

Data: name of realm, name of agent group, name of agent

Triggers: Execute remove agent from group Commandline interface.

FAILED_REMOVE_AGENT_FROM_GROUP

ID: AMCLI-4092

Level: INFO

Description: Unable to remove agent from group.

Data: name of realm, name of agent group, name of agent, error message

Triggers: Execute remove agent from group Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT SET AGENT PWD

ID: AMCLI-4100

Level: INFO

Description: Attempt to set agent password.

Data: realm, name of agent

Triggers: Execute set agent password Commandline interface.

SUCCEED SET AGENT PWD

ID: AMCLI-4101

Level: INFO

Description: Agent password is modified.

Data: realm, name of agent

Triggers: Execute set agent password Commandline interface.

FAILED SET AGENT PWD

ID: AMCLI-4102

Level: INFO

Description: Unable to set agent password.

Data: realm, name of agent, error message

Triggers: Execute set agent password Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SHOW_AGENT_GROUP ID: AMCLI-4110

Level: INFO

Description: Attempt to get attribute values of an agent group.

Data: name of realm, name of agent group

Triggers: Execute get the attribute values of an agent group Commandline interface.

SUCCEED SHOW AGENT GROUP

ID: AMCLI-4111

Level: INFO

Description: Attribute values are returned.

Data: name of realm, name of agent group

Triggers: Execute get the attribute values of an agent group Commandline interface.

FAILED SHOW AGENT GROUP

ID: AMCLI-4112

Level: INFO

Description: Unable to get the attribute values of an agent group.

Data: name of realm, name of agent group, error message

Triggers: Execute get the attribute values of an agent group Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT UPDATE AGENT GROUP

ID: AMCLI-4120

Level: INFO

Description: Attempt to set attribute values of an agent group.

Data: name of realm, name of agent group

Triggers: Execute update agent group Commandline interface.

SUCCEED_UPDATE AGENT GROUP

ID: AMCLI-4121

Level: INFO

Description: Agent group profile is modified.

Data: name of realm, name of agent group

Triggers: Execute update agent group Commandline interface.

FAILED_UPDATE_AGENT_GROUP

ID: AMCLI-4122

Level: INFO

Description: Unable to update an agent.

Data: name of realm, name of agent group, error message

Triggers: Execute update agent group Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SHOW_AGENT_TYPES

ID: AMCLI-4130

Level: INFO

Description: Attempt to show supported agent types.

Triggers: Execute show supported agent types Commandline interface.

SUCCEED_SHOW_AGENT_TYPES ID: AMCLI-4131

Level: INFO

Description: Supported agent types is displayed.

Triggers: Execute show supported agent types Commandline interface.

FAILED SHOW AGENT TYPES

ID: AMCLI-4132

Level: INFO

Description: Unable to show supported agent types.

Data: error message

Triggers: Execute show supported agent types Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SHOW_AGENT_GROUP_MEMBERS ID: AMCLI-4140

Level: INFO

Description: Attempt to show agent group members.

Data: name of realm, name of agent group

Triggers: Execute show agent group members Commandline interface.

SUCCEED SHOW AGENT GROUP MEMBERS

ID: AMCLI-4141

Level: INFO

Description: Agent group's members are displayed.

Data: name of realm, name of agent group

Triggers: Execute show agent group members Commandline interface.

FAILED_SHOW_AGENT_GROUP MEMBERS

ID: AMCLI-4142

Level: INFO

Description: Unable to show agent group members.

Data: name of realm, name of agent group, error message

Triggers: Execute show agent group members Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT LIST AGENT MEMBERSHIP

ID: AMCLI-4150

Level: INFO

Description: Attempt to show agent's membership.

Data: name of realm, name of agent

Triggers: Execute show agent's membership Commandline interface.

SUCCEED LIST AGENT MEMBERSHIP

ID: AMCLI-4151

Level: INFO

Description: Agent's membership are displayed.

Data: name of realm, name of agent

Triggers: Execute show agent's membership Commandline interface.

FAILED LIST AGENT MEMBERSHIP

ID: AMCLI-4152

Level: INFO

Description: Unable to show agent's membership.

Data: name of realm, name of agent, error message

Triggers: Execute show agent's membership Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT REGISTER AUTH MODULE

ID: AMCLI-4500

Level: INFO

Description: Attempt to register authentication module.

Data: name of service

Triggers: Execute register authentication module Commandline interface.

SUCCEED_REGISTER_AUTH_MODULE ID: AMCLI-4501

Level: INFO

Description: Authentication module is registered.

Data: name of service

Triggers: Execute register authentication module Commandline interface.

FAILED REGISTER AUTH MODULE

ID: AMCLI-4502

Level: INFO

Description: Unable to register authentication module.

Data: name of service, error message

Triggers: Execute register authentication module Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT UNREGISTER AUTH MODULE

ID: AMCLI-4510

Level: INFO

Description: Attempt to unregister authentication module.

Data: name of service

Triggers: Execute unregister authentication module Commandline interface.

SUCCEED UNREGISTER AUTH MODULE

ID: AMCLI-4511

Level: INFO

Description: Authentication module is unregistered.

Data: name of service

Triggers: Execute unregister authentication module Commandline interface.

FAILED UNREGISTER AUTH MODULE

ID: AMCLI-4512

Level: INFO

Description: Unable to unregister authentication module.

Data: name of service, error message

Triggers: Execute unregister authentication module Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_GET_SUPPORTED_AUTH_MODULES ID: AMCLI-4515

Level: INFO

Description: Attempt to get supported authentication modules in the system.

Triggers: Execute get supported authentication modules in the system Commandline interface.

SUCCEED GET SUPPORTED AUTH MODULES

ID: AMCLI-4516

Level: INFO

Description: Supported authentication modules in the system are displayed.

Triggers: Execute get supported authentication modules in the system module Commandline interface.

FAILED_GET_SUPPORTED_AUTH_MODULES

ID: AMCLI-4517

Level: INFO

Description: Failed to get supported authentication modules in the system.

Data: error message

Triggers: Execute get supported authentication modules in the system Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT REMOVE AGENT PROPERTIES

ID: AMCLI-4520

Level: INFO

Description: Attempt to remove property values of an agent.

Data: name of realm, name of agent, property names

Triggers: Execute remove property values of an agent Commandline

interface.

SUCCEED REMOVE AGENT PROPERTIES

ID: AMCLI-4521

Level: INFO

Description: Property values are removed.

Data: name of realm, name of agent, property names

Triggers: Execute remove property values of an agent Commandline

interface.

FAILED REMOVE AGENT PROPERTIES

ID: AMCLI-4522

Level: INFO

Description: Unable to remove property values of an agent.

Data: name of realm, name of agent, property names, error message

Triggers: Execute remove property values of an agent Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT GET SERVER CONFIG XML

ID: $A\overline{M}CLI-\overline{4}600$

Level: INFO

Description: Attempt to get server configuration XML.

Data: name of server

Triggers: Execute get server configuration XML Commandline interface.

SUCCEED GET SERVER CONFIG XML

ID: AMCLI-4601

Level: INFO

Description: Server configuration XML is displayed.

Data: name of server

Triggers: Execute get server configuration XML Commandline interface.

FAILED GET SERVER CONFIG XML

ID: AMCLI-4602

Level: INFO

Description: Unable to get server configuration XML.

Data: name of server, error message

Triggers: Execute get server configuration XML Commandline interface.

Actions: Check if servername is correct.; Look under debug file for more information.

ATTEMPT_SET_SERVER_CONFIG_XML

ID: AMCLI-4610

Level: INFO

Description: Attempt to set server configuration XML.

Data: name of server

Triggers: Execute set server configuration XML Commandline interface.

SUCCEED_SET_SERVER_CONFIG_XML

ID: AMCLI-4611

Level: INFO

Description: Server configuration XML is set.

Data: name of server

Triggers: Execute set server configuration XML Commandline interface.

FAILED SET SERVER CONFIG XML

ID: AMCLI-4612

Level: INFO

Description: Unable to set server configuration XML.

Data: name of server, error message

Triggers: Execute set server configuration XML Commandline interface.

Actions: Check if servername is correct.; Look under debug file for more information.

ATTEMPT LIST DATASTORE TYPES

ID: AMCLI-4700

Level: INFO

Description: Attempt to list supported datastore types.

Triggers: Execute list supported datastore types Commandline interface.

SUCCEEDED_LIST_DATASTORE_TYPES

ID: AMCLĪ-470Ī

Level: INFO

Description: List supported datastore types succeeded.

Triggers: Execute list supported datastore types Commandline interface.

FAILED LIST DATASTORE TYPES

ID: AMCLI-4702

Level: INFO

Description: Failed to list supported datastore types.

Data: error message

Triggers: Execute list supported datastore types Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_ADD_AUTH_CONFIG_ENTRY

ID: AMCLI-4800

Level: INFO

Description: Attempt to add authentication configuration entry.

Data: name of realm, name of authentication configuration, name of module

Triggers: Execute add authentication configuration entry Commandline interface.

SUCCEEDED ADD AUTH CONFIG ENTRY

ID: AMCLĪ-480Ī

Level: INFO

Description: Authentication instance configuration entry is created.

Data: name of realm, name of authentication configuration, name of module

Triggers: Execute add authentication configuration entry Commandline interface.

FAILED ADD AUTH CONFIG ENTRY

ID: AMCLI-4802

Level: INFO

Description: Failed to add authentication configuration entry.

Data: name of realm, name of authentication configuration, name of module, error message

Triggers: Execute add authentication configuration entry Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SHOW_DATASTORE

ID: AMCLI-5000

Level: INFO

Log Messages

Description: Attempt to show datastore profile.

Data: name of realm, name of datastore

Triggers: Execute show datastore Commandline interface.

SUCCEEDED SHOW DATASTORE

ID: AMCLI-5001

Level: INFO

Description: Show datastore succeeded.

Data: name of realm, name of datastore

Triggers: Execute show datastore Commandline interface.

FAILED SHOW DATASTORE

ID: AMCLI-5002

Level: INFO

Description: Failed to show datastore profile.

Data: name of realm, name of datastore, error message

Triggers: Execute show datastore Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_ADD_AMSDK_PLUGIN ID: AMCLI-5100

Level: INFO

Description: Add AMSDK IdRepo Plugin.

Data: name of datastore name

Triggers: Execute add AMSDK IdRepo Plugin Commandline interface.

SUCCEED ADD AMSDK PLUGIN

ID: AMCLI-5101

Level: INFO

Description: AMSDK plugin is added.

Data: name of datastore name

Triggers: Execute add AMSDK IdRepo Plugin Commandline interface.

FAILED_ADD_AMSDK_PLUGIN

ID: AMCLI-5102

Level: INFO

Description: Failed to add AMSDK IdRepo Plugin.

Data: name of datastore name, error message

Triggers: Execute add AMSDK IdRepo Plugin Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT SET SVC ATTR VALUES REALM

ID: AMCLI-5200

Level: INFO

Description: Attempt to set attribute value to a service that is assigned to a realm.

Data: name of realm, name of service

Triggers: Execute set attribute values a service that is assigned to a to realm Commandline interface.

SUCCEED_SET_SVC_ATTR_VALUES_REALM

ID: AMCLI-5201

Level: INFO

Description: Attribute values is set to a service that is assigned to a realm.

Data: name of realm, name of service

Triggers: Execute set attribute values to a service that is assigned to a realm Commandline interface.

FAILED SET SVC ATTR VALUES REALM

ID: AMCLI-5202

Level: INFO

Description: Unable to set attribute values to a service that is assigned to a realm.

Data: name of realm, name of service, error message

Triggers: Execute set attribute values to a service that is assigned to a realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT EMBEDDED STATUS

ID: AMCLI-5103

Level: INFO

Description: Get Embedded Status.

Data: port number of embedded store

Triggers: Execute Embedded Status Commandline interface.

SUCCEEDED EMBEDDED STATUS

ID: AMCLI-5104

Level: INFO

Description: Embedded Status Successful.

Data: port number of embedded store

Triggers: Execute Embedded Status Commandline interface.

FAILED EMBEDDED STATUS

ID: AMCLI-5105

Level: INFO

Description: Failed to get embedded status.

Data: port number of embedded store, error message

Triggers: Execute Embedded Status Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_ADD_COT MEMBER

ID: AMCLI-5106

Level: INFO

Description: Attempt to add a member to a Circle of Trust.

Data: realm, entity ID, circle of trust, protocol specification

Triggers: Execute add a member to a Circle of Trust Commandline interface.

SUCCEEDED ADD COT MEMBER

ID: AMCLI-5107

Level: INFO

Description: Adding a member to a Circle of Trust succeeded.

Data: realm, entity ID, circle of trust, protocol specification

Triggers: Execute add a member to a Circle of Trust Commandline interface.

FAILED ADD COT MEMBER

ID: AMCLI-5108

Level: INFO

Description: Failed to add a member to a circle of trust.

Data: realm, entity ID, circle of trust, protocol specification, error message

Triggers: Execute add a member to a Circle of Trust Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT DO BULK FEDERATION

ID: AMCLI-5109

Level: INFO

Description: Attempt to do bulk federation.

Data: metaAlias for local provider, Remote entity Id, File name of local to remote user Id mapping, Name of file that will be created by this sub command, protocol specification

Triggers: Execute Do Bulk Federation Commandline interface.

SUCCEEDED DO BULK FEDERATION

ID: AMCLI-5110

Level: INFO

Description: Bulk Federation succeeded.

Data: metaAlias for local provider, Remote entity Id, File name of local to remote user Id mapping, Name of file that will be created by this sub command, protocol specification

Triggers: Execute Do Bulk Federation Commandline interface.

FAILED DO BULK FEDERATION

ID: AMCLI-5111

Level: INFO

Description: Failed to do bulk federation.

Data: metaAlias for local provider, Remote entity Id, File name of local to remote user Id mapping, Name of file that will be created by this sub command, protocol specification, error message

Triggers: Execute Do Bulk Federation Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_CREATE_COT

ID: AMCLI-5112

Level: INFO

Description: Attempt to create Circle of Trust.

Data: Realm, Circle of Trust, Trusted Providers, Prefix URL for idp discovery

reader and writer URL

Triggers: Execute Create Circle of Trust Commandline interface.

SUCCEEDED CREATE COT

ID: AMCLI-5113

Level: INFO

Description: Creating Circle of Trust succeeded.

Data: Realm, Circle of Trust, Trusted Providers, Prefix URL for idp discovery

reader and writer URL

Triggers: Execute Create Circle of Trust Commandline interface.

FAILED_CREATE_COT

ID: AMCLI-5114

Level: INFO

Description: Failed to create Circle of Trust.

Data: Realm, Circle of Trust, Trusted Providers, Prefix URL for idp discovery

reader and writer URL, error message

Triggers: Execute Create Circle of Trust Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT CREATE METADATA TEMPL

ID: AMCLI-5115

Level: INFO

Description: Attempt to create metadata template.

Data: Entity ID, file name for the standard metadata to be created, file name for the extended metadata to be created, metaAlias for hosted identity provider to be created, metaAlias for hosted service provider to be created, metaAlias for hosted attribute authority to be created, metaAlias for hosted attribute query provider to be created, metaAlias for hosted authentication authority to be created, metaAlias for policy decision point to be created, metaAlias for policy enforcement point to be created, metaAlias for hosted affiliation, protocol specification

Triggers: Execute Create MetaData Template Commandline interface.

SUCCEEDED CREATE METADATA TEMPL

ID: AMCLI-5116

Level: INFO

Description: Creating MetaData Template succeeded.

Data: Entity ID, file name for the standard metadata to be created, file name for the extended metadata to be created, metaAlias for hosted identity provider to be created, metaAlias for hosted service provider to be created, metaAlias for hosted attribute authority to be created, metaAlias for hosted attribute query provider to be created, metaAlias for hosted authentication authority to be created, metaAlias for policy decision point to be created, metaAlias for policy enforcement point to be created, metaAlias for hosted affiliation, protocol specification

Triggers: Execute Create MetaData Template Commandline interface.

FAILED CREATE METADATA TEMPL

ID: AMCLI-5117

Level: INFO

Description: Failed to create metaData template.

Data: Entity ID, protocol specification, error message

Triggers: Execute Create MetaData Template Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_DELETE_COT

ID: AMCLI-5118

Level: INFO

Log Messages

Description: Attempt to delete Circle of Trust.

Data: Realm, Circle of Trust

Triggers: Execute Delete Circle of Trust Commandline interface.

SUCCEEDED DELETE COT

ID: AMCLĪ-5119

Level: INFO

Description: Deleting Circle of Trust succeeded.

Data: Realm, Circle of Trust

Triggers: Execute Delete Circle of Trust Commandline interface.

FAILED_DELETE_COT

ID: AMCLI-5120

Level: INFO

Description: Failed to delete Circle of Trust.

Data: Realm, Circle of Trust, error message

Triggers: Execute Delete Circle of Trust Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT DELETE ENTITY

ID: AMCLI-5121

Level: INFO

Description: Attempt to delete metadata.

Data: Realm, Entity ID, protocol specification

Triggers: Execute Delete Metadata Commandline interface.

SUCCEEDED DELETE ENTITY

ID: AMCLI-5122

Level: INFO

Description: Deleting Metadata succeeded.

Data: Realm, Entity ID, protocol specification

Triggers: Execute Delete Metadata Commandline interface.

FAILED_DELETE_ENTITY

ID: AMCLI-5123

Level: INFO

Description: Failed to delete metadata.

Data: Realm, Entity ID, protocol specification, error message

Triggers: Execute Delete Metadata Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT EXPORT ENTITY

ID: AMCLI-5124

Level: INFO

Description: Attempt to export entity.

Data: Realm, Entity ID, Name of file to save the standard metadata XML, Name of file to save the extended metadata XML, protocol specification

Triggers: Execute export entity Commandline interface.

SUCCEEDED EXPORT ENTITY

ID: AMCLI-5125

Level: INFO

Description: Exporting entity succeeded.

Data: Realm, Entity ID, Name of file to save the standard metadata XML, Name of file to save the extended metadata XML, protocol specification

Triggers: Execute export entity Commandline interface.

FAILED EXPORT ENTITY

ID: AMCLI-5126

Level: INFO

Description: Failed to export entity.

Data: Realm, Entity ID, Name of file to save the standard metadata XML, Name of file to save the extended metadata XML, protocol specification, error message

Triggers: Execute export entity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_IMPORT_BULK_FED_DATA

ID: AMCLI-5127

Level: INFO

Description: Attempt to import bulk federation data.

Data: metaAlias for local provider, File name of bulk federation data which is generated by this command, protocol specification

Triggers: Execute import bulk federation data Commandline interface.

SUCCEEDED_IMPORT_BULK_FED_DATA

ID: AMCLI-5128

Level: INFO

Description: Importing bulk federation data succeeded.

Data: metaAlias for local provider, File name of bulk federation data which is generated by this command, protocol specification

Triggers: Execute import bulk federation data Commandline interface.

FAILED IMPORT BULK FED DATA

ID: AMCLI-5129

Level: INFO

Description: Failed to import bulk federation data.

Data: metaAlias for local provider, File name of bulk federation data which is generated by this command, protocol specification, error message

Triggers: Execute import bulk federation data Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT IMPORT ENTITY

ID: AMCLI-5130

Level: INFO

Description: Attempt to import entity.

Data: Realm where entity resides, file name for the standard metadata to be imported, file name for the extended entity configuration to be imported, name of the Circle of Trust this entity belongs, protocol specification

Triggers: Execute import entity Commandline interface.

SUCCEEDED_IMPORT_ENTITY

ID: AMCLĪ-5131

Level: INFO

Description: Importing entity succeeded.

Data: Realm where entity resides, file name for the standard metadata to be imported, file name for the extended entity configuration to be imported, name of the Circle of Trust this entity belongs, protocol specification

Triggers: Execute import entity Commandline interface.

FAILED IMPORT ENTITY

ID: AMCLI-5132

Level: INFO

Description: Failed to import entity.

Data: Realm where entity resides, file name for the standard metadata to be imported, file name for the extended entity configuration to be imported, name of the Circle of Trust this entity belongs, protocol specification, error message

Triggers: Execute import entity Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT LIST COT MEMBERS

ID: AMCLI-5133

Level: INFO

Description: Attempt to list members in a circle of trust.

Data: Realm, Circle of trust, protocol specification

Triggers: Execute list members in a circle of trust Commandline interface.

SUCCEEDED LIST COT MEMBERS

ID: AMCLĪ-5134

Level: INFO

Description: Listing members in a circle of trust succeeded.

Data: Realm, Circle of trust, protocol specification

Triggers: Execute list members in a circle of trust Commandline interface.

FAILED_LIST_COT_MEMBERS ID: AMCLI-5135

Level: INFO

Description: Failed to list members in a circle of trust.

Data: Realm, Circle of trust, protocol specification, error message

Triggers: Execute list members in a circle of trust Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT LIST COTS

ID: AMCLI-5136

Level: INFO

Description: Attempt to list circles of trust.

Data: realm

Triggers: Execute list circles of trust Commandline interface.

SUCCEEDED LIST COTS

ID: AMCLĪ-5137

Level: INFO

Description: Listing circles of trust succeeded.

Data: realm

Triggers: Execute list circles of trust Commandline interface.

FAILED LIST COTS

ID: AMCLI-5138

Level: INFO

Description: Failed to list circles of trust.

Data: realm, error message

Triggers: Execute list circles of trust Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT LIST ENTITIES

ID: AMCLI-5139

Level: INFO

Description: Attempt to list entities under a realm.

Data: realm, protocol specification

Triggers: Execute list entities under a realm Commandline interface.

SUCCEEDED LIST ENTITIES

ID: AMCLĪ-5140

Level: INFO

Description: Listing entities under a realm succeeded.

Data: realm, protocol specification

Triggers: Execute list entities under a realm Commandline interface.

FAILED_LIST_ENTITIES

ID: AMCLI-5141

Level: INFO

Description: Failed to list entities under a realm.

Data: realm, protocol specification, error message

Triggers: Execute list entities under a realm Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT REMOVE COT MEMBER

ID: AMCLI-5142

Level: INFO

Description: Attempt to remove a member from a circle of trust.

 ${\tt Data: Realm\ where\ circle\ of\ trust\ resides,\ Circle\ of\ trust,\ Entity\ ID,\ protocol}$

specification

Triggers: Execute remove a member from a circle of trust Commandline

interface.

SUCCEEDED_REMOVE_COT_MEMBER

ID: AMCLI-5143

Level: INFO

Description: Removing a member from a circle of trust successful.

 $\mbox{\it Data:}$ Realm where circle of trust resides, Circle of trust, Entity ID, protocol specification

Triggers: Execute remove a member from a circle of trust Commandline interface.

FAILED REMOVE COT MEMBER

ID: AMCLI-5144

Level: INFO

Description: Failed to remove a member from a circle of trust.

Data: Realm where circle of trust resides, Circle of trust, Entity ID, protocol specification, error message

Triggers: Execute remove a member from a circle of trust Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT UPDATE ENTITY KEYINFO

ID: AMCLI-5145

Level: INFO

Description: Attempt to update XML signing and encryption key information in hosted entity metadata.

Data: Realm, Entity ID, Service provider signing certificate alias, Identity provider signing certificate alias, Service provider encryption certificate alias, Identity provider encryption certificate alias, protocol specification

Triggers: Execute Commandline interface.

SUCCEEDED UPDATE ENTITY KEYINFO

ID: AMCLI-5146

Level: INFO

Description: Updating XML signing and encryption key information in hosted entity metadata succeeded.

Data: Realm, Entity ID, Service provider signing certificate alias, Identity provider signing certificate alias, Service provider encryption certificate alias, Identity provider encryption certificate alias

Triggers: Execute update XML signing and encryption key information in hosted entity metadata Commandline interface.

$FAILED_UPDATE_ENTITY_KEYINFO$

ID: AMCLI-5147

Level: INFO

Description: Failed to update XML signing and encryption key information in hosted entity metadata.

Data: Realm, Entity ID, Service provider signing certificate alias, Identity provider signing certificate alias, Service provider encryption certificate alias, Identity provider encryption certificate alias, error message

Triggers: Execute update XML signing and encryption key information in hosted entity metadata Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT CREATE APPLICATION

ID: AMCLI-5500

Level: INFO

Description: Attempt to create application.

Data: Realm, Application name

Triggers: Execute create application Commandline interface.

SUCCEEDED CREATE APPLICATION

ID: AMCLĪ-5501

Level: INFO

Description: Create application succeeded.

Data: Realm, Application name

Triggers: Execute create application Commandline interface.

FAILED CREATE APPLICATION

ID: AMCLI-5502

Level: INFO

Description: Failed to create application.

Data: Realm, Application name, error message

Triggers: Execute create application Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT LIST APPLICATIONS

ID: AMCLI-5510

Level: INFO

Description: Attempt to list applications in a realm.

Data: Realm

Triggers: Execute list applications Commandline interface.

SUCCEEDED LIST APPLICATIONS

ID: AMCLĪ-551Ī

Level: INFO

Description: List applications in a realm succeeded.

Data: Realm

Triggers: Execute list applications Commandline interface.

FAILED LIST APPLICATIONS

ID: ĀMCLĪ-5512

Level: INFO

Description: Failed to list applications.

Data: Realm, error message

Triggers: Execute list applications Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_LIST_APPLICATION_TYPES

ID: AMCLI-5520

Level: INFO

Description: Attempt to list application types.

Triggers: Execute list application types Commandline interface.

SUCCEEDED_LIST_APPLICATION_TYPES

ID: AMCLĪ-552Ī

Level: INFO

Description: List application types succeeded.

Triggers: Execute list application types Commandline interface.

FAILED_LIST_APPLICATION_TYPES

ID: ĀMCLĪ-5522

Level: INFO

Description: Failed to list application types.

Data: error message

Triggers: Execute list application types Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT SHOW APPLICATION

ID: AMCLI-5530

Level: INFO

Description: Attempt to show application attributes.

Data: Realm, Application Name

Triggers: Execute show application Commandline interface.

SUCCEEDED SHOW APPLICATION

ID: AMCLI-5531

Level: INFO

Description: Attributes of application is displayed succeeded.

Data: Realm, Application Name

Triggers: Execute show application Commandline interface.

FAILED SHOW APPLICATION

ID: AMCLI-5532

Level: INFO

Description: Failed to show application attributes.

Data: Realm, Application Name, error message

Triggers: Execute show application Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT SET APPLICATION

ID: AMCLI-5540

Log Messages

Level: INFO

Description: Attempt to set application attributes.

Data: Realm, Application Name

Triggers: Execute set application attributes Commandline interface.

SUCCEEDED SET APPLICATION

ID: AMCLI-5541

Level: INFO

Description: Attributes of application is modified succeeded.

Data: Realm, Application Name

Triggers: Execute set application attributes Commandline interface.

FAILED SET APPLICATION

ID: AMCLI-5542

Level: INFO

Description: Failed to set application attributes.

Data: Realm, Application Name, error message

Triggers: Execute set application attributes Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT DELETE APPLICATIONS

ID: AMCLI-5550

Level: INFO

Description: Attempt to delete applications.

Data: Realm

Triggers: Execute delete applications Commandline interface.

SUCCEEDED_DELETE_APPLICATIONS

ID: AMCLI-5551

Level: INFO

Description: Application are deleted.

Data: Realm

Triggers: Execute delete applications Commandline interface.

FAILED DELETE APPLICATIONS

ID: AMCLI-5552

Level: INFO

Description: Failed to delete applications.

Data: Realm, error message

Triggers: Execute delete applications Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT SHOW APPLICATION TYPE

ID: AMCLI-5553

Level: INFO

Description: Attempt to show application type details.

Data: Application Type name

Triggers: Execute show application type Commandline interface.

SUCCEEDED SHOW APPLICATION TYPE

ID: AMCLI-5554

Level: INFO

Description: Show application type details succeded.

Data: Application Type name

Triggers: Execute show application type Commandline interface.

ATTEMPT DELETE APPLICATION TYPES

ID: AMCLI-5555

Level: INFO

Description: Attempt to delete application types.

Data: Application Type names

Triggers: Execute delete application types Commandline interface.

SUCCEEDED DELETE APPLICATION TYPES

ID: AMCLI-5556

Level: INFO

Description: Delete application types succeeded.

Data: Application Type names

Triggers: Execute delete application types Commandline interface.

FAILED_DELETE_APPLICATION_TYPES

ID: AMCLI-5557

Level: INFO

Description: Delete application types failed.

Data: Application Type names, error message

Triggers: Execute delete application types Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_CREATE_APPLICATION_TYPE

ID: AMCLI-5558

Level: INFO

Description: Attempt to create application type.

Data: Application Type name

Triggers: Execute create application type Commandline interface.

SUCCEEDED CREATE APPLICATION TYPE

ID: AMCLI-5559

Level: INFO

Description: Create application type succeeded.

Data: Application Type name

Triggers: Execute create application type Commandline interface.

FAILED CREATE APPLICATION TYPE

ID: AMCLI-5560

Level: INFO

Description: Failed to create application type.

Data: Application Type name, error message

Triggers: Execute create application type Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SHOW_ENTITLEMENT SVC

ID: AMCLI-5600

Level: INFO

Description: Attempt to show entitlement service configuration.

Triggers: Execute show entitlement service configuration Commandline interface.

SUCCEEDED SHOW ENTITLEMENT SVC

ID: AMCLI-5601

Level: INFO

Description: Entitlement service configuration is displayed.

Triggers: Execute show entitlement service configuration Commandline interface.

FAILED SHOW ENTITLEMENT SVC

ID: AMCLI-5602

Level: INFO

Description: Failed to display entitlement service configuration.

Data: error message

Triggers: Execute show entitlement service configuration Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_MODIFY_ENTITLEMENT SVC

ID: AMCLI-5610

Level: INFO

Description: Attempt to modify entitlement service configuration.

Triggers: Execute set entitlement service configuration Commandline interface.

SUCCEEDED MODIFY ENTITLEMENT SVC

ID: AMCLI-5611

Description: Entitlement service configuration is modified.

Triggers: Execute set entitlement service configuration Commandline

interface.

FAILED MODIFY ENTITLEMENT SVC

ID: AMCLI-5612

Level: INFO

Description: Failed to modify entitlement service configuration.

Data: error message

Triggers: Execute set entitlement service configuration Commandline

interface.

Actions: Look under debug file for more information.

ATTEMPT CREATE APPLICATION PRIVILEGE

ID: AMCLI-6010

Level: INFO

Description: Attempt to create application privilege.

Data: realm, application privilege name

Triggers: Execute create application privilege Commandline interface.

SUCCEEDED_CREATE_APPLICATION PRIVILEGE

ID: AMCLI-6011

Level: INFO

Description: Application privilege is created.

Data: realm, application privilege name

Triggers: Execute create application privilege Commandline interface.

FAILED CREATE APPLICATION PRIVILEGE

ID: AMCLI-6012

Level: INFO

Description: Failed to create application privilege.

Data: realm, application privilege name, error message

Triggers: Execute create application privilege Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT DELETE APPLICATION PRIVILEGE

ID: AMCLI-6020

Level: INFO

Description: Attempt to delete application privilege.

Data: realm, application privilege name

Triggers: Execute delete application privilege Commandline interface.

SUCCEEDED DELETE APPLICATION PRIVILEGE

ID: AMCLI-6021

Level: INFO

Description: Application privilege is deleted.

Data: realm, application privilege name

Triggers: Execute delete application privilege Commandline interface.

FAILED DELETE APPLICATION PRIVILEGE

ID: AMCLI-6022

Level: INFO

Description: Failed to delete application privilege.

Data: realm, application privilege name, error message

Triggers: Execute delete application privilege Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT_SHOW_APPLICATION_PRIVILEGE

ID: AMCLI-6020

Level: INFO

Description: Attempt to show application privilege.

Data: realm, application privilege name

Triggers: Execute show application privilege Commandline interface.

SUCCEEDED SHOW APPLICATION PRIVILEGE

ID: AMCLI-6021

Description: Application privilege is displayed.

Data: realm, application privilege name

Triggers: Execute show application privilege Commandline interface.

FAILED_SHOW_APPLICATION_PRIVILEGE

ID: AMCLI-6022

Level: INFO

Description: Failed to show application privilege.

Data: realm, application privilege name, error message

Triggers: Execute show application privilege Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT LIST APPLICATION PRIVILEGES

ID: AMCLI-6030

Level: INFO

Description: Attempt to list application privileges in a realm.

Data: realm

Triggers: Execute list application privileges Commandline interface.

SUCCEEDED LIST APPLICATION PRIVILEGES

ID: AMCLĪ-603Ī

Level: INFO

Description: Application privileges are displayed.

Data: realm

Triggers: Execute list application privileges Commandline interface.

FAILED LIST APPLICATION PRIVILEGES

ID: AMCLI-6032

Level: INFO

Description: Failed to list application privileges.

Data: realm, error message

Triggers: Execute list application privileges Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT UPDATE APPLICATION PRIVILEGE

ID: AMCLI-6040

Level: INFO

Description: Attempt to update application privilege.

Data: realm, application privilege name

Triggers: Execute update application privilege Commandline interface.

SUCCEEDED UPDATE APPLICATION PRIVILEGE

ID: AMCLI-6041

Level: INFO

Description: Application privilege is updated.

Data: realm, application privilege name

Triggers: Execute update application privilege Commandline interface.

FAILED UPDATE APPLICATION PRIVILEGE

ID: AMCLI-6042

Level: INFO

Description: Failed to update application privilege.

Data: realm, application privilege name, error message

Triggers: Execute update application privileges Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT ADD PLUGIN SCHEMA

ID: AMCLI-6043

Level: INFO

Description: Attempt to add Plug-in schema.

Data: name of service, name of interface, name of plugin, name of i18n key,

name of i18n name, name of class

Triggers: Execute add Plug-in schema Commandline interface.

SUCCEED ADD PLUGIN SCHEMA

ID: AMCLI-6044

Level: INFO

Description: Added Plug-in schema.

Data: name of service, name of plugin

Triggers: Execute add Plug-in schema Commandline interface.

FAILED ADD PLUGIN SCHEMA

ID: AMCLI-6045

Level: INFO

Description: Failed to add Plug-in schema.

Data: name of service, name of plugin, error message

Triggers: Execute add Plug-in schema Commandline interface.

Actions: Look under debug file for more information.

ATTEMPT REMOVE PLUGIN SCHEMA

ID: AMCLI-6046

Level: INFO

Description: Attempt to remove Plug-in schema.

Data: name of service, name of interface, name of plugin, name of i18n key,

name of i18n name, name of class

Triggers: Execute remove Plug-in schema Commandline interface.

SUCCEED_REMOVE_PLUGIN_SCHEMA

ID: AMCLI-6047

Level: INFO

Description: Removed Plug-in schema.

Data: name of service, name of plugin

Triggers: Execute remove Plug-in schema Commandline interface.

FAILED REMOVE PLUGIN SCHEMA

ID: AMCLI-6048

Log Messages

Description: Failed to remove Plug-in schema.

Data: name of service, name of plugin, error message

Triggers: Execute remove Plug-in schema Commandline interface.

Actions: Look under debug file for more information.

SUCCEED_SET_SITE_ID

ID: AMCLI-6049

Level: INFO

Description: Site ID is set.

Data: name of site, id of site

Triggers: Execute set site ID Commandline interface.

SUCCEED_SET_SITE_ID

ID: AMCLI-6050

Level: INFO

Description: Unable to set site ID.

Data: name of site, site ID, error message

Triggers: Execute set site ID Commandline interface.

Actions: Look under debug file for more information.

OpenAM logs the following CONSOLE messages.

ATTEMPT IDENTITY CREATION

ID: CONSOLE-1

Level: INFO

Description: Attempt to create Identity

Data: identity name, identity type, realm name

Triggers: Click on create button in Realm Creation Page.

IDENTITY CREATED

ID: CONSOLE-2

Level: INFO

Description: Creation of Identity succeeded.

Data: identity name, identity type, realm name

Triggers: Click on create button in Realm Creation Page.

SSO_EXCEPTION_IDENTITY_CREATION

ID: CONSOLE-3

Level: SEVERE

Description: Creation of Identity failed

Data: identity name, identity type, realm name, error message

Triggers: Unable to create an identity under a realm. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

IDM EXCEPTION IDENTITY CREATION

ID: CONSOLE-4

Level: SEVERE

Description: Creation of Identity failed

Data: identity name, identity type, realm name, error message

Triggers: Unable to create an identity under a realm due to data store error.

Actions: Look under data store log for more information.

ATTEMPT SEARCH IDENTITY

ID: CONSOLE-11

Level: INFO

Description: Attempt to search for Identities

Data: base realm, identity type, search pattern, search size limit, search time

limit

Triggers: Click on Search button in identity search view.

SUCCEED SEARCH IDENTITY

ID: CONSOLE-12

Level: INFO

Description: Searching for Identities succeeded

Data: base realm, identity type, search pattern, search size limit, search time limit

Triggers: Click on Search button in identity search view.

SSO_EXCEPTION_SEARCH_IDENTITY

ID: CONSOLE-13

Level: SEVERE

Description: Searching for identities failed

Data: identity name, identity type, realm name, error message

Triggers: Unable to perform search operation on identities under a realm. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

IDM EXCEPTION SEARCH IDENTITY

ID: CONSOLE-14

Level: SEVERE

Description: Searching for identities failed

Data: identity name, identity type, realm name, error message

Triggers: Unable to perform search operation on identities under a realm due to data store error.

Actions: Look under data store log for more information.

ATTEMPT READ IDENTITY ATTRIBUTE VALUE

ID: CONSOLE-21

Level: INFO

Description: Attempt to read attribute values of an identity

Data: identity name, name of attributes

Triggers: View identity profile view.

SUCCEED READ IDENTITY ATTRIBUTE VALUE

ID: CONSOLE-22

Description: Reading of attribute values of an identity succeeded

Data: identity name, name of attributes

Triggers: View identity profile view.

SSO EXCEPTION READ IDENTITY ATTRIBUTE VALUE

ID: CONSOLE-23

Level: SEVERE

Description: Reading of attribute values of an identity failed

Data: identity name, name of attributes, error message

Triggers: Unable to read attribute values of an identity. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

IDM EXCEPTION READ IDENTITY ATTRIBUTE VALUE

ID: CONSOLE-24

Level: SEVERE

Description: Reading of attribute values of an identity failed

Data: identity name, name of attributes, error message

Triggers: Unable to read attribute values of an identity due to data store

error.

Actions: Look under data store log for more information.

SMS EXCEPTION READ IDENTITY ATTRIBUTE VALUE

ID: CONSOLE-25

Level: SEVERE

Description: Reading of attribute values of an identity failed

Data: identity name, name of attributes, error message

Triggers: Unable to read attribute values of an identity due to exception service manager API.

Actions: Look under service manage log for more information.

ATTEMPT MODIFY IDENTITY ATTRIBUTE_VALUE

Description: Attempt to modify attribute values of an identity

Data: identity name, name of attributes

Triggers: Click on Save button in identity profile view.

SUCCEED MODIFY IDENTITY ATTRIBUTE VALUE

ID: CONSOLE-32

Level: INFO

Description: Modification of attribute values of an identity succeeded

Data: identity name, name of attributes

Triggers: Click on Save button in identity profile view.

SSO_EXCEPTION_MODIFY_IDENTITY_ATTRIBUTE_VALUE

ĪD: CONSOLE-33

Level: SEVERE

Description: Modification of attribute values of an identity failed

Data: identity name, name of attributes, error message

Triggers: Unable to modify attribute values of an identity. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

$IDM_EXCEPTION_MODIFY_IDENTITY_ATTRIBUTE_VALUE$

ID: CONSOLE-34

Level: SEVERE

Description: Modification of attribute values of an identity failed

Data: identity name, name of attributes, error message

error.

Actions: Look under data store log for more information.

ATTEMPT DELETE IDENTITY

Description: Attempt to delete identities

Data: realm name, name of identities to be deleted

Triggers: Click on Delete button in identity search view.

SUCCEED DELETE IDENTITY

ID: CONSOLE-42

Level: INFO

Description: Deletion of identities succeeded

Data: realm name, name of identities to be deleted

Triggers: Click on Delete button in identity search view.

SSO EXCEPTION DELETE IDENTITY

ID: CONSOLE-43

Level: SEVERE

Description: Deletion of identities failed

Data: realm name, name of identities to be deleted, error message

Triggers: Unable to delete identities. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

IDM EXCEPTION DELETE IDENTITY

ID: CONSOLE-44

Level: SEVERE

Description: Deletion of identities failed

Data: realm name, name of identities to be deleted, error message

Triggers: Unable to delete identities due to data store error.

Actions: Look under data store log for more information.

ATTEMPT READ IDENTITY MEMBERSHIP

Description: Attempt to read identity's memberships information

Data: name of identity, membership identity type

Triggers: View membership page of an identity.

SUCCEED READ IDENTITY MEMBERSHIP

ID: CONSOLE-52

Level: INFO

Description: Reading of identity's memberships information succeeded

Data: name of identity, membership identity type

Triggers: View membership page of an identity.

SSO EXCEPTION READ IDENTITY MEMBERSHIP

ĪD: CONSOLE-53

Level: SEVERE

Description: Reading of identity's memberships information failed.

Data: name of identity, membership identity type, error message

Triggers: Unable to read identity's memberships information. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

IDM EXCEPTION READ IDENTITY MEMBERSHIP

ID: CONSOLE-54

Level: SEVERE

Description: Reading of identity's memberships information failed.

Data: name of identity, membership identity type, error message

Triggers: Unable to read identity's memberships information due to data

store error.

Actions: Look under data store log for more information.

ATTEMPT READ IDENTITY MEMBER

Description: Attempt to read identity's members information

Data: name of identity, members identity type

Triggers: View members page of an identity.

SUCCEED READ IDENTITY MEMBER

ID: CONSOLE-62

Level: INFO

Description: Reading of identity's members information succeeded

Data: name of identity, members identity type

Triggers: View members page of an identity.

SSO EXCEPTION READ IDENTITY MEMBER

ĪD: CONSOLE-63

Level: SEVERE

Description: Reading of identity's members information failed.

Data: name of identity, member identity type, error message

Triggers: Unable to read identity's members information. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

IDM EXCEPTION READ IDENTITY MEMBER

ID: CONSOLE-64

Level: SEVERE

Description: Reading of identity's members information failed.

Data: name of identity, member identity type, error message

Triggers: Unable to read identity's members information due to data store

error.

Actions: Look under data store log for more information.

ATTEMPT_ADD IDENTITY MEMBER

Description: Attempt to add member to an identity

Data: name of identity, name of identity to be added.

Triggers: Select members to be added to an identity.

SUCCEED ADD IDENTITY MEMBER

ID: CONSOLE-72

Level: INFO

Description: Addition of member to an identity succeeded

Data: name of identity, name of identity added.

Triggers: Select members to be added to an identity.

SSO EXCEPTION ADD IDENTITY MEMBER

ID: CONSOLE-73

Level: SEVERE

Description: Addition of member to an identity failed.

Data: name of identity, name of identity to be added., error message

Triggers: Unable to add member to an identity. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

IDM_EXCEPTION_ADD_IDENTITY MEMBER

ID: CONSOLE-74

Level: SEVERE

Description: Addition of member to an identity failed.

Data: name of identity, name of identity to be added., error message

Triggers: Unable to add member to an identity due to data store error.

Actions: Look under data store log for more information.

ATTEMPT_REMOVE IDENTITY MEMBER

ID: CONSOLE-81

Log Messages

Description: Attempt to remove member from an identity

Data: name of identity, name of identity to be removed.

Triggers: Select members to be removed from an identity.

SUCCEED REMOVE IDENTITY MEMBER

ID: CONSOLE-82

Level: INFO

Description: Removal of member from an identity succeeded

Data: name of identity, name of identity removed.

Triggers: Select members to be removed from an identity.

SSO EXCEPTION REMOVE IDENTITY MEMBER

ID: CONSOLE-83

Level: SEVERE

Description: Removal of member to an identity failed.

Data: name of identity, name of identity to be removed., error message

Triggers: Unable to remove member from an identity. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

IDM_EXCEPTION_REMOVE IDENTITY MEMBER

ID: CONSOLE-84

Level: SEVERE

Description: Removal of member from an identity failed.

Data: name of identity, name of identity to be removed., error message

Triggers: Unable to remove member to an identity due to data store error.

Actions: Look under data store log for more information.

ATTEMPT READ IDENTITY ASSIGNED SERVICE

ID: CONSOLE-91

Level: INFO

Description: Attempt to read assigned service names of an identity

Data: name of identity

Triggers: Click on Add button in service assignment view of an identity.

SUCCEED READ IDENTITY ASSIGNED SERVICE

ID: CONSOLE-92

Level: INFO

Description: Reading assigned service names of an identity succeeded

Data: name of identity

Triggers: Click on Add button in service assignment view of an identity.

SSO EXCEPTION READ IDENTITY ASSIGNED SERVICE

ID: CONSOLE-93

Level: SEVERE

Description: Reading assigned service names of an identity failed.

Data: name of identity, error message

Triggers: Unable to read assigned service names of an identity. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

$IDM_EXCEPTION_READ_IDENTITY_ASSIGNED_SERVICE$

ID: CONSOLE-94

Level: SEVERE

Description: Reading assigned service names of an identity failed.

Data: name of identity, error message

Triggers: Unable to read assigned service names of an identity due to data store error.

Actions: Look under data store log for more information.

ATTEMPT_READ_IDENTITY_ASSIGNABLE_SERVICE

ID: CONSOLE-101

Level: INFO

Description: Attempt to read assignable service names of an identity

Data: name of identity

Triggers: View the services page of an identity.

SUCCEED READ IDENTITY ASSIGNABLE SERVICE

ID: CONSOLE-102

Level: INFO

Description: Reading assignable service names of an identity succeeded

Data: name of identity

Triggers: View the services page of an identity.

SSO EXCEPTION READ IDENTITY ASSIGNABLE SERVICE

ID: CONSOLE-103

Level: SEVERE

Description: Reading assignable service names of an identity failed.

Data: name of identity, error message

Triggers: Unable to read assignable service names of an identity. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

$IDM_EXCEPTION_READ_IDENTITY_ASSIGNABLE_SERVICE$

ID: CONSOLE-104

Level: SEVERE

Description: Reading assignable service names of an identity failed.

Data: name of identity, error message

Triggers: Unable to read assignable service names of an identity due to data store error.

Actions: Look under data store log for more information.

ATTEMPT IDENTITY ASSIGN SERVICE

ID: CONSOLE-111

Level: INFO

Description: Attempt to assign a service to an identity

Data: name of identity, name of service

Triggers: Click Add button of service view of an identity.

SUCCEED_IDENTITY_ASSIGN_SERVICE

ID: CONSOLE-112

Level: INFO

Description: Assignment of service to an identity succeeded

Data: name of identity, name of service

Triggers: Click Add button of service view of an identity.

SSO_EXCEPTION_IDENTITY_ASSIGN_SERVICE

ID: CONSOLE-113

Level: SEVERE

Description: Assignment of service to an identity failed.

Data: name of identity, name of service, error message

Triggers: Unable to assign service to an identity. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

IDM EXCEPTION IDENTITY ASSIGN SERVICE

ID: CONSOLE-114

Level: SEVERE

Description: Assignment of service to an identity failed.

Data: name of identity, name of service, error message

Triggers: Unable to assign service to an identity due to data store error.

Actions: Look under data store log for more information.

ATTEMPT_IDENTITY_UNASSIGN SERVICE

ID: CONSOLE-121

Level: INFO

Description: Attempt to unassign a service from an identity

Data: name of identity, name of service

Triggers: Click Remove button in service view of an identity.

SUCCEED IDENTITY UNASSIGN SERVICE

ID: CONSOLE-122

Level: INFO

Description: Unassignment of service to an identity succeeded

Data: name of identity, name of service

Triggers: Click Remove button in service view of an identity.

SSO_EXCEPTION_IDENTITY_UNASSIGN_SERVICE

ID: CONSOLE-123

Level: SEVERE

Description: Unassignment of service from an identity failed.

Data: name of identity, name of service, error message

Triggers: Unable to unassign service from an identity. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

IDM EXCEPTION IDENTITY UNASSIGN SERVICE

ID: CONSOLE-124

Level: SEVERE

Description: Unassignment of service from an identity failed.

Data: name of identity, name of service, error message

Triggers: Unable to unassign service from an identity due to data store error.

Actions: Look under data store log for more information.

ATTEMPT_IDENTITY_READ_SERVICE_ATTRIBUTE VALUES

ID: CONSOLE-131

Level: INFO

Description: Attempt to read service attribute values of an identity

Data: name of identity, name of service

Triggers: View service profile view of an identity.

SUCCEED_IDENTITY_READ_SERVICE_ATTRIBUTE_VALUES ID: CONSOLE-132

Level: INFO

Description: Reading of service attribute values of an identity succeeded

Data: name of identity, name of service

Triggers: View service profile view of an identity.

SSO_EXCEPTION_IDENTITY_READ_SERVICE_ATTRIBUTE_VALUES

ID: CONSOLE-133

Level: SEVERE

Description: Reading of service attribute values of an identity failed.

Data: name of identity, name of service, error message

Triggers: Unable to read service attribute values of an identity. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation

Actions: Look under data store log for more information.

IDM_EXCEPTION_IDENTITY_READ_SERVICE_ATTRIBUTE_VALUES ID: CONSOLE-134

Level: SEVERE

Description: Reading of service attribute values of an identity failed.

Data: name of identity, name of service, error message

Triggers: Unable to read service attribute values of an identity due to data store error.

Actions: Look under data store log for more information.

ATTEMPT_IDENTITY_WRITE_SERVICE_ATTRIBUTE_VALUES

ID: CONSOLE-141

Level: INFO

Description: Attempt to write service attribute values to an identity

Data: name of identity, name of service

Triggers: Click on Save button in service profile view of an identity.

SUCCEED_IDENTITY_WRITE_SERVICE_ATTRIBUTE_VALUES ID: CONSOLE-142

Level: INFO

Description: Writing of service attribute values to an identity succeeded

Data: name of identity, name of service

Triggers: Click on Save button in service profile view of an identity.

SSO_EXCEPTION_IDENTITY_WRITE_SERVICE_ATTRIBUTE_VALUES ID: CONSOLE-143

Level: SEVERE

Description: Writing of service attribute values to an identity failed.

Data: name of identity, name of service, error message

Triggers: Unable to write service attribute values to an identity. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

IDM_EXCEPTION_IDENTITY_WRITE_SERVICE_ATTRIBUTE_VALUES ID: CONSOLE-144

Level: SEVERE

Description: Writing of service attribute values to an identity failed.

Data: name of identity, name of service, error message

Triggers: Unable to write service attribute values to an identity due to data store error.

Actions: Look under data store log for more information.

ATTEMPT_READ_ALL_GLOBAL_DEFAULT_ATTRIBUTE_VALUES ID: CONSOLE-201

Level: INFO

Description: Attempt to read all global service default attribute values

Data: name of service

Triggers: View global configuration view of a service.

SUCCEED_READ_ALL_GLOBAL_DEFAULT_ATTRIBUTE_VALUES ID: CONSOLE-202

Level: INFO

Description: Reading of all global service default attribute values succeeded

Data: name of service

Triggers: View global configuration view of a service.

ATTEMPT_READ_GLOBAL_DEFAULT_ATTRIBUTE_VALUES

ID: CONSOLE-203

Level: INFO

Description: Attempt to read global service default attribute values

Data: name of service, name of attribute

Triggers: View global configuration view of a service.

${\tt SUCCEED_READ_GLOBAL_DEFAULT_ATTRIBUTE_VALUES}$

ID: CONSOLE-204

Level: INFO

Description: Reading of global service default attribute values succeeded

Data: name of service, name of attribute

Triggers: View global configuration view of a service.

FAILED READ GLOBAL DEFAULT ATTRIBUTE VALUES

ID: CONSOLE-205

Level: INFO

Description: Reading of global service default attribute values failed

Data: name of service, name of attribute

Triggers: View global configuration view of a service.

Actions: Look under service management log for more information.

ATTEMPT WRITE GLOBAL DEFAULT ATTRIBUTE VALUES

ID: CONSOLE-211

Description: Attempt to write global service default attribute values

Data: name of service, name of attribute

Triggers: Click on Save button in global configuration view of a service.

SUCCEED_WRITE_GLOBAL_DEFAULT_ATTRIBUTE_VALUES

ID: CONSOLE-212

Level: INFO

Description: Writing of global service default attribute values succeeded

Data: name of service, name of attribute

Triggers: Click on Save button in global configuration view of a service.

$SSO_EXCEPTION_WRITE_GLOBAL_DEFAULT_ATTRIBUTE_VALUES$

ID: CONSOLE-213

Level: SEVERE

Description: Writing of global service default attribute values failed.

Data: name of service, name of attribute, error message

Triggers: Unable to write global service default attribute values. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS_EXCEPTION_WRITE_GLOBAL_DEFAULT_ATTRIBUTE_VALUES ID: CONSOLE-214

Level: SEVERE

Description: Writing of global service default attribute values failed.

Data: name of service, name of attribute, error message

Triggers: Unable to write service default attribute values due to service management error.

Actions: Look under service management log for more information.

$ATTEMPT_READ_GLOBAL_SUB_CONFIGURATION_NAMES$

ID: CONSOLE-221

Description: Attempt to get sub configuration names

Data: name of service, name of base global sub configuration

Triggers: View a global service view of which its service has sub schema.

SUCCEED_READ_GLOBAL_SUB_CONFIGURATION_NAMES

ID: CONSOLE-222

Level: INFO

Description: Reading of global sub configuration names succeeded

Data: name of service, name of base global sub configuration

Triggers: View a global service view of which its service has sub schema.

SSO_EXCEPTION_READ_GLOBAL_SUB_CONFIGURATION_NAMES

ID: CONSOLE-223

Level: SEVERE

Description: Reading of global sub configuration names failed.

Data: name of service, name of base global sub configuration, error message

Triggers: Unable to get global sub configuration names. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS_EXCEPTION_READ_GLOBAL_SUB_CONFIGURATION_NAMES

ID: CONSOLE-224

Level: SEVERE

Description: Reading of global sub configuration names failed.

Data: name of service, name of base global sub configuration, error message

Triggers: Unable to get global sub configuration names due to service management error.

Actions: Look under service management log for more information.

ATTEMPT DELETE GLOBAL SUB CONFIGURATION

ID: CONSOLE-231

Description: Attempt to delete sub configuration

Data: name of service, name of base global sub configuration, name of sub configuration to be deleted

Triggers: Click on delete selected button in global service profile view.

SUCCEED_DELETE_GLOBAL_SUB_CONFIGURATION

ID: CONSOLE-232

Level: INFO

Description: Deletion of sub configuration succeeded

Data: name of service, name of base global sub configuration, name of sub configuration to be deleted

Triggers: Click on delete selected button in global service profile view.

SSO EXCEPTION DELETE GLOBAL SUB CONFIGURATION

ID: CONSOLE-233

Level: SEVERE

Description: Deletion of sub configuration failed.

Data: name of service, name of base global sub configuration, name of sub configuration to be deleted, error message

Triggers: Unable to delete sub configuration. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS_EXCEPTION_DELETE_GLOBAL_SUB_CONFIGURATION

ID: CONSOLE-234

Level: SEVERE

Description: Deletion of sub configuration failed.

Data: name of service, name of base global sub configuration, name of sub configuration to be deleted, error message

Triggers: Unable to delete sub configuration due to service management error.

Actions: Look under service management log for more information.

ATTEMPT_CREATE_GLOBAL_SUB_CONFIGURATION ID: CONSOLE-241

Level: INFO

Description: Attempt to create sub configuration

Data: name of service, name of base global sub configuration, name of sub configuration to be created, name of sub schema to be created

Triggers: Click on add button in create sub configuration view.

${\tt SUCCEED_CREATE_GLOBAL_SUB_CONFIGURATION}$

ID: CONSOLE-242

Level: INFO

Description: Creation of sub configuration succeeded

Data: name of service, name of base global sub configuration, name of sub configuration to be created, name of sub schema to be created

Triggers: Click on add button in create sub configuration view.

SSO_EXCEPTION_CREATE_GLOBAL_SUB_CONFIGURATION

ID: CONSOLE-243

Level: SEVERE

Description: Creation of sub configuration failed.

Data: name of service, name of base global sub configuration, name of sub configuration to be created, name of sub schema to be created, error message

Triggers: Unable to create sub configuration. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS_EXCEPTION_CREATE_GLOBAL_SUB_CONFIGURATION

ID: CONSOLE-244

Level: SEVERE

Description: Creation of sub configuration failed.

Data: name of service, name of base global sub configuration, name of sub configuration to be created, name of sub schema to be created, error message Triggers: Unable to create sub configuration due to service management error.

Actions: Look under service management log for more information.

SUCCEED_READ_GLOBAL_SUB_CONFIGURATION_ATTRIBUTE_VALUES ID: CONSOLE-251

Level: INFO

Description: Reading of sub configuration's attribute values succeeded

Data: name of service, name of sub configuration

Triggers: View sub configuration profile view.

ATTEMPT_WRITE_GLOBAL_SUB_CONFIGURATION_ATTRIBUTE_VALUES ID: CONSOLE-261

Level: INFO

Description: Attempt to write sub configuration's attribute values

Data: name of service, name of sub configuration

Triggers: Click on save button in sub configuration profile view.

SUCCEED_WRITE_GLOBAL_SUB_CONFIGURATION_ATTRIBUTE_VALUES ID: CONSOLE-262

Level: INFO

Description: Writing of sub configuration's attribute values succeeded

Data: name of service, name of sub configuration

Triggers: Click on save button in sub configuration profile view.

SSO_EXCEPTION_WRITE_GLOBAL_SUB_CONFIGURATION_ATTRIBUTE_VALUES ID: CONSOLE-263

Level: SEVERE

Description: Writing of sub configuration's attribute value failed.

Data: name of service, name of sub configuration, error message

Triggers: Unable to write sub configuration's attribute values. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS_EXCEPTION_WRITE_GLOBAL_SUB_CONFIGURATION_ATTRIBUTE_VALUES_NAMES ID: CONSOLE-264

Level: SEVERE

Description: Writing of sub configuration's attribute value failed.

Data: name of service, name of sub configuration, error message

Triggers: Unable to write sub configuration's attribute value due to service management error.

Actions: Look under service management log for more information.

ATTEMPT GET POLICY NAMES

ID: CONSOLE-301

Level: INFO

Description: Attempt to get policy names under a realm.

Data: name of realm

Triggers: View policy main page.

SUCCEED_GET POLICY NAMES

ID: CONSOLE-302

Level: INFO

Description: Getting policy names under a realm succeeded

Data: name of realm

Triggers: View policy main page.

SSO_EXCEPTION_GET_POLICY_NAMES

ID: CONSOLE-303

Level: SEVERE

Description: Getting policy names under a realm failed.

Data: name of realm, error message

Triggers: Unable to get policy names under a realm. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under policy log for more information.

POLICY EXCEPTION GET POLICY NAMES

ID: CONSOLE-304

Level: SEVERE

Description: Getting policy names under a realm failed.

Data: name of realm, error message

Triggers: Unable to get policy names under a realm due to policy SDK related errors.

Actions: Look under policy log for more information.

ATTEMPT CREATE POLICY

ID: CONSOLE-311

Level: INFO

Description: Attempt to create policy under a realm.

Data: name of realm, name of policy

Triggers: Click on New button in policy creation page.

SUCCEED CREATE POLICY

ID: CONSOLE-312

Level: INFO

Description: Creation of policy succeeded

Data: name of realm, name of policy

Triggers: Click on New button in policy creation page.

SSO_EXCEPTION_CREATE_POLICY

ID: CONSOLE-313

Level: SEVERE

Description: Creation of policy failed.

Data: name of realm, name of policy, error message

Triggers: Unable to create policy under a realm. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under policy log for more information.

POLICY EXCEPTION CREATE POLICY

ID: CONSOLE-314

Level: SEVERE

Description: Creation of policy failed.

Data: name of realm, name of policy, error message

Triggers: Unable to create policy under a realm due to policy SDK related

errors.

Actions: Look under policy log for more information.

ATTEMPT MODIFY POLICY

ID: CONSOLE-321

Level: INFO

Description: Attempt to modify policy.

Data: name of realm, name of policy

Triggers: Click on Save button in policy profile page.

SUCCEED MODIFY POLICY

ID: CONSOLE-322

Level: INFO

Description: Modification of policy succeeded

Data: name of realm, name of policy

Triggers: Click on Save button in policy profile page.

SSO_EXCEPTION_MODIFY_POLICY

ID: CONSOLE-323

Level: SEVERE

Description: Modification of policy failed.

Data: name of realm, name of policy, error message

Triggers: Unable to modify policy under a realm. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under policy log for more information.

POLICY EXCEPTION MODIFY POLICY

ID: CONSOLE-324

Level: SEVERE

Description: Modification of policy failed.

Data: name of realm, name of policy, error message

Triggers: Unable to modify policy due to policy SDK related errors.

Actions: Look under policy log for more information.

ATTEMPT DELETE POLICY

ID: CONSOLE-331

Level: INFO

Description: Attempt to delete policy.

Data: name of realm, names of policies

Triggers: Click on Delete button in policy main page.

SUCCEED DELETE POLICY

ID: CONSOLE-332

Level: INFO

Description: Deletion of policy succeeded

Data: name of realm, name of policies

Triggers: Click on Delete button in policy main page.

SSO_EXCEPTION_DELETE_POLICY ID: CONSOLE-333

Level: SEVERE

Description: Deletion of policy failed.

Data: name of realm, name of policies, error message

Triggers: Unable to delete policy. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under policy log for more information.

POLICY_EXCEPTION_DELETE_POLICY ID: CONSOLE-334

Level: SEVERE

Description: Deletion of policy failed.

Data: name of realm, name of policies, error message

Triggers: Unable to delete policy due to policy SDK related errors.

Actions: Look under policy log for more information.

ATTEMPT GET REALM NAMES

ID: CONSOLE-401

Level: INFO

Description: Attempt to get realm names

Data: name of parent realm

Triggers: View realm main page.

SUCCEED_GET_REALM_NAMES

ID: CONSOLE-402

Level: INFO

Description: Getting realm names succeeded.

Data: name of parent realm

Triggers: View realm main page.

SMS_EXCEPTION_GET_REALM_NAMES

ID: CONSOLE-403

Level: SEVERE

Description: Getting realm names failed.

Data: name of parent realm, error message

Triggers: Unable to get realm names due to service management SDK

exception.

Actions: Look under service management log for more information.

ATTEMPT CREATE REALM

Description: Attempt to create realm

Data: name of parent realm, name of new realm

Triggers: Click on New button in create realm page.

SUCCEED CREATE REALM

ID: CONSOLE-412

Level: INFO

Description: Creation of realm succeeded.

Data: name of parent realm, name of new realm

Triggers: Click on New button in create realm page.

SMS_EXCEPTION_CREATE_REALM ID: CONSOLE-413

Level: SEVERE

Description: Creation of realm failed.

Data: name of parent realm, name of new realm, error message

Triggers: Unable to create new realm due to service management SDK

exception.

Actions: Look under service management log for more information.

ATTEMPT DELETE REALM

ID: CONSOLE-421

Level: INFO

Description: Attempt to delete realm

Data: name of parent realm, name of realm to delete

Triggers: Click on Delete button in realm main page.

SUCCEED_DELETE_REALM

ID: CONSOLE-422

Level: INFO

Description: Deletion of realm succeeded.

Data: name of parent realm, name of realm to delete

Triggers: Click on Delete button in realm main page.

SMS EXCEPTION DELETE REALM

ID: CONSOLE-423

Level: SEVERE

Description: Deletion of realm failed.

Data: name of parent realm, name of realm to delete, error message

Triggers: Unable to delete realm due to service management SDK exception.

Actions: Look under service management log for more information.

ATTEMPT_GET_ATTR_VALUES_OF_REALM

ID: CONSOLE-431

Level: INFO

Description: Attempt to get attribute values of realm

Data: name of realm

Triggers: View realm profile page.

SUCCEED GET ATTR VALUES OF REALM

ID: CONSOLE-432

Level: INFO

Description: Getting attribute values of realm succeeded.

Data: name of realm

Triggers: View realm profile page.

SMS EXCEPTION GET ATTR VALUES OF REALM

ID: CONSOLE-433

Level: SEVERE

Description: Getting attribute values of realm failed.

Data: name of realm, error message

Triggers: Unable to get attribute values of realm due to service management

SDK exception.

Actions: Look under service management log for more information.

ATTEMPT_SET_ATTR_VALUES_OF_REALM

ID: CONSOLE-441

Level: INFO

Description: Attempt to modify realm's profile

Data: name of realm

Triggers: Click on Save button in realm profile page.

SUCCEED SET ATTR VALUES OF REALM

ID: CONSOLE-442

Level: INFO

Description: Modification of realm's profile succeeded.

Data: name of realm

Triggers: Click on Save button in realm profile page.

SMS EXCEPTION SET ATTR VALUES OF REALM

ID: CONSOLE-443

Level: SEVERE

Description: Modification of realm's profile failed.

Data: name of realm, error message

Triggers: Unable to modify realm's profile due to service management SDK $\,$

exception.

Actions: Look under service management log for more information.

ATTEMPT GET DELEGATION SUBJECTS

ID: CONSOLE-501

Level: INFO

Description: Attempt to get delegation subjects under a realm

Data: name of realm, search pattern

Triggers: View delegation main page.

SUCCEED GET DELEGATION SUBJECTS

Description: Getting delegation subjects under a realm succeeded.

Data: name of realm, search pattern

Triggers: View delegation main page.

SSO EXCEPTION GET DELEGATION SUBJECTS

ID: CONSOLE-503

Level: SEVERE

Description: Getting delegation subjects under a realm failed.

Data: name of realm, search pattern, error message

Triggers: Unable to get delegation subjects. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under delegation management log for more information.

DELEGATION EXCEPTION GET DELEGATION SUBJECTS

ID: CONSOLE-504

Level: SEVERE

Description: Getting delegation subjects under a realm failed.

Data: name of realm, search pattern, error message

Triggers: Unable to get delegation subjects due to delegation management SDK related errors.

Actions: Look under delegation management log for more information.

ATTEMPT GET PRIVILEGES OF DELEGATION SUBJECT

ID: CONSOLE-511

Level: INFO

Description: Attempt to get privileges of delegation subject

Data: name of realm, ID of delegation subject

Triggers: View delegation subject profile page.

SUCCEED_GET_PRIVILEGES_OF_DELEGATION_SUBJECT

Description: Getting privileges of delegation subject succeeded.

Data: name of realm, ID of delegation subject

Triggers: View delegation subject profile page.

SSO_EXCEPTION_GET_PRIVILEGES_OF_DELEGATION_SUBJECT

ID: CONSOLE-513

Level: SEVERE

Description: Getting privileges of delegation subject failed.

Data: name of realm, ID of delegation subject, error message

Triggers: Unable to get privileges of delegation subject. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under delegation management log for more information.

DELEGATION_EXCEPTION_GET_PRIVILEGES_OF_DELEGATION_SUBJECT ID: CONSOLE-514

Level: SEVERE

Description: Getting privileges of delegation subject failed.

Data: name of realm, ID of delegation subject, error message

Triggers: Unable to get privileges of delegation subject due to delegation management SDK related errors.

Actions: Look under delegation management log for more information.

ATTEMPT_MODIFY DELEGATION PRIVILEGE

ID: CONSOLE-521

Level: INFO

Description: Attempt to modify delegation privilege

Data: name of realm, ID of delegation privilege, ID of subject

Triggers: Click on Save button in delegation subject profile page.

SUCCEED MODIFY DELEGATION PRIVILEGE

Description: Modification of delegation privilege succeeded.

Data: name of realm, ID of delegation privilege, ID of subject

Triggers: Click on Save button in delegation subject profile page.

SSO EXCEPTION MODIFY DELEGATION PRIVILEGE

ID: CONSOLE-523

Level: SEVERE

Description: Modification of delegation privilege failed.

Data: name of realm, ID of delegation privilege, ID of subject, error message

Triggers: Unable to modify delegation privilege. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under delegation management log for more information.

DELEGATION EXCEPTION MODIFY DELEGATION PRIVILEGE

ID: CONSOLE-524

Level: SEVERE

Description: Modification of delegation privilege failed.

Data: name of realm, ID of delegation privilege, ID of subject, error message

Triggers: Unable to modify delegation privilege due to delegation management SDK related errors.

Actions: Look under delegation management log for more information.

ATTEMPT GET ID REPO NAMES

ID: CONSOLE-601

Level: INFO

Description: Attempt to get data store names

Data: name of realm

Triggers: View data store main page.

SUCCEED GET ID REPO NAMES

Description: Getting data store names succeeded.

Data: name of realm

Triggers: View data store main page.

SSO EXCEPTION GET ID REPO NAMES

ID: CONSOLE-603

Level: SEVERE

Description: Getting data store names failed.

Data: name of realm, error message

Triggers: Unable to get data store names. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS_EXCEPTION_GET ID REPO NAMES

ID: CONSOLE-604

Level: SEVERE

Description: Getting data store names failed.

Data: name of realm, error message

Triggers: Unable to get data store names due to service management SDK exception.

Actions: Look under service management log for more information.

ATTEMPT_GET_ATTR_VALUES_ID_REPO

ID: CONSOLE-611

Level: INFO

Description: Attempt to get attribute values of identity repository

Data: name of realm, name of identity repository

Triggers: View data store profile page.

SUCCEED GET ATTR VALUES ID REPO

Description: Getting attribute values of data store succeeded.

Data: name of realm, name of identity repository

Triggers: View data store profile page.

SSO EXCEPTION GET ATTR VALUES ID REPO

ID: CONSOLE-613

Level: SEVERE

Description: Getting attribute values of data store failed.

Data: name of realm, name of identity repository, error message

Triggers: Unable to get attribute values of identity repository. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS EXCEPTION GET ATTR VALUES ID REPO

ID: CONSOLE-614

Level: SEVERE

Description: Getting attribute values of data store failed.

Data: name of realm, name of identity repository, error message

Triggers: Unable to get attribute values of data store due to service management SDK exception.

Actions: Look under service management log for more information.

ATTEMPT CREATE ID REPO

ID: CONSOLE-621

Level: INFO

Description: Attempt to create identity repository

Data: name of realm, name of identity repository, type of identity repository

Triggers: Click on New button in data store creation page.

SUCCEED CREATE ID REPO

Description: Creation of data store succeeded.

Data: name of realm, name of identity repository, type of identity repository

Triggers: Click on New button in data store creation page.

SSO EXCEPTION CREATE ID REPO

ID: CONSOLE-623

Level: SEVERE

Description: Creation of data store failed.

Data: name of realm, name of identity repository, type of identity repository, error message

Triggers: Unable to create identity repository. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS EXCEPTION CREATE ID REPO

ID: CONSOLE-624

Level: SEVERE

Description: Creation data store failed.

Data: name of realm, name of identity repository, type of identity repository, error message

Triggers: Unable to create data store due to service management SDK exception.

Actions: Look under service management log for more information.

ATTEMPT DELETE ID REPO

ID: CONSOLE-631

Level: INFO

Description: Attempt to delete identity repository

Data: name of realm, name of identity repository

Triggers: Click on Delete button in data store main page.

SUCCEED_DELETE_ID_REPO

ID: CONSOLE-632

Level: INFO

Description: Deletion of data store succeeded.

Data: name of realm, name of identity repository

Triggers: Click on Delete button in data store main page.

SSO_EXCEPTION_DELETE_ID_REPO

ID: CONSOLE-633

Level: SEVERE

Description: Deletion of data store failed.

Data: name of realm, name of identity repository, error message

Triggers: Unable to delete identity repository. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS EXCEPTION DELETE ID REPO

ID: CONSOLE-634

Level: SEVERE

Description: Deletion data store failed.

Data: name of realm, name of identity repository, error message

Triggers: Unable to delete data store due to service management SDK exception.

Actions: Look under service management log for more information.

ATTEMPT MODIFY ID REPO

ID: CONSOLE-641

Level: INFO

Description: Attempt to modify identity repository

Data: name of realm, name of identity repository

Triggers: Click on Save button in data store profile page.

SUCCEED_MODIFY_ID_REPO

ID: CONSOLE-642

Level: INFO

Description: Modification of data store succeeded.

Data: name of realm, name of identity repository

Triggers: Click on Save button in data store profile page.

SSO_EXCEPTION_MODIFY_ID_REPO

ID: CONSOLE-643

Level: SEVERE

Description: Modification of data store failed.

Data: name of realm, name of identity repository, error message

Triggers: Unable to modify identity repository. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS EXCEPTION MODIFY ID REPO

ID: CONSOLE-644

Level: SEVERE

Description: Modification data store failed.

Data: name of realm, name of identity repository, error message

Triggers: Unable to modify data store due to service management SDK exception.

Actions: Look under service management log for more information.

ATTEMPT GET ASSIGNED SERVICE OF REALM

ID: CONSOLE-701

Level: INFO

Description: Attempt to get assigned services of realm

Data: name of realm

Triggers: View realm's service main page.

SUCCEED_GET_ASSIGNED_SERVICE_OF_REALM

ID: CONSOLE-702

Level: INFO

Description: Getting assigned services of realm succeeded.

Data: name of realm

Triggers: View realm's service main page.

CONFIGURATION_EXCEPTION_GET_ASSIGNED_SERVICE_OF_REALM

ID: CONSOLE-703

Level: SEVERE

Description: Getting assigned services of realm failed.

Data: name of realm, error message

Triggers: Unable to get assigned services of realm due authentication

configuration exception.

Actions: Look under authentication log for more information.

SMS EXCEPTION GET ASSIGNED SERVICE OF REALM

ID: CONSOLE-704

Level: SEVERE

Description: Getting assigned services of realm failed.

Data: name of realm, error message

Triggers: Unable to get assigned services of realm due to service

management SDK exception.

Actions: Look under service management log for more information.

IDREPO_EXCEPTION_GET_ASSIGNED_SERVICE_OF_REALM

ID: CONSOLE-705

Level: SEVERE

Description: Getting assigned services of realm failed.

Data: name of realm, error message

Triggers: Unable to get assigned services of realm due to data store SDK

exception.

Actions: Look under service management log for more information.

SSO_EXCEPTION_GET_ASSIGNED_SERVICE_OF_REALM ID: CONSOLE-706

Level: SEVERE

Description: Getting assigned services of realm failed.

Data: name of realm, error message

Triggers: Unable to get assigned services of realm. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

ATTEMPT_GET_ASSIGNABLE_SERVICE_OF_REALM

ID: CONSOLE-711

Level: INFO

Description: Attempt to get assignable services of realm

Data: name of realm

Triggers: View realm's service main page.

SUCCEED GET ASSIGNABLE SERVICE OF REALM

ID: CONSOLE-712

Level: INFO

Description: Getting assignable services of realm succeeded.

Data: name of realm

Triggers: View realm's service main page.

CONFIGURATION_EXCEPTION_GET_ASSIGNABLE_SERVICE_OF_REALM

ID: CONSOLE-713

Level: SEVERE

Description: Getting assignable services of realm failed.

Data: name of realm, error message

Triggers: Unable to get assignable services of realm due authentication configuration exception.

Actions: Look under authentication log for more information.

SMS_EXCEPTION_GET_ASSIGNABLE_SERVICE_OF_REALM ID: CONSOLE-714

Level: SEVERE

Description: Getting assignable services of realm failed.

Data: name of realm, error message

Triggers: Unable to get assignable services of realm due to service management SDK exception.

Actions: Look under service management log for more information.

IDREPO_EXCEPTION_GET_ASSIGNABLE_SERVICE_OF_REALM ID: CONSOLE-715

Level: SEVERE

Description: Getting assignable services of realm failed.

Data: name of realm, error message

Triggers: Unable to get assignable services of realm due to ID Repository management SDK exception.

Actions: Look under ID Repository management log for more information.

SSO_EXCEPTION_GET_ASSIGNABLE_SERVICE_OF_REALM ID: CONSOLE-716

Level: SEVERE

Description: Getting assignable services of realm failed.

Data: name of realm, error message

Triggers: Unable to get assignable services of realm. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

ATTEMPT_UNASSIGN_SERVICE_FROM_REALM

ID: CONSOLE-721

Level: INFO

Description: Attempt to unassign service from realm

Data: name of realm, name of service

Triggers: Click on Unassign button in realm's service page.

SUCCEED_UNASSIGN_SERVICE_FROM_REALM

ID: CONSOLE-722

Level: INFO

Description: Unassign service from realm succeeded.

Data: name of realm, name of service

Triggers: Click on Unassign button in realm's service page.

SMS_EXCEPTION_UNASSIGN_SERVICE_FROM_REALM

ID: CONSOLE-723

Level: SEVERE

Description: Unassign service from realm failed.

Data: name of realm, name of service, error message

Triggers: Unable to unassign service from realm due to service management

SDK exception.

Actions: Look under service management log for more information.

SSO_EXCEPTION_UNASSIGN_SERVICE_FROM_REALM

ID: CONSOLE-725

Level: SEVERE

Description: Unassign service from realm failed.

Data: name of realm, name of service, error message

Triggers: Unable to unassign service from realm. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store management log for more information.

IDREPO_EXCEPTION_UNASSIGN_SERVICE_FROM_REALM

ID: CONSOLE-724

Level: SEVERE

Description: Unassign service from realm failed.

Data: name of realm, name of service, error message

Triggers: Unable to unassign service from realm due to data store management SDK exception.

Actions: Look under data store management log for more information.

ATTEMPT_ASSIGN_SERVICE_TO_REALM ID: CONSOLE-731

Level: INFO

Description: Attempt to assign service to realm

Data: name of realm, name of service

Triggers: Click on assign button in realm's service page.

SUCCEED ASSIGN SERVICE TO REALM

ID: CONSOLE-732

Level: INFO

Description: Assignment of service to realm succeeded.

Data: name of realm, name of service

Triggers: Click on assign button in realm's service page.

SMS EXCEPTION ASSIGN SERVICE TO REALM

ID: CONSOLE-733

Level: SEVERE

Description: Assignment of service to realm failed.

Data: name of realm, name of service, error message

Triggers: Unable to assign service to realm due to service management SDK exception.

Actions: Look under service management log for more information.

SSO_EXCEPTION_ASSIGN_SERVICE TO REALM

ID: CONSOLE-734

Level: SEVERE

Description: Assignment of service to realm failed.

Data: name of realm, name of service, error message

Triggers: Unable to assign service to realm. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

IDREPO_EXCEPTION_ASSIGN_SERVICE_TO_REALM

ID: CONSOLE-735

Level: SEVERE

Description: Assignment of service to realm failed.

Data: name of realm, name of service, error message

Triggers: Unable to assign service to realm due to data store SDK exception.

Actions: Look under service management log for more information.

$ATTEMPT_GET_ATTR_VALUE_OF_SERVICE_UNDER_REALM$

ID: CONSOLE-741

Level: INFO

Description: Attempt to get attribute values of service in realm

Data: name of realm, name of service, name of attribute schema

Triggers: View realm's service profile page.

SUCCEED_GET_ATTR_VALUE_OF_SERVICE_UNDER_REALM

ID: CONSOLE-742

Level: INFO

Description: Getting of attribute values of service under realm succeeded.

Data: name of realm, name of service, name of attribute schema

Triggers: View realm's service profile page.

SMS_EXCEPTION_GET_ATTR_VALUE_OF_SERVICE_UNDER_REALM

ID: CONSOLE-743

Level: SEVERE

Description: Getting of attribute values of service under realm failed.

Data: name of realm, name of service, name of attribute schema, error message

Triggers: Unable to get attribute values of service due to service management SDK exception.

Actions: Look under service management log for more information.

IDREPO_EXCEPTION_GET_ATTR_VALUE_OF_SERVICE_UNDER_REALM ID: CONSOLE-744

Level: INFO

Description: Getting of attribute values of service under realm failed.

Data: name of realm, name of service, name of attribute schema, error message

Triggers: Unable to get attribute values of service due to data store SDK exception.

Actions: Look under service management log for more information.

SSO_EXCEPTION_GET_ATTR_VALUE_OF_SERVICE_UNDER_REALM ID: CONSOLE-745

Level: SEVERE

Description: Getting of attribute values of service under realm failed.

Data: name of realm, name of service, name of attribute schema, error message

Triggers: Unable to get attribute values of service. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

ATTEMPT_MODIFY_SERVICE_UNDER_REALM ID: CONSOLE-751

Level: INFO

Description: Attempt to modify attribute values of service in realm

Data: name of realm, name of service

Triggers: Click on Save button in realm's service profile page.

SUCCEED_MODIFY_SERVICE_UNDER_REALM ID: CONSOLE-752

Level: INFO

Description: Modification of attribute values of service under realm succeeded.

Data: name of realm, name of service

Triggers: Click on Save button in realm's service profile page.

SMS EXCEPTION MODIFY SERVICE UNDER REALM

ID: CONSOLE-753

Level: SEVERE

Description: Modification of attribute values of service under realm failed.

Data: name of realm, name of service, error message

Triggers: Unable to modify attribute values of service due to service management SDK exception.

Actions: Look under service management log for more information.

IDREPO_EXCEPTION_MODIFY_SERVICE_UNDER_REALM

ID: CONSOLE-754

Level: SEVERE

Description: Modification of attribute values of service under realm failed.

Data: name of realm, name of service, error message

Triggers: Unable to modify attribute values of service due to data store error.

Actions: Look under data store log for more information.

SSO_EXCEPTION_MODIFY_SERVICE_UNDER_REALM

ID: CONSOLE-755

Level: SEVERE

Description: Modification of attribute values of service under realm failed.

Data: name of realm, name of service, error message

Triggers: Unable to modify attribute values of service. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation

Actions: Look under data store log for more information.

ATTEMPT GET AUTH TYPE

Description: Attempt to get authentication type

Data: server instance name

Triggers: View authentication profile page.

SUCCEED GET AUTH TYPE

ID: CONSOLE-802

Level: INFO

Description: Getting of authentication type succeeded.

Data: server instance name

Triggers: View authentication profile page.

SMS_EXCEPTION_GET_AUTH_TYPE ID: CONSOLE-803

Level: SEVERE

Description: Getting of authentication type failed.

Data: error message

Triggers: Unable to get authentication type due to authentication

configuration SDK exception.

Actions: Look under authentication management log for more information.

ATTEMPT GET AUTH INSTANCE

ID: CONSOLE-811

Level: INFO

Description: Attempt to get authentication instances under a realm

Data: name of realm

Triggers: View authentication profile page.

SUCCEED GET AUTH INSTANCE

ID: CONSOLE-812

Level: INFO

Description: Getting of authentication instances under a realm succeeded.

Data: name of realm

Triggers: View authentication profile page.

AUTH CONFIG EXCEPTION GET AUTH INSTANCE

ID: CONSOLE-813

Level: SEVERE

Description: Getting of authentication instances under a realm failed.

Data: name of realm, error message

Triggers: Unable to get authentication instance due to authentication

configuration SDK exception.

Actions: Look under authentication management log for more information.

ATTEMPT REMOVE AUTH INSTANCE

ID: CONSOLE-821

Level: INFO

Description: Attempt to remove authentication instances under a realm

Data: name of realm, name of authentication instance

Triggers: View authentication profile page.

SUCCEED REMOVE AUTH INSTANCE

ID: CONSOLE-822

Level: INFO

Description: Removal of authentication instances under a realm succeeded.

Data: name of realm, name of authentication instance

Triggers: View authentication profile page.

AUTH CONFIG EXCEPTION REMOVE AUTH INSTANCE

ID: CONSOLE-823

Level: SEVERE

Description: Removal of authentication instances under a realm failed.

Data: name of realm, name of authentication instance, error message

Triggers: Unable to remove authentication instance due to authentication configuration SDK exception.

Actions: Look under authentication management log for more information.

ATTEMPT_CREATE_AUTH_INSTANCE

ID: CONSOLE-831

Level: INFO

Description: Attempt to create authentication instance under a realm

Data: name of realm, name of authentication instance, type of authentication

instance

Triggers: Click on New button in authentication creation page.

SUCCEED CREATE AUTH INSTANCE

ID: CONSOLE-832

Level: INFO

Description: Creation of authentication instance under a realm succeeded.

Data: name of realm, name of authentication instance, type of authentication

instance

Triggers: Click on New button in authentication creation page.

AUTH CONFIG EXCEPTION CREATE AUTH INSTANCE

ID: CONSOLE-833

Level: SEVERE

Description: Creation of authentication instance under a realm failed.

Data: name of realm, name of authentication instance, type of authentication

instance, error message

Triggers: Unable to create authentication instance due to authentication

configuration exception.

Actions: Look under authentication configuration log for more information.

ATTEMPT MODIFY AUTH INSTANCE

ID: CONSOLE-841

Level: INFO

Description: Attempt to modify authentication instance

Data: name of realm, name of authentication service

Triggers: Click on Save button in authentication profile page.

$SUCCEED_MODIFY_AUTH_INSTANCE$

ID: CONSOLE-842

Level: INFO

Description: Modification of authentication instance succeeded.

Data: name of realm, name of authentication service

Triggers: Click on Save button in authentication profile page.

SMS EXCEPTION MODIFY AUTH INSTANCE

ID: CONSOLE-843

Level: SEVERE

Description: Modification of authentication instance failed.

Data: name of realm, name of authentication service, error message

Triggers: Unable to modify authentication instance due to service management SDK exception.

Actions: Look under service anagement log for more information.

SSO EXCEPTION MODIFY AUTH INSTANCE

ID: CONSOLE-844

Level: SEVERE

Description: Modification of authentication instance failed.

Data: name of realm, name of authentication service, error message

Triggers: Unable to modify authentication instance. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

ATTEMPT GET AUTH INSTANCE PROFILE

ID: CONSOLE-851

Level: INFO

Description: Attempt to get authentication instance profile

Data: name of realm, name of authentication instance

Triggers: View authentication instance profile page.

SUCCEED_GET_AUTH_INSTANCE_PROFILE

ID: CONSOLE-852

Level: INFO

Description: Getting of authentication instance profile succeeded.

Data: name of realm, name of authentication instance

Triggers: View authentication instance profile page.

AUTH_CONFIGURATION_EXCEPTION_GET_AUTH_INSTANCE_PROFILE

ID: CONSOLE-853

Level: SEVERE

Description: Getting of authentication instance profile failed.

Data: name of realm, name of authentication instance, error message

Triggers: Unable to get authentication instance profile due to authentication configuration SDK exception.

Actions: Look under authentication management log for more information.

ATTEMPT MODIFY AUTH INSTANCE PROFILE

ID: CONSOLE-861

Level: INFO

Description: Attempt to modify authentication instance profile

Data: name of realm, name of authentication instance

Triggers: Click on Save button in authentication instance profile page.

SUCCEED MODIFY AUTH INSTANCE PROFILE

ID: CONSOLE-862

Level: INFO

Description: Modification of authentication instance profile succeeded.

Data: name of realm, name of authentication instance

Triggers: Click on Save button in authentication instance profile page.

AUTH CONFIGURATION EXCEPTION MODIFY AUTH INSTANCE PROFILE

ID: CONSOLE-863

Level: SEVERE

Description: Modification of authentication instance profile failed.

Data: name of realm, name of authentication instance, error message

Triggers: Unable to modify authentication instance profile due to authentication configuration SDK exception.

Actions: Look under authentication management log for more information.

SMS_EXCEPTION_MODIFY_AUTH_INSTANCE_PROFILE

ID: CONSOLE-864

Level: SEVERE

Description: Modification of authentication instance profile failed.

Data: name of realm, name of authentication instance, error message

Triggers: Unable to modify authentication instance profile due to service management SDK exception.

Actions: Look under service management log for more information.

SSO EXCEPTION MODIFY AUTH INSTANCE PROFILE

ID: CONSOLE-865

Level: SEVERE

Description: Modification of authentication instance profile failed.

Data: name of realm, name of authentication instance, error message

Triggers: Unable to modify authentication instance profile. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

ATTEMPT_GET_AUTH_PROFILE_IN_REALM

ID: CONSOLE-871

Level: INFO

Description: Attempt to get authentication profile under a realm

Data: name of realm

Triggers: View authentication profile under a realm page.

SUCCEED_GET_AUTH_PROFILE_IN_REALM

Description: Getting authentication profile under a realm succeeded.

Data: name of realm

Triggers: View authentication profile under a realm page.

SMS CONFIGURATION EXCEPTION GET AUTH PROFILE IN REALM

ID: CONSOLE-873

Level: SEVERE

Description: Getting authentication profile under a realm failed.

Data: name of realm, error message

Triggers: Unable to get authentication profile under a realm due to service

management SDK exception.

Actions: Look under service management log for more information.

ATTEMPT_GET_AUTH_CONFIG_PROFILE

ID: CONSOLE-881

Level: INFO

Description: Attempt to get authentication configuration profile

Data: name of realm, name of authentication configuration

Triggers: View authentication configuration profile page.

SUCCEED GET AUTH CONFIG PROFILE

ID: CONSOLE-882

Level: INFO

Description: Getting authentication configuration profile succeeded.

Data: name of realm, name of authentication configuration

Triggers: View authentication configuration profile page.

SSO_EXCEPTION_GET_AUTH_CONFIG_PROFILE

ID: CONSOLE-883

Level: SEVERE

Description: Getting authentication configuration profile failed.

Data: name of realm, name of authentication configuration, error message

Triggers: Unable to get authentication configuration profile. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS EXCEPTION GET AUTH CONFIG PROFILE

ID: CONSOLE-884

Level: SEVERE

Description: Getting authentication configuration profile failed.

Data: name of realm, name of authentication configuration, error message

Triggers: Unable to get authentication configuration profile due to service management SDK exception.

Actions: Look under service management log for more information.

AUTH_CONFIGURATION_EXCEPTION_GET_AUTH_CONFIG_PROFILE ID: CONSOLE-885

Level: SEVERE

Description: Getting authentication configuration profile failed.

Data: name of realm, name of authentication configuration, error message

Triggers: Unable to get authentication configuration profile due to authentication configuration SDK exception.

Actions: Look under authentication configuration log for more information.

ATTEMPT_MODIFY_AUTH_CONFIG_PROFILE

ID: CONSOLE-891

Level: INFO

Description: Attempt to modify authentication configuration profile

Data: name of realm, name of authentication configuration

Triggers: Click on Save button in authentication configuration profile page.

SUCCEED MODIFY AUTH CONFIG PROFILE

ID: CONSOLE-892

Level: INFO

Description: Modification of authentication configuration profile succeeded.

Data: name of realm, name of authentication configuration

Triggers: Click on Save button in authentication configuration profile page.

SSO EXCEPTION MODIFY AUTH CONFIG PROFILE

ID: CONSOLE-893

Level: SEVERE

Description: Modification of authentication configuration profile failed.

Data: name of realm, name of authentication configuration, error message

Triggers: Unable to modify authentication configuration profile. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS EXCEPTION MODIFY AUTH CONFIG PROFILE

ID: CONSOLE-894

Level: SEVERE

Description: Modification of authentication configuration profile failed.

Data: name of realm, name of authentication configuration, error message

Triggers: Unable to modify authentication configuration profile due to service management SDK exception.

Actions: Look under service management log for more information.

AUTH_CONFIGURATION_EXCEPTION_MODIFY_AUTH_CONFIG_PROFILE ID: CONSOLE-895

Level: SEVERE

Description: Modification of authentication configuration profile failed.

Data: name of realm, name of authentication configuration, error message

Triggers: Unable to modify authentication configuration profile due to authentication configuration SDK exception.

Actions: Look under authentication configuration log for more information.

$ATTEMPT_CREATE_AUTH_CONFIG$

Description: Attempt to create authentication configuration

Data: name of realm, name of authentication configuration

Triggers: Click on New button in authentication configuration creation page.

SUCCEED CREATE AUTH CONFIG

ID: CONSOLE-902

Level: INFO

Description: Creation of authentication configuration succeeded.

Data: name of realm, name of authentication configuration

Triggers: Click on New button in authentication configuration creation page.

SSO EXCEPTION CREATE AUTH CONFIG

ĪD: CONSOLE-903

Level: SEVERE

Description: Creation of authentication configuration failed.

Data: name of realm, name of authentication configuration, error message

Triggers: Unable to create authentication configuration. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS EXCEPTION CREATE AUTH CONFIG

ID: CONSOLE-904

Level: SEVERE

Description: Creation of authentication configuration failed.

Data: name of realm, name of authentication configuration, error message

Triggers: Unable to create authentication configuration due to service management SDK exception.

Actions: Look under service management log for more information.

AUTH_CONFIGURATION_EXCEPTION_CREATE_AUTH_CONFIG

Level: SEVERE

Description: Creation of authentication configuration failed.

Data: name of realm, name of authentication configuration, error message

Triggers: Unable to create authentication configuration due to authentication configuration SDK exception.

Actions: Look under authentication configuration log for more information.

ATTEMPT_GET_ENTITY_DESCRIPTOR

ID: CONSOLE-1001

Level: INFO

Description: Attempt to get entity descriptor names.

Data: search pattern

Triggers: View entity descriptor main page.

SUCCEED_GET_ENTITY_DESCRIPTOR

ID: CONSOLE-1002

Level: INFO

Description: Getting entity descriptor names succeeded

Data: search pattern

Triggers: View entity descriptor main page.

FEDERATION_EXCEPTION_GET_ENTITY_DESCRIPTOR

ID: CONSOLE-1003

Level: SEVERE

Description: Getting entity descriptor names failed.

Data: search pattern, error message

Triggers: Unable to get entity descriptor names due to federation SDK

related errors.

Actions: Look under federation log for more information.

ATTEMPT_CREATE_ENTITY_DESCRIPTOR

ID: CONSOLE-1011

Level: INFO

Description: Attempt to create entity descriptor.

Data: descriptor realm, descriptor name, descriptor protocol, descriptor type

Triggers: Click on New button in entity descriptor creation page.

SUCCEED CREATE ENTITY DESCRIPTOR

ID: CONSOLE-1012

Level: INFO

Description: Creation entity descriptor succeeded

Data: descriptor realm, descriptor name, descriptor protocol, descriptor type

Triggers: Click on New button in entity descriptor creation page.

FEDERATION EXCEPTION CREATE ENTITY DESCRIPTOR

ID: CONSOLE-1013

Level: SEVERE

Description: Creation entity descriptor failed.

Data: descriptor realm, descriptor name, descriptor protocol, descriptor type,

error message

Triggers: Unable to create entity descriptor due to federation SDK related

errors.

Actions: Look under federation log for more information.

ATTEMPT DELETE ENTITY DESCRIPTORS

ID: CONSOLE-1021

Level: INFO

Description: Attempt to delete entity descriptors.

Data: descriptor names

Triggers: Click on Delete button in entity descriptor main page.

SUCCEED DELETE ENTITY DESCRIPTORS

ID: CONSOLE-1022

Level: INFO

Description: Deletion entity descriptors succeeded

Data: descriptor names

Triggers: Click on Delete button in entity descriptor main page.

FEDERATION_EXCEPTION_DELETE_ENTITY_DESCRIPTORS

ID: CONSOLE-1023

Level: SEVERE

Description: Deletion entity descriptors failed.

Data: descriptor names, error message

 $\label{todelete} \mbox{Triggers: Unable to delete entity descriptors due to federation SDK related}$

errors.

Actions: Look under federation log for more information.

ATTEMPT_GET_AFFILIATE_ENTITY_DESCRIPTOR_ATTR_VALUES

ID: CONSOLE-1031

Level: INFO

Description: Attempt to get attribute values of an affiliate entity descriptor.

Data: descriptor realm, descriptor name, descriptor protocol

Triggers: View affiliate entity descriptor profile page.

SUCCEED_GET_AFFILIATE_ENTITY_DESCRIPTOR_ATTR_VALUES

ID: CONSOLE-1032

Level: INFO

Description: Getting of attribute values of an affiliate entity descriptor

succeeded.

Data: descriptor realm, descriptor name, descriptor protocol

Triggers: View affiliate entity descriptor profile page.

FEDERATION_EXCEPTION_GET_AFFILIATE_ENTITY_DESCRIPTOR_ATTR_VALUES

ID: CONSOLE-1033

Level: SEVERE

Description: Getting of attribute values of an affiliate entity descriptor failed.

Data: descriptor realm, descriptor name, descriptor protocol, error message

Triggers: Unable to get attribute value of an affiliate entity descriptor due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTEMPT_MODIFY_AFFILIATE_ENTITY_DESCRIPTOR ID: CONSOLE-1041

Level: INFO

Description: Attempt to modify an affiliate entity descriptor.

Data: descriptor realm, descriptor name, descriptor protocol

Triggers: Click on Save button of affiliate entity descriptor profile page.

SUCCEED_MODIFY_AFFILIATE_ENTITY_DESCRIPTOR

ID: CONSOLE-1042

Level: INFO

Description: Modification of an affiliate entity descriptor succeeded.

Data: descriptor realm, descriptor name, descriptor protocol

Triggers: Click on Save button of affiliate entity descriptor profile page.

FEDERATION_EXCEPTION_MODIFY_AFFILIATE_ENTITY_DESCRIPTOR

ID: CONSOLE-1043

Level: SEVERE

Description: Modification of an affiliate entity descriptor failed.

Data: descriptor realm, descriptor name, descriptor protocol, error message

Triggers: Unable to modify an affiliate entity descriptor due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTRIBUTE_FORMAT_EXCEPTION_MODIFY_AFFILIATE_ENTITY_DESCRIPTOR

ID: CONSOLE-1044

Level: SEVERE

Description: Modification of an affiliate entity descriptor failed.

Data: descriptor name, error message

Triggers: Unable to modify an affiliate entity descriptor due to incorrect

number format of one or more attribute values.

Actions: Look under federation log for more information.

ATTEMPT_GET_ENTITY_DESCRIPTOR_ATTR_VALUES

ID: CONSOLE-1051

Level: INFO

Description: Attempt to get attribute values of an entity descriptor.

Data: descriptor realm, descriptor name, descriptor protocol, descriptor type

Triggers: View entity descriptor profile page.

SUCCEED_GET_ENTITY_DESCRIPTOR_ATTR_VALUES

ID: CONSOLE-1052

Level: INFO

Description: Getting attribute values of entity descriptor succeeded.

Data: descriptor realm, descriptor name, descriptor protocol, descriptor type

Triggers: View entity descriptor profile page.

FEDERATION EXCEPTION GET ENTITY DESCRIPTOR ATTR VALUES

ID: CONSOLE-1053

Level: SEVERE

Description: Getting attribute values of entity descriptor failed.

Data: descriptor realm, descriptor name, descriptor protocol, descriptor type,

error message

Triggers: Unable to get attribute values of entity descriptor due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTEMPT MODIFY ENTITY DESCRIPTOR

ID: CONSOLE-1061

Level: INFO

Description: Attempt to modify entity descriptor.

Data: descriptor realm, descriptor name, descriptor protocol, descriptor type

Triggers: Click on Save button in entity descriptor profile page.

SUCCEED MODIFY ENTITY DESCRIPTOR

Description: Modification of entity descriptor succeeded.

Data: descriptor realm, descriptor name, descriptor protocol, descriptor type

Triggers: Click on Save button in entity descriptor profile page.

FEDERATION EXCEPTION MODIFY ENTITY DESCRIPTOR

ID: CONSOLE-1063

Level: SEVERE

Description: Modification of entity descriptor failed.

Data: descriptor realm, descriptor name, descriptor protocol, descriptor type, error message

Triggers: Unable to modify entity descriptor due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTEMPT GET AUTH DOMAINS

ID: CONSOLE-1101

Level: INFO

Description: Attempt to get authentication domain names.

Data: search pattern

Triggers: View authentication domain main page.

SUCCEED GET AUTH DOMAINS

ID: CONSOLE-1102

Level: INFO

Description: Getting authentication domain names succeeded.

Data: search pattern

Triggers: View authentication domain main page.

FEDERATION_EXCEPTION_GET_AUTH_DOMAINS

ID: CONSOLE-1103

Level: SEVERE

Description: Getting authentication domain names failed.

Data: name of realm, error message

Triggers: Unable to get authentication domain names due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTEMPT CREATE AUTH DOMAIN

ID: CONSOLE-1111

Level: INFO

Description: Attempt to create authentication domain

Data: name of authentication domain

Triggers: Click on New button in authentication domain creation page.

SUCCEED CREATE AUTH DOMAIN

ID: CONSOLE-1112

Level: INFO

Description: Creation authentication domain succeeded.

Data: name of authentication domain

Triggers: Click on New button in authentication domain creation page.

FEDERATION EXCEPTION CREATE AUTH DOMAIN

ID: CONSOLE-1113

Level: SEVERE

Description: Creation authentication domain failed.

Data: name of authentication domain, error message

Triggers: Unable to create authentication domain due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTEMPT_DELETE_AUTH_DOMAINS

ID: CONSOLE-1121

Level: INFO

Description: Attempt to delete authentication domains

Data: name of realm, name of authentication domains

Triggers: Click on Delete button in authentication domain main page.

SUCCEED_DELETE_AUTH_DOMAIN

ID: CONSOLE-1122

Level: INFO

Description: Deletion authentication domain succeeded.

Data: name of realm, name of authentication domains

Triggers: Click on Delete button in authentication domain main page.

FEDERATION EXCEPTION DELETE AUTH DOMAIN

ID: CONSOLE-1123

Level: SEVERE

Description: Deletion authentication domain failed.

Data: name of realm, name of authentication domains, error message

Triggers: Unable to delete authentication domain due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTEMPT GET AUTH DOMAIN ATTR VALUES

ID: CONSOLE-1131

Level: INFO

Description: Attempt to get authentication domain's attribute values

Data: name of realm, name of authentication domain

Triggers: View authentication domain profile page.

SUCCEED_GET_AUTH_DOMAIN_ATTR_VALUES

ID: CONSOLE-1132

Level: INFO

Description: Getting attribute values of authentication domain succeeded.

Data: name of realm, name of authentication domain

Triggers: View authentication domain profile page.

FEDERATION_EXCEPTION_GET_AUTH_DOMAIN_ATTR_VALUES

Level: SEVERE

Description: Getting attribute values of authentication domain failed.

Data: name of realm, name of authentication domains, error message

Triggers: Unable to get attribute values of authentication domain due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTEMPT_MODIFY_AUTH_DOMAIN

ID: CONSOLE-1141

Level: INFO

Description: Attempt to modify authentication domain

Data: name of realm, name of authentication domain

Triggers: Click on Save button in authentication domain profile page.

SUCCEED MODIFY AUTH DOMAIN

ID: CONSOLE-1142

Level: INFO

Description: Modification authentication domain succeeded.

Data: name of realm, name of authentication domain

Triggers: Click on Save button in authentication domain profile page.

FEDERATION_EXCEPTION_MODIFY_AUTH_DOMAIN

ID: CONSOLE-1143

Level: SEVERE

Description: Modification authentication domain failed.

Data: name of realm, name of authentication domain, error message

Triggers: Unable to modify authentication domain due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTEMPT_GET_ALL_PROVIDER_NAMES

ID: CONSOLE-1151

Level: INFO

Description: Attempt to get all provider names

Data: realm name

Triggers: View authentication domain profile page.

SUCCEED GET ALL PROVIDER NAMES

ID: CONSOLE-1152

Level: INFO

Description: Getting all provider names succeeded.

Data: realm name

Triggers: View authentication domain profile page.

FEDERATION EXCEPTION GET ALL PROVIDER NAMES

ID: CONSOLE-1153

Level: SEVERE

Description: Getting all provider names failed.

Data: error message

Triggers: Unable to get all provider names due to federation SDK related

errors.

Actions: Look under federation log for more information.

ATTEMPT_GET_PROVIDER_NAMES_UNDER_AUTH_DOMAIN ID: CONSOLE-1161

Level: INFO

Description: Attempt to get provider names under a authentication domain

Data: name of realm, name of authentication domain

Triggers: View authentication domain profile page.

SUCCEED GET PROVIDER NAMES UNDER AUTH DOMAIN

ID: CONSOLE-1162

Level: INFO

Description: Getting provider names under authentication domain succeeded.

Data: name of realm, name of authentication domain

Triggers: View authentication domain profile page.

FEDERATION_EXCEPTION_GET_PROVIDER_NAMES_UNDER_AUTH_DOMAIN ID: CONSOLE-1163

Level: SEVERE

Description: Getting provider names under authentication domain failed.

Data: name of realm, name of authentication domain, error message

Triggers: Unable to get provider names under authentication domain due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTEMPT_ADD_PROVIDERS_TO_AUTH_DOMAIN

ID: CONSOLE-1171

Level: INFO

Description: Attempt to add providers to an authentication domain

Data: name of realm, name of authentication domain, name of providers

Triggers: Click on Save button in provider assignment page.

SUCCEED_ADD_PROVIDERS_TO_AUTH_DOMAIN

ID: CONSOLE-1172

Level: INFO

Description: Addition of provider to an authentication domain succeeded.

Data: name of realm, name of authentication domain, name of providers

Triggers: Click on Save button in provider assignment page.

FEDERATION_EXCEPTION_ADD_PROVIDERS_TO_AUTH_DOMAIN ID: CONSOLE-1173

Level: SEVERE

Description: Addition of provider to an authentication domain failed.

Data: name of realm, name of authentication domain, name of providers, error message

Triggers: Unable to add provider to authentication domain due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTEMPT_REMOVE_PROVIDERS_FROM_AUTH_DOMAIN ID: CONSOLE-1181

Level: INFO

Description: Attempt to remove providers from authentication domain

Data: name of realm, name of authentication domain, name of providers

Triggers: Click on Save button in provider assignment page.

SUCCEED_REMOVE_PROVIDERS_FROM_AUTH_DOMAIN

ID: CONSOLE-1182

Level: INFO

Description: Deletion of providers from authentication domain succeeded.

Data: name of realm, name of authentication domain, name of providers

Triggers: Click on Save button in provider assignment page.

FEDERATION_EXCEPTION_REMOVE_PROVIDERS_FROM_AUTH_DOMAIN

ID: CONSŌLE-1183

Level: SEVERE

Description: Deletion of provider from authentication domain failed.

Data: name of realm, name of authentication domain, name of providers,

error message

Triggers: Unable to remove provider from authentication domain due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTEMPT_CREATE PROVIDER

ID: CONSOLE-1301

Level: INFO

Description: Attempt to create provider

Data: name of provider, role of provider, type of provider

Triggers: Click on Save button in provider assignment page.

SUCCEED_CREATE_PROVIDER

ID: CONSOLE-1302

Level: INFO

Description: Creation of providers succeeded.

Data: name of provider, role of provider, type of provider

Triggers: Click on Save button in provider assignment page.

FEDERATION EXCEPTION CREATE PROVIDER

ID: CONSOLE-1303

Level: SEVERE

Description: Creation of provider failed.

Data: name of provider, role of provider, type of provider, error message

Triggers: Unable to create provider due to federation SDK related errors.

Actions: Look under federation log for more information.

FEDERATION EXCEPTION CREATE PROVIDER

ID: CONSOLE-1304

Level: SEVERE

Description: Creation of provider failed.

Data: name of provider, role of provider, type of provider, error message

Triggers: Unable to create provider due to federation SDK related errors.

Actions: Look under federation log for more information.

INVOCATION_TARGET_EXCEPTION_CREATE_PROVIDER

ID: CONSOLE-1305

Level: SEVERE

Description: Creation of provider failed.

Data: name of provider, role of provider, type of provider, error message

Triggers: Unable to create provider because Administration Console cannot find the appropriate methods to set values for this provider.

Actions: This is a web application error. Please contact Sun Support for assistant.

ATTEMPT_GET_PROVIDER_ATTRIBUTE_VALUES ID: CONSOLE-1311

Level: INFO

Description: Attempt to get attribute values for provider

Data: name of provider, role of provider, type of provider

Triggers: View provider profile page.

SUCCEED GET PROVIDER ATTRIBUTE VALUES

ID: CONSOLE-1312

Level: INFO

Description: Getting attribute values of providers succeeded.

Data: name of provider, role of provider, type of provider

Triggers: View provider profile page.

ATTEMPT_GET_HANDLER_TO_PROVIDER

ID: CONSOLE-1321

Level: INFO

Description: Attempt to get handler to provider

Data: name of provider, role of provider

Triggers: View provider profile page.

SUCCEED_GET_HANDLER_TO_PROVIDER

ID: CONSOLE-1322

Level: INFO

Description: Getting handler to provider succeeded.

Data: name of provider, role of provider

Triggers: View provider profile page.

FEDERATION_EXCEPTION_GET_HANDLER_TO_PROVIDER

ID: CONSOLE-1323

Level: SEVERE

Description: Getting handler to provider failed.

Data: name of provider, role of provider, error message

Triggers: Unable to get handler to provider due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTEMPT_MODIFY_PROVIDER

ID: CONSOLE-1331

Level: INFO

Description: Attempt to modify provider

Data: name of provider, role of provider

Triggers: Click on Save button in provider profile page.

SUCCEED MODIFY PROVIDER

ID: CONSOLE-1332

Level: INFO

Description: Modification of provider succeeded.

Data: name of provider, role of provider

Triggers: Click on Save button in provider profile page.

FEDERATION EXCEPTION MODIFY PROVIDER

ID: CONSOLE-1333

Level: SEVERE

Description: Modification of provider failed.

Data: name of provider, role of provider, error message

Triggers: Unable to modify provider due to federation SDK related errors.

Actions: Look under federation log for more information.

INVOCATION TARGET EXCEPTION MODIFY PROVIDER

ID: CONSOLE-1334

Level: SEVERE

Description: Modification of provider failed.

Data: name of provider, role of provider, error message

Triggers: Unable to modify provider because Administration Console cannot find the appropriate methods to set values for this provider.

Actions: This is a web application error. Please contact Sun Support for assistant.

ATTEMPT DELETE PROVIDER

ID: CONSOLE-1341

Level: INFO

Description: Attempt to delete provider

Data: name of provider, role of provider

Triggers: Click on delete provider button in provider profile page.

SUCCEED DELETE PROVIDER

ID: CONSOLE-1342

Level: INFO

Description: Deletion of provider succeeded.

Data: name of provider, role of provider

Triggers: Click on delete provider button in provider profile page.

FEDERATION EXCEPTION DELETE PROVIDER

ID: CONSOLE-1343

Level: SEVERE

Description: Deletion of provider failed.

Data: name of provider, role of provider, error message

Triggers: Unable to delete provider due to federation SDK related errors.

Actions: Look under federation log for more information.

ATTEMPT GET PROSPECTIVE TRUSTED PROVIDER

ID: CONSOLE-1351

Level: INFO

Description: Attempt to get prospective trusted provider

Data: name of provider, role of provider

Triggers: View add trusted provider page.

SUCCEED_GET_PROSPECTIVE_TRUSTED_PROVIDER

ID: CONSOLE-1352

Level: INFO

Description: Getting of prospective trusted provider succeeded.

Data: name of provider, role of provider

Triggers: View add trusted provider page.

FEDERATION_EXCEPTION_GET_PROSPECTIVE_TRUSTED_PROVIDER

ID: CONSOLE-1353

Level: SEVERE

Description: Getting of prospective trusted provider failed.

Data: name of provider, role of provider, error message

Triggers: Unable to get prospective trusted provider due to federation SDK related errors.

related errors.

Actions: Look under federation log for more information.

ATTEMPT GET ATTR VALUE SCHEMA TYPE

ID: CONSOLE-2001

Level: INFO

Description: Attempt to get attribute values of schema type of a service schema

Data: name of service, name of schema type, name of attribute schemas

Triggers: View service profile page.

SUCCEED_GET_ATTR_VALUE_SCHEMA_TYPE

ID: CONSOLE-2002

Level: INFO

 $Description: Getting \ attribute \ values \ of \ schema \ type \ of \ a \ service \ schema$

succeeded.

Data: name of service, name of schema type, name of attribute schemas

Triggers: View service profile page.

SSO_EXCEPTION_GET_ATTR_VALUE_SCHEMA TYPE

ID: CONSOLE-2003

Level: SEVERE

Description: Getting attribute values of schema type of a service schema failed.

Data: name of service, name of schema type, name of attribute schemas, error message

Triggers: Unable to get attribute values of schema type of a service schema. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS_EXCEPTION_GET_ATTR_VALUE_SCHEMA_TYPE

ID: CONSOLE-2004

Level: SEVERE

Description: Getting attribute values of schema type of a service schema failed.

Data: name of service, name of schema type, name of attribute schemas, error message

Triggers: Unable to get attribute values of schema type of a service schema due to service management SDK related errors.

Actions: Look under service management log for more information.

NO_SCHEMA_GET_ATTR_VALUE_SCHEMA_TYPE

ID: CONSOLE-2005

Level: INFO

Description: Getting attribute values of schema type of a service schema failed.

Data: name of service, name of schema type, name of attribute schemas

Triggers: View service profile page.

Actions: Need no action on this event. Console attempts to get a schema from a service but schema does not exist.

ATTEMPT_GET_ATTR_VALUE_ATR_SCHEMA_SCHEMA_TYPE

ID: CONSOLE-2011

Level: INFO

Description: Attempt to get attribute values of attribute schema of a schema type of a service schema

Data: name of service, name of schema type, name of attribute schemas

Triggers: View service profile page.

SUCCEED_GET_ATTR_VALUE_ATR_SCHEMA_SCHEMA_TYPE ID: CONSOLE-2012

Level: INFO

Description: Getting attribute values of attribute schema of a schema type of a service schema succeeded.

Data: name of service, name of schema type, name of attribute schemas

Triggers: View service profile page.

SSO_EXCEPTION_GET_ATTR_VALUE_ATR_SCHEMA_SCHEMA_TYPE ID: CONSOLE-2013

Level: SEVERE

Description: Getting attribute values of attribute schema of a schema type of a service schema failed.

Data: name of service, name of schema type, name of attribute schemas, error message

Triggers: Unable to get attribute values of schema type of a service schema. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS_EXCEPTION_GET_ATTR_VALUE_ATR_SCHEMA_SCHEMA_TYPE ID: CONSOLE-2014

Level: SEVERE

Description: Getting attribute values of attribute schema of a schema type of a service schema failed.

Data: name of service, name of schema type, name of attribute schemas, error message

Triggers: Unable to get attribute values of schema type of a service schema due to service management SDK related errors.

Actions: Look under service management log for more information.

ATTEMPT_SET_ATTR_VALUE_ATR_SCHEMA_SCHEMA_TYPE ID: CONSOLE-2021

Level: INFO

Description: Attempt to modify attribute values of attribute schema of a schema type of a service schema

Data: name of service, name of schema type, name of attribute schemas

Triggers: Click on Save button in service profile page.

SUCCEED_SET_ATTR_VALUE_ATR_SCHEMA_SCHEMA_TYPE ID: CONSOLE-2022

Level: INFO

Description: Modification attribute values of attribute schema of a schema type of a service schema succeeded.

Data: name of service, name of schema type, name of attribute schemas

Triggers: Click on Save button in service profile page.

SSO_EXCEPTION_SET_ATTR_VALUE_ATR_SCHEMA_SCHEMA_TYPE ID: CONSOLE-2023

Level: SEVERE

Description: Modification attribute values of attribute schema of a schema type of a service schema failed.

Data: name of service, name of schema type, name of attribute schemas, error message

Triggers: Unable to modify attribute values of schema type of a service schema. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under service management log for more information.

SMS_EXCEPTION_SET_ATTR_VALUE_ATR_SCHEMA_SCHEMA_TYPE ID: CONSOLE-2024

Level: SEVERE

Description: Modification attribute values of attribute schema of a schema type of a service schema failed.

Data: name of service, name of schema type, name of attribute schemas, error message

Triggers: Unable to modify attribute values of schema type of a service schema due to service management SDK related errors.

Actions: Look under service management log for more information.

ATTEMPT CLIENT DETECTION GET DEVICE NAMES

ID: CONSOLE-2501

Level: INFO

Description: Attempt to get device names of client detection service

Data: name of profile, name of style, search pattern

Triggers: View client profile page.

SUCCEED CLIENT DETECTION GET DEVICE NAMES

ID: CONSOLE-2502

Level: INFO

Description: Getting device names of client detection service succeeded.

Data: name of profile, name of style, search pattern

Triggers: View client profile page.

ATTEMPT CLIENT DETECTION DELETE CLIENT

ID: CONSOLE-2511

Level: INFO

Description: Attempt to delete client in client detection service

Data: type of client

Triggers: Click on client type delete hyperlink page.

SUCCEED CLIENT DETECTION DELETE CLIENT

ID: CONSOLE-2512

Level: INFO

Description: Deletion of client in client detection service succeeded.

Data: type of client

Triggers: Click on client type delete hyperlink page.

CLIENT_SDK_EXCEPTION_CLIENT_DETECTION_DELETE_CLIENT ID: CONSOLE-2513

Level: SEVERE

Description: Deletion of client in client detection service failed.

Data: type of client, error message

Triggers: Unable to delete client due to client detection SDK related errors.

Actions: Look under client detection management log for more information.

ATTEMPT_CLIENT_DETECTION_CREATE_CLIENT

ID: CONSOLE-2521

Level: INFO

Description: Attempt to create client in client detection service

Data: type of client

Triggers: Click on New button in Client Creation Page.

SUCCEED CLIENT DETECTION CREATE CLIENT

ID: CONSOLE-2522

Level: INFO

Description: Creation of client in client detection service succeeded.

Data: type of client

Triggers: Click on New button in Client Creation Page.

CLIENT SDK EXCEPTION CLIENT DETECTION CREATE CLIENT

ID: CONSOLE-2523

Level: SEVERE

Description: Creation of client in client detection service failed.

Data: type of client, error message

Triggers: Unable to create client due to client detection SDK related errors.

Actions: Look under client detection management log for more information.

INVALID_CLIENT_TYPE_CLIENT_DETECTION_CREATE_CLIENT

ID: CONSOLE-2524

Level: INFO

Description: Creation of client in client detection service failed.

Data: type of client, error message

Triggers: Unable to create client because client type is invalid.

Actions: Check the client type again before creation.

ATTEMPT_CLIENT_DETECTION_GET_CLIENT_PROFILE

ID: CONSOLE-2531

Level: INFO

Description: Attempt to get client profile in client detection service

Data: type of client, classification

Triggers: View client profile page.

SUCCEED CLIENT DETECTION GET CLIENT PROFILE

ID: CONSOLE-2532

Level: INFO

Description: Getting of client profile in client detection service succeeded.

Data: type of client, classification

Triggers: View client profile page.

ATTEMPT_CLIENT_DETECTION_MODIFY_CLIENT_PROFILE

ID: CONSOLE-2541

Level: INFO

Description: Attempt to modify client profile in client detection service

Data: type of client

Triggers: Click on Save button client profile page.

${\tt SUCCEED_CLIENT_DETECTION_MODIFY_CLIENT_PROFILE}$

ID: CONSOLE-2542

Level: INFO

Description: Modification of client profile in client detection service

succeeded.

Data: type of client

Triggers: Click on Save button client profile page.

CLIENT_SDK_EXCEPTION_CLIENT_DETECTION_CREATE_CLIENT

ID: CONSOLE-2543

Level: SEVERE

Description: Modification of client profile in client detection service failed.

Data: type of client, error message

 $\label{tomodify} \mbox{Triggers: Unable to modify client profile due to client detection SDK related}$

errors.

Actions: Look under client detection management log for more information.

ATTEMPT_GET_CURRENT_SESSIONS

ID: CONSOLE-3001

Level: INFO

Description: Attempt to get current sessions

Data: name of server, search pattern

Triggers: View session main page.

SUCCEED_GET_CURRENT_SESSIONS

ID: CONSOLE-3002

Level: INFO

Description: Getting of current sessions succeeded.

Data: name of server, search pattern

Triggers: View session main page.

SESSION_EXCEPTION_GET_CURRENT_SESSIONS

ID: CONSOLE-3003

Level: SEVERE

Description: Getting of current sessions failed.

Data: name of server, name of realm, error message

Triggers: Unable to get current sessions due to session SDK exception.

Actions: Look under session management log for more information.

ATTEMPT INVALIDATE SESSIONS

ID: CONSOLE-3011

Level: INFO

Description: Attempt to invalidate session

Data: name of server, ID of session

Triggers: Click on Invalidate button in session main page.

SUCCEED INVALIDATE SESSIONS

ID: CONSOLE-3012

Level: INFO

Description: Invalidation of session succeeded.

Data: name of server, ID of session

Triggers: Click on Invalidate button in session main page.

SESSION EXCEPTION INVALIDATE SESSIONS

ID: CONSOLE-3013

Level: SEVERE

Description: Invalidation of session failed.

Data: name of server, ID of session, error message

Triggers: Unable to invalidate session due to session SDK exception.

Actions: Look under session management log for more information.

ATTEMPT GET SITE NAMES

ID: CONSOLE-12001

Level: INFO

Description: Attempt to get site names

Data: server instance name

Triggers: View site and server management page.

SUCCEED GET SITE NAMES

ID: CONSOLE-12002

Level: INFO

Description: Site names are returned.

Data: server instance name

Triggers: View site and server management page.

SSO EXCEPTION GET SITE NAMES

ID: CONSOLE-12003

Level: SEVERE

Description: Get site names.

Data: error message

Triggers: Unable to get site names. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS_EXCEPTION_GET_SITE_NAMES

ID: CONSOLE-12004

Level: SEVERE

Description: Get site names.

Data: error message

Triggers: Unable to get site names due the SMS API error.

Actions: Look under service management SDK log for more information.

ATTEMPT GET SITE PRIMARY URL

ID: CONSOLE-12011

Level: INFO

Description: Attempt to get primary URL of site.

Data: Site Name

Triggers: View site profile page.

SUCCEED GET SITE PRIMARY URL

ID: CONSOLE-12012

Level: INFO

Description: Primary URL of site is returned.

Data: Site Name

Triggers: View site profile page.

SSO EXCEPTION GET SITE PRIMARY URL

ID: CONSOLE-12013

Level: SEVERE

Description: Get primary URL of site.

Data: Site Name, error message

Triggers: Unable to get primary URL of site. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS EXCEPTION GET SITE PRIMARY URL

ID: CONSOLE-12014

Level: SEVERE

Description: Get primary URL of site.

Data: Site Name, error message

Triggers: Unable to get primary URL of site due the SMS API error.

Actions: Look under service management SDK log for more information.

ATTEMPT_GET_SITE_FAILOVER_URLS

ID: CONSOLE-12021

Level: INFO

Description: Attempt to get failover URLs of site.

Data: Site Name

Triggers: View site profile page.

SUCCEED_GET_SITE_FAILOVER_URLS

ID: CONSOLE-12022

Level: INFO

Description: Failover URLs of site is returned.

Data: Site Name

Triggers: View site profile page.

SSO EXCEPTION GET SITE FAILOVER URLS

ID: CONSOLE-12023

Level: SEVERE

Description: Get failover URLs of site.

Data: Site Name, error message

Triggers: Unable to get failover URLs of site. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS EXCEPTION GET SITE FAILOVER URLS

ID: CONSOLE-12024

Level: SEVERE

Description: Get failover URLs of site.

Data: Site Name, error message

Triggers: Unable to get failover URLs of site due the SMS API error.

Actions: Look under service management SDK log for more information.

ATTEMPT GET SITE MEMBERS

ID: CONSOLE-12031

Level: INFO

Description: Attempt to get members of site.

Data: Site Name

Triggers: View site profile page.

SUCCEED GET SITE MEMBERS

ID: CONSOLE-12032

Level: INFO

Description: Members of site is returned.

Data: Site Name

Triggers: View site profile page.

SSO EXCEPTION GET SITE MEMBERS

ID: CONSOLE-12033

Level: SEVERE

Description: Get members of site.

Data: Site Name, error message

Triggers: Unable to get members of site. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS EXCEPTION GET SITE MEMBERS

ID: CONSOLE-12034

Level: SEVERE

Description: Get members of site.

Data: Site Name, error message

Triggers: Unable to get members of site due the SMS API error.

Actions: Look under service management SDK log for more information.

ATTEMPT CREATE SITE

ID: CONSOLE-12041

Level: INFO

Description: Attempt to create site.

Data: Site Name

Triggers: View create site page.

SUCCEED_CREATE_SITE

ID: CONSOLE-12042

Level: INFO

Description: Site is created.

Data: Site Name

Triggers: Click on create button on creation page.

SSO EXCEPTION CREATE SITE

ID: CONSOLE-12043

Level: SEVERE

Description: Create site.

Data: Site Name, error message

Triggers: Unable to create site. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS_EXCEPTION_CREATE_SITE

ID: CONSOLE-12044

Level: SEVERE

Description: Create site.

Data: Site Name, error message

Triggers: Unable to create site due the SMS API error.

Actions: Look under service management SDK log for more information.

ATTEMPT CREATE SERVER

ID: CONSOLE-12051

Level: INFO

Description: Attempt to create server.

Data: Server Name

Triggers: View create server page.

SUCCEED CREATE SERVER

ID: CONSOLE-12052

Level: INFO

Description: Server is created.

Data: Server Name

Triggers: Click on create button on creation page.

SSO_EXCEPTION_CREATE_SERVER ID: CONSOLE-12053

Level: SEVERE

Description: Create server.

Data: Server Name, error message

Triggers: Unable to create server. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS_EXCEPTION_CREATE_SERVER

ID: CONSOLE-12054

Level: SEVERE

Description: Create server.

Data: Server Name, error message

Triggers: Unable to create server due the SMS API error.

Actions: Look under service management SDK log for more information.

CONFIGURATION EXCEPTION CREATE SERVER

ID: CONSOLE-12055

Level: SEVERE

Description: Create server.

Data: Server Name, error message

Triggers: Unable to create server due the incorrect data format error.

Actions: Look under console log for more information.

IO_EXCEPTION_CREATE_SERVER

ID: CONSOLE-12056

Level: SEVERE

Description: Create server.

Data: Server Name, error message

Triggers: Unable to create server due the incorrect data format error.

Actions: Look under console log for more information.

ATTEMPT_DELETE_SITE

ID: CONSOLE-12061

Level: INFO

Description: Attempt to delete site.

Data: Site Name

Triggers: Click on delete site button.

SUCCEED_DELETE_SITE

ID: CONSOLE-12062

Level: INFO

Description: Site is deleted.

Data: Site Name

Triggers: Click on delete button.

SSO EXCEPTION DELETE SITE

ID: CONSOLE-12063

Level: SEVERE

Description: Delete site.

Data: Site Name, error message

Triggers: Unable to delete site. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS_EXCEPTION_DELETE_SITE

ID: CONSOLE-12064

Level: SEVERE

Description: Delete site.

Data: Site Name, error message

Triggers: Unable to delete site due the SMS API error.

Actions: Look under service management SDK log for more information.

ATTEMPT MODIFY SITE

ID: CONSOLE-12071

Level: INFO

Description: Attempt to modify site.

Data: Site Name

Triggers: Click on OK button in site profile page.

SUCCEED MODIFY SITE

ID: CONSOLE-12072

Level: INFO

Description: Site is nodified.

Data: Site Name

Triggers: Click on OK button in site profile page.

SSO_EXCEPTION_MODIFY_SITE ID: CONSOLE-12073

Level: SEVERE

Description: Modify site.

Data: Site Name, error message

Triggers: Unable to modify site. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS_EXCEPTION_MODIFY_SITE

ID: CONSOLE-12074

Level: SEVERE

Description: Modify site.

Data: Site Name, error message

Triggers: Unable to modify site due the SMS API error.

Actions: Look under service management SDK log for more information.

CONFIGURATION EXCEPTION MODIFY SITE

ID: CONSOLE-12075

Level: SEVERE

Description: Modify site.

Data: Site Name, error message

Triggers: Unable to modify site due the incorrect data format.

Actions: Look under console log for more information.

ATTEMPT GET SERVER NAMES

ID: CONSOLE-12081

Level: INFO

Description: Attempt to get server names.

Data: server instance name

Triggers: View site and server management page.

SUCCEED_GET_SERVER_NAMES

ID: CONSOLE-12082

Level: INFO

Description: Server names are returned.

Data: server instance name

Triggers: View site and server management page.

SSO_EXCEPTION_GET_SERVER_NAMES

ID: CONSOLE-12083

Level: SEVERE

Description: Get server name.

Data: error message

Triggers: Unable to get server names. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS_EXCEPTION_GET_SERVER NAMES

ID: CONSOLE-12084

Level: SEVERE

Description: Get server name.

Data: error message

Triggers: Unable to get server names due the SMS API error.

Actions: Look under service management SDK log for more information.

ATTEMPT GET SERVER SITE

ID: CONSOLE-12091

Level: INFO

Description: Attempt to get server's site.

Data: Server Name

Triggers: View server profile page.

SUCCEED_GET_SERVER_SITE

ID: CONSOLE-12092

Level: INFO

Description: Server's site name is returned.

Data: Server Name

Triggers: View server profile page.

SSO_EXCEPTION_GET_SERVER_SITE ID: CONSOLE-12093

Level: SEVERE

Description: Get server's site name.

Data: Server Name, error message

Triggers: Unable to get server's site. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS EXCEPTION GET SERVER SITE

ID: CONSOLE-12094

Level: SEVERE

Description: Get server's site name.

Data: Server Name, error message

Triggers: Unable to get server's site due the SMS API error.

Actions: Look under service management SDK log for more information.

ATTEMPT DELETE SERVER

ID: CONSOLE-12101

Level: INFO

Description: Attempt to delete server.

Data: Server Name

Triggers: Click on delete button in server management page.

SUCCEED DELETE SERVER

ID: CONSOLE-12102

Level: INFO

Description: Server is delete.

Data: Server Name

Triggers: Click on delete button in server management page.

SSO EXCEPTION DELETE SERVER

ID: CONSOLE-12103

Level: SEVERE

Description: Delete server.

Data: Server Name, error message

Triggers: Unable to delete server. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS_EXCEPTION_DELETE_SERVER

ID: CONSOLE-12104

Level: SEVERE

Description: Delete server.

Data: Server Name, error message

Triggers: Unable to delete server due the SMS API error.

Actions: Look under service management SDK log for more information.

ATTEMPT CLONE SERVER

ID: CONSOLE-12201

Level: INFO

Description: Attempt to clone server.

Data: Server Name, Cloned Server Name

Triggers: Click on clone button in server management page.

SUCCEED_CLONE_SERVER

ID: CONSOLE-12202

Level: INFO

Description: Server is cloned.

Data: Server Name, Cloned Server Name

Triggers: Click on clone button in server management page.

SSO EXCEPTION CLONE SERVER

ID: CONSOLE-12203

Level: SEVERE

Description: clone server.

Data: Server Name, Cloned Server Name, error message

Triggers: Unable to clone server. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS_EXCEPTION_CLONE_SERVER

ID: CONSOLE-12204

Level: SEVERE

Description: clone server.

Data: Server Name, Cloned Server Name, error message

Triggers: Unable to clone server due the SMS API error.

Actions: Look under service management SDK log for more information.

CONFIGURATION EXCEPTION_CLONE_SERVER

ID: CONSOLE-12205

Level: SEVERE

Description: clone server.

Data: Server Name, Cloned Server Name, error message

Triggers: Unable to clone server due the data format error.

Actions: Look under console log for more information.

ATTEMPT_GET_SERVER_CONFIG

ID: CONSOLE-12211

Level: INFO

Description: Attempt to get server's configuration.

Data: Server Name

Triggers: View server profile page.

SUCCEED_GET_SERVER_CONFIG

ID: CONSOLE-12212

Level: INFO

Description: Server's configuration is returned.

Data: Server Name

Triggers: View server profile page.

SSO_EXCEPTION_GET_SERVER_CONFIG ID: CONSOLE-12213

Level: SEVERE

Description: Get server's configuration.

Data: Server Name, error message

Triggers: Unable to get server's configuration. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS_EXCEPTION_GET_SERVER_CONFIG ID: CONSOLE-12214

Level: SEVERE

Description: Get server's configuration.

Data: Server Name, error message

Triggers: Unable to get server's configuration due the SMS API error.

Actions: Look under service management SDK log for more information.

IO EXCEPTION GET SERVER CONFIG

ID: CONSOLE-12215

Level: SEVERE

Description: get server's configuration.

Data: Server Name, error message

Triggers: Unable to get server's configuration due the data parsing error.

Actions: Look under console log for more information.

ATTEMPT_GET_SERVER_DEFAULT_CONFIG

ID: CONSOLE-12221

Level: INFO

Description: Attempt to get server default configuration.

Data: server instance name

Triggers: View server profile page.

SUCCEED GET SERVER DEFAULT CONFIG

ID: CONSOLE-12222

Level: INFO

Description: Server default configuration is returned.

Data: server instance name

Triggers: View server profile page.

ATTEMPT MODIFY SERVER

ID: CONSOLE-12231

Level: INFO

Description: Attempt to modify server.

Data: Server Name

Triggers: Click on OK button in server profile page.

SUCCEED MODIFY SERVER

ID: CONSOLE-12232

Level: INFO

Description: Server is modified.

Data: Server Name

Triggers: Click on OK button in server profile page.

SSO EXCEPTION MODIFY SERVER

ID: CONSOLE-12233

Level: SEVERE

Description: modify server.

Data: Server Name, error message

Triggers: Unable to modify server. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

$SMS_EXCEPTION_MODIFY_SERVER$

ID: CONSOLE-12234

Level: SEVERE

Description: modify server.

Data: Server Name, error message

Triggers: Unable to modify server due the SMS API error.

Actions: Look under service management SDK log for more information.

IO EXCEPTION MODIFY_SERVER

ID: CONSOLE-12235

Level: SEVERE

Description: modify server.

Data: Server Name, error message

Triggers: Unable to modify server due the data parsing error.

Actions: Look under console log for more information.

CONFIGURATION_EXCEPTION_MODIFY_SERVER

ID: CONSOLE-12236

Level: SEVERE

Description: modify server.

Data: Server Name, error message

Triggers: Unable to modify server due the incorrect data format error.

Actions: Look under console log for more information.

ATTEMPT MODIFY SERVER INHERITANCE

ID: CONSOLE-12241

Level: INFO

Description: Attempt to modify server's inheritance.

Data: Server Name

Triggers: Click on OK button in server inheritance setting page.

SUCCEED MODIFY SERVER INHERITANCE

ID: CONSOLE-12242

Level: INFO

Description: Server's inheritance setting is modified.

Data: Server Name

Triggers: Click on OK button in server inheritance setting page.

SSO_EXCEPTION_MODIFY_SERVER_INHERITANCE ID: CONSOLE-12243

Level: SEVERE

Description: Modify server's inheritance.

Data: Server Name, error message

Triggers: Unable to modify server's inheritance. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS EXCEPTION MODIFY SERVER INHERITANCE

ID: CONSOLE-12244

Level: SEVERE

Description: Modify server's inheritance.

Data: Server Name, error message

Triggers: Unable to modify server's inheritance due the SMS API error.

Actions: Look under service management SDK log for more information.

IO EXCEPTION MODIFY SERVER INHERITANCE

ID: CONSOLE-12245

Level: SEVERE

Description: modify server's inheritance.

Data: Server Name, error message

Triggers: Unable to modify server's inheritance due the data parsing error.

Actions: Look under console log for more information.

CONFIGURATION EXCEPTION MODIFY SERVER INHERITANCE

ID: CONSOLE-12246

Level: SEVERE

Description: modify server's inheritance.

Data: Server Name, error message

Triggers: Unable to modify server's inheritance due the incorrect data format

error.

Actions: Look under console log for more information.

ATTEMPT GET SERVER CONFIG XML

ID: CONSOLE-12251

Level: INFO

Description: Attempt to get server's configuration XML.

Data: Server Name

Triggers: View server's server configuration XML profile page.

SUCCEED GET SERVER CONFIG XML

ID: CONSOLE-12252

Level: INFO

Description: Server's configuration XML is returned.

Data: Server Name

Triggers: View server's server configuration XML profile page.

SSO EXCEPTION GET SERVER CONFIG XML

ID: CONSOLE-12253

Level: SEVERE

Description: Get server's configuration XML.

Data: Server Name, error message

Triggers: Unable to get server's configuration XML. It may be the single sign on token of the user has expired; or the user does not have permission to

perform this operation.

Actions: Look under access management SDK log for more information.

SMS EXCEPTION GET SERVER CONFIG XML

ID: CONSOLE-12254

Level: SEVERE

Description: sGget server's configuration XML.

Data: Server Name, error message

Triggers: Unable to get server's configuration XML due the SMS API error.

Actions: Look under service management SDK log for more information.

GENERIC EXCEPTION GET SERVER CONFIG XML

ID: CONSOLE-12255

Level: SEVERE

Description: sGget server's configuration XML.

Data: Server Name, error message

Triggers: Unable to get server's configuration XML due the data parsing error.

Actions: Look under console log for more information.

ATTEMPT SET SERVER CONFIG XML

ID: CONSOLE-12261

Level: INFO

Description: Attempt to set server's configuration XML.

Data: Server Name

Triggers: Click on OK button in server's server configuration XML profile

page.

SUCCEED_SET_SERVER_CONFIG_XML

ID: CONSOLE-12262

Level: INFO

Description: Server's configuration XML is modified.

Data: Server Name

Triggers: Click on OK button in server's server configuration XML profile

page.

SSO_EXCEPTION_SET_SERVER_CONFIG_XML

ID: CONSOLE-12263

Level: SEVERE

Description: set server's configuration XML.

Data: Server Name, error message

Triggers: Unable to set server's configuration XML. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under access management SDK log for more information.

SMS EXCEPTION SET SERVER CONFIG XML

ID: CONSOLE-12264

Level: SEVERE

Description: sGset server's configuration XML.

Data: Server Name, error message

Triggers: Unable to set server's configuration XML due the SMS API error.

Actions: Look under service management SDK log for more information.

ATTEMPT SEARCH AGENT

ID: CONSOLE-13001

Level: INFO

Description: Attempt to search for agents

Data: base realm, agent type, search pattern, search size limit, search time

limit

Triggers: Click on Search button in agent search view.

SUCCEED SEARCH AGENT

ID: CONSOLE-13002

Level: INFO

Description: Searching for agents succeeded

Data: base realm, agent type, search pattern, search size limit, search time

limit

Triggers: Click on Search button in agent search view.

EXCEPTION SEARCH AGENT

ID: CONSOLE-13003

Level: SEVERE

Description: Searching for agents failed

Data: base realm, agent type, search pattern, search size limit, search time

limit, error message

Triggers: Unable to perform search operation on agents under a realm. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

ATTEMPT_DELETE_AGENT

ID: CONSOLE-13011

Level: INFO

Description: Attempt to delete agents

Data: base realm, agent names

Triggers: Click on Delete button in agent home page.

SUCCEED_DELETE_AGENT

ID: CONSOLE-13012

Level: INFO

Description: Agents are deleted

Data: base realm, agent names

Triggers: Click on Delete button in agent home page.

EXCEPTION DELETE AGENT

ID: CONSOLE-13013

Level: SEVERE

Description: Deletion of agents failed

Data: base realm, agent names, error message

Triggers: Unable to perform delete operation on agents under a realm. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

ATTEMPT_SEARCH AGENT GROUP

ID: CONSOLE-13021

Level: INFO

Description: Attempt to search for agent groups

Data: base realm, agent type, search pattern, search size limit, search time

limit

Triggers: Click on Search button in agent search view.

SUCCEED SEARCH AGENT GROUP

ID: CONSOLE-13022

Level: INFO

Description: Searching for agent groups succeeded

Data: base realm, agent type, search pattern, search size limit, search time

limit

Triggers: Click on Search button in agent search view.

EXCEPTION_SEARCH_AGENT_GROUP

ID: CONSOLE-13023

Level: SEVERE

Description: Searching for agent groups failed

Data: base realm, agent type, search pattern, search size limit, search time

limit, error message

Triggers: Unable to perform search operation on agent groups under a realm. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

ATTEMPT DELETE AGENT GROUP

ID: CONSOLE-13031

Level: INFO

Description: Attempt to delete agent groups

Data: base realm, agent group names

Triggers: Click on Delete button in agent home page.

SUCCEED DELETE AGENT GROUP

ID: CONSOLE-13032

Level: INFO

Description: Agent groups are deleted

Data: base realm, agent group names

Triggers: Click on Delete button in agent home page.

EXCEPTION DELETE AGENT GROUP

ID: CONSOLE-13033

Level: SEVERE

Description: Deletion of agent groups failed

Data: base realm, agent group names, error message

Triggers: Unable to perform delete operation on agents under a realm. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

ATTEMPT_CREATE_AGENT

ID: CONSOLE-13041

Level: INFO

Description: Attempt to create agent

Data: base realm, agent name, agent type

Triggers: Click on New button in agent home page.

SUCCEED CREATE AGENT

ID: CONSOLE-13042

Level: INFO

Description: Agent is created

Data: base realm, agent name, agent type

Triggers: Click on New button in agent home page.

EXCEPTION CREATE AGENT

ID: CONSOLE-13043

Level: SEVERE

Description: Creation of agent failed

Data: base realm, agent name, agent type, error message

Triggers: Unable to perform create agent. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

ATTEMPT CREATE AGENT GROUP

ID: CONSOLE-13051

Level: INFO

Description: Attempt to create agent group

Data: base realm, agent group name, agent type

Triggers: Click on New button in agent home page.

SUCCEED CREATE AGENT GROUP

ID: CONSOLE-13052

Level: INFO

Description: Agent group is created

Data: base realm, agent group name, agent type

Triggers: Click on New button in agent home page.

EXCEPTION CREATE AGENT GROUP

ID: CONSOLE-13053

Level: SEVERE

Description: Creation of agent group failed

Data: base realm, agent group name, agent type, error message

Triggers: Unable to perform create agent group. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

ATTEMPT GET AGENT ATTRIBUTE VALUES

ID: CONSOLE-13061

Level: INFO

Description: Attempt to get agent attribute values

Data: agent universal Id

Triggers: Visit agent profile page.

SUCCEED GET AGENT ATTRIBUTE VALUES

ID: CONSOLE-13062

Level: INFO

Description: Agent attribute values is retrieved.

Data: agent universal Id

Triggers: Visit agent profile page.

EXCEPTION GET AGENT ATTRIBUTE VALUES

ID: CONSOLE-13063

Level: SEVERE

Description: Unable to get agent attribute values

Data: agent universal Id, error message

Triggers: Unable to perform get agent attribute values. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

ATTEMPT_SET_AGENT_ATTRIBUTE VALUE

ID: CONSOLE-13071

Level: INFO

Description: Attempt to set agent attribute values

Data: agent universal Id

Triggers: Click on save button in agent profile page.

SUCCEED SET AGENT ATTRIBUTE VALUE

ID: CONSOLE-13072

Level: INFO

Description: Agent attribute values set successfully

Data: agent universal Id

Triggers: Click on save button in agent profile page.

EXCEPTION_SET_AGENT_ATTRIBUTE_VALUE

ID: CONSOLE-13073

Level: SEVERE

Description: Unable to set agent attribute values

Data: agent universal Id, error message

Triggers: Unable to perform set agent attribute values. It may be the single sign on token of the user has expired; or the user does not have permission to perform this operation.

Actions: Look under data store log for more information.

ATTEMPT_GET_ATTR_VALUES_OF_SESSION_HA_PROPERTIES ID: CONSOLE-13074

Level: INFO

Description: Attempt to read session HA properties

Data: name of attribute

Triggers: Click on Save button in session profile page.

SUCCEED_GET_ATTR_VALUES_OF_SESSION_HA_PROPERTIES

ID: CONSOLE-13075

Level: INFO

Description: Read Access of session HA properties succeeded.

Data: name of attribute

Triggers: Click on Save button in session profile page.

SMS_EXCEPTION_GET_ATTR_VALUES_OF_SESSION_HA_PROPERTIES

ID: CONSOLE-13076

Level: SEVERE

Description: Read Access of session HA properties failed.

Data: name of attribute, error message

Triggers: Unable to modify session HA properties due to service management SDK exception.

Actions: Look under service management log for more information.

ATTEMPT_SET_ATTR_VALUES_OF_SESSION_HA_PROPERTIES

ID: CONSOLE-13077

Level: INFO

Description: Attempt to modify session HA properties

Data: name of attribute

Triggers: Click on Save button in session profile page.

SUCCEED SET ATTR VALUES OF SESSION HA PROPERTIES

ID: CONSOLE-13078

Level: INFO

Description: Modification of session HA properties succeeded.

Data: name of attribute

Triggers: Click on Save button in session profile page.

SMS EXCEPTION SET ATTR VALUES OF SESSION HA PROPERTIES

ID: CONSOLE-13079

Level: SEVERE

Description: Modification of session HA properties failed.

Data: name of attribute, error message

Triggers: Unable to modify session HA properties due to service management

SDK exception.

Actions: Look under service management log for more information.

OpenAM logs the following CORETOKEN messages.

TOKEN_CREATE_SUCCESS

ID: CORETOKEN-1

Level: INFO

Description: Creating a token succeeded

Data: token type, token subject, token attribute names

Triggers: Create token

TOKEN READ SUCCESS

ID: CORETOKEN-2

Level: INFO

Description: Retrieving a token succeeded

Data: token type, token subject

Triggers: Read token

TOKEN_UPDATE_SUCCESS

ID: CORETOKEN-3

Level: INFO

Description: Updating a token succeeded

Data: names of attributes updated

Triggers: Update token

TOKEN SEARCH SUCCESS

ID: CORETOKEN-4

Level: INFO

Description: Searching tokens succeeded

Data: guery, number of entries returned

Triggers: Search token

TOKEN_DELETE_SUCCESS

ID: CORETOKEN-5

Level: INFO

Description: Removing a token succeeded

Triggers: Delete token

EXPIRED_TOKEN_DELETE_SUCCESS ID: CORETOKEN-6

Level: INFO

Description: Removing an expired token succeeded

Triggers: Token expired

UNABLE_TO_CREATE_TOKEN ID: CORETOKEN-7

Level: INFO

Description: Creating a token failed

Data: error message, token type, token subject, token attribute names

Triggers: Create token

UNABLE TO READ TOKEN ID: CORETOKEN-8

Level: INFO

Description: Retrieving a token failed

Data: error message

Triggers: Read token

UNABLE TO UPDATE TOKEN

ID: CORETOKEN-9

Level: INFO

Description: Updating a token failed

Data: error message

Triggers: Update token

UNABLE_TO_SEARCH_TOKEN ID: CORETOKEN-10

Level: INFO

Description: Searching tokens failed

Data: query, error message

Triggers: Search Token

UNABLE TO DELETE TOKEN

ID: CORETOKEN-11

Level: INFO

Description: Removing a token failed

Data: error message

Triggers: Delete token

OpenAM logs the following ENTITLEMENT messages.

ATTEMPT ADD PRIVILEGE

ID: ENTITLEMENT-1

Level: INFO

Description: Attempt to add privilege.

Data: realm, privilege name

Triggers: Add privilege API is called.

SUCCEEDED ADD PRIVILEGE

ID: ENTITLEMENT-2

Level: INFO

Description: Privilege is added.

Data: realm, privilege name

Triggers: Add privilege API is called.

FAILED ADD PRIVILEGE

ID: ENTITLEMENT-3

Level: INFO

Description: Failed to add privilege.

Data: realm, privilege name, error message

Triggers: Add privilege API is called.

Actions: Privilege might already exists.; Administrator might not have the

permission to add privilege.

ATTEMPT ADD REFERRAL

ID: ENTITLEMENT-11

Level: INFO

Description: Attempt to add referral privilege.

Data: realm, privilege name

Triggers: Add referral privilege API is called.

SUCCEEDED ADD REFERRAL

ID: ENTITLEMENT-12

Level: INFO

Description: Referral Privilege is added.

Data: realm, privilege name

Triggers: Add referral privilege API is called.

FAILED_ADD_REFERRAL ID: ENTITLEMENT-13

Level: INFO

Description: Failed to add referral privilege.

Data: realm, privilege name, error message

Triggers: Add referral privilege API is called.

Actions: Privilege might already exists.; Administrator might not have the

permission to add referral privilege.

ATTEMPT REMOVE PRIVILEGE

ID: ENTITLEMENT-21

Level: INFO

Description: Attempt to remove privilege.

Data: realm, privilege name

Triggers: Remove privilege API is called.

SUCCEEDED REMOVE PRIVILEGE

ID: ENTITLEMENT-22

Level: INFO

Description: Privilege is removed.

Data: realm, privilege name

Triggers: Removed privilege API is called.

FAILED REMOVE PRIVILEGE

ID: ENTITLEMENT-23

Level: INFO

Description: Failed to removed privilege.

Data: realm, privilege name, error message

Triggers: Removed privilege API is called.

Actions: Administrator might not have the permission to remove privilege.

$ATTEMPT_REMOVE_REFERRAL$

ID: ENTITLEMENT-31

Level: INFO

Description: Attempt to remove referral privilege.

Data: realm, privilege name

Triggers: Remove referral privilege API is called.

SUCCEEDED REMOVE REFERRAL

ID: ENTITLEMENT-32

Level: INFO

Description: Referral privilege is removed.

Data: realm, privilege name

Triggers: Removed referral privilege API is called.

$FAILED_REMOVE_REFERRAL$

ID: ENTITLEMENT-33

Level: INFO

Description: Failed to removed referral privilege.

Data: realm, privilege name, error message

Triggers: Removed referral privilege API is called.

Actions: Administrator might not have the permission to remove privilege.

ATTEMPT_SAVE_APPLICATION

ID: ENTITLEMENT-101

Level: INFO

Description: Attempt to save application.

Data: realm, application name

Triggers: Save application API is called.

SUCCEEDED SAVE APPLICATION

ID: ENTITLEMENT-102

Level: INFO

Description: Application is saved.

Data: realm, application name

Triggers: Save application API is called.

$FAILED_SAVE_APPLICATION$

ID: ENTITLEMENT-103

Level: INFO

Description: Failed to save application.

Data: realm, application name, error message

Triggers: Save application API is called.

Actions: Administrator might not have the permission to save application.

ATTEMPT_REMOVE_APPLICATION

ID: ENTITLEMENT-111

Level: INFO

Description: Attempt to remove application.

Data: realm, application name

Triggers: Remove application API is called.

SUCCEEDED REMOVE APPLICATION

ID: ENTITLEMENT-112

Level: INFO

Description: Application is removed.

Data: realm, application name

Triggers: Remove application API is called.

FAILED REMOVE APPLICATION

ID: ENTITLEMENT-113

Level: INFO

Description: Failed to remove application.

Data: realm, application name, error message

Triggers: Remove application API is called.

Actions: Administrator might not have the permission to remove application.

OpenAM logs the following LOG messages.

LOG START NEW LOGGER

ID: LOG-1

Level: INFO

Description: Logging Started - New Logger

Data: current location

Triggers: Logging started by getting a new Logger.

LOG END

ID: LOG-2

Level: INFO

Description: Logging Terminated - Server Stopped

Data: current location

Triggers: Logging terminated by server shutdown.

LOG START CONFIG

ID: LOG-3

Level: INFO

Description: Logging Started - Configuration Change

Data: old location, new location, old backend, new backend, old security status, new security status, old status, new status, old level, new level

Triggers: Logging started after logging configuration change.

LOG END CONFIG

ID: LOG-4

Level: INFO

Description: Logging Terminated - Configuration Change

Data: old location, new location, old backend, new backend, old security status, new security status, old status, new status, old level, new level

Triggers: Logging terminated by logging configuration change.

OpenAM logs the following OAuth2Provider messages.

CREATED TOKEN

ID: OAuth2Provider-1

Level: INFO

Description: Created an oauth 2.0 token

Data: message, token info

Triggers: Creating a new oauth 2.0 token

DELETED TOKEN

ID: OAuth2Provider-2

Level: INFO

Description: Deleted an oauth 2.0 token

Data: message, token info

Triggers: Deleteing an oauth 2.0 token

FAILED_CREATE_TOKEN

ID: OAuth2Provider-3

Level: INFO

Description: Failed to creating an oauth 2.0 token

Triggers: Failed creating an oauth 2.0 token

FAILED_DELETE_TOKEN ID: OAuth2Provider-4

Level: INFO

Description: Failed deleting an oauth 2.0 token

Triggers: Failed deleting an oauth 2.0 token

CREATED CLIENT

ID: OAuth2Provider-11

Level: INFO

Description: Created an oauth 2.0 Client

Data: message, token info

Triggers: Creating a new oauth 2.0 client

DELETED CLIENT

ID: OAuth2Provider-12

Level: INFO

Description: Deleted an oauth 2.0 client

Data: message, token info

Triggers: Deleteing an oauth 2.0 client

FAILED CREATE CLIENT

ID: OAuth2Provider-13

Level: INFO

Description: Failed to creating an oauth 2.0 client

Triggers: Failed creating an oauth 2.0 client

FAILED_DELETE_CLIENT

ID: OAuth2Provider-14

Level: INFO

Description: Failed deleting an oauth 2.0 client

Triggers: Failed deleting an oauth 2.0 client

AUTHENTICATED_CLIENT

ID: OAuth2Provider-15

Level: INFO

Description: Authenticated an oauth 2.0 client

Data: message, client id

Triggers: Authenticating a oauth 2.0 client

FAILED AUTHENTICATE CLIENT

ID: OAuth2Provider-16

Level: INFO

Description: Failed authenticating an oauth 2.0 client

Triggers: Failed authenticating an oauth 2.0 client

OpenAM logs the following POLICY messages.

POLICY EVALUATION

ID: POLICY-1

Level: INFO

Description: Evaluating policy succeeded

Data: policy name, realm name, service type name, resource name, action

names, policy decision

Triggers: Evaluating policy.

PROTECTED RESOURCES

ID: POLICY-2

Level: INFO

Description: Getting protected policy resources succeeded

Data: principal name, resource name, protecting policies

Triggers: Getting protected policy resources.

POLICY_CREATE_SUCCESS ID: POLICY-3

Level: INFO

Description: Creating policy in a realm succeeded

Data: policy name, realm name

Triggers: Creating policy in a realm.

POLICY MODIFY SUCCESS

ID: POLICY-4

Level: INFO

Description: Modifying policy in a realm succeeded

Data: policy name, realm name

Triggers: Modifying policy in a realm.

POLICY REMOVE SUCCESS

ID: POLICY-5

Level: INFO

Description: Removing policy from a realm succeeded

Data: policy name, realm name

Triggers: Removing policy from a realm.

POLICY_ALREADY_EXISTS_IN_REALM

ID: POLICY-6

Level: INFO

Description: Policy already exists in the realm

Data: policy name, realm name

Triggers: Creating policy in the realm.

UNABLE TO ADD POLICY

ID: POLICY-7

Level: INFO

Description: Creating policy in a realm failed

Data: policy name, realm name

Triggers: Creating policy in a realm.

Actions: Check if the user has privilege to create a policy in the realm.

UNABLE_TO_REPLACE POLICY

ID: POLICY-8

Level: INFO

Description: Replacing policy in a realm failed

Data: policy name, realm name

Triggers: Replacing policy in a realm.

Actions: Check if the user has privilege to replace a policy in the realm.

DID NOT REPLACE POLICY

ĪD: POLICY-81

Level: INFO

Description: Did not replace policy - A diifferent policy with the new name

already exists in the realm

Data: new policy name, realm name

Log Messages

Triggers: Replacing policy in a realm

UNABLE TO REMOVE POLICY

ID: POLICY-9

Level: INFO

Description: Removing policy from a realm failed

Data: policy name, realm name

Triggers: Removing policy from a realm.

Actions: Check if the user has privilege to remove a policy from the realm.

PROXIED POLICY EVALUATION

ID: POLICY-10

Level: INFO

Description: Computing policy decision by an administrator succeeded

Data: admin name, principal name, resource name, policy decision

Triggers: Computing policy decision by an administrator.

PROXIED POLICY EVALUATION IGNORING SUBJECTS

ID: POLICY-11

Level: INFO

Description: Computing policy decision by an administrator ignoring subjects

succeeded

Data: admin name, resource name, policy decision

Triggers: Computing policy decision by an administrator ignoring subjects.

OpenAM logs the following SESSION messages.

SESSION CREATED

ID: SESSION-1

Level: INFO

Description: Session is Created

Data: User ID

Triggers: User is authenticated.

SESSION_IDLE_TIMED_OUT ID: SESSION-2

Level: INFO

Description: Session has idle timedout

Data: User ID

Triggers: User session idle for long time.

SESSION MAX TIMEOUT

ID: SESSION-3

Level: INFO

Description: Session has Expired

Data: User ID

Triggers: User session has reached its maximun time limit.

SESSION LOGOUT

ID: SESSION-4

Level: INFO

Description: User has Logged out

Data: User ID

Triggers: User has logged out of the system.

SESSION REACTIVATION

ID: SESSION-5

Level: INFO

Description: Session is Reactivated

Data: User ID

Triggers: User session state is active.

SESSION DESTROYED

ID: SESSION-6

Level: INFO

Description: Session is Destroyed

Data: User ID

Triggers: User session is destroyed and cannot be referenced.

SESSION PROPERTY CHANGED

ID: SESSION-7

Level: INFO

Description: Session's property is changed.

Data: User ID

Triggers: User changed session's unprotected property.

SESSION_UNKNOWN EVENT

ID: SESSION-8

Level: INFO

Description: Session received Unknown Event

Data: User ID

Triggers: Unknown session event

SESSION PROTECTED PROPERTY ERROR

ID: SESSION-9

Level: INFO

Description: Attempt to set protected property

Data: User ID

Triggers: Attempt to set protected property

SESSION QUOTA EXHAUSTED

ID: SESSION-10

Level: INFO

Description: User's session quota has been exhausted.

Data: User ID

Triggers: Session quota exhausted

SESSION DATABASE UNAVAILABLE

ID: SESSION-11

Level: INFO

Description: Session database used for session failover and session constraint is not available.

Data: User ID

Triggers: Unable to reach the session database.

SESSION DATABASE BACK ONLINE

ID: SESSION-12

Level: INFO

Description: Session database is back online.

Data: User ID

Triggers: Session database is back online..

SESSION_MAX_LIMIT_REACHED

ID: SESSION-13

Level: INFO

Description: The total number of valid sessions hosted on the AM server has

reached the max limit.

Data: User ID

Triggers: Session max limit reached.

Chapter 3 Error Messages

This chapter lists common error messages from OpenAM, with remedial actions where possible.

Common Authentication Errors

An error occurred while storing the user profile.

When using the Membership module, the attributes and elements likely do not match the self-registration settings in the Membership.xml file.

Action: Enter a unique user name.

A user already exists with this name in the given organization.

When using the Membership module, you cannot create a new user with the same user name as an existing user.

Action: Enter a unique user name.

Authentication Exception

The authentication was not handled properly.

Action: Check the login URL for invalid characters, especially in the query string parameters.

Authentication Failed

Usually this occurs when the user provides incorrect credentials.

Action: If the credentials are valid and correct, check that you are using the correct authentication module.

Cannot redirect to default page

OpenAM cannot redirect to the Success URL or the Failure URL.

Action: Check the web application container logs where OpenAM is running.

Invalid Password

The password is not valid.

Action: If you have not incorrectly typed the password, check that the password has at least 8 characters, and has not expired.

Logout Failure

The user cannot log out.

Action: Restart OpenAM.

Maximum Session Limit was reached

Action: Logout and login again.

Missing the confirmation password field.

When using the Membership module to create a user account, you must confirm the password value.

Action: Enter a the password again.

No password was entered

When using the Membership module to create a user account, you must enter a password.

Action: Enter a password.

No user name was entered

When using the Membership module to create a user account, you must enter a user name.

Action: Enter a user name.

No user profile was found matching the entered user name in the given organization.

When using the Membership module, no profile exists for the user.

Action: Select New User from the login screen.

No configuration found

Action: Check the configuration for the authentication module or chain for the realm.

No organization found

Action: Check that the requested realm exists.

One of the required fields was not completed.

Action: Check for missing required fields.

Specified authentication module is denied.

Action: Check that the authentication module is registered in the realm, that templates are in place for the module, and that the module is selected in the Core Authentication module list.

This organization is not active

The requested realm is set to Inactive.

Action: Change the status in OpenAM Console.

The password and the confirm password do not match.

Error shown when using the Membership module.

Action: Type the password values again.

The password entered does not contain enough characters.

When using the Membership module, the password provided has fewer than 8 characters.

Action: Enter a longer password.

The User Name and Password fields cannot have the same value.

When using the Membership module, you cannot create a user with identical user name and password values.

Action: Use a different user name or password.

User has no profile in the specified organization.

Action: Check that the user exists in the subjects for the realm.

User is not active

Action: Change the user status from inactive to active in OpenAM console.

User session has timed out.

Action: Log in again.

You are already logged in

No Success URL redirect is defined for the user.

Action: Set up an appropriate Success URL redirect, or use the goto parameter in the login URL guery string.

Common Console Errors

Could not create identity object. User does not have sufficient access. Permissions prevented the operation.

Action: Perform the operation as a user with sufficient access, or have an administrator grant you sufficient access.

Invalid user's start location. Please contact your administrator.

The Administrator DN is no longer valid.

Action: Edit the User service to use the proper value for the Administrator DN.

Size limit exceeded.

Your search returned more entries that the data store allows.

Action: Refine your search, or increase Maximum Results Returned from a Search in the Administration service.

Time limit exceeded.

Your search took more time to search the data store than was allowed.

Action: Refine your search, or increase Timeout for Search in the Administration Service.

There are no attributes to display.

No user-editable attributes are defined for the selected object.

There are no entities.

What you are searching for did not match anything in the data store.

Action: Refine your search.

Unable to get attribute from data store.

Occurs when a profile has been modified concurrently by another user.

Action: Refresh the display.

Chapter 4 Ports Used

OpenAM software uses the following TCP/IP ports by default. Sometimes multiple services are configured on a single system with slightly different port numbers. For example, while the default port number for a servlet container such as Tomcat is 8080, a second instance of Tomcat might be configured with a port number of 18080. In all cases shown, communications proceed using TCP.

When you configure a firewall for OpenAM, make sure to include open ports for any installed and related components, including web services (80, 443), servlet containers (8009, 8080, 8443), and external applications such as a Remote Access Dial In User Service (1645).

Additional ports may be used, depending on other components of your deployment. If you are using external OpenDJ servers, refer to the *Ports Used* appendix of the OpenDJ Administration Guide.

Table 4.1. Default TCP/IP Ports Used by OpenAM

Port Number	Description
1689	Port for Java Management eXtension traffic, disabled by default
4444	Port for the embedded administration connector, enabled by default.
8080	Web application container port number

Port Number	Description
8082	HTTP port for monitoring OpenAM, disabled by default
8085	SNMP port for monitoring OpenAM, disabled by default
9999	RMI port for monitoring OpenAM, disabled by default.
50389, 50899, 58989	Supports LDAP communication between embedded OpenAM data stores.
57943, 58943	Used by the SecurID Authentication Module.

Chapter 5 Localization

This chapter lists languages and locales supported for OpenAM.

OpenAM console and end user pages are localized for the following languages.

- English
- French
- German
- Japanese
- Korean
- Simplified Chinese
- Spanish
- Traditional Chinese

OpenAM supports the following locales.

Afrikaans

Code tag: af

Albanian

Code tag: sq

Basque

Code tag: eu

Byelorussian

Code tag: be

Bulgarian

Code tag: bg

Catalan

Code tag: ca

Chinese

Code tag: zh

Croatian

Code tag: hr

Czech

Code tag: cs

Danish

Code tag: da

Dutch

Code tag: nl

English

Code tag: en

Faroese

Code tag: fo

Finnish

Code tag: fi

French

Code tag: fr

Galician

Code tag: gl

German

Code tag: de

Greek

Code tag: el

Hungarian

Čode tag: hu

Icelandic

Code tag: is

Indonesian

Code tag: id

Irish

Code tag: ga

Italian

Code tag: it

Japanese

Code tag: ja

Korean

Code tag: ko

Norwegian

Code tag: no

Polish

Code tag: pl

Portuguese

Code tag: pt

Romanian

Code tag: ro

Russian

Code tag: ru

Serbian

Code tag: sr

Slovakian

Code tag: sk

Slovenian

Code tag: sl

Spanish

Code tag: es

Swedish

Code tag: sv

Turkish

Code tag: tr

Ukrainian Code tag: uk

Chapter 6 Supported Standards

OpenAM implements the following RFCs, Internet-Drafts, and standards.

OAuth 2.0

The OAuth 2.0 Authorization Framework, in which OpenAM can play the roles of authorization server and of client.

The OAuth 2.0 Authorization Framework: Bearer Token Usage, in which OpenAM plays the role of authorization server.

Assertion Framework for OAuth 2.0, which is an Internet-Draft.

SAML 2.0 Bearer Assertion Profiles for OAuth 2.0, which is an Internet-Draft.

JSON Web Token (JWT) Profile for OAuth 2.0 Client Authentication and Authorization Grants, which is an Internet-Draft.

OpenID Connect 1.0

OpenAM plays the role of OpenID provider. The OpenID Connect specifications also depend on OAuth 2.0, JSON Web Token, and Simple Web Discovery and related specifications. The following descriptions are from the OpenID Connect 1.0 web site.

Basic Client Profile. Lightweight simple self-contained specification for a web-based Relying Party using the OAuth code flow.

Implicit Client Profile. Lightweight simple self-contained specification for a web-based Relying Party using the OAuth implicit flow.

Discovery. Defines how user and provider endpoints are dynamically discovered.

Dynamic Registration. Defines how clients dynamically register with OpenID Providers.

Standard. Full HTTP binding specification, for both clients and OpenID Providers; references Messages.

Messages. Lists all the messages that are used in OpenID Connect. You can use this to create additional bindings for Connect, such as an OpenID Connect binding for XMPP.

Session Management. Defines how to manage OpenID Connect sessions.

OAuth 2.0 Multiple Response Types. Registration document for several specific new response types, in accordance with the stipulations of the OAuth Parameters Registry.

Representational State Transfer (REST)

Style of software architecture for web-based, distributed systems.

Security Assertion Markup Language (SAML)

Standard, XML-based framework for creating and exchanging security information between online partners. OpenAM supports multiple versions of SAML including 2.0.

Liberty Alliance Project Identity Federation Framework (Liberty ID-FF)

Federation standard, whose concepts and capabilities contributed to SAML 2.0.

Simple Object Access Protocol

Lightweight protocol intended for exchanging structured information in a decentralized, distributed environment.

Web Services Description Language (WSDL)

XML format for describing network services as a set of endpoints operating on messages containing either document-oriented or procedure-oriented information.

Web Services Federation Language (WS-Federation)

Identity federation standard, part of the Web Services Security framework.

eXtensible Access Control Markup Language (XACML)

Chapter 7 Service Endpoints

A service endpoint is a URL which serves as the access port for a web service. It may be a standard HTML-based web page, or it may be a *.jsp page.

As every service endpoint is a potential security issue, it may be appropriate to restrict access to some of those endpoints that you do not use. But be careful. Some endpoints, such as isAlive.jsp in the main /path/to/tomcat/webapps/openam directory, are essential and should not be blocked or changed.

Given the large number of available endpoints, this chapter has been organized primarily by subdirectory. Most of the directories were created when the OpenAM war archive was copied to the appropriate web application container, such as the webapps/ subdirectory.

OpenAM may expose several hundred service endpoints, listed in this chapter. Each endpoint shown is listed relative to the deployment URL. For example, if you have deployed OpenAM at https://openam.example.com:8443/openam/, the full URL to the isAlive.jsp endpoint is https://openam.example.com:8443/openam/isAlive.jsp.

OpenAM includes two types of endpoints. One is based on URL patterns, shown with the url-pattern tag. You can find these patterns in the web.xml file, in the / path/to/tomcat/webapps/openam/WEB-INF directory. The other type is based on *.jsp pages, starting in the main /path/to/tomcat/webapps/openam directory, and also in many associated subdirectories. If you copied or created a WAR archive to a name other than openam.war, as described in the installation guide, substitute for the second openam accordingly.

Some of these endpoints can be applied directly to a URL when you've connected to the OpenAM server; for example, if you've configured OpenAM on http://idp.example.com:8080/openam, you can log in and review debug options by navigating to http://idp.example.com:8080/openam/Debug.jsp

Other endpoints can only be used when called by some option in the OpenAM console. For example, while the AgentAdd.jsp endpoint exists in the console/ agentconfig subdirectory, you would get an error by navigating directly to a URL such as http://sp.example.com:8080/openam/console/agentconfig/AgentAdd.jsp. For that particular endpoint, you'll have click through the options required to add an agent. (Access Control > realm name > Agents > Agent > New)

In general, this chapter does not include dynamic endpoints, such as those that may include security tokens. The endpoints described in this chapter are based on files included in the installation of an OpenAM server.

There have been two security advisories related to OpenAM endpoints: OpenAM Security Advisory #201203 and OpenAM Security Advisory #201204

Several options are available for endpoints at risk. Recommendations from the noted security advisories include the following:

- Filter requests to prevent or restrict access to vulnerable endpoints with a reverse proxy or equivalent hardware device. Such options can be configured to limit access by IP address or fully-qualified domain name.
- Use a patch. If available, download links should be listed in the security advisory. The patch may be limited to one or more endpoint files.
- Remove access from the configuration. If a problematic endpoint is configured in the web.xml file of the aforementioned WEB-INF subdirectory, you can remove the section that points to that endpoint.
- Remove the endpoint file from the configuration. Some endpoint files, such as proxy.jsp or ssoadm.jsp, are not essential to the basic operation of OpenAM.

Of course, you can take additional steps to help secure your OpenAM deployment. For more information, see the the chapter on *Securing OpenAM in the Administration Guide*.

7.1 JSP Endpoints

The OpenAM WAR archive includes *.jsp files in a number of different categories. Many are associated with the applicable subdirectory, such as console/realm. The following sections will examine each *.jsp file, divided by subdirectories.

In some highlighted cases, the noted *.jsp file appears in the code for one or more .java files. If you remove the noted *.jsp file from the container, there is a

risk that will break some functionality within OpenAM. In other cases, such as any files related to the GUI installation wizard, the applicable *.jsp file can be safely removed from a production system.

7.2 Main Directory JSP Endpoints

If you're working in Tomcat, you'll find the endpoints in this subsection in the / path/to/tomcat/webapps/openam directory. For other web application containers, you may find the endpoints in a different openam subdirectory.

Debug.jsp

Supports debug logging by service. For more information, see the *Administration Guide* chapter on *Debug Logging by Service*.

encode.jsp

Enables access to a page that encodes text passwords. The algorithm is based on PBEWithMD5AndDES, password-based encryption (PBE) using the MD5 message-digest algorithm, configured with the data encryption standard (DES)

getServerInfo.jsp

Supports requests for server information. As getServerInfo.jsp is encoded in some .java files, you should retain getServerInfo.jsp in your deployment.

isAlive.isp

Verifies the current status of the OpenAM service; the "Server is ALIVE:" message also verifies activity on OpenAM systems behind load balancers. This can be a useful tool in a production environment.

nowritewarning.jsp

Displays a permission error message, used by the GUI-based installation wizard.

proxyidpfinder.jsp

Supports access to a remote identity provider, through the federation broker.

services.jsp

Lists active services within OpenAM. The details shown on this page can be used with the ssoadm command to create a second OpenAM server with matching services. Be aware, the amadmin administrative user is hard-coded into this file. If you change the identity of the administrative user to something other than amadmin, that user won't have access to services.jsp.

showServerConfig.jsp

Specifies configuration information for the system, including the URL, the OS, the Java VM, the configuration directory, and more.

ssoadm.jsp

Supports GUI-based access to the options associated with the ssoadm command. The ssoadm.jsp file is disabled by default. Instructions for enabling this feature are available from the *Administration Guide* entry on *OpenAM ssoadm.jsp*.

validateWait.jsp

May be called by the validator.jsp or validatorMain.jsp files, to display progress in verifying the status of federation.

validator.jsp

Refers to the ValidateSAML2 function to identify the realm, IdP and SP for the federation.

validatorAuthFail.jsp

Starts an "Authentication Failed" message.

validatorFooter.jsp

Incorporates a "Back to Login" button in validatorMain.jsp.

validatorMain.jsp

Sets up a federation connectivity test. If you've set up a Federation Circle of Trust, this file is accessible from the "Test Federation Connectivity" option in the main OpenAM console.

validatorRpt.jsp

Opens a "Connectivity Test Results" window, specifying the status of a federation circle of trust. Tests relate to IdP authentication, SP authentication, account linking, single log out, single sign on, and account unlinking.

validatorStatus.jsp

Adds information to validator.jsp and validatorMain.jsp with federation status information as it relates to the currently configured circle of trust.

All of the validat*.jsp files near the end of this list relate to testing and verifying federation. It requires at least one identity provider (IDP) and one service provider (SP). At least one of these components must be configured remotely to set up a valid Circle of Trust (COT). If federation does not apply to your configuration, the validat*.jsp files are not essential to your configuration.

7.3 User Interface JSP Endpoints

The endpoints in this section can be found in several com_sun_web_ui/jsp/subdirectories. These endpoints appear to relate to JavaHelp; per OPENAM-806, this functionality was removed from OpenAM, starting with version 9.5.3. Thus, the endpoints in this section, with one possible exception (Masthead.jsp in the com_sun_web_ui/jsp/version subdirectory) may no longer serve any purpose.

DateTimeWindow.jsp

The only endopint in the com_sun_web_ui/jsp/datetime subdirectory. May be a legacy endpoint; it calls a DateTimeWindowViewBean class; the corresponding .java file does not exist in the current trunk.

Help.jsp

One of two endpoints in the com_sun_web_ui/jsp/help subdirectory. May be a legacy endpoint; it calls a HelpViewBean class; the corresponding .java file does not exist in the current trunk.

Masthead.isp

One of two endpoints in the com_sun_web_ui/jsp/help subdirectory. Also exists in a slightly different format in the com_sun_web_ui/jsp/help2 subdirectory, as well as the com_sun_web_ui/jsp/version subdirectory. May be a legacy endpoint; it calls a MastheadViewBean class; the Masthead.jsp file and the corresponding MastheadViewBean.java were last changed in 2004. (However, the Masthead.jsp file in the com_sun_web_ui/jsp/version subdirectory includes a VersionViewBean.java file that is used by the Version.jsp endpoint used in the console/base subdirectory.

ButtonNav.jsp

Specifies an endpoint in the com_sun_web_ui/jsp/help2 directory. Points to a ButtonNavViewBean class; the associated .java file no longer exists in the trunk.

Help2Ie.isp

Specifies an endpoint in the com_sun_web_ui/jsp/help2 directory. Points to a Help2ViewBean class; the associated .java file no longer exists in the trunk.

Help2Nav4.jsp

Specifies an endpoint in the com_sun_web_ui/jsp/help2 directory. Points to a Help2ViewBean class; the associated .java file no longer exists in the trunk.

Help2Nav6up.isp

Specifies an endpoint in the com_sun_web_ui/jsp/help2 directory. Points to a Help2ViewBean class; the associated .java file no longer exists in the trunk.

Navigator.jsp

Specifies an endpoint in the com_sun_web_ui/jsp/help2 directory. Points to a NavigatorViewBean class; the associated .java file no longer exists in the trunk.

AdvancedSort.jsp

Specifies an endpoint in the com sun web ui/jsp/table directory.

Table.jsp

Specifies an endpoint in the com_sun_web_ui/jsp/table directory. Points to a TableViewBean class; the associated .java file no longer exists in the trunk..

Default Authentication JSP Endpoints

WizardWindow.jsp

Points to an endpoint in the com_sun_web_ui/jsp/wizard subdirectory. Points to a WizardWindowViewBean class, which appears to be unused by any other .jsp file.

7.4 Default Authentication JSP Endpoints

Many of the .jsp files in this category can be modified to help you modify the messages that appear to users in the OpenAM console. Standard messages for most of these endpoints can be found in the amAuth.properties and amAuthUI.properties files. You'll find the endpoints in this subsection in the config/auth/default subdirectory.

account expired.jsp

Specifies an error page for account expiration. The message displayed to the user can be modified in the amAuthUI.properties file.

authException.jsp

Option to Exception.jsp; called if there is an existing resource bundle, as specified in AuthExceptionViewBean.java.

auth_error_template.jsp

Specifies an error page for authentication errors. The message displayed to the user can be modified in the amAuthUI.properties file.

disclaimer.jsp

Associated with the self-registration module, which can be configured in the OpenAM Console, under Access Control > Realm Name > Authentication > Module Instances. The default disclaimer is associated with the disclaimer.notice parameter, defined in the amAuthUI.properties file.

disclaimerDeclined.jsp

Associated with the self-registration module, which can be configured in the OpenAM Console, under Access Control > Realm Name > Authentication > Module Instances. The default disclaimer_denied message is associated with the disclaimer.declined parameter, defined in the amAuthUI.properties file.

Exception.jsp

Includes the following error message: "Authentication Service is not initialized." Cited by several other .java files in the code, so it should not be removed in a secure deployment..

invalidAuthlevel.jsp

Used to specify an issue with the authentication level. The default invalidanthlevel and contactadmin messages can be redefined in the amAuthUI.properties file.

Default Authentication JSP Endpoints

invalidPCookieUserID.jsp

Notes a problem with a specified user name for a cookie, which presumably does not exist in the relevant domain. The default cookie.notpersistent and contactadmin messages can be modified in the amAuthUI.properties file.

invalid domain.jsp

Displays a "No such Organization found" message when a domain is not defined in the OpenAM database. Refers to the nosuch.domain parameter in the amAuthUI.properties file.

login denied.jsp

Defines the response of OpenAM to a user who enters an undefined profile. Uses the userhasnosuchprofile.org and contactadmin parameters in the amAuthUI.properties file.

login failed template.jsp

Provides a message in the event of a login failure. The message uses the auth.failed parameter in the amAuthUI.properties file.

Login.jsp

Specifies a regular authentication template. As noted in the *Administration Guide* entry on *Securing OpenAM Administration*, the Login.jsp file may be customized for different deployments.

Logout.jsp

The Logout.jsp file may also be customized for different deployments.

maxSessions.jsp

Specifies the message given to users when the number of sessions has hit the preconfigured limit. The default is 5000, defined in the OpenAM console under Configuration > Servers and Sites > Default Server Settings > Session. The message uses the session.max.limit parameter defined in the amAuthUI.properties file.

membership.jsp

Specifies information for the page associated with the self-registration module.

Message.jsp

Calls text messages related to the authentication process.

module denied.jsp

Includes a message to a target user that he does not have access to a specified module. The message uses the authmodule.denied parameter defined in the amAuthUI.properties file..

module template.jsp

Adds a page which can be used to help customize appropriate modules.

Default Authentication JSP Endpoints

new_org.jsp

Includes a warning when a user is trying to access a different realm. The message uses the newOrg.agree parameter, as defined in the amAuthUI.properties file.

noConfig.jsp

Specifies the lack of a defined configuration module. The message uses the noconfig.found parameter, defined in the amAuthUI.properties file.

OAuthActivate.jsp

Shows a default template for entering an activation code. Used by OAuth.xml for password changes. As this file is not configured for OAuth2, the file is deprecated and may be removed from a future release.

OAuthPwd.isp

Displays a password change screen, with an option for terms and conditions of service. As this file is not configured for OAuth2, it is deprecated and may be removed from a future release.

org inactive.jsp

Transmits the message that the target organization is not active in the OpenAM database.

profileError.jsp

Specifies the message that is sent when there's a failure in the use of the self-registration module. Associated with the profile.error parameter, defined in the amAuthUI.properties file.

Redirect.jsp

Notes a file used by other code to redirect users for events such as login failures.

register.jsp

Identifies the page with the self-registration template.

session timeout.jsp

Adds a message to a user when a session has gone past its allocated login time. Uses the session.timeout parameter, defined in the amAuthUI.properties file.

userDenied.jsp

Associated with role-based authentication. Tells a user when the required role has not been configured for that user. Message defined by the user.not.inrole parameter, defined in the amAuthUI.prooperties file.

user inactive.jsp

Identifies a message sent to a user that is not currently active in the database. Message defined by the usernot active parameter, as shown in the amAuthUI.properties file.

7.5 Default Federation JSP Endpoints

Many of the files in this config/federation/default subdirectory use the com.sun.liberty.LibertyManager interface. In general, you'll want to keep these files in a production deployment, to support adding to and deleting users from different Circles Of Trust (COT). Many of these files are customizable for different organizational interfaces. Interfaces in different languages may be configured in slightly different subdirectories such as config/federation/default fr.

cdclogin.jsp

Supports a non-blank page for cross-domain single sign-ons; associated with a Cross-Domain Controller (CDC) servlet.

CommonLogin.jsp

Supports links to login pages of trusted identity providers.

Error.jsp

Sets up an error message, using the com.sun.liberty.LibertyManager interface.

Federate.isp

Supports a connection to providers that can be configured in a federation.

FederationDone.jsp

Specifies the status of a federation request; the default response is either "The user has cancelled account federation." or "Federation has been successfully completed with the remote provider.

Footer.isp

Sets up code that you can use to include a custom footer on all pages.

Header.jsp

Sets up code that you can use to include a custom header on all pages; the default version is configured with the OpenAM logo.

ListOfCOTs.jsp

When a service provider (SP) belongs to more than one COT, this page prompts the user to select a preferred identity provider (IDP).

LogoutDone.jsp

Specifies success or failure during a logout operation. Where a user has an account on multiple providers, he may see the following message: "Unable to log the user out from one or more providers where the user may still have active sessions."

NameRegistration.isp

Supports registration with a new remote provider; this endpoint is associated with NameRegistrationDone.jsp.

Console Agent Configuration JSP Endpoints

NameRegistrationDone.jsp

Displays different messages based on a registration attempt with a remote provider. The message varies depending on whether the request was successful, a failure, or cancelled.

Termination.jsp

Supports defederation from an existing remote provider; goes with TerminationDone,jsp.

TerminationDone.jsp

Displays different messages based on a defederation attempt with a remote provider. The message varies depending on whether the request was successful, a failure, or cancelled.

7.6 Console Agent Configuration JSP Endpoints

The JSP files in the console/agentconfig subdirectory relate to the configuration of Web Agents. To see what is done by each JSP file, log into the console as the administrator. Select Access Control > [Some Realm] > Agents. Several of the options that appear corresponds to the JSP files in the target subdirectory.

Some of the endpoints include messages from relevant sections of the amConsole.properties file. The agents in this directory are part of the com.sun.identity.console.agentconfig package.

Several endpoints relate to Web Service Client (WSC) policy agents, which secure outgoing requests and validate incoming requests from Web Service Providers (WSP). For more information, see the chapter on *Configuring Policy Agent Profiles* in the Administrative Guide.

If you are not using agent functionality such as that related to the Security Token Service (STS), the related endpoints listed in this section may not be essential in a production deployment.

AgentAdd.isp

Includes a newly created web agent for a specified realm. The AgentAdd page appears in the OpenAM console after an agent is added to a realm.

AgentConfigInherit.jsp

Allows an administrator to review default settings for the agent, as configured in the Inheritance Settings page. Inheritance assumes that agent is part of a previously confiugred group. To access Inheritance Settings, refer to the *Creating Agent Profiles*" section of the Administration Guide.

AgentDump.jsp

Displays information about the current configuration of an agent or an agent group, and how it might be exported.

AgentExportPolicy.jsp

Shows how the information about an agent may be exported.

AgentGroup.jsp

Includes a newly created agent group for common web agents within a specified realm. The AgentGroup page appears in the OpenAM console after an agent is added to a realm.

AgentGroupMembers.jsp

Supports the display of agents that are members of a specified agent group.

Agents.jsp

Enables access to a form to specify a new agent to add. The same form is used for every category of new agents configured from the OpenAM console, when you navigate to Access Control -> [Realm name] -> Agents.

Home.isp

Per comments in the HomeViewBean, this file should forward requests for other agents.

WebServiceClientEdit.jsp

Includes customizable options for web service clients. Accessible when you edit and then save or export the configuration for a specific web service client.

WebServiceProviderEdit.jsp

Includes customizable options for web service providers. Accessible when you edit and then save or export the configuration for a specific web service provider.

WebServiceSTSEdit.jsp

Includes customizable options for web service STS providers. Accessible when you edit and then save or export the configuration for a specific web service STS provider.

WebServiceUserCredAdd.jsp

Supports the configuration of an WSP agent username and password.

WebServiceUserCredEdit.jsp

Supports changes to an WSP agent username and password.

7.7 Console Ajax JSP Endpoints

The only JSP file that appears to be active in this subdirectory is AjaxProxy.jsp, which appears to be used by several other endpoints.

AjaxProxy.jsp

Specifies an element used by several other endpoints, including ConfigureGoogleApps.jsp and ConfigureSalesForceApps.jsp.

Console Authentication JSP Endpoints

FileUpload.jsp

Used by the FileUploader.jsp endpoint, described in the section on Federation Console JSP Endpoints.

7.8 Console Authentication JSP Endpoints

You can find console authentication endpoints in the console/authentication subdirectory. The associated endpoints relate to authentication settings in a realm. To access these endpoints, navigate to Access Control > [some realm] > Authentication.

AuthConfig.jsp

Part of the creation of a New Authentication Chain; associated with the Authentication Chaining section of the Authentication tab for a realm.

AuthProperties.jsp

Specifies properties that might be configured under the authentication tab for a specific or top-level realm.

CoreAttributes.jsp

Associated with the Core section of the Authentication tab of a specific or the top-level realm. Includes options for Realm Attributes, Persistent Cookies, Account Lockout, and Post-Authentication Processing.

EditAuthType.jsp

Supports changes to Module Instances, under the Authentication tab of a specific or the top-level realm.

NewAuthConfig.jsp

Associated with the creation of a New Authentication Chain, an option available from the Authentication Chaining section of the Authentication tab.

NewAuthInstance.isp

Supports the implementation of a new authentication module, available from the Module Instances section of the Authentication tab.

ReorderAuthChains.isp

Supports a change in sequence of authentication criteria; to access, select an existing Authentication Chaining service under the Authentication tab for a specified realm.

7.9 Base Console JSP Endpoints

The endpoints in this subdirectory (console/base) relate to options associated with the "home page" for the OpenAM GUI console; in essence, these are the options available when you log in as the administrative user (typically amadmin).

Delegation Console JSP Endpoints

AMAdminFrame.jsp

Defaults to the opening page for the OpenAM console.

AMInvalidURL.jsp

Provides an "Invalid URL" error message.

AMLogin.jsp

Redirects users to the default login page; assumes no user is currently logged into OpenAM.

AMPost.jsp

Endpoint that either returns success of a post or an "Invalid or Missing Input" error.

AMUncaughtException.jsp

Default uncaught exception error message endpoint: "An error occurred while processing this request. Contact your administrator."

Authenticated.jsp

Displays a "You're logged in" information message.

CloseWindow.jsp

Endpoint that closes existing windows.

Message.isp

Specifies a template endpoint used for messages.

Version.jsp

Specifies current version information, copyright notice, and licensing.

7.10 Delegation Console JSP Endpoints

The two service endpoints under the console/delegation subdirectory relate to the privileges associated with configured realms.

Delegation.jsp

Associated with the privileges for a realm. The privileges can be assigned for different groups of users, as configured via Access Control > [realm] > Subjects > Group.

DelegationProperties.jsp

Supports changes in properties for group privileges, described in the Delegation.jsp endpoint. To get to these properties, select Access Control > [some realm] > Privileges > [name of group].

7.11 Federation Console JSP Endpoints

Federation Console JSP Endpoints

The JSP files in this section relate to federation, specified in the console/ federation subdirectory. Specifically, when you access the OpenAM GUI console and click the Federation tab, the variety of options that you select call the JSP files in this directory. References in each JSP file in that subdirectory are associated with the Federation tab.

Generally, the JSP files in this directory are essential if you want to add or modify federation partners in your Circles of Trust (COT), SAMLv2 / ID-FF / WS-Federation entity providers, and SAML 1.x configured partners.

If you're not using the legacy elements of federation, such as Liberty ID-FF, WS-Federation, and SAML 1.x, you may be able to delete related service endpoints in a more secure deployment.

Many of the endpoints in this section are accessible from the OpenAM console, under the Federation tab. Some of the endpoints are accessible only after you've created an appropriate entity provider, such as SAMLv2, ID-FF, or WS-Federation.

CreateCOT.isp

When you create a Circle of Trust (COT) via Federation > New, you can access the COT Configuration window. You can then access all configured COTs.

CreateSAML2MetaData.jsp

Used when creating a new entity provider, configured with the SAML2 protocol.

FSAuthDomainsEditViewBean.jsp

Associated with an edit of a COT; to access, select a previously configured COT.

FSSAMLSelectTrustedPartnerType.jsp

Opened when you configure a new Trusted Partner under the SAML 1.x Configuration section.

FSSAMLService.jsp

Associated with FSSAMLServiceViewBean, which is used by a number of other JSP files in the console/federation subdirectory.

FSSAMLSetTrustedPartnerType.jsp

Associated with the FSSAMLSetTrustedPartnersEdit.jsp file; used when you select a configured SAML 1.x Configuration trusted partner.

FSSAMLSiteIDAdd.jsp

Supports the addition of a Site ID for a SAML-configured partner.

FSSAMLSiteIDEdit.jsp

Supports the modification of a Site ID for a SAML-configured partner.

Federation Console JSP Endpoints

FSSAMLTargetURLsAdd.jsp

Includes a new POST to a specified URL.

FSSAMLTargetURLsEdit.jsp

Supports editing of a POST to a specified URL.

FSSAMLTrustedPartnersAdd.jsp

Called when you create a new "trusted partner" in the SAML 1.x Configuration area of the Federation window.

FSSAMLTrustedPartersEdit.jsp

Called when you edit an existing "trusted partner" in the SAML 1.x Configuration area of the Federation window.

Federation.jsp

Cited when you click New in the "Circle of Trust" section of the Federation window.

FileUploader.jsp

Called by the ImportEntity.jsp file, to support uploads of metadata files associated with a previously configured entity provider.

IDFFAffiliate.jsp

Specifies an IDFF affiliate in a COT.

IDFFGeneral.jsp

Includes general parameters associated with an IDFF affiliate in a COT. The corresponding IDFFGeneralViewBean parameter is cited only in this and the IDFFGeneralViewBean.java files.

IDFFIDP.jsp

Associated with the Identity Provider (IDP) for IDFF.

ISFFSP.jsp

Associated with the Service Provider (SP) for IDFF.

ImportEntity.jsp

Supports the import of pre-existing metadata files which define an entity provider. Allows you to import metadata from a URL to a desired Realm.

SAMLv2Affiliate.jsp

Enables a view of SAML version 2 affiliates.

SAMLv2AttrAuthority.jsp

Associated with an IDP acting as an attribute authority.

SAMLv2AttrQuery.jsp

Supports queries and saves of SAML2 attribute metadata.

SAMLv2AuthnAuthority.jsp

Enables communication with an IDP acting as an authentication authority.

Federation Console JSP Endpoints

SAMLv2General.jsp

Identifies general properties of a SAML version 2 affiliate.

SAMLv2IDPAdvanced.jsp

Supports the configuration of advanced properties for a SAMLv2 IDP.

SAMLv2AssertionContent.jsp

Associated with the Assertion Content tab, accessible when you select Federation > Entity Providers > Provider Name.

SAMLv2AssertionProcessing.jsp

Associated with the Assertion Processing tab, accessible when you select Federation > Entity Providers > Provider Name.

SAMLv2IDPServices.jsp

Supports the configuration of IDP service properties for a SAML2 provider.

SAMLv2PDP.jsp

Enables the configuration of a SAMLv2-based Policy Decision Point (PDP).

SAMLv2PEP.jsp

Enables the configuration of a SAMLv2-based Policy Enforcement Point (PEP).

SAMLv2SPAdvanced.isp

Supports the configuration of advanced properties for a SP. Accessible when you select Federation > Entity Providers > Provider Name > SP > Advanced.

SAMLv2SPAssertionContent.jsp

Associated with the Assertion Content tab; supports the configuration of such for SPs; It is accessible when you select Federation > Entity Providers > Provider Name > SP > Assertion Content.

SAMLv2SPAssertionProcessing.jsp

Associated with the Assertion Content tab; supports the configuration of assertion processing-related properties for SPs. It is accessible when you select Federation > Entity Providers > Provider Name > SP > Assertion Processing.

SAMLv2SPServices.isp

Supports the configuration of services-related properties for an SP. It is accessible when you select Federation > Entity Providers > Provider Name > SP > Services.

WSFedGeneral.jsp

Associated with the configuration of a legacy WS-Federation entity provider.

WSFedIDP.jsp

Supports the configuration of an IDP under WS-Federation.

WSFedSP.jsp

Supports the configuration of an SP under WS-Federation.

7.12 Policy Console JSP Endpoints

The JSP service endpoints in the console/policy subdirectory relate to a policies under a specific realm. To v iew the options listed in this section, start the GUI console and navigate to Access Control > [Name of Realm] > Policies.

For more information, see the chapter on *Defining Authorization Policies OpenAM in the Administration Guide*.

AuthToRealm.jsp

Supports a policy that depends on the realm where the user authenticated.

AuthToRealmAdd.jsp

Adds a policy that depends on the realm where the user authenticated.

AuthToRealmEdit.jsp

Edits an existing policy that depends on the realm where the user authenticated.

AuthToServiceAdd.jsp

Enables a policy that depends on an authentication realm for a user.

AuthToServiceEdit.jsp

Edits a policy that depends on an authentication realm for a user.

ConditionAdd.jsp

Supports adding a condition to a policy realm. Associated with the SelectConditionType.jsp file.

ConditionEdit.jsp

Edits a condition that has been added to a policy realm. Associated with the SelectConditionType.jsp file.

ConditionProxy.jsp

Supports a proxy of a condition that has been added to a policy realm. Cited only by the ConditionProxyViewBean.java file.

IdentityMembershipConditionAdd.jsp

Supports a policy that depends on a list of selected OpenAM subjects, as well as group membership.

IdentityMembershipConditionEdit.jsp

Edits an existing policy that depends on a list of selected OpenAM subjects, as well as group membership.

IdentitySubject.jsp

Supports the configuration of a policy based on users or groups.

IdentitySubjectAdd.jsp

Adds a policy that configures a policy based on users or groups.

IdentitySubjectEdit.jsp

Edits an existing policy based on the configuration of users or groups.

IDRepoResponseProviderAdd.isp

Identifies a response provider that provide additional information on policy enforcement, such as why a request was allowed or denied.

IDRepoResponseProviderEdit.jsp

Edits an ID response provider that provide additional information on policy enforcement, such as why a request was allowed or denied.

PMAuthenticatedUsersSubjectAdd.jsp

Supports the configuration of a new policy for authenticated users.

PMAuthenticatedUsersSubjectEdit.jsp

Supports the editing of an existing policy for authenticated users.

PMDefaultAuthLevelCondition.jsp

Supports a policy that depends on the realm where the user authenticated, with a minimum or maximum acceptable authentication level.

PMDefaultAuthLevelConditionAdd.jsp

Adds a policy that depends on the realm where the user authenticated, with a minimum or maximum acceptable authentication level.

PMDefaultAuthLevelConditionEdit.jsp

Edits an existing policy that depends on the realm where the user authenticated, with a minimum or maximum acceptable authentication level.

PMDefaultAuthSchemeCondition.jsp

Supports the configuration of a policy that depends on the realm where the user authenticated.

PMDefaultAuthSchemeConditionAdd.jsp

Adds a policy that depends on the realm where the user authenticated.

PMDefaultAuthSchemeConditionEdit.jsp

Edits an existing policy that depends on the realm where the user authenticated.

PMDefaultIPCondition.isp

Supports a policy based on clients in a specific range of IP addresses or associated with a specific DNS domain name.

PMDefaultIPConditionAdd.jsp

Adds a policy based on clients in a specific range of IP addresses or associated with a specific DNS domain name.

PMDefaultIPConditionEdit.jsp

Edits an existing policy based on clients in a specific range of IP addresses or associated with a specific DNS domain name.

PMDefaultSessionCondition.jsp

Supports the configuration of an Active Session policy condition.

PMDefaultSessionConditionAdd.jsp

Adds a new policy related to an Active Session policy condition.

PMDefaultSessionConditionEdit.jsp

Edits an existing policy related to an Active Session policy condition.

PMDefaultTimeCondition.jsp

Relates to a policy associated with time restrictions on a user or group.

PMDefaultTimeConditionAdd.jsp

Adds a policy for time restrictions on a user or a group.

PMDefaultTimeConditionEdit.jsp

Edits an existing policy related to time restrictions on a user or a group.

PMDSAMERoleSubject.jsp

Used for user/group roles associated with the Directory Server Access Management Edition.

PMLDAPGroupSubject.jsp

Relates to a policy dependent on group membership within the LDAP database.

PMLDAPOrgSubject.jsp

Relates to a policy dependent on organizational (OU) membership within the LDAP database.

PMLDAPRoleSubject.jsp

Relates to a policy dependent on user roles configured within the LDAP database.

Policy.jsp

Displays currently configured policies for the target realm.

PolicyNormalAdd.isp

Shows what policy has been added from the Policies tab, after configuring a new policy with the New Policy button.

PolicyNormalEdit.jsp

Supports the creation of a new policy rule, or the edit of an existing policy rule. To access, click New in any policy category, or select an existing policy.

PolicyReferralAdd.jsp

Displays a newly configured referral policy.

PolicyReferralEdit.jsp

Supports editing of an existing referral policy.

PolicySelectType.jsp

Supports selection of a policy, by name, in either a "normal" or a "referral" category.

ReferralAdd.jsp

Adds referrals to and from an existing policy.

ReferralEdit.jsp

Edits referrals associated with an existing policy.

ReferralProxy.jsp

Supports changes in referrals to and from an existing policy.

ResponseProviderAdd.jsp

Associated with IDRepoResponseProviderAdd.jsp.

ResponseProviderEdit.jsp

Associated with IDRepoResponseProviderEdit.jsp.

ResponseProviderProxy.jsp

Supports changes in response providers for an existing policy.

RuleAdd.isp

Displays a newly created policy, in the Edit Policy window.

RuleEdit.jsp

Supports edits of an existing policy.

RuleWithPrefixAdd.jsp

Associated with the SelectServiceType.jsp endpoint.

RuleWithPrefixEdit.jsp

Associated with the SelectServiceType.jsp endpoint.

RuleNoResourceAdd.jsp

Associated with the SelectServiceType.jsp endpoint.

RuleNoResourceEdit.jsp

Associated with the SelectServiceType.jsp endpoint.

SelectConditionType.jsp

Enables a policy that depends on whether the information for a specific user can be found in the identity repository LDAP database.

SelectRealm.isp

Opens a window that supports a selection from existing realms, based on available authentication modules.

SelectReferralType.jsp

Supports the configuration of a referral type for a sub-realm.

SelectResponseProviderType.jsp

Supports the configuration of a response provider type for an identity repository.

SelectServiceType.jsp

Supports the configuration of a policy service type; supports the customization of a new rule for configurable service types such as the Discovery Service.

SelectSubjectType.jsp

Enables creation of a policy for web service clients, associated with federated access management.

SessionPropertyAdd.jsp

Supports a policy that depends on attributes in a user's session.

SessionPropertyConditionAdd.jsp

Supports a policy that includes conditions based on attributes in a user's session.

SessionPropertyConditionEdit.jsp

Edits conditions in a policy based on attributes in a user's session.

SessionPropertyEdit.jsp

Edits attributes in a policy based on attributes in a user's session.

SubjectAdd.jsp

Supports the configuration of a new policy for authenticated users; associated with PMAuthenticatedUsersSubjectAdd.jsp.

SubjectEdit.jsp

Edits the configuration of a policy for authenticated users; associated with PMAuthenticatedUsersSubjectEdit.jsp.

SubjectNoneAdd.jsp

Associated with a policy for web service clients; related to SelectSubjectType.jsp.

SubjectNoneEdit.jsp

Supports the configuration of a new policy for authenticated users; associated with PMAuthenticatedUsersSubjectEdit.jsp.

SubjectProxy.jsp

Configures a proxy for web service client policies; associated with SelectSubjectType.jsp.

7.13 IDM Console JSP Endpoints

This group of service endpoints are associated with an identity management (IDM) interface from OpenAM. You can find these endpoints in the console/idm subdirectory. You may not need all of the functionality provided by the endpoints in this section.

Some of the endpoints in this section include references to UM*.jsp endpoints, User Console JSP Endpoints located in the console/user subdirectory, and described later in this chapter.

EndUser.jsp

Accesses the information page for the currently logged in user.

Entities.jsp

Opens the list of currently configured users, available via Access Control > [selected realm] > Subjects.

EntityAdd.jsp

Used when adding a new user or group.

EntityDiscoveryDescriptionAdd.jsp

Associated with the Discovery Service. To access that service, select a non-administrative user and select the Services tab. The EntityDiscoveryDescriptionAdd.jsp file is used when selecting a new Security Mechanism ID as a Service Description as a new Discovery Resource Offering.

EntityDiscoveryDescriptionEdit.jsp

Associated with an edit of an existing Security Mechanism ID.

EntityEdit.jsp

Called when saving changes to an existing user.

EntityMembers.jsp

Lists the members of a configured group.

EntityMembersFilteredIdentity.jsp

Lists the members of a configured group based on some filter.

EntityMembership.jsp

Accessed when a regular user is made a member of a previously configured group.

EntityResourceOffering.jsp

Supports custom resource offering entries for a previously configured user. Also seen when accessing the UMUserResourceOffering.jsp file.

EntityResourceOfferingAdd.jsp

Supports entries of new resource offerings for a previously configured user. Also seen when accessing the UMUserResourceOfferingAdd.jsp file.

EntityResourceOfferingEdit.jsp

Supports edits of existing resource offerings for a previously configured user. Also seen when accessing the UMUserResourceOfferingEdit.jsp file.

EntityServices.jsp

Supports a new service for a specific user. As of this writing, available services are: Dashboard, Discovery Service, Liberty Personal Profile Service, and Session.

Home.jsp

Opens a list of currently configured users.

ServicesAdd.isp

Accessible after adding a new service for a currently configured user; associated with the EntityServices.jsp file.

ServicesEdit.isp

Accessible for editing services associated with a currently configured user.

ServicesNoAttribute.jsp

Used if a configured organization has no available attributes.

ServicesSelect.jsp

Opened when adding a service for a specific user.

7.14 Console Realm JSP Endpoints

If you want to know how to configure services and data stores within a realm, you'll want to understand the workings of these service endpoints. If you want to customize realms in production, you'll want to keep these endpoints available on an OpenAM console. You can find these endpoints in the console/realm subdirectory.

HomePage.isp

Associated with the main Access Control page in the OpenAM GUI console, which lists configured realms. If you call realm/HomePage.jsp directly, it

cites messages associated with changes for a specific user, and functions more closely associated with JSP endpoints in the console/idm subdirectory.

IDRepo.jsp

Enables links with directory server data stores within a realm. To access, select Access Control > [some realm] > Data Stores > New. You should see a variety of supported directory server data stores, such as Active Directory, OpenDJ, and Tivoli Directory Server.

IDRepoAdd.jsp

Appears when you add a data store; associated with the IDRepo.jsp service endpoint.

IDRepoEdit.jsp

Appears when you edit an existing data store; associated with the IDRepo.jsp service endpoint.

IDRepoSelectType.jsp

Includes a list of supported data stores, from Active Directory to OpenDJ; associated with the IDRepo.jsp service endpoint.

RMRealm.jsp

Supports the configuration of a new realm, or editing of an existing realm.

RMRealmAdd.jsp

Supports the addition of a new realm; associated with the RMRealm.jsp service endpoint.

RealmDiscoveryDescriptionAdd.jsp

Supports a new description for a realm; associated with the RealmResourceOffering.jsp service endpoint.

RealmDiscoveryDescriptionEdit.jsp

Supports an edited description; associated with the RealmResourceOffering.jsp service endpoint.

RealmProperties.isp

Works with the pages that allow you to edit an existing realm.

RealmResourceOffering.jsp

Supports the configuration of a security mechanism to a new realm resource offering. Requires the configuration of the discovery service, and the configuration of a directory resource offering for the specified realm.

RealmResourceOfferingAdd.jsp

Supports the addition of a security mechanism to a new realm resource offering. Requires the configuration of the discovery service, and the configuration of a directory resource offering for the specified realm.

RealmResourceOfferingEdit.jsp

Supports the editing of a security mechanism for an existing realm resource offering. Requires the configuration of the discovery service, and the configuration of a directory resource offering for the specified realm.

Services.jsp

Supports the configuration of a service within a specified realm.

ServicesAdd.jsp

Supports the addition of a service to a specified realm; available services to add include Administration, Dashboard, Discovery, Globalization Settings, OAuth2 Provider, Password Reset, Session, and User.

ServicesCannotAssignService.jsp

If a desired service is not compatible with directory data available from an organization, it is rejected.

ServicesEdit.jsp

Supports the editing of an existing service; associated with the Services.jsp endpoint.

ServicesNoAttribute.jsp

Supports the editing of an existing service; called if the attribute cannot be found or changed.

ServicesSelect.jsp

Implements step 1 of the addition of a new service; associated with the Services.jsp endpoint.

7.15 Service Console JSP Endpoints

You can find the JSP files in this category in the console/service subdirectory. Most of the endpoints are accessible in the console, from various options associated with the Configuration menu. If you don't use some of the functionality described such as Liberty ID-FF or SOAP binding, you may be able to delete the associated endpoints.

G11NCharsetAliasAdd.jsp

Supports the configuration of a new character set alias. Accessible from the Globalization Settings > Charset Aliases submenu.

G11NCharsetAliasEdit.isp

Supports the editing of an existing character set alias. Accessible from the Globalization Settings > Charset Aliases submenu.

G11NSupportedCharsetAdd.jsp

Supports the configuration of a new character set supported by a locale. Accessible from the Globalization Settings > Charsets Supported by Each Locale submenu.

G11NCharsetAliasEdit.jsp

Supports the editing of an existing character set supported by a locale. Accessible from the Globalization Settings > Charsets Supported by Each Locale submenu.

MAPClientManager.jsp

Supports a list of client types. Associated with the Default Client Type option available via Configuration > System > Client Detection.

MAPCreateDevice.jsp

Supports creation of client devices.

MAPCreateDeviceTwo.jsp

Supports creation of client devices.

MAPDeviceProfile.jsp

Supports step 1 of creating a new client device.

MAPDuplicationDevice.jsp

Used with duplicate client devices.

SCConfig.jsp

Associated with basic Service Configuration data, and the other endpoints accessible from the Configuration menu.

SCConfigAuth.jsp

Supports the configuration of available authentication databases. You can get to this window by selecting Configuration > Authentication.

SCConfigConsole.jsp

Supports the configuration of administrative an globalization console properties. You can get to this window by selecting Configuration > Console.

SCConfigGlobal.jsp

Supports the configuration of OpenAM global properties. You can get to this window by selecting Configuration > Global.

SCConfigSystem.jsp

Supports the configuration of OpenAM system properties. You can get to this window by selecting Configuration > System.

SCPlatform30.jsp

Accesses current global attributes and cookie domain settings. To get to this window, select Configuration > System > Platform.

SCPolicy.jsp

Supports a view of the current policy configuration. To access this window, select Configuration > Global > Policy Configuration.

SCPolicyResourceComparatorAdd.jsp

Supports the addition of a new resource comparator to the current policy configuration. To access the relevant window, select Configuration > Global > Policy Configuration.

SCPolicyResourceComparatorEdit.jsp

Supports the editing of an existing resource comparator in the current policy configuration. To access the relevant window, select Configuration > Global > Policy Configuration.

SCSAML2SOAPBinding.jsp

Enables a review of current SAMLv2 SOAP binding request handlers. Associated with SOAP-based communications, using SAMLv2 requests, between a client and a server. To access the relevant screen, select Configuration > Global > SAMLv2 SOAP Binding.

SCSAML2SOAPBindingRequestHandlerListAdd.jsp

Allows you to add a new SAMLv2 SOAP binding request handler. To access the relevant screen, select Configuration > Global > SAMLv2 SOAP Binding.

SCSAML2SOAPBindingRequestHandlerListDup.jsp

Allows you to duplicate an existing SAMLv2 SOAP binding request handler. To access the relevant screen, select Configuration > Global > SAMLv2 SOAP Binding.

SCSAML2SOAPBindingRequestHandlerListEdit.jsp

Allows you to edit an existing SAMLv2 SOAP binding request handler. To access the relevant screen, select Configuration > Global > SAMLv2 SOAP Binding.

SCSOAPBinding.jsp

Enables a review of current SOAP binding request handlers. Associated with the Liberty Alliance Project Identity Federation Framework (Liberty ID-FF).

SCSOAPBindingRequestHandlerListAdd.jsp

Allows you to add a new SOAP binding request handler. Associated with the Liberty Alliance Project Identity Federation Framework (Liberty ID-FF).

SCSOAPBindingRequestHandlerListDup.jsp

Allows you to duplicate an existing SOAP binding request handler. Associated with the Liberty Alliance Project Identity Federation Framework (Liberty ID-FF).

SCSOAPBindingRequestHandlerListEdit.jsp

Allows you to edit an existing SOAP binding request handler. Associated with the Liberty Alliance Project Identity Federation Framework (Liberty ID-FF).

SecurityTokenService.jsp

Supports the configuration of tokens associated with the Security Token Service (STS). To access the associated screen, select Configuration > Global > Security Token Service.

ServerAdd.jsp

Supports the addition of an OpenAM server to work behind a load balancer in support of Session Failover (SFO). Available from Configuration > Servers and Sites, in the Servers subsection.

ServerClone.jsp

Supports the cloning of an existing OpenAM server to work behind a load balancer in support of Session Failover (SFO). Available from Configuration > Servers and Sites, in the Servers subsection.

ServerConfigInherit.jsp

Supports the inheritance of the default configuration for servers, as it relates to SFO.

ServerConfigXMLAddServer.jsp

Enables the configuration fo a new server; relates to SFO.

ServerConfigXML.jsp

Supports the review of the XML settings of an existing server, as it relates to SFO.

ServerEditAdvanced.jsp

Supports the editing of advanced properties for default servers, in the configuration of servers for SFO. To access, select Configuration > Severs and Sites > Default Server Settings, and click Advanced.

ServerEditGeneral.jsp

Supports the editing of general properties for default servers, such as the base directory, default locale, debug level, mail server for notifications, and more. Relates to the configuration of servers for SFO. To access, select Configuration > Severs and Sites > Default Server Settings, and click General.

ServerEditSDK.jsp

Supports the editing of SDK-related properties for default servers, associated with SFO. Supports editing of settings such as datastore notifications, event service connection retries, LDAP connections, Time To Live (TTL) for user entries, and more. To access, select Configuration > Severs and Sites > Default Server Settings, and click SDK.

ServerEditSecurity.isp

Supports the editing of security properties for default servers; associated with SFO. Includes default security settings such as encryption keys,

cookie encoding, key stores, and certificate management. To access, select Configuration > Severs and Sites > Default Server Settings, and click Security.

ServerEditSession.jsp

Supports the editing of session properties for default servers; associated with SFO. Note the Session Limit default specifies a maximum of 5000, well short of the 100,000 sessions that can be handled by a standard 3GB dual-core production system. To access, select Configuration > Severs and Sites > Default Server Settings, and click Session.

ServerSite.jsp

Associated with the addition or editing of a load balancer that distributes requests to other OpenAM servers. Available from the Configuration > Servers and Sites, in the Servers subsection.

SiteAdd.jsp

Enables the configuration of a load balancer to distribute requests to other existing OpenAM servers. Available from the Configuration > Servers and Sites, in the Sites subsection.

SiteEdit.jsp

Enables changes to a configured load balancer in how it distributes requests to other existing OpenAM servers. Available from the Configuration > Servers and Sites, in the Sites subsection.

SMDiscoveryBootstrapRefOffAdd.jsp

Includes new resource offerings for the discovery service, bootstrapped using a standard such as SAML2.

SMDiscoveryBootstrapRefOffEdit.jsp

Supports the editing of existing resource offerings for the discovery service, bootstrapped with a standard such as SAML2.

SMDiscoveryDescriptionAdd.jsp

Includes the addition of of new options for the discovery service.

SMDiscoveryDescriptionEdit.jsp

Supports the editing of existing options for the discovery service.

SMDiscoveryProviderResourceIdMapperAdd.jsp

Supports the mapping of a new resource ID for the discovery service.

SMDiscoveryProviderResourceIdMapperEdit.jsp

Supports the editing of an existing resource ID for the discovery service.

SMDiscoveryService.jsp

Supports a review and configuration of the Discovery Server, for global attributes, the ResourceID Mapper plug-in, and bootstrapping.

SMG11N.jsp

Allows you to configure globalization settings for OpenAM; accessible via Configuration > Console > Globalization Settings.

SMG11N.jsp

Allows you to configure globalization settings for OpenAM; accessible via Configuration > Console > Globalization Settings.

STSExportPolicy.jsp

Allows you to review and copy STS policies for export, input, and output. You can review this via Configuration > Global > Security Token Service > Export Policy.

SubConfigAdd.jsp

Allows you to configure a secondary configuration instance; accessible via Configuration > Global > Session.

SubConfigEdit.jsp

Allows you to edit an existing secondary configuration instance; accessible via Configuration > Global > Session.

SubSchemaTypeSelect.jsp

Allows you to configure a schema assocaited with breadcrumbs.

7.16 Session Console JSP Endpoints

There are currently two service endpoints configured in the console/session subdirectory, related to login sessions.

SMProfile.isp

Provides information on current login session statistics. Available from the Sessions tab from the main console.

SessionHAStatistics.jsp

Supports session high availability statistics collection.

7.17 Task Console JSP Endpoints

The service endpoints in the console/task subdirectory relate to the options available from the default start page when an administrator logs into the OpenAM console. If you don't use Google Apps or Salesforce, you may not need some of the functionality in the associated endpoints.

CompleteCreateHostedIDP.jsp

Provides information on what the administrator can do after configuring an Identity Provider (IDP). Options listed include registering a remote Service

Provider (SP), creating a fedlet, configuring Google Apps, and configuring Salesforce CRM. Includes links to such functionality, which depend on the configuration of a Circle of Trust (CoT).

ConfigureGoogleApps.jsp

Supports the configuration of Google Apps for Single-sign on (SSO). Requires a CoT configured with an IDP.

ConfigureGoogleAppsComplete.jsp

Enables entries to configure the SP. Includes steps "To Enable Access to the Google Apps API."

ConfigureGoogleAppsWarning.jsp

Includes a default warning message related to the ConfigureGoogleApps.jsp endpoint. The message is self-explanatory, though grammatically questionable: "Unable to configure because there are no circle of trust with Identity Provider."

ConfigureOAuth2.jsp

Supports the configuration of OAuth2 Authorization. For more information, see the the chapter on *Managing OAuth2 Authorization in the Administration Guide*.

ConfigureSalesForceApps.jsp

Accessible when you select the Configure Salesforce CRM link shown in the main GUI console. Requires IDP and SP information for an appropriate CoT, where OpenAM is the IDP and Salesforce is configured as the SP.

ConfigureSalesForceAppsComplete.jsp

Supports the configuration of SSO with a Salesforce CRM account. Includes instructions on the settings to add to an applicable Salesforce account.

ConfigureSalesForceAppsFinishWarning.jsp

Sets up a warning message related to a need for a Salesforce Login URL for the configuration.

CreateFedlet.jsp

A fedlet supports federation for a SP that does not already have its own federation solution. For more information, see the the chapter on *Using Fedlets in Java Web Applications in the Development Guide* .

CreateFedletWarning.jsp

Sets up a warning message related to the prerequisite for a CoT with the IDP.

CreateHostedIDP.jsp

Supports the configuration of a SAMLv2 IDP on the local instance of OpenAM.

CreateHostedSP.jsp

Supports the configuration of a SAMLv2 SP on the local instance of OpenAM.

CreateRemoteIDP.jsp

Supports the configuration of a SAMLv2 IDP on a remote system, within a configured CoT.

CreateRemoteSP.jsp

Supports the configuration of a SAMLv2 SP on a remote system, within a configured CoT.

Home.jsp

Endpoint that redirects the client to the startup page for OpenAM.

ValidateSAML2Setup.jsp

Supports the test of a federation connection between an IDP and SP in a CoT.

7.18 User Console JSP Endpoints

Endpoints in the console/user subdirectory support account configuration tasks. Many of these endpoints are accessible by realm. From the home page screen, select Access Control > [realm] > Subjects > [name of user]. This should open up an Edit User screen

UMChangeUserPassword.jsp

This service endpoint is normally opened in a separate window to enable a user (or administrator) to change their login password. Accessible from the Edit User screen. All you need to do from the screen is click Edit next to the Password entry.

UMUserDiscoveryDescriptionAdd.jsp

Relates to the security mechanism identifier associated wih a user. To access from the screen for an individual user, select Services > Discovery Service > Add > scroll down to the Service Description box > New Description > select and Add a Security Mechanism ID. Example IDs include urn:liberty:security:2003-08:ClientTLS:SAML, which relates to the former Liberty Alliance project, using Transaction Layer Security (TLS) on the client, with SAML assertions.

UMUserDiscoveryDescriptionEdit.jsp

Supports editing of the security mechanism identifier associated with a user. Closely related to the UMUserDiscoveryDescriptionAdd.jsp endpoint.

UMUserPasswordResetOptions.jsp

Allows you to "Force Change Password on Next Login". Accessible from the Edit User screen for a specific user, via the "Password Reset Options" entry near the bottom of the window.

Web Services Console JSP Endpoints

UMUserResourceOffering.jsp

Accessible as an option to the Discovery Service for a specific user. To access from the Edit User screen for a specific user, select Services > Discovery Service > Add.

UMUserResourceOfferingAdd.jsp

Accessible as an option to the Discovery Service for a specific user. To access from the Edit User screen for a specific user, select Services > Discovery Service > Add.

UMUserResourceOfferingEdit.jsp

Accessible as an option to the Discovery Service for a specific user. To edit an existing resource offering, navigate to the Edit User screen for a specific user, select Services > Discovery Service > [some previously configured service].

7.19 Web Services Console JSP Endpoints

Web services include endpoints in the console/webservices subdirectory. You can use them to define legacy options for services such as the Liberty Identity Federation Framework (ID-FF). As such, these endpoints may be less essential to your implementation of OpenAM. For more information, see the *OpenAM Wiki on Web Services*.

WSAuthNServices.jsp

Supports the configuration of various mechanism handlers for authentication, including CRAM-MD5, PLAIN, and SSOToken.

WSAuthNServicesHandlersAdd.jsp

Supports the addition of a new mechanism handler for authentication.

WSAuthNServicesHandlersEdit.isp

Supports changes to an existing mechanism handler for authentication.

WSPPServiceDSAttributeMapListAdd.jsp

Enables the addition of a new LDAP attribute, with a name prefix.

WSPPServiceDSAttributeMapListEdit.jsp

Enables the editing of an existing LDAP attribute, with a name prefix.

WSPPServiceSupportedContainerAdd.jsp

Enables the creation of a new supported container for ID-FF.

WSPPServiceSupportedContainerEdit.jsp

Enables the editing of an existing container.

WSPersonalProfileService.isp

Allows you to configure ID-FF for global attributes, supported containers, PPLDAP attributes and alternative security mechanisms.

7.20 OAuth JSP Endpoints

Includes endpoints in the oauth, oauth2, and oauth2c subdirectories. Some of the service endpoints in the oauth subdirectory are based on OAuth 1.0, which may be deprecated in an upcoming release.

deleteconsumer.jsp

This endpoint is used to delete consumer systems, which get resources from service providers (SPs) based on OAuth 1.0 tokens.

deletetoken.jsp

This endpoint is used to delete an existing OAuth 1.0 token.

index.isp

Specifies an endpoint used to register and delete service consumers, which get resources from SPs. Provides access to registerconsumer.jsp and deleteconsumer.jsp. Associated with OAuth 1.0.

registerconsumer.jsp

Defines an endpoint used to register a consumer of services from SPs. Associated with OAuth 1.0.

userconsole.jsp

Allows a user to authorize or revoke a request for an OAuth 1.0 token..

registerClient.jsp

Enables registration of an OAuth 2.0 client with the OpenAM OAuth 2.0 authorization service. For details, see the Administration Guide chatper on *Managing OAuth 2.0 Authorization*.

OAuthLogout.jsp

Used to log out the resource owner with teh OAuth 2.0 provider. For more information, see the Administration Guide chapter on *Defining Authentication Services*.

OAuthProxy.jsp

Endpoint used for redirection. For more information, see the Administration Guide chapter on *Managing OAuth 2.0 Authorization*.

7.21 Password JSP Endpoints

The endpoints in this section can be found in the password/ui subdirectory. Each of these endpoints use the PWResetViewBeanBase.java file, as a class to set up messages. You can view some of these endpoints by omitting the password. For example, to view the effect of the PWResetUserValidation.jsp endpoint on an OpenAM system using an URL of openam.example.org in a

standard Tomcat container, navigate to http://openam.exmaple.org/openam/ui/PWResetUserValidation.jsp. You can set associated options from the main console by selecting Configuration > Global > Password Reset. For more information on the process, see the chapter on *Configuring Password Reset in the Administration Guide*.

PWResetBase.jsp

This simple endpoint includes a redirection of the ServiceURI, and specifies OpenAM as the ProductName. It's cited by the other endpoints in the password/ui subdirectory.

PWResetInvalidURL.jsp

This endpoint is called with the PWResetInvalidURLViewBean class, when a module servlet gets an invalid URL.

PWResetQuestion.jsp

Starts the password reset process by propmting for the User ID. For more information on the process, see the method for the associated PWResetQuestionModel, available from the Interface PWResetQuestionModel specification page.

PWResetSuccess.jsp

Specifies the endpoint that is called when an account password is successfully reset.

PWResetUncaughtException.jsp

Specifies a "Contact your administrator" message when there is an error in a related endpoint.

PWResetUserValidation.jsp

Opens a screen that prompts for a user ID (UID). If that UID is found in the database, configured with an accessible email address, on a system connected to a mail server, a reset link is sent to that address.

7.22 SAML2 JSP Endpoints

You can find the endpoints described in this section in the saml2/jsp subdirectory. As of this writing, some of these endpoints are not used in the current implementation of OpenAM. Active endpoints in this category are discussed in the chapter on *Managing SAML2 Federation in the Administration Guide*.

default.jsp

May be used by other files to return a success or failure message. While the default.jsp name is common in the trunk, the jsp/default.jsp filename is used only by SPSingleLogout.java, which is not commonly used.

exportmetadata.jsp

Supports the export of XML-based metadata with other providers within a circle of trust (CoT). Currently used. For more information, see the chapter on *Managing SAML2 Federation in the Administration Guide*.

fedletAttrQuery.jsp

Supports the configuration of SAML attribute guery headers.

fedletAttrResp.jsp

Supports the configuration of SAML attribute response headers.

fedletSS0Init.jsp

Previously used to start single sign-on at the Fedlet.

fedletSampleApp.jsp

Specifies a sample fedlet application that can be removed in production.

fedletXACMLQuery.jsp

Enables a sample SAML XACML query handler; used for testing, to prompt users to specify a resource URL along with an action (GET, POST).

fedletXACMLResp.jsp

Retrieves a sample SAML XACML resource URL for a yes, no, or maybe decision (PERMIT, DENY, or INDETERMINATE).

idpMNIPOST.jsp

The MNI in several JSP files relate to ManageNameID, which sets up corresponding accounts on IDPs and SPs. This particular JSP file processes a request from an IDP through an HTTP redirect.

idpMNIRedirect.jsp

The MNI in several JSP files relate to ManageNameID, which sets up corresponding accounts on IDPs and SPs. This particular JSP file processes a request from an IDP through an HTTP redirect. It uses a metadata-based alias, an entity ID for the service provider, and the type of MNI request; examples include NewID and terminate.

idpMNIRequestInit.jsp

The MNI in several JSP files relate to ManageNameID, which sets up corresponding accounts on IDPs and SPs. As described in the *Managing SAML2 Federation in the Administration Guide* chapter of the Administration Guide, it allows you to change federation of persistently linked accounts. The chapter also includes an example of this endpoint at work.

idpSSOFederate.jsp

Specifies an endpoint that takes authentication requests from an SP, with a SAMLRequest data, a metaAlias and a RelayState with information from the target URL.

idpSS0Init.jsp

Specifies an endpoint that starts SSO, either from cache, or by verifying metaAlias and SP identifier data. For more information, see the chapter on *Managing SAML2 Federation in the Administration Guide*.

idpSingleLogoutInit.jsp

Starts a LogoutRequest from the identity provider. For more information, see the chapter on *Managing SAML2 Federation in the Administration Guide*.

idpSingleLogoutPOST.jsp

Specifies an endpoint that receives logout requests from IDPs and receives logout responses from SPs. Also sends logout responses to SPs.

idpSingleLogoutRedirect.jsp

Takes the SAMLRequest and SAMLResponse messages for logouts from the SP. May also handle the RelayState directive.

SA IDP.jsp

Used for SAML authentication for communication with identity providers (IDPs).

SA SP.jsp

Used for SAML authentication for communication with service providers (SPs).

saeerror.jsp

Returns an error message related to Secure Attribute Exchange (SAE). Currently used only by the SA IDP.jsp and SA SP.jsp endpoints.

saml2error.jsp

Endpoint that may return one of many error codes, specified in the comments of the file.

spAssertionConsumer.jsp

Used on a SP, to interpret information from an IDP. The request to the IDP is an AuthnRequest; the response from the IDP is read by this endpoint.

spMNIPOST.jsp

The MNI in several JSP files relate to ManageNameID, which sets up corresponding accounts on IDPs and SPs. This particular endpoint takes the associated request, using an HTTP Redirect, from a SP. Less commonly used.

spMNIRedirect.jsp

This particular endpoint handles the ManageNameIDRequest and ManageNameIDRespnose messages with the help of HTTP Redirect. Less commonly used.

spMNIRequestInit.jsp

This particular endpoint supports changes to federation of persistently linked accounts, in a fashion similar to idpMNIRequestInit.jsp. For an example of

this endpoint in work, see the chapter on *Managing SAML2 Federation in the Administration Guide*.

spSS0Init.jsp

Supports SSO messages from the SP. For more information and an example of how this endpoint is used, see the chapter on *Managing SAML2*Federation in the Administration Guide.

spSingleLogoutInit.jsp

Supports SSO messages from the SP. For more information, see the chapter on *Managing SAML2 Federation in the Administration Guide*.

spSingleLogoutPOST.isp

Specifies an endpoint that receives logout requests from SPs and receives logout responses from IDPs. Also sends logout responses to IDPs. Converse endpoint to idpSingleLogoutPOST.jsp.

spSingleLogoutRedirect.jsp

Takes the SAMLRequest and SAMLResponse messages for logouts from the IDP. May also handle the RelayState directive. Converse endpoint to idpSingleLogoutRedirect.jsp.

7.23 WS Federation JSP Endpoints

The endpoints described in this section, in the wsfederation/jsp subdirectory, relate to Kantera Alliance standards that originated with the Liberty Alliance Project Identity Federation Framework.

logout.jsp

Shows a page after a successful logout.

multi.jsp

Used for multi-federation protocol configurations.

post.jsp

Sets up a form for single sign-on (SSO) responses sent from the IDP to the SP.

realmSelection.jsp

Default display if no realms are defined.

7.24 WEB-INF Endpoints

The OpenAM WAR archive includes pointers to different URL patterns in the web.xml file. The following section includes a description of each of the identified URL patterns.

Many of the endpoints in this section are based on what you would add to an OpenAM URL. Many of the endpoints described in the web.xml file are not directly related to the .jsp files described in other parts of this chapter.

The endpoints in this chapter are taken from all items tagged with the url-pattern label. These endpoints are listed in that they appear in the web.xml file available at the time of this writing; the list is changed frequently. If you want to disable one or more of these endpoints, you may be able to delete them from the web.xml file.

Each of the url-patterns shown in the web.xml file is associated with elements such as a filter-name or a servlet-name. The definitions that follow use those elements to help identify the function of each endpoint listed in the web.xml file. Many of these elements can be directly related to a .java file.

The endpoints in this section are in the order found in the list of url-pattern entries shown in the web.xml file at the time of this writing.

This entry is more of a filter for all endpoints. It's associated with the ResponseValidationFilter, which checks for valid URLs. It's also associated with the AMSetupFilter.java file; on systems not yet configured, it redirects users to the setup wizard.

ws/*

Specifies a group of URLs related to authentication endpoints, as it is associated with the AuthNFilter.java and AuthZFilter.java files. However, those files (and the associated RestServiceManager.java file) are not called by any other files in the trunk.

/login

With the help of the LoginLogoutMapping.java file, this would forward to the /UI/Login.jsp endpoint.

/logout

With the help of the LoginLogoutMapping.java file, this would forward to the /UI/Logout.jsp endpoint.

/UI/*

With the help of the LoginServlet.java file, this forwards to the default login page for an OpenAM system.

/config/configurator

Uses the AMSetupServlet, which as noted in the associated .java file, "is the first class to get loaded by the Servlet * container"

/setup/setSetupProgress

Used by the installation wizard to display the progress.

/upgrade/setUpgradeProgress

Used by the upgrade wizard to display progress.

/ui/*

Associated with the servlet naemd PWResetServlet, associated with password resets.

/gateway

Used with the servlet named GatewayServlet. Associated with the Gateway.java file, which takes an authentication module and forwards it to a login URL.

/GetHttpSession

The associated .java file is associated with Session Failover (SFO).

/sessionservice, /profileservice, /policyservice, /namingservice, /loggingservice, /authservice, /notificationservice

All of these endpoints are associated with OpenAM Security Advisory #201203. As suggested in the advisory, if you're using OpenAM version 9.5.4 or 10.0.0, you should be sure to apply the updates required to upgrade your systems to versions 9.5.5 or 10.0.1 (or higher).

/jaxrpc/*, /identityservices/*

These endpoints provide information on configured web services, including the port name, status, URL, and implementation class. Both endpoints show the same data. The IdentityServices servlet name points to the following description: "Web Service Endpoint - Identity Services".

/SMSServlet

Includes system configuration information when available, as documented in the comments to the AMSystemConfig.java file.

/notification

The associated servlet named notificationservlet appears to be commonly used. When the URL is entered, the default output is 200, associated with an URL success message.

/entitlementmonitor

Used by the NetworkMonitor.java file, which is essential to the monitoring of OpenAM services.

/identity/*

Possibly a legacy endpoint. While the associated IdentityServicesHandler servlet is identified as "REST Endpoint - Identity Services", it is only cited in the IdentityServicesHandler.java file.

/resources/*

Linked to an oauth servlet. The associated com.sun.identity.oauth.service.RestService class is rarely used.

/authentication/*

Associated with the servlet named AuthServlet. The associated AuthServer.java file is the controller servlet for realm authentication pages. When the URL is entered prior to login, it defaults to the standard login page.

/base/*

Associated with the servlet named AMBaseServlet. While the associated AMBaseServlet.java file is rarely used, the URL prior to login defaults to the standard login page.

/service/*

Associated with the servlet named SCServlet. While the associated SCServlet.java file is rarely used, the URL prior to login defaults to the standard login page.

/session/*

Associated with the servlet named SMServlet. While the associated SMServlet.java file is rarely used, the URL prior to login defaults to the standard login page.

/realm/*

Associated with the servlet named RMServlet. While the associated RMServlet.java file is rarely used, the URL prior to login defaults to the standard login page.

/policy/*

Associated with the servlet named PMServlet. While the associated PMServlet.java file is rarely used, the URL prior to login defaults to the standard login page.

/idm/*

Associated with the servlet named IDMServlet. While the associated IDMServlet.java file is rarely used, the URL prior to login defaults to the standard login page.

/user/*

Associated with the servlet named UMServlet. While the associated UMServlet.java file is rarely used, the URL prior to login defaults to the standard login page.

/delegation/*

Associated with the servlet named DelegationServlet. While the associated DelegationServlet.java file is rarely used, the URL prior to login defaults to the standard login page.

/task/*

Associated with the servlet named TaskServlet. While the associated TaskServlet.java file is rarely used, the URL prior to login defaults to the standard login page.

/agentconfig/*

Associated with the servlet named AgentConfigurationServlet. The associated AgentConfigurationServlet class is called by the amAccessControl.xml file, which suggests that it can be configured from the GUI console, through the Agents section of the Access Control menu. It is rarely used otherwise. The URL prior to login defaults to the standard login page.

/ccversion/*

Associated with the servlet named click-servlet. There is no associated click-servlet.java or ClickServlet.java file.

/federation/*

Associated with the servlet named FSServlet. While the associated FSServlet.java file is rarely used, the URL prior to login defaults to the standard login page.

/webservices

Used by the WSServlet.java and SecurityTokenService.java files. If you're using web services and/or the Security Token Service (STS), you may want to keep this in place.

/sts

Associated with the STS. Be aware, this endpoint exposes basic service and port information for STS, Metadata Exchange (MEX), Simple Object Access Protocol 1.1 (SOAP11), and Web Service Definition Language (WSDL) endpoints without logons.

/sts/mex

Associated with the STS. Be aware, this endpoint exposes basic service and port information for STS, Metadata Exchange (MEX), Simple Object Access Protocol 1.1 (SOAP11), and Web Service Definition Language (WSDL) endpoints without logons.

/sts/soap11

Associated with the STS. Be aware, this endpoint exposes basic service and port information for STS, Metadata Exchange (MEX), Simple Object Access Protocol 1.1 (SOAP11), and Web Service Definition Language (WSDL) endpoints without logons.

/sts/mexsoap11

Associated with the STS. Unlike related STS endpoints, it returns a 404 message by default.

/SPMniSoap/*

Used by a servlet named SPMniSoap; associated with a com.sun.identity.saml2.servlet.SPManageNameIDServiceSOAP servlet class. The associated .java file works with Manage Name ID communications using

SOAP binding from the SP. As the former spMNISOAP.jsp file no longer exists in the trunk, this may be a legacy endpoint.

/SPMniPOST/*

Used by a servlet named spMNIPOST.jsp; previously defined in the SAML2 JSP Endpoints section.

/SPMniRedirect/*

Used by a servlet named spMNIRedirect.jsp; previously defined in the SAML2 ISP Endpoints section.

/SPMniInit/*

Used by a servlet named spMNIRequestInit.jsp; previously defined in the SAML2 JSP Endpoints section.

/SPECP/*

The associated SPECPService class receives and processes single logout (SLO) requests, using SOAP bindings on the SP.

/SPSloSoap/*

The associated SPSingleLogoutServiceSOAP class receives and processes single logout (SLO) requests, using SOAP bindings on the SP.

/SPSloPOST/*

Used by a servlet named spSingleLogoutPOST.jsp; previously defined in the SAML2 JSP Endpoints section.

/SPSloRedirect/*

Used by a servlet named spSingleLogoutRedirect.jsp; previously defined in the SAML2 JSP Endpoints section.

/SPSloInit/*

Used by a servlet named spSingleLogoutInit.jsp; previously defined in the SAML2 JSP Endpoints section.

/Consumer/*, /SSORedirect/*

Used by a servlet named spAssertionConsumer.jsp; previously defined in the SAML2 JSP Endpoints section.

/SSOPOST/*, /SSORedirect/*

Used by a servlet named idpSSOFederate.jsp; previously defined in the SAML2 JSP Endpoints section.

/SSORedirect/*

Used by a servlet named idpSSOFederate.jsp; previously defined in the SAML2 JSP Endpoints section.

/NIMSoap/*

Used by a servlet named NameIDMappingServiceSOAP.

/AIDReqUri/*

Used by a servlet named AssertionIDRequestServiceSoap.

/AIDReqSoap/*

Used by a servlet named AssertionIDRequestServiceSoap.

/AuthnQuerySerivceSoap/*

Used by a servlet named AuthnQueryServiceSoap.

/AttributeServiceSoap/*

Used by a servlet named AttributeServiceSoap.

/SSOSoap/*

Used by a servlet named SSOSoap.

/IDPMniSoap/*

Used by a servlet named IDPMniSoap.

/IDPMniPOST/*

Used by a servlet named idpMNIPOST.jsp; previously defined in the SAML2 JSP Endpoints section.

/IDPMniRedirect/*

Used by a servlet named idpMNIRedirect.jsp; previously defined in the SAML2 JSP Endpoints section.

/IDPMniInit/*

Used by a servlet named idpMNIRequestInit.jsp; previously defined in the SAML2 JSP Endpoints section.

/IDPSloSoap/*

Used by a servlet named IDPSloSoap.

/IDPSloPOST/*

Used by a servlet named idpSingleLogoutPOST.jsp; previously defined in the SAML2 JSP Endpoints section.

/IDPSloRedirect/*

Used by a servlet named idpSingleLogoutRedirect.jsp; previously defined in the SAML2 JSP Endpoints section.

/IDPSloInit/*

Used by a servlet named idpSingleLogoutInit.jsp; previously defined in the SAML2 JSP Endpoints section.

/ArtifactResolver/*

Used by a servlet named IDPArtifactResolver.

/spssoinit

Used by a servlet named spSSOInit.jsp; previously defined in the SAML2 JSP Endpoints section.

/idpssoinit

Used by a servlet named idpSSOInit.jsp; previously defined in the SAML2 JSP Endpoints section.

/idpSS0Federate

Used by a servlet named idpSSOFederate.jsp; previously defined in the SAML2 JSP Endpoints section.

/idpsaehandler/*

Used by a servlet named SA_IDP.jsp; previously defined in the SAML2 JSP Endpoints section.

/spsaehandler/*

Used by a servlet named IDP_SP.jsp; previously defined in the SAML2 JSP Endpoints section.

/idpfinder

Used by a servlet named IDPFinderService; The associated FSIDPFinderService.java file can be used to find a preferred IDP with a common domain cookie.

/cdcservlet

Used by a servlet named CDCServlet. It is associated with a Cross Domain Controller Servlet, as described in the the chapter on $Configuring\ Cross-Domain\ Single\ Sign\ On\ in\ the\ Administration\ Guide$.

/SAMLAwareServlet

Used by a servlet named SAMLAwareServlet. It is associated with communications between a client, an SP, and an IDP. The transfer service on the IDP is the SAML Aware Servlet, and is part of the client web browser artifact profile. It validates a session token from a request run through the IDP.

/SAMLPOSTProfileServlet

Used by a servlet named SAMLPOSTProfileServlet. It is associated with communications between a client, an SP, and an IDP. The transfer service on the IDP is the SAML Aware Servlet, and is part of the client web browser POST profile, which supplies assertion IDs, and returns the response to the client browser.

/SAMLSOAPReceiver

Used by a servlet named SAMLSOAPReceiver. The servlet extracts a SAML request from a message sent in SOAP format. That message can be a query for authorization, attributes, or authentication. It supports POST messages only.

/AssertionManagerServlet/*

Used by a servlet named AssertionManagerServlet. It supports dynamic substitution, using the host name, port number, and the deployment location.

/FSAssertionManagerServlet/*

Used by a servlet named FSAssertionManagerServlet. It provides remote interfaces for the assertion manager class.

/SecurityTokenManagerServlet/*

Used by a servlet named SecurityTokenManagerServlet. It supports dynamic substitution, using session parameters.

/preLogin

Used by a servlet named preLoginHandler. As there is no associated .java or .jsp file, it may be a legacy endpoint.

/postLogin/*

Used by a servlet named postLoginHandler. As there is no associated .java or .jsp file, it may be a legacy endpoint.

/federation

Used by a servlet named FederationServlet. Associated with the com.sun.identity.federation.login.FSFederationHandler class. The matching FSFederationHandler.java file processes requests to initiate a federation.

/consentHandler

Used by a servlet named consentHandler. Associated with the com.sun.identity.federation.login.FSConsentHandler class. The matching FSConsentHandler.java file processes redirect requests in an existing federation.

/ProcessLogout/*

Used by a servlet named ProcessLogout. Associated with the FSProcessLogoutServlet class. It is designed to handle single logout requests related to Kantera / Liberty ID-FF processes.

/ReturnLogout/*

Used by a servlet named ReturnLogout. Associated with the FSReturnLogoutServlet class. It is designed to handle single logout responses related to Kantera / Liberty ID-FF processes. (Note the subtle difference with the ProcessLogout endpoint which handles logout requests.)

/liberty-logout

Used by a servlet named LogoutServlet. Associated with the FSSingleLogoutServlet class. It is designed to start single logout requests related to Kantera / Liberty ID-FF processes.

/SingleSignOnService/*

Used by a servlet named SingleSignOnService. Associated with the FSSSOAndFedService class. Configured for SSO on the IDP.

/IntersiteTransferService

Used by a servlet named IntersiteTransferService. Associated with the FSIntersiteTransferService class. It is designed to send a AuthnRequest to an IDP.

/AssertionConsumerService/*

Used by a servlet named AssertionConsumerService. Associated with the FSAssertionConsumerService class. For more information, see the chapter on *Managing SAML 2.0 Federation in the Administration Guide*.

/SOAPReceiver/*

Used by a servlet named SOAPReceiver. Associated with the FSSOAPReceiver class. SOAP endpoint that handles federation and specifies a URI to the SP.

/federation-terminate

Used by a servlet named FederationTerminationServlet. Associated with the FSTerminationInitiationServlet.java file, used to initiate termination of a federation connection. The IDP will send the termination request to the associated URL.

/ProcessTermination/*

Used by a servlet named ProcessTermination. Associated with the FSTerminationRequestServlet class. The associated .java file is used when a request is received by a remote SP.

/ReturnTermination/*

Used by a servlet named ReturnTermination. Associated with the FSTerminationReturnServlet class. The associated .java file is used to define a URL used by an IP to send termination responses.

/InitiateRegistration/*

Used by a servlet named InitiateRegistration. Associated with the FSRegistrationInitiationServlet class. The associated .java file is used to handle the registration request from a remote IDP.

/ProcessRegistration/*

Used by a servlet named ProcessRegistration. Associated with the FSRegistrationRequestServlet class. Processes registration requests from remote SPs.

/ReturnRegistration/*

Used by a servlet named ReturnRegistration. Associated with the FSRegistrationReturnServlet class. Defines a URL for IDPs to send registration responses.

/Liberty/*

Used by a servlet named WSSOAPReceiver. Associated with the SOAPReceiver class. Defines an endpoint that handles SOAP requests.

/WSPRedirectHandler/*

Used by a servlet named WSPRedirectHandler. Associated with the WSPRedirectHandlerServlet class. Used by the SP for user redirects.

/idffwriter, /saml2writer

Used by a servlet with a matching name (idffwriter, saml2writer). Associated with the CookieWriterServlet class. Used by the IDP to help the web container find app-specific info such as Java classes or Java Archives (JARs).

/idffreader, /saml2reader

Used by a servlet with a matching name (idffreader, saml2reader). Associated with the CookieReaderServlet class. Used by the SP to help find the preferred IDP.

/multiprotocolrelay

Used by a servlet named MultiProtocolRelayServlet. Associated with the MultiProtocolRelayServlet class. Used as a RelayState to continue to the next protocol; associated with a federation.

/WSFederationServlet/*, /FederationMetadata/*

Used by a servlet named WSFederationServlet. Associated with the WSFederationServlet class. Used as a service endpoint for WS-Federation.

/RealmSelection/*

Used by am endpoint named realmSelection.jsp. Previously defined in the WS-Federation JSP Endpoints section.

/saml2query/*

Used by a servlet named saml2query. Associated with the QueryHandlerServlet class. The corresponding .java file receives and processes SAML2 queries.

/federationws/*

Used by a servlet named federationrest. Associated with the ServletContainer class. Does not appear to be included in any current .java or .jsp file, so it may be a legacy endpoint.

/xacml/*

Used by a servlet named XACMLContentAdapter. Associated with the XacmlContentHandlerService class. Provides the main endpoint for all XACML requests.

/frrest/oauth2/*

Used by a servlet named OAuth2Rest. Associated with the RestTokenDispatcher class. class. For more information, see the the chapter on *Using RESTful Web Services*.

/oauth2/registerClient.jsp

Used by a servlet named OAuth2RegisterClient. For more information, see the the Administration Guide chapter on *Managing OAuth 2.0 Authorization*.

/oauth2/*

Used by a servlet named OAuth2RestletAdapter. Associated with the RestTokenDispatcher class. For more information, see the chapter on the chapter on *Using RESTful Web Services*.

/json/*

Used by a servlet named ForgeRockRest. Associated with the HttpServlet class. For more information, see the chapter on $Using \ RESTful \ Web$ Services. In addition, you can read more about associated REST endpoints in reference#json-rest-endpoints $JSON \ REST \ Endpoints$

7.25 JSON REST Endpoints

The endpoints in this section document the REST-based JSON interfaces used for authentication and authorization.

/json/agents

Authorization: Supports the PassThroughAuthorizationFilter. No authorization logic is performed in the filter. Information is logged. The authorization logic is performed by the underlying identity services.

/json/authenticate

Authentication: Supports HTTP GET and POST methods. Can handle Integrated Windows Authentication.

Authorization: No filter.

/json/dashboard

Authorization: Supports the PassThroughAuthorizationFilter. No authorization logic is performed in the filter. Information is logged.

/json/groups

Authorization: Supports the PassThroughAuthorizationFilter. No authorization logic is performed in the filter. Information is logged. The authorization logic is performed by the underlying identity services.

/ison/serverinfo

Authorization: Supports the PassThroughAuthorizationFilter. No authorization logic is performed in the filter. Information is logged. One subendpoint, /json/serverinfo/cookieDomains, supports HTTP GET.

/ison/sessions

Authorization: Supports the SessionResourceAuthZFilter. Allows POST _action=logout for all users. Other functionality is limited to the administrative amadmin superuser.

/json/tokens

 $\label{lem:authorization:supports} Authorization Filter.\ Access \ limited\ to\ the\ amadmin\ superuser.$

/json/users

Authentication: Supports HTTP POST. Uses the _action query parameter with the following allowed values: register, confirm, forgotPassword, forgotPasswordReset.

Authorization: Supports the PassThroughAuthorizationFilter. No authorization logic is performed in the filter. Information is logged. The authorization logic is performed by the underlying identity services.

7.26 Well-Known Endpoints

The endpoints described in this section are Well-Known URIs supported by OpenAM.

/.well-known/openid-configuration

Exposes OpenID Provider configuration by HTTP GET as specified by OpenID Connect Discovery 1.0. No query string parameters are required.

/.well-known/webfinger

Allows a client to retrieve the provider URL for an end user by HTTP GET as specified by OpenID Connect Discovery 1.0.

For an example, see Configuring OpenAM For OpenID Connect Discovery.

Chapter 8 XUI Configuration Parameters

The configuration of the XUI is based on settings in the themeConfig.json file. When OpenAM is installed, this file can be found in the /path/to/webapps/XUI directory.

Interface Stability: Internal

XUI is not supported for production use.

The following table depicts the parameters found in this file. All color codes are standard CSS Hex colors. If there is more than one theme, they may inherit parameters from the default theme.

- themes: Title; also represents an array of theme objects.
 - name: Theme title.
 - path: Relative path to CSS files.
 - realms: For a realm named test, enter ["test.*"].
 - regex: true or false.
 - icon: Filename of icon.
 - settings: Includes logo, lessVars, footer.
 - logo: Parameters for the logo, including src, title, alt, height, width.
 - src: Filename with logo.

- title: Title attribute, shown behind the graphic.
- alt: Text that appears upon cursor hover.
- height: Logo height.
- width: Logo width.
- lessVars: Settings for variables used in LESS CSS stylesheets.
 - background-color: Standard background color; use hex or standard color words.
 - background-image: URL or relative path to file image
 - background-repeat: If set to repeat, fills screen with multiple copies of the image.
 - background-position: Position of the background image, in a format such as left top or right bottom.
 - footer-background-color: Background color of the footer area; hex or standard color words accepted.
 - column-padding: Distance between columns.
 - login-container-width: Width of view box with login text boxes
 - login-container-label-align: Alignment of labels in the login container, such as left, right, or center.
 - message-background-color: Login message background color.
 - content-background: Login container background color.
 - font-color: Login container font color.
 - font-size: Despite the name, this is the distance between login labels and text boxes
 - font-family: Available fonts.
 - site-width: Total width available for the login screen.
 - line-height: Height of text lines.
 - color-active: Border color of active text box and menu option.
 - color-inactive: Border color of inactive text box.

- active-menu-color: Color of active menu option.
- active-menu-font-color: Color of the font used in the active menu option.
- inactive-menu-color: Color of inactive menu options.
- inactive-menu-font-color: Color of font used in the inactive menu options.
- active-menu-color: Color of active menu option.
- button-hover-lightness: Reduction in color, in percent.
- href-color: Color of text links.
- href-color-hover: Color of text links of the optiom currently being hovered over by the pointer
- color-error: Color of error text.
- color-warning: Color of warning text.
- color-success: Color of text of a success message.
- color-info: Color of information message.
- color-inactive: Text color of inactive messages.
- input-border-basic: Border color of active input text box.
- header-border-color: Border color of the header.
- footer-height: Height of the footer.
- footer: Parameters in the footer, typically mailto and phone.
 - mailto: Email address.
 - phone: Telephone number.

Index

Configuration, 123 Authentication, 123 Console, 125 Global, 133 Servers and Sites, 154 System, 126	L Languages supported, 561 Locales supported, 561 Logs Administrative Files, 175 Debug Files, 178 O OpenID Connect, 618
D	Р
Default ports, 559	Ports used, 559
Endpoints, 569 JSP, 570 Base Console, 580 Console Agent Configuration, 578 Console Ajax, 579 Console Authentication, 580 Console Realm, 591 Default Authentication Configuration, 574 Default Console, 577 Delegation Console, 581 Federation Console, 581 IDM Console, 590 Main Directory, 571 OAuth, 602 Password, 602 Policy Console, 585 SAML2, 603 Service Console, 598 Task Console, 598 User Console, 598 User Console, 600 User Interface, 572 Web Services Console, 601 WS Federation, 606 WEB-INF, 606 Well-Known, 618 Error messages Authentication, 555	R REST JSON, 617 S Supported languages, 561 Supported locales, 561 Supported standards Liberty ID-FF, 566 OAuth 2.0, 565 OpenID Connect 1.0, 565 REST, 566 SAML, 566 SOAP, 566 WS-Federation, 566 WSDL, 566 XACML, 566

Console, 557

565