Data Types

Every value in Rust is of a certain *data type*, which tells Rust what kind of data is being specified so it knows how to work with that data. We'll look at two data type subsets: scalar and compound.

Keep in mind that Rust is a *statically typed* language, which means that it must know the types of all variables at compile time. The compiler can usually infer what type we want to use based on the value and how we use it. In cases when many types are possible, such as when we converted a String to a numeric type using parse in the "Comparing the Guess to the Secret Number" section in Chapter 2, we must add a type annotation, like this:

```
let guess: u32 = "42".parse().expect("Not a number!");
```

If we don't add the : u32 type annotation shown in the preceding code, Rust will display the following error, which means the compiler needs more information from us to know which type we want to use:

error: could not compile `no_type_annotations` due to previous error

You'll see different type annotations for other data types.

Scalar Types

A *scalar* type represents a single value. Rust has four primary scalar types: integers, floating-point numbers, Booleans, and characters. You may recognize these from other programming languages. Let's jump into how they work in Rust.

Integer Types

An *integer* is a number without a fractional component. We used one integer type in Chapter 2, the u32 type. This type declaration indicates that the value it's associated with should be an unsigned integer (signed integer types start with i instead of u) that takes up 32 bits of space. Table 3-1 shows the built-in integer types in Rust. We can use any of these variants to declare the type of an integer value.

Table 3-1: Integer Types in Rust

Length	Signed	Unsigned
8-bit	i8	u8
16-bit	i16	u16
32-bit	i32	u32
64-bit	i64	u64
128-bit	i128	u128
arch	isize	usize

Each variant can be either signed or unsigned and has an explicit size. *Signed* and *unsigned* refer to whether it's possible for the number to be negative—in other words, whether the number needs to have a sign with it (signed) or whether it will only ever be positive and can therefore be represented without a sign (unsigned). It's like writing numbers on paper: when the sign matters, a number is shown with a plus sign or a minus sign; however, when it's safe to assume the number is positive, it's shown with no sign. Signed numbers are stored using two's complement representation.

Each signed variant can store numbers from $-(2^{n-1})$ to 2^{n-1} - 1 inclusive, where n is the number of bits that variant uses. So an $\frac{1}{8}$ can store numbers from $-(2^7)$ to 2^7 - 1, which equals -128 to 127. Unsigned variants can store numbers from 0 to 2^n - 1, so a us can store numbers from 0 to 2^8 - 1, which equals 0 to 255.

Additionally, the isize and usize types depend on the architecture of the computer your program is running on, which is denoted in the table as "arch": 64 bits if you're on a 64-bit architecture and 32 bits if you're on a 32-bit architecture.

You can write integer literals in any of the forms shown in Table 3-2. Note that number literals that can be multiple numeric types allow a type suffix, such as 57u8, to designate the type. Number literals can also use $_$ as a visual separator to make the number easier to read, such as 1_000 , which will have the same value as if you had specified 1000.

Table 3-2: Integer Literals in Rust

Number literals	Example
Decimal	98_222
Hex	0xff
Octal	0077
Binary	0b1111_0000
Byte (u8 only)	b'A'

So how do you know which type of integer to use? If you're unsure, Rust's defaults are generally good places to start: integer types default to i32. The primary situation in which you'd use isize or usize is when indexing some sort of collection.