# COMP201

Computer
Systems &
Programming





Aykut Erdem // Koç University // Fall 2020

# Recap

- Static Linking
- Symbol Resolution
- Relocation
- Static Libraries

# Plan for Today

- Shared Libraries
- Case study: Library interpositioning
- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Method 0: Bump Allocator
- Method 1: Implicit Free List Allocator
- Method 2: Explicit Free List Allocator


**Disclaimer:** Slides for this lecture were borrowed from

—Nick Troccoli's Stanford CS107 class

### Lecture Plan

- Shared Libraries
- Case study: Library interpositioning
- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Method 0: Bump Allocator
- Method 1: Implicit Free List Allocator
- Method 2: Explicit Free List Allocator

# Recap: Linking with Static Libraries



### Modern Solution: Shared Libraries

### Static libraries have the following disadvantages:

- Duplication in the stored executables (every function needs libc)
- Duplication in the running executables
- Minor bug fixes of system libraries require each application to explicitly relink


### Modern solution: Shared Libraries

- Object files that contain code and data that are loaded and linked into an application dynamically, at either load-time or run-time
- Also called: dynamic link libraries, DLLs, .so files

# Shared Libraries (cont.)

- Dynamic linking can occur when executable is first loaded and run (load-time linking).
  - Common case for Linux, handled automatically by the dynamic linker (ld-linux.so).
  - Standard C library (libc.so) usually dynamically linked.
- Dynamic linking can also occur after program has begun (run-time linking).
  - In Linux, this is done by calls to the dlopen() interface.
    - Distributing software.
    - High-performance web servers.
    - Runtime library interpositioning.
- Shared library routines can be shared by multiple processes.
  - More on this when you learn about virtual memory

# Dynamic Linking at Load-time



# Dynamic Linking at Run-time

```
#include <stdio.h>
#include <stdlib.h>
#include <dlfcn.h>
int x[2] = \{1, 2\};
int y[2] = \{3, 4\};
int z[2];
int main()
    void *handle;
    void (*addvec)(int *, int *, int *, int);
    char *error;
    /* Dynamically load the shared library that contains addvec() */
    handle = dlopen("./libvector.so", RTLD_LAZY);
    if (!handle) {
        fprintf(stderr, "%s\n", dlerror());
        exit(1);
                                                                                 dll.c
```

# Dynamic Linking at Run-time

```
/* Get a pointer to the addvec() function we just loaded */
addvec = dlsym(handle, "addvec");
if ((error = dlerror()) != NULL) {
    fprintf(stderr, "%s\n", error);
    exit(1);
/* Now we can call addvec() just like any other function */
addvec(x, y, z, 2);
printf("z = [%d %d]\n", z[0], z[1]);
/* Unload the shared library */
if (dlclose(handle) < 0) {</pre>
    fprintf(stderr, "%s\n", dlerror());
    exit(1);
return 0;
                                                                             dll.c
```

# Linking Summary

 Linking is a technique that allows programs to be constructed from multiple object files.

- Linking can happen at different times in a program's lifetime:
  - Compile time (when a program is compiled)
  - Load time (when a program is loaded into memory)
  - Run time (while a program is executing)
- Understanding linking can help you avoid nasty errors and make you a better programmer.

### Lecture Plan

- Shared Libraries
- Case study: Library interpositioning
- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Method 0: Bump Allocator
- Method 1: Implicit Free List Allocator
- Method 2: Explicit Free List Allocator

# Case Study: Library Interpositioning

- Library interpositioning: powerful linking technique that allows programmers to intercept calls to arbitrary functions
- Interpositioning can occur at:
  - Compile time: When the source code is compiled
  - Link time: When the relocatable object files are statically linked to form an executable object file
  - Load/run time: When an executable object file is loaded into memory, dynamically linked, and then executed.

# Some Interpositioning Applications

### Security

- Confinement (sandboxing)
- Behind the scenes encryption

### Debugging

- In 2014, two Facebook engineers debugged a treacherous 1-year old bug in their iPhone app using interpositioning
- Code in the SPDY networking stack was writing to the wrong location
- Solved by intercepting calls to Posix write functions (write, writev, pwrite)

Source: Facebook engineering blog post at https://code.facebook.com/posts/313033472212144/debugging-file-corruption-on-ios/

# Some Interpositioning Applications

### Monitoring and Profiling

- Count number of calls to functions
- Characterize call sites and arguments to functions
- Malloc tracing
  - Detecting memory leaks
  - Generating address traces

# Example program

```
#include <stdio.h>
#include <malloc.h>

int main()
{
    int *p = malloc(32);
    free(p);
    return(0);
}
```

- Goal: trace the addresses and sizes of the allocated and freed blocks, without breaking the program, and without modifying the source code.
- Three solutions: interpose on the lib malloc and free functions at compile time, link time, and load/run time.

### #ifdef COMPILETIME #include <stdio.h> #include <malloc.h> /\* malloc wrapper function \*/ void \*mymalloc(size t size) void \*ptr = malloc(size); printf("malloc(%d)=%p\n", (int)size, ptr); return ptr; /\* free wrapper function \*/ void myfree(void \*ptr) free(ptr); printf("free(%p)\n", ptr); #endif

# Compile-time Interpositioning

mymalloc.c

# Compile-time Interpositioning

```
#define malloc(size) mymalloc(size)
#define free(ptr) myfree(ptr)

void *mymalloc(size_t size);
void myfree(void *ptr);

malloc.h
```

```
linux> make intc
gcc -Wall -DCOMPILETIME -c mymalloc.c
gcc -Wall -I. -o intc int.c mymalloc.o
linux> make runc
./intc
malloc(32)=0x1edc010
free(0x1edc010)
linux>
```

# Link-time Interpositioning

```
#ifdef LINKTIME
#include <stdio.h>
void * real malloc(size t size);
void __real_free(void *ptr);
/* malloc wrapper function */
void * wrap malloc(size t size)
   void *ptr = __real_malloc(size); /* Call libc malloc */
   printf("malloc(%d) = %p\n", (int)size, ptr);
    return ptr;
/* free wrapper function */
void wrap free(void *ptr)
    real free(ptr); /* Call libc free */
   printf("free(%p)\n", ptr);
#endif
```

# Link-time Interpositioning

```
linux> make intl
gcc -Wall -DLINKTIME -c mymalloc.c
gcc -Wall -c int.c
gcc -Wall -Wl,--wrap,malloc -Wl,--wrap,free -o intl int.o mymalloc.o
linux> make runl
./intl
malloc(32) = 0x1aa0010
free(0x1aa0010)
linux>
```

- The "-W1" flag passes argument to linker, replacing each comma with a space.
- The "--wrap, malloc" arg instructs linker to resolve references in a special way:
  - Refs to malloc should be resolved as wrap malloc
  - Refs to \_\_real\_malloc should be resolved as malloc

### #ifdef RUNTIME #define \_GNU\_SOURCE #include <stdio.h> #include <stdlib.h> #include <dlfcn.h> /\* malloc wrapper function \*/ void \*malloc(size\_t size) void \*(\*mallocp)(size t size); char \*error; mallocp = dlsym(RTLD NEXT, "malloc"); /\* Get addr of libc malloc \*/ if ((error = dlerror()) != NULL) { fputs(error, stderr); exit(1); char \*ptr = mallocp(size); /\* Call libc malloc \*/ printf("malloc(%d) = %p\n", (int)size, ptr); return ptr;

# Load/Run-time Interpositioning

mymalloc.c

# Load/Run-time Interpositioning

```
/* free wrapper function */
void free(void *ptr)
   void (*freep)(void *) = NULL;
    char *error;
    if (!ptr)
        return;
    freep = dlsym(RTLD_NEXT, "free"); /* Get address of libc free */
    if ((error = dlerror()) != NULL) {
        fputs(error, stderr);
        exit(1);
    freep(ptr); /* Call libc free */
    printf("free(%p)\n", ptr);
                                                                            mymalloc.c
#endif
```

# Load/Run-time Interpositioning

```
linux> make intr
gcc -Wall -DRUNTIME -shared -fpic -o mymalloc.so mymalloc.c -ldl
gcc -Wall -o intr int.c
linux> make runr
(LD_PRELOAD="./mymalloc.so" ./intr)
malloc(32) = 0xe60010
free(0xe60010)
linux>
```

• The LD\_PRELOAD environment variable tells the dynamic linker to resolve unresolved refs (e.g., to malloc) by looking in mymalloc.so first.

# Interpositioning Recap

### Compile Time

 Apparent calls to malloc/free get macro-expanded into calls to mymalloc/myfree

### Link Time

- Use linker trick to have special name resolutions
  - malloc → \_\_wrap\_malloc
  - \_\_real\_malloc → malloc

### Load/Run Time

 Implement custom version of malloc/free that use dynamic linking to load library malloc/free under different names

# COMP201 Topic 8: How do the core malloc/realloc/free memory-allocation operations work?

## How do malloc/realloc/free work?

Pulling together all our COMP201 topics this semester:

- Testing
- Efficiency
- Bit-level manipulation
- Memory management
- Pointers
- Generics
- Assembly
- And more...

# Learning Goals

- Learn the restrictions, goals and assumptions of a heap allocator
- Understand the conflicting goals of utilization and throughput
- Learn about different ways to implement a heap allocator


### Lecture Plan

- Shared Libraries
- Case study: Library interpositioning
- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Method 0: Bump Allocator
- Method 1: Implicit Free List Allocator
- Method 2: Explicit Free List Allocator


# Running a program

- Creates new process
- Sets up address space/segments
- Read executable file, load instructions, global data
   Mapped from file into gray segments
- Libraries loaded on demand


- Set up stack
   Reserve stack segment, init %rsp, call main
- malloc written in C, will init self on use Asks OS for large memory region, parcels out to service requests



### The Stack Revisited



# Today: The Heap



Heap memory persists until caller indicates it no longer needs it.

Managed by C standard library functions (malloc, realloc, free)

This lecture:
How does heap
management work?

### Lecture Plan

- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Method 0: Bump Allocator
- Method 1: Implicit Free List Allocator
- Method 2: Explicit Free List Allocator

### Your role so far: Client

```
void *malloc(size_t size);
```

Returns a pointer to a block of heap memory of at least size bytes, or NULL if an error occurred.


### void free(void \*ptr);

Frees the heap-allocated block starting at the specified address.

### void \*realloc(void \*ptr, size\_t size);

Changes the size of the heap-allocated block starting at the specified address to be the new specified size. Returns the address of the new, larger allocated memory region.


# Your role now: Heap Hotel Concierge



(aka **Heap Allocator**)

# What is a heap allocator?

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).



# What is a heap allocator?

0x13

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

Request 1: Hi! May I please have 2 bytes of heap memory?

0x12

0x11

0x10

Allocator: Sure, I've given you address 0x10.

0x18

AVAILABLE

0x15

0x16

0x17


0x14

0x19

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

Request 1: Hi! May I please have 2 bytes of heap memory?

Allocator: Sure, I've given you address 0x10.



- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

Request 2: Howdy!
May I please have 3
bytes of heap memory?

Allocator: Sure, I've given you address 0x12.

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
FOR RI	EQUEST 1				AVA	ILABLE			


- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

Request 2: Howdy!
May I please have 3
bytes of heap memory?


Allocator: Sure, I've given you address 0x12.

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
FOR REC	QUEST 1	FC	OR REQUE	ST 2			AVAILAB	LE	

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no longer need pieces of it.



- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no longer need pieces of it.



- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no longer need pieces of it.

Request 3: Hello there! I'd like to request 2 bytes of heap memory, please.

Allocator: Sure thing. I've given you address 0x10.

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
AVA	ILABLE	F	OR REQUE	ST 2			AVAILAB	LE	

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no longer need pieces of it.

Request 3: Hello there!
I'd like to request 2 bytes of heap memory, please.

Allocator: Sure thing. I've given you address 0x10.

0×10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
FOR RE	EQUEST 3	F	OR REQUE	ST 2			AVAILAB	LE	

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no longer need pieces of it.

Request 3: Hi again!
I'd like to request the region of memory at 0x10 be reallocated to 4 bytes.

Allocator: Sure thing. I've given you address 0x15.

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
FOR REQ	UEST 3	FO	R REQUES	ST 2			AVAILABI	_E	

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no longer need pieces of it.

Request 3: Hi again!
I'd like to request the region of memory at 0x10 be reallocated to 4 bytes.

Allocator: Sure thing. I've given you address 0x15.

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
AVAI	LABLE	FC	OR REQUE	EST 2		FOR RE	EQUEST 3		AVAILABLE

#### Lecture Plan

- Shared Libraries
- Case study: Library interpositioning
- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Method 0: Bump Allocator
- Method 1: Implicit Free List Allocator
- Method 2: Explicit Free List Allocator

## Heap Allocator Functions

```
void *malloc(size_t size);

void free(void *ptr);

void *realloc(void *ptr, size_t size);
```

A heap allocator must...

- 1. Handle arbitrary request sequences of allocations and frees
- 2. Keep track of which memory is allocated and which is available
- 3. Decide which memory to provide to fulfill an allocation request
- 4. Immediately respond to requests without delay

A heap allocator must...

- 1. Handle arbitrary request sequences of allocations and frees
- 2. Keep track of which memory is allocated and which is available
- 3. Decide which memory to provide to fulfill an allocation request
- 4. Immediately respond to requests without delay

A heap allocator cannot assume anything about the order of allocation and free requests, or even that every allocation request is accompanied by a matching free request.

A heap allocator must...

- 1. Handle arbitrary request sequences of allocations and frees
- 2. Keep track of which memory is allocated and which is available
- 3. Decide which memory to provide to fulfill an allocation request
- 4. Immediately respond to requests without delay

A heap allocator marks memory regions as **allocated** or **available**. It must remember which is which to properly provide memory to clients.

A heap allocator must...

- 1. Handle arbitrary request sequences of allocations and frees
- 2. Keep track of which memory is allocated and which is available
- 3. Decide which memory to provide to fulfill an allocation request
- 4. Immediately respond to requests without delay

A heap allocator may have options for which memory to use to fulfill an allocation request. It must decide this based on a variety of factors.

A heap allocator must...

- 1. Handle arbitrary request sequences of allocations and frees
- 2. Keep track of which memory is allocated and which is available
- 3. Decide which memory to provide to fulfill an allocation request
- 4. Immediately respond to requests without delay

A heap allocator must respond immediately to allocation requests and should not e.g. prioritize or reorder certain requests to improve performance.

A heap allocator must...

- 1. Handle arbitrary request sequences of allocations and frees
- 2. Keep track of which memory is allocated and which is available
- 3. Decide which memory to provide to fulfill an allocation request
- 4. Immediately respond to requests without delay
- 5. Return addresses that are 8-byte-aligned (must be multiples of 8).

## Heap Allocator Goals

- Goal 1: Maximize **throughput**, or the number of requests completed per unit time. This means minimizing the average time to satisfy a request.
- <u>Goal 2:</u> Maximize memory **utilization**, or how efficiently we make use of the limited heap memory to satisfy requests.

#### Utilization

- The primary cause of poor utilization is fragmentation. Fragmentation occurs when otherwise unused memory is not available to satisfy allocation requests.
- In this example, there is enough aggregate free memory to satisfy the request, but no single free block is large enough to handle the request.
- In general: we want the largest address used to be as low as possible.

Request 6: Hi! May I please have 4 bytes of heap memory?

Allocator: I'm sorry, I don't have a 4 byte block available...

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
Req. 1	Free	Req. 2	Free	Req. 3	Free	Req. 4	Free	Req. 5	Free

#### Utilization

Question: what if we shifted these blocks down to make more space? Can we do this?

- A. YES, great idea!
- B. YES, it can be done, but not a good idea for some reason (e.g. not efficient use of time)
- C. NO, it can't be done!

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
Req. 1	Req. 2	Req. 3	Req. 4	Req. 5			Free		

### Utilization

Question: what if we shifted these blocks down to make more space? Can we do this?

• No - we have already guaranteed these addresses to the client. We cannot move allocated memory around, since this will mean the client will now have incorrect pointers to their memory!

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0×17	0x18	0x19
Req. 1	Req. 2	Req. 3	Req. 4	Req. 5			Free		

## Fragmentation

- Internal Fragmentation: an allocated block is larger than what is needed (e.g. due to minimum block size)
- External Fragmentation: no single block is large enough to satisfy an allocation request, even though enough aggregate free memory is available

## Heap Allocator Goals

- Goal 1: Maximize **throughput**, or the number of requests completed per unit time. This means minimizing the average time to satisfy a request.
- Goal 2: Maximize memory **utilization**, or how efficiently we make use of the limited heap memory to satisfy requests.

These are seemingly conflicting goals – for instance, it may take longer to better plan out heap memory use for each request.

Heap allocators must find an appropriate balance between these two goals!

## Heap Allocator Goals

- Goal 1: Maximize throughput, or the number of requests completed per unit time. This means minimizing the average time to satisfy a request.
- Goal 2: Maximize memory utilization, or how efficiently we make use of the limited heap memory to satisfy requests.

Other desirable goals:

Locality ("similar" blocks allocated close in space)

Robust (handle client errors)

Ease of implementation/maintenance

#### Lecture Plan

- Shared Libraries
- Case study: Library interpositioning
- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Method 0: Bump Allocator
- Method 1: Implicit Free List Allocator
- Method 2: Explicit Free List Allocator

Let's say we want to entirely prioritize throughput, and do not care about utilization at all. This means we do not care about reusing memory. How could we do this?

# 1. Utilization 2. Throughput






**Never** reuses memory

**Ultra** fast, short routines

- A **bump allocator** is a heap allocator design that simply allocates the next available memory address upon an allocate request and does nothing on a free request.
- Throughput: each malloc and free execute only a handful of instructions:
  - It is easy to find the next location to use
  - Free does nothing!
- Utilization: we use each memory block at most once. No freeing at all, so no memory is ever reused. 🕾

```
void *a = malloc(8);
void *b = malloc(4);
void *c = malloc(24);
free(b);
void *d = malloc(8);
```



```
void *a = malloc(8);
void *b = malloc(4);
void *c = malloc(24);
free(b);
void *d = malloc(8);
```

Variable	Value
a	0x10

0x10 0x	14 0x18	0x1c	0x20	0x24	0x28	0x2c	0x30	0x34
а				AV	AILABLE			

```
void *a = malloc(8);
void *b = malloc(4);
void *c = malloc(24);
free(b);
void *d = malloc(8);
```

Variable	Value
а	0x10
b	0x18

0x10 0x14	0x18 0x1c 6	0x20 0x24	0x28	0x2c	0x30	0x34
а			AV	AILABLE		

```
void *a = malloc(8);
void *b = malloc(4);
void *c = malloc(24);
free(b);
void *d = malloc(8);
```

Variable	Value
a	0x10
b	0x18
С	0x20

0x10 0x1	.4 0x18	0x1c	0x20	0x24	0x28	0x2c	0x30	0x34
а	k	+ padding	9			С		

```
void *a = malloc(8);
void *b = malloc(4);
void *c = malloc(24);
free(b);
void *d = malloc(8);
```

Variable	Value
а	0x10
b	0x18
С	0x20

0x10 0x14	0x18	0x1c	0x20	0x24	0x28	0x2c	0x30	0x34
а	b	+ padding	9			С		

```
void *a = malloc(8);
void *b = malloc(4);
void *c = malloc(24);
free(b);
void *d = malloc(8);
```

Variable	Value				
a	0x10				
b	0x18				
С	0x20				
d	NULL				

0x10	0x14	0x18	0x1c	0x20	0x24	0x28	0x2c	0x30	0x34
	а	b +	padding				С		

## Summary: Bump Allocator

- A bump allocator is an extreme heap allocator it optimizes only for throughput, not utilization.
- Better allocators strike a more reasonable balance. How can we do this?

#### Questions to consider:

- 1. How do we keep track of free blocks?
- 2. How do we choose an appropriate free block in which to place a newly allocated block?
- 3. After we place a newly allocated block in some free block, what do we do with the remainder of the free block?
- 4. What do we do with a block that has just been freed?

#### Lecture Plan

- Shared Libraries
- Case study: Library interpositioning
- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Method 0: Bump Allocator
- Method 1: Implicit Free List Allocator
- Method 2: Explicit Free List Allocator

- **Key idea:** in order to reuse blocks, we need a way to track which blocks are allocated and which are free.
- We could store this information in a separate global data structure, but this is inefficient.
- Instead: let's allocate extra space before each block for a **header** storing its payload size and whether it is allocated or free.
- When we allocate a block, we look through the blocks to find a free one, and we update its header to reflect its allocated size and that it is now allocated.
- When we free a block, we update its header to reflect it is now free.
- The header should be 8 bytes (or larger).
- By storing the block size of each block, we implicitly have a list of free blocks.

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
0x10
       0x18
                     0x28
              0x20
                            0x30
                                   0x38
                                          0x40
                                                 0x48
                                                         0x50
                                                                0x58
 72
Free
```

```
Variable
void *a = malloc(4);
                                                                Value
void *b = malloc(8);
                                                                0x18
 void *c = malloc(4);
 free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
0x10
       0x18
              0x20
                      0x28
                             0x30
                                    0x38
                                            0x40
                                                   0x48
                                                          0x50
                                                                  0x58
  8
                56
        a +
Used
               Free
        pad
```

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```

Variable	Value
а	0x18
b	0x28

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Used	a + pad	8 Used	Ь	40 Free					

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```

Variable	Value
a	0x18
b	0x28
С	0x38

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Used	a + pad	8 Used	b	8 Used	c + pad	24 Free			

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```

Variable	Value
a	0x18
b	0x28
С	0x38

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Used	a + pad	8 Free	b	8 Used	c + pad	24 Free			

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```

Variable	Value
a	0x18
b	0x28
С	0x38
d	0x28

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Used	a + pad	8 Used	d	8 Used	c + pad	24 Free			

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```

Variable	Value				
a	0x18				
b	0x28				
С	0x38				
d	0x28				

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	d	8 Used	c + pad	24 Free			

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```

Variable	Value
а	0x18
b	0x28
С	0x38
d	0x28
е	0x48

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	d	8 Used	c + pad	24 Used		е	

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```

Value
0x18
0x28
0x38
0x28
0x48

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	d	8 Used	c + pad	24 Used		е	

# Representing Headers

How can we store both a size and a status (Free/Allocated) in 8 bytes?

Int for size, int for status? no! malloc/realloc use size\_t for sizes!

**Key idea:** block sizes will *always be multiples of 8*. (Why?)

- Least-significant 3 bits will be unused!
- Solution: use one of the 3 least-significant bits to store free/allocated status


How can we choose a free block to use for an allocation request?

- First fit: search the list from beginning each time and choose first free block that fits.
- Next fit: instead of starting at the beginning, continue where previous search left off.
- Best fit: examine every free block and choose the one with the smallest size that fits.
- First fit/next fit easier to implement
- What are the pros/cons of each approach?

# Implicit Free List Summary

#### For all blocks,

- Have a header that stores size and status.
- Our list links *all* blocks, allocated (A) and free (F).



#### Keeping track of free blocks:

- Improves memory utilization (vs bump allocator)
- Decreases throughput (worst case allocation request has O(A + F) time)
- Increases design complexity ©

Up to you!

```
void *e = malloc(16);
```

So far, we have seen that a reasonable allocation request splits a free block into an allocated block and a free block with remaining space. What about edge cases?

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	d	8 Used	c + pad	24 Free			

Up to you!

```
void *e = malloc(16);
```

So far, we have seen that a reasonable allocation request splits a free block into an allocated block and a free block with remaining space. What about edge cases?

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	d	8 Used	c + pad	16 Used		е	???

Up to you!

```
void *e = malloc(16);
```

So far, we have seen that a reasonable allocation request splits a free block into an allocated block and a free block with remaining space. What about edge cases?

**A. Throw into allocation for** e **as extra padding?** *Internal fragmentation – unused bytes because of padding* 

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	d	8 Used	c + pad	24 Used		e + pac	d

Up to you!

```
void *e = malloc(16);
```

So far, we have seen that a reasonable allocation request splits a free block into an allocated block and a free block with remaining space. What about edge cases?

A. Throw into allocation for e as extra padding?

**B. Make a "zero-byte free block"?** External fragmentation – unused free blocks

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	d	8 Used	c + pad	16 Used		е	0 Free

# Revisiting Our Goals

#### Questions we considered:

- 1. How do we keep track of free blocks? Using headers!
- 2. How do we choose an appropriate free block in which to place a newly allocated block? **Iterate through all blocks**.
- 3. After we place a newly allocated block in some free block, what do we do with the remainder of the free block? **Try to make the most of it!**
- 4. What do we do with a block that has just been freed? **Update its** header!

# Implicit Allocator

- **Must have** headers that track block information (size, status in-use or free) –you must use the 8 byte header size, storing the status using the free bits (this is larger than the 4 byte headers specified in the book, as this makes it easier to satisfy the alignment constraint and store information).
- Must have free blocks that are recycled and reused for subsequent malloc requests if possible
- Must have a malloc implementation that searches the heap for free blocks via an implicit list (i.e. traverses block-by-block).
- Does not need to have coalescing of free blocks
- Does not need to support in-place realloc

# Coalescing


```
void *e = malloc(24); // returns NULL!
```

You do not need to worry about this problem for the implicit allocator, but this is a requirement for the *explicit* allocator! (More about this later).

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free		8 Free		8 Free		24 Used			

#### In-Place Realloc

```
void *a = malloc(4);
void *b = realloc(a, 8);
```



#### In-Place Realloc

```
void *a = malloc(4);
void *b = realloc(a, 8);
```

Variable	Value
a	0x10

0x10	0x18	0×20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8	a +	56							
Used	pad	Free							
	ı								

#### In-Place Realloc

```
void *a = malloc(4);
void *b = realloc(a, 8);
```

Variable	Value
а	0x10
b	0x28

The implicit allocator can always move memory to a new location for a realloc request. The *explicit* allocator must support in-place realloc (more on this later).

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	b	40 Free					

# Summary: Implicit Allocator

 An implicit allocator is a more efficient implementation that has reasonable throughput and utilization due to its recycling of blocks.

#### Can we do better?

- 1. Can we avoid searching all blocks for free blocks to reuse?
- 2. Can we merge adjacent free blocks to keep large spaces available?
- 3. Can we avoid always copying/moving data during realloc?

## Recap

- Shared Libraries
- Case study: Library interpositioning
- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Method 0: Bump Allocator
- Method 1: Implicit Free List Allocator

#### Practice 1

• For the following heap layout, what would the heap look like after the following request is made, assuming we are using an **implicit** free list allocator with a **first-fit** approach?

[24 byte payload, free] [16 byte payload, free] [8 byte payload, allocated for A]

```
void *b = malloc(8);
```

[8 byte payload, allocated for B] [8 byte payload, free] [16 byte payload, free] [8 byte payload, allocated for A]

#### Practice 2

• For the following heap layout, what would the heap look like after the following request is made, assuming we are using an **implicit** free list allocator with a **best-fit** approach?

[24 byte payload, free] [8 byte payload, free] [8 byte payload, allocated for A]

void \*b = malloc(8);

[24 byte payload, free] [8 byte payload, allocated for B] [8 byte payload, allocated for A]