COMP201

Computer
Systems &
Programming





Aykut Erdem // Koç University // Fall 2021

Recap

- Static Linking
- Symbol Resolution
- Relocation
- Static Libraries
- Shared Libraries

Plan for Today

- The Heap So Far
- What Is A Heap Allocator?
- Heap Allocator Requirements and Goals
- Bump Allocator
- Implicit Free List Allocator
- Explicit Free List Allocator

Disclaimer: Slides for this lecture were borrowed from

- —Nick Troccoli's Stanford CS107 class
- —Ruth Anderson's UW CSE 351 class

Multiple Ways to Store Program Data

- Static global data
 - Fixed size at compile-time
 - Entire lifetime of the program (loaded from executable)
 - Portion is read-only (e.g. string literals)
- Stack-allocated data
 - Local/temporary variables
 - Can be dynamically sized (in some versions of C)
 - Known lifetime (deallocated on return)

Dynamic (heap) data

- Size known only at runtime (i.e. based on user-input)
- Lifetime known only at runtime (long-lived data structures)

```
int array[1024];
int* foo(int n) {
  int tmp;
  int local_array[n];

int* dyn =
    (int*)malloc(n*sizeof(int));
  return dyn;
}
```

COMP201 Topic 8: How do the core malloc/realloc/free memory-allocation operations work?

How do malloc/realloc/free work?

Pulling together all our COMP201 topics this semester:

- Testing
- Efficiency
- Bit-level manipulation
- Memory management
- Pointers
- Generics
- Assembly
- And more...

Learning Goals

- Learn the restrictions, goals and assumptions of a heap allocator
- Understand the conflicting goals of utilization and throughput
- Learn about different ways to implement a heap allocator


Lecture Plan

- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Bump Allocator
- Implicit Free List Allocator
- Explicit Free List Allocator


Running a program

- Creates new process
- Sets up address space/segments
- Read executable file, load instructions, global data
 Mapped from file into gray segments
- Libraries loaded on demand


- Set up stack
 Reserve stack segment, init %rsp, call main
- malloc written in C, will init self on use Asks OS for large memory region, parcels out to service requests



The Stack Revisited



Today: The Heap



Heap memory persists until caller indicates it no longer needs it.

Managed by C standard library functions (malloc, realloc, free)

This lecture:
How does heap
management work?

Lecture Plan

- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Bump Allocator
- Implicit Free List Allocator
- Explicit Free List Allocator

Revisited: Allocating Memory in C

- Need to #include <stdlib.h>
- void* malloc(size_t size)
 - Allocates a continuous block of size bytes of uninitialized memory
 - Returns a pointer to the beginning of the allocated block; NULL indicates failed request
 - Typically aligned to an 8-byte (x86) or 16-byte (x86-64) boundary
 - Returns NULL if allocation failed (also sets errno) or size==0
 - Different blocks not necessarily adjacent
- Good practices:
 - -ptr = (int*) malloc(n*sizeof(int));
 - sizeof makes code more portable
 - void* is implicitly cast into any pointer type; explicit typecast will help you catch coding errors when pointer types don't match

Revisited: Allocating Memory in C

- Need to #include <stdlib.h>
- void* malloc(size_t size)
 - Allocates a continuous block of size bytes of uninitialized memory
 - Returns a pointer to the beginning of the allocated block; **NULL** indicates failed request
 - Typically aligned to an 8-byte (x86) or 16-byte (x86-64) boundary
 - Returns NULL if allocation failed (also sets errno) or size==0
 - Different blocks not necessarily adjacent
- Related functions:
 - void* calloc(size_t nitems, size_t size)
 - "Zeros out" allocated block
 - void* realloc(void* ptr, size_t size)
 - Changes the size of a previously allocated block (if possible)
 - void* sbrk(intptr_t increment)
 - Used internally by allocators to grow or shrink the heap

Revisited: Freeing Memory in C

- Need to #include <stdlib.h>
- void free(void* p)
 - Releases whole block pointed to by **p** to the pool of available memory
 - Pointer p must be the address originally returned by m/c/realloc (i.e. beginning of the block), otherwise system exception raised
 - Don't call free on a block that has already been released or on NULL

Memory Allocation Example in C

```
void foo(int n, int m) {
  int i, *p;
  p = (int*) malloc(n*sizeof(int));
                                     /* allocate block of n ints */
                                            /* check for allocation error */
  if (p == NULL) {
    perror("malloc");
    exit(0);
  for (i=0; i<n; i++)
                                            /* initialize int array */
    p[i] = i;
                                            /* add space for m ints to end of p block */
  p = (int*) realloc(p,(n+m)*sizeof(int));
  if (p == NULL) {
                                            /* check for allocation error */
   perror("realloc");
    exit(0);
  for (i=n; i < n+m; i++)
                                            /* initialize new spaces */
    p[i] = i;
  for (i=0; i<n+m; i++)</pre>
                                            /* print new array */
   printf("%d\n", p[i]);
  free(p);
                                            /* free p */
```

Your role so far: Client

```
void *malloc(size_t size);
```

Returns a pointer to a block of heap memory of at least size bytes, or NULL if an error occurred.

void free(void *ptr);

Frees the heap-allocated block starting at the specified address.

void *realloc(void *ptr, size_t size);

Changes the size of the heap-allocated block starting at the specified address to be the new specified size. Returns the address of the new, larger allocated memory region.

Your role now: Heap Hotel Concierge



(aka **Heap Allocator**)


Types of heap allocators

- Explicit allocator: programmer allocates and frees space
 - -Example: malloc and free in C


- Implicit allocator: programmer only allocates space (no free)
 - Example: garbage collection in Java, Caml, and Lisp

Dynamic memory allocation

- Allocator organizes heap as a collection of variable-sized blocks, which are either allocated or free
 - Allocator requests pages in the heap region; virtual memory hardware and OS kernel allocate these pages to the process
 - Application objects are typically smaller than pages, so the allocator manages blocks within pages
 - (Larger objects handled too; ignored here)



- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).



0x13

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

0x14

Request 1: Hi! May I please have 2 bytes of heap memory?

0x12

0x11

0x10

Allocator: Sure, I've given you address 0x10.

0x18

AVAILABLE

0x16

0x17

0x15

0x19

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

Request 1: Hi! May I please have 2 bytes of heap memory?

Allocator: Sure, I've given you address 0x10.

 0x10
 0x11
 0x12
 0x13
 0x14
 0x15
 0x16
 0x17
 0x18
 0x19

 FOR REQUEST 1
 AVAILABLE

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

Request 2: Howdy!
May I please have 3
bytes of heap memory?

Allocator: Sure, I've given you address 0x12.

 0x10
 0x11
 0x12
 0x13
 0x14
 0x15
 0x16
 0x17
 0x18
 0x19

 FOR REQUEST 1
 AVAILABLE

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

Request 2: Howdy!
May I please have 3
bytes of heap memory?

Allocator: Sure, I've given you address 0x12.

0x10 0x11	0x12	0x13	0x14	0x15	0x16	0×17	0x18	0x19
FOR REQUEST	1	FOR REQU	EST 2			AVAILAB	LE	

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

Request 1: I'm done with the memory I requested. Thank you!

Allocator: Thanks. Have a good day!

0X10 0X11	0x12	0x13	0x14	0x15	0x16	0x1/	0x18	0x19
FOR REQUES	Г1	FOR REQU	EST 2			AVAILAB	LE	

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

Request 1: I'm done with the memory I requested. Thank you!

Allocator: Thanks. Have a good day!

0x10 0x11	0x12 0x13 0x14	0x15 0x16 0x1/ 0x18 0x19
AVAILABLE	FOR REQUEST 2	AVAILABLE

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

Request 3: Hello there! I'd like to request 2 bytes of heap memory, please.

Allocator: Sure thing. I've given you address 0x10.

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
AVA	ILABLE	F	OR REQUE	EST 2			AVAILAB	LE	

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

Request 3: Hello there! I'd like to request 2 bytes of heap memory, please.

Allocator: Sure thing. I've given you address 0x10.

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
FOR RE	EQUEST 3	F	OR REQUE	EST 2			AVAILAB	LE	

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

Request 3: Hi again!
I'd like to request the region of memory at 0x10 be reallocated to 4 bytes.

Allocator: Sure thing. I've given you address 0x15.

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
FOR RE	EQUEST 3	F	OR REQUE	EST 2			AVAILAB	LE	

- A heap allocator is a set of functions that fulfills requests for heap memory.
- On initialization, a heap allocator is provided the starting address and size of a large contiguous block of memory (the heap).
- A heap allocator must manage this memory as clients request or no

Request 3: Hi again!
I'd like to request the region of memory at 0x10 be reallocated to 4 bytes.

Allocator: Sure thing. I've given you address 0x15.

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
AVA	ILABLE	F	OR REQUE	EST 2		FOR R	EQUEST 3		AVAILABLE

Lecture Plan

- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Bump Allocator
- Implicit Free List Allocator
- Explicit Free List Allocator

Heap Allocator Functions

```
void *malloc(size_t size);
void free(void *ptr);
void *realloc(void *ptr, size_t size);
```

All these heap allocators functions should work in harmony, and of course in an efficient manner! More on this later...

Heap Allocator Requirements

A heap allocator must...

- 1. Handle arbitrary request sequences of allocations and frees
- 2. Keep track of which memory is allocated and which is available
- 3. Decide which memory to provide to fulfill an allocation request
- 4. Immediately respond to requests without delay

Heap Allocator Requirements

A heap allocator must...

- 1. Handle arbitrary request sequences of allocations and frees
- 2. Keep track of which memory is allocated and which is available
- 3. Decide which memory to provide to fulfill an allocation request
- 4. Immediately respond to requests without delay

A heap allocator cannot assume anything about the order of allocation and free requests, or even that every allocation request is accompanied by a matching free request.

Heap Allocator Requirements

A heap allocator must...

- 1. Handle arbitrary request sequences of allocations and frees
- 2. Keep track of which memory is allocated and which is available
- 3. Decide which memory to provide to fulfill an allocation request
- 4. Immediately respond to requests without delay

A heap allocator marks memory regions as **allocated** or **available**. It must remember which is which to properly provide memory to clients.

Heap Allocator Requirements

A heap allocator must...

- 1. Handle arbitrary request sequences of allocations and frees
- 2. Keep track of which memory is allocated and which is available
- 3. Decide which memory to provide to fulfill an allocation request
- 4. Immediately respond to requests without delay

A heap allocator may have options for which memory to use to fulfill an allocation request. It must decide this based on a variety of factors.

Heap Allocator Requirements

A heap allocator must...

- 1. Handle arbitrary request sequences of allocations and frees
- 2. Keep track of which memory is allocated and which is available
- 3. Decide which memory to provide to fulfill an allocation request
- 4. Immediately respond to requests without delay

A heap allocator must respond immediately to allocation requests and should not e.g. prioritize or reorder certain requests to improve performance.

Heap Allocator Requirements

A heap allocator must...

- 1. Handle arbitrary request sequences of allocations and frees
- 2. Keep track of which memory is allocated and which is available
- 3. Decide which memory to provide to fulfill an allocation request
- 4. Immediately respond to requests without delay
- 5. Return addresses that are 8-byte-aligned (must be multiples of 8).

Heap Allocator Goals

- Goal 1: Maximize **throughput**, or the number of requests completed per unit time. This means minimizing the average time to satisfy a request.
- <u>Goal 2:</u> Maximize memory **utilization**, or how efficiently we make use of the limited heap memory to satisfy requests.

Utilization

- The primary cause of poor utilization is fragmentation. Fragmentation occurs when otherwise unused memory is not available to satisfy allocation requests.
- In this example, there is enough aggregate free memory to satisfy the request, but no single free block is large enough to handle the request.
- In general: we want the largest address used to be as low as possible.

Request 6: Hi! May I please have 4 bytes of heap memory?

Allocator: I'm sorry, I don't have a 4 byte block available...

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
Req. 1	Free	Req. 2	Free	Req. 3	Free	Req. 4	Free	Req. 5	Free

Utilization

Question: what if we shifted these blocks down to make more space? Can we do this?

A. YES, great idea!

B. YES, it can be done, but not a good idea for some reason (e.g. not efficient use of time)

C. NO, it can't be done!

0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
Req. 1	Req. 2	Req. 3	Req. 4	Req. 5			Free		

Utilization

Question: what if we shifted these blocks down to make more space? Can we do this?

• **No** - we have already guaranteed these addresses to the client. We cannot move allocated memory around, since this will mean the client will now have incorrect pointers to their memory!


0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19
Req. 1	Req. 2	Req. 3	Req. 4	Req. 5			Free		

Fragmentation

- Poor memory utilization is caused by fragmentation
 - Sections of memory are not used to store anything useful, but cannot satisfy allocation requests
 - Two types: internal and external
- Recall: Fragmentation in structs
 - Internal fragmentation was wasted space inside of the struct (between fields) due to alignment
 - External fragmentation was wasted space between struct instances (e.g. in an array) due to alignment
- Now referring to wasted space in the heap inside or between allocated blocks

Internal Fragmentation

 For a given block, internal fragmentation occurs if payload is smaller than the block




Causes:

- Padding for alignment purposes
- Overhead of maintaining heap data structures (inside block, outside payload)
- Explicit policy decisions (e.g. return a big block to satisfy a small request)
- Easy to measure because only depends on past requests

External Fragmentation

= 8-byte word

- For the heap, external fragmentation occurs when allocation/free pattern leaves "holes" between blocks
 - That is, the aggregate payload is non-continuous
 - Can cause situations where there is enough aggregate heap memory to satisfy request, but no single free block is large enough



- Don't know what future requests will be
 - Difficult to impossible to know if past placements will become problematic

Heap Allocator Goals

- Goal 1: Maximize **throughput**, or the number of requests completed per unit time. This means minimizing the average time to satisfy a request.
- <u>Goal 2:</u> Maximize memory **utilization**, or how efficiently we make use of the limited heap memory to satisfy requests.

These are seemingly conflicting goals – for instance, it may take longer to better plan out heap memory use for each request.

Heap allocators must find an appropriate balance between these two goals!

Heap Allocator Goals

- Goal 1: Maximize **throughput**, or the number of requests completed per unit time. This means minimizing the average time to satisfy a request.
- Goal 2: Maximize memory utilization, or how efficiently we make use of the limited heap memory to satisfy requests.

Other desirable goals:

Locality ("similar" blocks allocated close in space)

Robust (handle client errors)

Ease of implementation/maintenance

Lecture Plan

- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Bump Allocator
- Implicit Free List Allocator
- Explicit Free List Allocator

Let's say we want to entirely prioritize throughput, and do not care about utilization at all. This means we do not care about reusing memory. How could we do this?

1. Utilization 2. Throughput






Never reuses memory

Ultra fast, short routines

- A **bump allocator** is a heap allocator design that simply allocates the next available memory address upon an allocate request and does nothing on a free request.
- Throughput: each malloc and free execute only a handful of instructions:
 - It is easy to find the next location to use
 - Free does nothing!
- Utilization: we use each memory block at most once. No freeing at all, so no memory is ever reused. 🕾

```
void *a = malloc(8);
void *b = malloc(4);
void *c = malloc(24);
free(b);
void *d = malloc(8);
```



```
void *a = malloc(8);
void *b = malloc(4);
void *c = malloc(24);
free(b);
void *d = malloc(8);
```

Variable	Value
а	0x10

0x10	0x14	0x18	0x1c	0x20	0x24	0x28	0x2c	0x30	0x34
	а				AVA	AILABLE			

```
void *a = malloc(8);
void *b = malloc(4);
void *c = malloc(24);
free(b);
void *d = malloc(8);
```

Variable	Value
а	0x10
b	0x18

0x10 0x14	0x18 0x1c 0	0x20 0x24	0x28	0x2c	0x30	0x34
а	b + padding		AV	AILABLE		

```
void *a = malloc(8);
void *b = malloc(4);
void *c = malloc(24);
free(b);
void *d = malloc(8);
```

Variable	Value
a	0x10
b	0x18
С	0x20

0x10	0x14	0x18	0x1c	0x20	0x24	0x28	0x2c	0x30	0x34
6		h + t	padding				С		

```
void *a = malloc(8);
void *b = malloc(4);
void *c = malloc(24);
free(b);
void *d = malloc(8);
```

Variable	Value
a	0x10
b	0x18
С	0x20

0x10	0x14	0x18	0x1c	0x20	0x24	0x28	0x2c	0x30	0x34
	а	b +	padding				С		

```
void *a = malloc(8);
void *b = malloc(4);
void *c = malloc(24);
free(b);
void *d = malloc(8);
```

Variable	Value
a	0x10
b	0x18
С	0x20
d	NULL

0x10	0x14	0x18	0x1c	0x20	0x24	0x28	0x2c	0x30	0x34
а	3	b + p	padding				С		

Summary: Bump Allocator

- A bump allocator is an extreme heap allocator it optimizes only for throughput, not utilization.
- Better allocators strike a more reasonable balance. How can we do this?

Questions to consider:

- 1. How do we keep track of free blocks?
- 2. How do we choose an appropriate free block in which to place a newly allocated block?
- 3. After we place a newly allocated block in some free block, what do we do with the remainder of the free block?
- 4. What do we do with a block that has just been freed?

Implementation Issues

- How do we know how much memory to free given just a pointer?
- How do we keep track of the free blocks?
- How do we pick a block to use for allocation (when many might fit)?
- What do we do with the extra space when allocating a structure that is smaller than the free block it is placed in?
- How do we reinsert a freed block into the heap?

Lecture Plan

- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Bump Allocator
- Implicit Free List Allocator
- Explicit Free List Allocator

- **Key idea:** in order to reuse blocks, we need a way to track which blocks are allocated and which are free.
- We could store this information in a separate global data structure, but this is inefficient.
- Instead: let's allocate extra space before each block for a **header** storing its payload size and whether it is allocated or free.
- When we allocate a block, we look through the blocks to find a free one, and we update its header to reflect its allocated size and that it is now allocated.
- When we free a block, we update its header to reflect it is now free.
- The header should be 8 bytes (or larger).
- By storing the block size of each block, we implicitly have a list of free blocks.

- **Key idea:** in order to reuse blocks, we need a way to track which blocks are allocated and which are free.
- We could store this information in a separate global data structure, but this is inefficient.
- Instead: let's allocate extra space before each block for a **header** storing its payload size and whether it is allocated This is larger than the 4 byte headers
- When we allocate a block, we look through specified in the book, as this makes it we update its header to reflect its allocate easier to satisfy the alignment
- When we free a block, we update its heat constraint and store information!.
- The header should be 8 bytes (or larger).
- By storing the block size of each block, we implicitly have a list of free blocks.

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
0x10
       0x18
                     0x28
              0x20
                            0x30
                                   0x38
                                          0x40
                                                 0x48
                                                         0x50
                                                                0x58
 72
Free
```

```
Variable
void *a = malloc(4);
                                                                Value
void *b = malloc(8);
                                                                0x18
 void *c = malloc(4);
 free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
0x10
       0x18
              0x20
                      0x28
                             0x30
                                    0x38
                                            0x40
                                                   0x48
                                                          0x50
                                                                  0x58
  8
                56
        a +
Used
               Free
        pad
```

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```

Variable	Value
a	0x18
b	0x28

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Used	a + pad	8 Used	b	40 Free					

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```

Variable	Value
a	0x18
b	0x28
С	0x38

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Used	a + pad	8 Used	b	8 Used	c + pad	24 Free			

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```

Variable	Value
a	0x18
b	0x28
С	0x38

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Used	a + pad	8 Free	b	8 Used	c + pad	24 Free			

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```

Variable	Value
a	0x18
b	0x28
С	0x38
d	0x28

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Used	a + pad	8 Used	d	8 Used	c + pad	24 Free			

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```

Variable	Value
a	0x18
b	0x28
С	0x38
d	0x28

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	d	8 Used	c + pad	24 Free			

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```

Variable	Value			
a	0x18			
b	0x28			
С	0x38			
d	0x28			
е	0x48			

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	d	8 Used	c + pad	24 Used		е	

```
void *a = malloc(4);
void *b = malloc(8);
void *c = malloc(4);
free(b);
void *d = malloc(8);
free(a);
void *e = malloc(24);
```


Variable	Value			
a	0x18			
b	0x28			
С	0x38			
d	0x28			
е	0x48			


0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	d	8 Used	c + pad	24 Used		е	

Representing Headers

- For each block we need: size, is-allocated?
 - Could store using two words, but wasteful
- Standard trick
 - If blocks are aligned, some low-order bits of size are always 0
 - Use lowest bit as an allocated/free flag (fine as long as aligning to K>1)
 - When reading size, must remember to mask out this bit! 8 bytes

Format of allocated and free blocks:





Implicit Free List Allocator

How can we choose a free block to use for an allocation request?

- First fit: search the list from beginning each time and choose first free block that fits.
- Next fit: instead of starting at the beginning, continue where previous search left off.
- Best fit: examine every free block and choose the one with the smallest size that fits.
- First fit/next fit easier to implement
- What are the pros/cons of each approach?

Implicit List: Finding a Free Block

First fit

- Can take time linear in total number of blocks
- In practice can cause "splinters" at beginning of list

Next fit

- Like first-fit, but search list starting where previous search finished
- Should often be faster than first-fit: avoids re-scanning unhelpful blocks
- Some research suggests that fragmentation is worse

Best fit

- Search the list, choose the best free block: large enough AND with fewest bytes left over
- Keeps fragments small—usually helps fragmentation
- Usually worse throughput

Practice 1

• For the following heap layout, what would the heap look like after the following request is made, assuming we are using an **implicit** free list allocator with a **first-fit** approach?

[24 byte payload, free] [16 byte payload, free] [8 byte payload, allocated for A]

```
void *b = malloc(8);
```

[8 byte payload, allocated for B] [8 byte payload, free] [16 byte payload, free] [8 byte payload, allocated for A]

Practice 2

• For the following heap layout, what would the heap look like after the following request is made, assuming we are using an **implicit** free list allocator with a **best-fit** approach?


[24 byte payload, free] [8 byte payload, free] [8 byte payload, allocated for A]

[24 byte payload, free] [8 byte payload, allocated for B] [8 byte payload, allocated for A]

Implicit Free List Summary

For all blocks,

- Have a header that stores size and status.
- Our list links all blocks, allocated (A) and free (F).



Keeping track of free blocks:

- Improves memory utilization (vs bump allocator)
- Decreases throughput (worst case allocation request has O(A + F) time)
- Increases design complexity ©

```
void *e = malloc(16);
```

So far, we have seen that a reasonable allocation request splits a free block into an allocated block and a free block with remaining space. What about edge cases?

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	d	8 Used	c + pad	24 Free			

```
void *e = malloc(16);
```

So far, we have seen that a reasonable allocation request splits a free block into an allocated block and a free block with remaining space. What about edge cases?

0x1	L0	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
Fı	8 ree	a + pad	8 Used	d	8 Used	c + pad	16 Used		е	???

```
void *e = malloc(16);
```

So far, we have seen that a reasonable allocation request splits a free block into an allocated block and a free block with remaining space. What about edge cases?

A. Throw into allocation for e **as extra padding?** *Internal fragmentation – unused bytes because of padding*

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	d	8 Used	c + pad	24 Used		e + pac	k

```
void *e = malloc(16);
```

So far, we have seen that a reasonable allocation request splits a free block into an allocated block and a free block with remaining space. What about edge cases?

A. Throw into allocation for e as extra padding?

B. Make a "zero-byte free block"? External fragmentation – unused free blocks

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	d	8 Used	c + pad	16 Used		е	0 Free

Revisiting Our Goals

Questions we considered:

- 1. How do we keep track of free blocks? Using headers!
- 2. How do we choose an appropriate free block in which to place a newly allocated block? **Iterate through all blocks**.
- 3. After we place a newly allocated block in some free block, what do we do with the remainder of the free block? **Try to make the most of it!**
- 4. What do we do with a block that has just been freed? **Update its** header!

Coalescing

```
void *e = malloc(24); // returns NULL!
```

We do not need to worry about this problem for the implicit allocator, but investigate this for the *explicit* allocator! (More about this later).

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free		8 Free		8 Free		24 Used			

In-Place Realloc


```
void *a = malloc(4);
void *b = realloc(a, 8);
```



In-Place Realloc

```
void *a = malloc(4);
void *b = realloc(a, 8);
```

Variable	Value				
а	0x10				



In-Place Realloc

```
void *a = malloc(4);
void *b = realloc(a, 8);
```

Variable	Value
а	0x10
b	0x28

The implicit allocator can always move memory to a new location for a realloc request. The *explicit* allocator must support in-place realloc (more on this later).

0x10	0x18	0x20	0x28	0x30	0x38	0x40	0x48	0x50	0x58
8 Free	a + pad	8 Used	b	40 Free					

Summary: Implicit Allocator

 An implicit allocator is a more efficient implementation that has reasonable throughput and utilization due to its recycling of blocks.

Can we do better?

- 1. Can we avoid searching all blocks for free blocks to reuse?
- 2. Can we merge adjacent free blocks to keep large spaces available?
- 3. Can we avoid always copying/moving data during realloc?

Recap

- The heap so far
- What is a heap allocator?
- Heap allocator requirements and goals
- Method 0: Bump Allocator
- Method 1: Implicit Free List Allocator

Next: Explicit Free List Allocator, Wrapping Up