# SAMBA SERVER ON CENTOS 7

# installing samba server(server side configuration):

### step1:

#### requirements:

- 1) Centos server, ip: 192.168.0.50
- 2) client (ubuntu or centos), ip: 192.168.0.100
- 3) internet connection

#### step2:

update repository and install the necessary samba packages

- => yum update -y
- =>yum install samba samba-client samba-common

#### step3:

create a group and add user in that group who can use the samba share.

```
=>groupadd test
=>useradd user1
=>useradd user2
=>usermod -a -G test user1
=>usermod -a -G test user2
```

### step4:

Create a directory and give proper permission for that user and group

- =>mkdir/share
- =>chmod 777 /share
- =>chgrp test/share

```
[root@localhost ~]# mkdir /share
[root@localhost ~]# chmod 777 /share
[root@localhost ~]# chgrp test /share
[root@localhost ~]# █
```

#### step5:

Configure SElinux .you can either disable the SEinux or set the proper boolean value and security otherwise it will not let you connect to the server.In this we are not going to disable SElinux we will change the boolean value.

```
=> setsebool -P samba_export_all_ro=1 samba_export_all_rw=1
```

- => getsebool –a | grep samba\_export
- => semanage fcontext -at samba\_share\_t "/share(/.\*)?"
- => restorecon /share

```
[root@localhost ~]# setsebool -P samba_export_all_ro=1
[root@localhost ~]# setsebool -P samba_export_all_rw=1
[root@localhost ~]# getsebool -a | grep samba_export
samba_export_all_ro --> on
samba_export_all_rw --> on
[root@localhost ~]# semanage fcontext -at samba_share_t "/share(/.*)?"
[root@localhost ~]# restorecon /share
[root@localhost ~]# 

[root@localhost ~]# 

[root@localhost ~]#
```

#### step6:

we have to change the firewall settings for allowing the connection

- =>firewall-cmd –permanent –add-service=samba
- =>firewall-cmd -reload

```
[root@localhost ~]#
[root@localhost ~]# firewall-cmd --permanent --add-service=samba
success
[root@localhost ~]# firewall-cmd --reload
success
[root@localhost ~]# 

[root@local
```

#### step7:

This is the most important path of the part.we need to edit the configuration of the samba share

=> vim /etc/samba/smb.conf

#### [share]

comment=Directory for for samba share browsable=yes path=/share public=no valid users=@test write list=@test writeable=yes create mask=0770 Force create mode=0770 force group=test

```
[share]
    comment = Directory for samba share
    create mask = 0770
    force create mode = 0770
    force group = test
    path = /share
    valid users = @test
    write list = @test
[root@localhost ~]#
```

#### step8:

Test the configuration with the 'testparm' command.if there is any error in the configuration this command will tell you that

=>testparm

```
[root@localhost ~]# testparm
Load smb config files from /etc/samba/smb.conf
rlimit_max: increasing rlimit_max (1024) to minimum Windows limit (16384)
Processing section "[homes]"
Processing section "[printers]"
Processing section "[print$]"
Processing section "[share]"
Loaded services file OK.
Server role: ROLE_STANDALONE

Press enter to see a dump of your service definitions
```

#### <u>step9:</u>

we have to add the user of the test group to the samba

- =>smbpasswd -a user1
- =>smbpasswd -a user2

```
[root@localhost ~]# smbpasswd -a user1

New SMB password:

Retype new SMB password:

Added user user1.

[root@localhost ~]# smbpasswd -a user2

New SMB password:

Retype new SMB password:

Added user user2.

[root@localhost ~]#
```

#### <u>step10:</u>

restart the samba server to make the change the in effect

- =>systemctl start smb
- =>systemctl start nmb

```
[root@localhost ~]# systemctl start smb
[root@localhost ~]# systemctl start nmb
[root@localhost ~]#
```

#### **step11:**

we have to enable the smb and nmb service to make start this on boot time

- =>systemctl enable smb
- =>systemctl enable nmb

```
[root@localhost ~]# systemctl enable smb

Created symlink from /etc/systemd/system/multi-user.target.wants/smb.service to
/usr/lib/systemd/system/smb.service.
[root@localhost ~]# systemctl enable nmb

Created symlink from /etc/systemd/system/multi-user.target.wants/nmb.service to
/usr/lib/systemd/system/nmb.service.
[root@localhost ~]# 

[root@localhost ~]#
```

#### <u>step12:</u>

Test the connection from the server

=>smbclient -L localhost -U user1

```
[root@localhost ~]# smbclient -L localhost -U user1
Enter SAMBA\user1's password:
       Sharename
                       Type
                                Comment
                       ----
                      Disk
                                Printer Drivers
       print$
       share
                      Disk
                                Directory for samba share
                      IPC
Disk
       IPC$
                                IPC Service (Samba 4.8.3)
                                Home Directories
       user1
Reconnecting with SMB1 for workgroup listing.
       Server
                            Comment
       Workgroup
                           Master
       SAMBA
                            LOCALHOST
[root@localhost ~]#
```

=>smbclient -L localhost -U user2

```
[root@localhost ~]# smbclient -L localhost -U user2
Enter SAMBA\user2's password:
       Sharename
                       Type
                                 Comment
       print$
                       Disk
                                Printer Drivers
                      Disk
                                Directory for samba share
       share
       IPC$
                      IPC
                                 IPC Service (Samba 4.8.3)
                      Disk
                                Home Directories
       user2
Reconnecting with SMB1 for workgroup listing.
       Server
                            Comment
       ------
                            -----
       Workgroup
                           Master
       SAMBA
                            LOCALHOST
[root@localhost ~]#
```

# installing samba Client(linux client):

### step1:

install packages in the client

=>yum update -y

- =>yum install samba samba-client samba-common -y
- =>yum install cifs-utils -y

#### step2:

Test the connection from the client

=>smbclient -L 192.168.0.50 -U user1

```
tanvirrahman@pop-os:~
smbclient -L 192.168.0.50 -U user1
WARNING: The "syslog" option is deprecated
Enter WORKGROUP\user1's password:
       Sharename
                       Type
                                Comment
                                -----
       -----
                       ----
       print$
                     Disk Printer Drivers
Disk Directory for samba share
       share
                      IPC
       IPC$
                               IPC Service (Samba 4.8.3)
                       Disk
                                Home Directories
       user1
Reconnecting with SMB1 for workgroup listing.
                            Comment
       Server
                            -----
       Workgroup
                            Master
       SAMBA
                            LOCALHOST
       WORKGROUP
                            MECHANIC
```

#### step3:

make the directory for mounting and give the proper permission

- =>mkdir/share
- =>chmod 777 /share

```
root@pop-os:~
> mkdir /share

root@pop-os:~
> chmod 777 /share

root@pop-os:~
> |
```

### step4:

mount the the network share

=>mount //192.168.0.50/share /share -o username=user1

```
root@pop-os:~
> mount //192.168.0.50/share /share -o username=user1
Password for user1@//192.168.0.50/share: ****

root@pop-os:~
>
```

see the the network share

=>mount | grep cifs

### Additional step(permanent mount):

adding a credential file in /share folder

=> vim /share/.smbcredentials

username=user1

password=<password\_for\_user\_1>

adding an entry to the '/etc/fstab' file

=>vim /etc/fstab

//192.168.0.50/share /share cifs credentials=/share/.smbcredentials

#### **Test the share:**

create a file in the /share folder from the client side

=>touch/share/test.txt

```
root@pop-os:/share
> touch /share/test.txt
root@pop-os:/share
>
```

Now test from the server side

=>ls -l/share

```
[root@localhost ~]# ls -l /share
total 0
-rwxrwx---. 1 user1 test 0 Sep 7 00:00 test.txt
[root@localhost ~]#
```