# Quick guide for the use of the last version of the scripts (11/04/2010)

This is only a quick guide. More details can be found in details.doc.

NOTE: In this document it is always assumed when using octave commands that the path of the scripts has been previously added to octave's path:

> addpath('f:\project\scripts')

For this version of the scripts you need Octave 3.2.3

a) Download the <u>last folder's structure</u> (last version of octave scripts is included)

### Step 0. Import kml



Two ways:

**b1**) Import the kml with BTB 0.6. If this is the case you have to create by hand **mapeo.txt**, and copy it inside f:\project folder.

**b2)** (recommended) Use importakml script to import the kml.

Copy the kml file (i.e. ejemplo.kml) inside **s0\_import** folder. The initial and final parts of the file have to be removed with a text editor, leaving only the coordinates data separated with commas

Open octave and execute:

- > cd f:\project\s0 import
- > importakml('example.kml'<del>.0.5</del>)

the second parameter of importakml (i.e. 0.5) is the maximum error measured in meters allowed for the final road position respect to the position internally calculated as the ideal one. Using a big value will remove detail, like small and abrupt direction changes and will result in a road defined with less nodes. The direction of the kml can be reversed by editing importakl.m and changing a parameter found in the first lines of this file.

A file named f:\project\mapeo.txt will be created. This files establishes a relationship between the terrestrial coordinates and the BTB coordinates for two points of the point. The correspondence could be visually checked using Google Earth and the graphs generated by importakml.

c) Before closing the graphs it is recommended to write down the minimum and maximum coordinates of the track (minimum and maximum in both dimensions, horizontal and vertical, x and z respectively). Those limits will be useful if we are going to use Google Earth to get elevation data.

#### Step 1. Getting elevation data



We can retrieve elevation data from **d1**) the <u>seamless server</u> (the best option for USA) or **d2**) from Google Earth through 3DR Builder or BTBlofty.

- **d1)** Once we have downloaded the data from the server, we copy the .hdr and .flt files inside s2\_elevation folder and we type (using the right file names, of course):
- > cd f:\project\s2\_elevation
- > leer gridfloat('ned 03263284.hdr','ned 03263284.flt');

The result of this action will be a file called **lamalla.mat** inside s2\_elevation\salida folder. lamalla.mat depends upon mapeo.txt, so if mapeo.txt is changed, lamalla.mat should be generated again.Jump to section e)

- **d2)** We will generate a coordinates grid whose elevation is going to be retrieved with 3DR Builder or BTBLofty (values should be changed to fit each track):
- > cd f:\project\s2 elevation
- > make grid(-1800,1800,-1500,1500,25,5000)

this will create a grid of points separated 25m with a extension from x=-1800 to x=1800 and from z=-1500 to z=1500. The road should be completely covered by that grid. It is recommended to use a safety margin (100m, for example) to avoid problems.

If you are going to use BTBLofty, it will be necessary to split the grid points into several files. That can be made adding another parameter to make\_grid specifying the number of points per file. 30000 is the limit for BTBLofty, but it is better to use 5000 points because bigger values make the process slow down. If you are using the free version of 3D Route Builder 500 points/file is the limit. Inside the "salida" folder a few files named gridXXX.kml have been created. Open them with 3D Route Builder or BTBLofty to get the elevation of the points. Once you have the data save it inside "salida" folder as gridXXX\_relleno.kml. The initial and final parts of the file have to be removed with a text editor, leaving only the coordinates data separated with

commas. Now we run:

> read grid

A file called **lamalla.mat** will be created inside s2\_elevation\salida.lamalla.mat depends upon mapeo.txt, so if mapeo.txt is changed, lamalla.mat should be generated again. Just call read grid again, that's all.

The same steps must be done inside s2\_elevation\_b, using a bigger grid, enough to cover all the terrain. Separation parameter for the points for this grid can have a bigger value if compared with the one created inside s2\_elevation.

**Step 2. Road anchors generation** 



e) Copy the file nodos.xml generated in step b) inside f:\project\venue folder.

Run:

- > cd f:\project\Venue
- > btb06(5)

The parameter for btb06 is the road width in meters.

Files **nac.mat** and **anchors.mat** have been created inside f:\project\ folder, and **nodos.mat** and **porcentajes.mat** inside f:\project\ Venue folder.

Step 3. Raising the road



dar altura is a script that raises the road trying to fit existing terrain elevation data.

corregir is a script that changes terrain elevation data trying to fit the road elevation

**<u>f1</u>**) If we want to raise the road according to the terrain elevation data we should execute:

- > cd f:\project\s3 road
- > coge datos

profile

- > creartrack1
- > dar altura(25,0.15,-0.15)

25 is a smoothing factor (always odd. The bigger, the smoother in height the road will be) and the two values 0.15 and -0.15 are the maximum and minimum slopes allowed to the road. It is recommended to test different values, observing in the graphs how the road will fit the mountain. A 4<sup>th</sup> parameter can be used to change the spacing of the elevation points used for setting <u>definitive</u> road elevation (if not indicated 25m will be used). The bigger, the smoother. If 4<sup>th</sup> parameter is 0, the <u>smoothing</u> method from previous versions is used.

The output of this step is f:\project\s3 road\salida\nodes.xml

dar altura creates a elevation profile for the track, but with the last version of the scripts you can change it to fit real elevation changes just clicking with the mouse. Watch tutorial inside documentation folder.

**f2)** If elevation data available is not so good, you can create a road with a smooth elevation profile and then change elevation data to make the mountains fit that road.

First we create the smooth road:

> coge datos

> creartrack1

>dar altura(53,1,-1,100)

Then we change the elevation data for the terrain

> corregir

And we create a new road that fits the new elevation data.

> dar altura(21,0.25,-0.25)

If we don't like the result, running coge datos again will get original elevation values

- g) Copy f:\project\s3 road\salida\nodes.xml inside the Venue folder and run again:
- > cd f:\project\Venue
- > btb06(5)

**Step 4. Creating the terrain mesh** 



#### h)

> cd s1 mesh

> mallado regular(12,3)

Parameters for mallado\_regular are the width of driveable terrain on both sides of the road and the number of "panels" on each side.

mallado\_regular creates a file called f:\project\s1\_mesh\salida\anchors\_carretera.geo. This file is the base for creating the terrain with gmsh. If you want you can add a grid showing the limits of available elevation data:

### $\geq$ addgrid(1,1,100000)

Where the first 2 parameters are the number of horizontal and vertical divisions of the grid and the last parameter sets the start number for the points of the grid. It should be high enough to avoid using an already existing value.

### i) Mesh generation:

Open anchors\_carretera.geo with gmsh and create the surfaces for the mesh. It is mandatory to create a surface on the start and end of the road. Otherwise the script that creates the invisible protection walls will crash.

Create a Plane Surface for the non-driveable zone (with the driveable zone as its internal boundary).

Close gmsh.

Open anchors\_carretera.geo with a text editor and define the Physical Surface 222 with the non-driveable surface and complete the Physical surface 111 with the surfaces created on each end of the road.

Save the file.

Open again anchors\_carretera.geo with gmsh. Create the mesh (Mesh->2D) and save it (File->Save Mesh).

Open anchors\_carretera.msh with gmsh and check that the mesh is complete (including the ends of the road).

Extract nodes data (nodos.txt) and polygons data (elements.txt) from anchors carretera.msh:

> cd f:\project\s1\_mesh\salida

> trocea malla

Two files, **nodos.txt** and **elements.txt**, have been created.

# **Step 5. Creating the terrain**



- i) Raise the terrain
- > cd f:\project\s4\_terrain
- > coge\_datos
- > procesar nodostxt

procesar\_nodostxt admits as parameter the maximum elevation noise (in meters) desired. If, i.e., we run **procesar\_nodostxt(0.5)** the elevation of each node is increased a random value between 0 and 0.5m. It also admits lower and upper noise limits: **procesar\_nodostxt([-0.5 0.5])** 

k) The next step is simplifying the mesh to reduce the amount of polygons (triangles). If you don't want to simplify, just copy f:\project\s4\_terrain\elements.txt inside "salida" folder and jump to step m)

We split the mesh in three parts (conducibles.ply, noconducibles.ply and intocables.ply):

> simplificar

We use MeshLab to simplify the ply files or to remove unreferences vertex in them. Resulting meshes should be saved inside "salida" folder with names i.ply, n.ply y c.ply

We put the meshes together:

> juntar mallas

### Step 6. Protection wall



- n) Invisible protection wall creation:
- Run:
- > cd f:\project\s7 walls
- > coge datos
- > poner\_muro

Two files will be created inside the "salida" folder: **muros.txt** and **muros\_invertidos.txt**. One of them should work ok as a wall that prevents the car from falling outside of the limits of the driveable zone. Poner\_muro accepts an optional parameter: the LOD out value for the walls. If it is not specified, LOD out of 5m will be used.

### **Step 7: splitting terrain and road**



# **q)** Road and terrain splitting

It is recommended to split the road in-to several segments. After doing that, the terrain must be regenerated to adapt the TerrainFaces to the new situation.

- > cd f:\project\s10 split
- > coge datos
- > partir\_track(8)
- > procesar elementstxt mt(0)

where the parameter for partir\_track is the number of segments the road will be splitted into.

Sometimes we want to have more control on the points used to split the original track. If that is the case, we can do as follows:

- > cd f:\project\s10 split
- > coge datos
- > split track(8)

A new figure will be created showing the nodes selected for splitting the road. The numbers of those nodes will be saved in the file "pos\_nodes.txt". Looking at the graph we can decide if we want to accept those splitting points or if we want to edit by hand 'pos\_nodes.txt' to change those points. When we are finished, we go on with the process

- > partir track(8)
- > procesar elementstxt mt(0)

And partir track will find "pos nodes.txt" and those splitting points will be used.

Now, s10\_split\salida\lis.txt is the new list of TerrainFaces, and it must replace the old list inside the Venue.xml. listado\_tracks is the new list of tracks and must replace the old one inside Venue.xml).

#### **Step 8: Join the parts**



Run:

> cd f:\project\s9\_join

> join all

Now copy f:\project\s9\_join\salida\Venue.xml and try to open it with BTB. If the protection walls are not collidable you can try Venue wallsreversed.xml

**p)** Copy the just created Venue.xml inside the BTB project folder, copy WP.zip inside the XPacks subfolder, and open the project with BTB.

This tutorial and the scripts **are not free** software. Using them implies accepting the author's conditions. These conditions **specifically prohibit distribution or the use for commercial purposes**. Modifications of the code are only allowed for personal and non-commercial purposes.

The author accepts no responsibility or liability for any harm produced using the method or the scripts.