Script	Run it in directory
add_dat_to_geo Reads the .dat files created by SASPlanet while splitting a satellite image and creates a grid that can be saved as grid.geo or appended to	s1_mesh
salida\joined.geo. This script also created a list of background images	
(s1_mesh\list_bi.txt) ready to be included in the Venue.xml.	
NOTE: this script internally calls addgrid, so addgrid.hlg is overwritten.	
addgrid.m Creates a grid with .geo format. Two possibilities:	s1_mesh
addgrid(numx,numz) You want to view the available elevation data using a numx X numz grid	
addgrid(xmin,xmax,zmin,zmax,step) Creates a grid with the specified limits and line separation.	
If another parameter is added to the command, no matter its value, the list of points and lines created will be explicit (instead of using a "for loop").	
addgrid creates a file called addgrid.hlg ready to be opened with SASPLanet to get the satellite images for that area.	
add_sobject.m Creates a list of SObjects to be inserted by hand in the Venue.xml. add_sobject(num_points) Parameter is the maximum number of points used by one SObject. Longer SObjects will be splitted.	s7_walls_b
addt.m Opens joined.geo and replaces the last occurrence of a Plane Surface followed by a Spline with the code to define that surface as Transinite	s1_mesh
btb_a_coor.m	base directory
Returns the terrestrial coordinates of a BTB point > [mapeo] = textread('mapeo.txt', '%f'); > x = 2380.47;	
<pre>> z=-2350.67; > [longitud altura latitud]=BTB_a_coor(x,0,z,mapeo)</pre>	
btb06.m Creates the points in both borders of the road, where the road and the	venue
terrain will be linked (they are called anchors). Parameter is the separation between anchors on right and left side. It will affect the	
mesh created by mallado_regular	han dinatan
coor_a_btb.m Returns the BTB coordinates of a point given the terrestrial	base directory
coordinates	
<pre>> [mapeo] = textread('mapeo.txt','%f'); > longit = -73.67; > latit = 41.47;</pre>	
> [x1 y1 z1]=coor_a_BTB(longit, latit, elevation, mapeo)	

corregir.m	s3 road
For a given road, compares the elevation profile assigned using	35_10au
dar altura and that obtained from elevation data (from lamalla.mat),	
and changes the terrain elevation data (lamalla.mat) to fit the	
elevation profile set with dar altura.	
cievation prome set with dar_aitura.	
corregir also accepts a kml file as a parameter and uses its coordinates and altitude to change lamalla.mat. This could be useful if we have a kml with altitudes we trust, but dangerous as those altitudes could have an offset respect to the elevation data available. corregir('file.kml')	
create_hlg	s1_mesh
Creates file s1_mesh\grid.hlg (open it with SASPlanet) with the	
boundary coordinates (box) of anchors_carretera.msh (run	
trocea_malla before using create_hlg)	
creartrack1.m	s3_road
Gets elevation values for a road from its coordinates and elevation	
data (lamalla.mat)	
cut_lamalla.m	s2_elevation
Reduces the size of lamalla.mat. Useful if data comes for a too big	s2_elevation_b
zone.	
cut_lamalla([xmin xmax],[zmin zmax])	
dar_altura.m	s3_road
Softens the output from creartrack1 and gives the nodes of the track	
their elevation and slope to fit that curve.	
dar_altura(smooth_factor,pos_slope,neg_slope,step,interactive)	
- smooth is a smoothing factor, the bigger the smoother	
- pos_slope and neg_slope are the maximum and minimum	
slopes allowed (1 means 45 degrees)	
- the final elevation profile is constructed using one point	
each "step" meters. Use a small value to preserve the	
profile's details, and a big value to smooth them. 25m is used if omitted	
- If interactive==0, the script doesn't give the user the option to edit the profile by hand and exists	
to cuit the profile by hand and exists	

importakml.m Reads a kml file and from it creates a mapping between terrestrial and BTB coordinates. importakml(kml_file) All the original points of the kml will be converted to nodes of the road importakml(kml_file,'decimate',factor) Keeps 1 from every "factor" points of the kml as nodes of the road. For example if the kml has 100 points and factor==2, the road will have 50 nodes. importakml_old(kml_file,tolerance) Uses the old "approach". An ideal smooth road with a huge amount of nodes that follows the coordinates of the kml file (using akima splines). Finally some nodes are removed. A node is removed if removing it doesn't deviate the road more than "tolerance" meters from the "ideal path"	s0_import
join_all.m Final step of the process. Joins all the tracks, terrain, pacenotes and walls, creating a file called Venue.xml. To open this file good luck and WP.zip Xpack are needed.	s9_join
join_geos.m Joins the anchors_carretera.geo files created with mallado_regular for all the projects, creating file joined.geo inside s1_mesh\salida folder. This file should be edited with gmsh.	s1_mesh
juntar_mallas.m Reads i.ply, c.ply and n.ply from s4_terrain\salida and joins them in one single mesh (files anchors_contaltura.txt and elements.txt)	s4_terrain
leehgt.m Creates lamalla.mat from a .hgt file (1 degree x 1 degree) leehgt(fichero,latitud,longitud) Data extension is from latittud to latitud+1 and from longitud to longitud+1	s2_elevation s2_elevation_b
<pre>leehgt2.m The same as leehgt, but joins 2 adjacent .hgt files leehgt2(file1,latit1,longit1,file2,latit2,longit2) if latit1==latit2, longit1 should be <longit2 <latit2<="" be="" if="" latit1="" longit1="=longit2," pre="" should=""></longit2></pre>	s2_elevation s2_elevation_b
leer_gridfloat.m Creates lamalla.mat from gridfloat file. First parameter is the .hdt and second one is .flt	s2_elevation s2_elevation_b
leetif.m Creates lamalla.mat from a geotiff file listc.m Reads salida\joined.geo and creates a file called listc.geo with the id numbers of all the Plane Surfaces created inside joined.geo after its creation (last line of joined.geo after its creation is the reference used by listc)	s2_elevation s2_elevation_b s1_mesh

make_grid.m Creates several files containing a regular grid of points with terrestrial coordinates. Those files should be "raised" with BTBLofty or a similar application and save with a different name: grid001.kml should be saved in the same folder as grid001_relleno.kml make_grid(xmin, xmax, zmin, zmax, step, file_size) Parameters are x and z minimum and maximum values, and distance between points of the grid. Maximum file_size depends upon the application to be used. 5000 is recommended for BTBLofty.	s2_elevation s2_elevation_b
mallado_regular.m Creates a terrain mesh on both sides of the road. Position of road borders (anchors) is taken from btb06 output. Besides the road a terrain of a specified width will be created, splitted in the transversal direction into the desired number of panels. Terrain width (meters) is the first parameter and the number of panels is the second one.	s1_mesh
muro_pegado.m Creates walls on both sides of the road (from start to end). List of walls can be found in salida folder and should be inserted by hand inside the Venue.xml file (updating the total walls count, if needed) muro_pegado(tam_wall,offset) Parameters are the limit of points per wall and the displacement in meters in the outside direction from the road border (the width specified as btb06 parameter is used to compute border position)	s7_walls_b
pacenotes.m Gets the track shape from a driveline.ini file. Output from thius script will be used by pacenotes 2	pacenotes
pacenotes_a.m Gets the track shape from anchors created by btb06. Output from this script will be used by pacenotes2 a	pacenotes
pacenotes2.m Creates a new pacenotes.ini file using the old one and the output from pacenotes.m pacenotes2(sensibility,distance) Parameters are the sensibility for curve detection and the distance you want to move the pacenotes to the start of the road. 10 means 50m.	pacenotes
pacenotes2_a.m Creates a list of pacenotes in BTB format ready to be inserted inside the Venue.xml. Join.all looks for this pacenotes and if they exist, includes them inside Venue.xml. Parameters are the same as pacenotes2	pacenotes
partir_track.m Splits a track into several segments. Reads split points from pos_nodes.txt	s10_plit
plot_lamalla.m Plots the contents of salida\lamalla.mat as a surface. poner_muro.m	s2_elevation s2_elevation_b s7_walls
Creates walls in the boundary between driveable and non-driveable zones. Walls are automatically included inside Venue.xml by join_all	

nuccessor elementates and m	a10 anl!4
procesar_elementstxt_mt.m Creates the terrain in DTD format from the mash erected by	s10_split
Creates the terrain in BTB format from the mesh created by	
juntar_mallas and the output from partir_track.	
By default terrain is splitted using a 10x10 grid, but user can choose	
another grid size.	
procesar_elementstxt_mt(cells_x,cells_z,do_mapping)	
Will split the terrain using a cells_x X cells_z grid, and If	
do_mapping is 1, terrain will be created with background	
images blending (see add_dat_to_geo).	
procesar nodostxt.m	s4 terrain
Nodes of anchors carretera.msh mesh receive a elevation value taken	
from lamalla.mat, if possible, or lamalla2.mat	
process sons.m	base directory
This script processes all the sons in a multitrack project. It should be	of father
first edited to set the desired values for the parameters of the scripts	or racinor
called.	
read grid.m	s2 elevation
Reads the gridXXX relleno files and created lamalla.mat, with all the	_
elevation info collected	s2_elevation_b
	-1l
readkml.m	s1_mesh
Translates a route from a kml file to a curve in gmsh format and BTB	
coordinates. Output file is written in salida foler, with the same name	
as input, but .geo extension.	
readkml('file.kml',curve)	
Second parameter can be "t", for adding straight lines, "s" for	
adding a spline, or "st" for adding both	
simplificar.m	
Splits anchors carretera.msh in three parts that should be processed	
with MeshLab: intocables.ply, conducibles.ply and noconducibles.ply	
Also creates a folder no splitted with a separate .ply file for each	
surface of the non-driveable zone, so it is possible to simplify them	
individually.	
split track.m	s10 split
Selects the points for splitting a track into several segments. Writes	STO_SPIIC
those points in file pos nodes.txt, allowing the user to change them	
before running partir_track	s4 townsin
terrain_noise.m	s4_terrain
Adds a random value to the elevation of the nodes of the terrain.	
Random value will be in the range specified. Use this script just	
before join_all	
terrain_noise([ymin ymax])	
trocea_malla.m	s1_mesh
Splits anchors_carretera.msh into 2 parts: list of mesh nodes	
(nodos.txt) and triangles (elements.txt)	
vercontorno.m	s2_elevation
Shows a contour plot using the terrain elevation data (lamalla.mat)	s2_elevation_b
and the road position (output from btb06)	_