Institute of Artificial Intelligence Innovation Department of Computer Science

Operating System Lecture 07: Memory Management

Shuo-Han Chen 陳碩漢 shch@nycu.edu.tw

Wed. 10:10 - 12:00 EC115 + Fri. 11:10 - 12:00 Online

Questionnaire of HW01

- Second questionnaire of this semester
- There are some Dcard discussions and feedback on HW01
 - Please let me know more (before 10/10 23:59)
- Our response
 - Create a channel for discussion so that everyone can see the QA
 - Provide in-depth HW explanation to a certain level (may not be up to your expectation)
 - Final grade is for sure to be adjusted
 - Possible act: Relax the late submission penalty





Course Schedule

W	Date	Lecture	Online	Homework
1	Sept. 4	Lec00: Couse Overview & Historical Prospective		
2	Sept. 11	Lec01: Introduction	V	
3	Sept. 18	Lec02: OS Structure	V	HW01 Due 10/5
4	Sept. 25	Lec03: Processes Concept	X	
5	Oct. 2	Typhoon – No class	V	
6	Oct. 9	Lec07: Memory Management	V	HW02
7	Oct. 16	Lec08: Virtual Memory Management	V	
8	Oct. 23	Lec04: Process Scheduling	V	
9	Oct. 30	School Midterm Exam		
10	Nov. 6	Lec05: Process Synchronization	V	HW03
11	Nov. 13	Lec06: Deadlocks	V	
12	Nov. 20	School Event – No class		
13	Nov. 27	Lec09: File System Interface	V	HW04
14	Dec. 4	Lec10: File System Implementation	V	
15	Dec. 11	Lec11: Mass Storage System & Lec12: IO Systems	V	
16	Dec. 18	School Final Exam		

Overview

- Background
- Swapping
- Contiguous Allocation
- Paging
- Segmentation
- Segmentation with Paging


Background

- Main memory and registers are the only storage CPU can access directly
- Collection of processes are waiting on disk to be brought into memory and be executed
- Multiple programs are brought into memory to improve resource utilization and response time to users
- A process may be moved between disk and memory during its execution

Outline


- How to refer memory in a program?
 - address binding
- How to load a program into memory?
 - static/dynamic loading and linking
- How to move a program between mem. & disk?
 - swap
- How to allocate memory?
 - paging, segment

Multistep Processing of a User Program




Address Binding - Compile Time

- Program is written as symbolic code
- Compiler translates symbolic code into *absolute code*
- If starting location changes -> recompile
- Example: MS-DOS .COM format binary



Address Binding - Load Time

- Compiler translates symbolic code into relocatable code
- Relocatable code:
 - Machine language that can be run from any memory location
- If starting location -> reload the code




Source Program

Disk Image

Memory Content


Address Binding - Execution Time

- Compiler translates symbolic code into logical-address (i.e. virtual-address) code
- Special hardware (i.e. MMU) is needed for this scheme
- Most general-purpose OS use this method



Memory-Management Unit (MMU)

- Hardware device that maps virtual to physical address
- The value in the relocation register is added to every address generated by a user process at the time it is sent to memory



Logical vs. Physical Address

- Logical address generated by CPU
 - a.k.a. virtual address
- Physical address seen by the memory module
- compile-time & load-time address binding
 - logical addr = physical addr
- Execution-time address binding
 - logical addr ≠ physical addr
- The user program deals with logical addresses; it never sees the real physical addresses

Outline

- How to refer memory in a program?
 - address binding
- How to load a program into memory?
 - static/dynamic loading and linking
- How to move a program between mem. & disk?
 - swap
- How to allocate memory?
 - paging, segment

Dynamic Loading

- The entire program must be in memory for it to execute?
- No, we can use dynamic-loading
 - A routine is loaded into memory when it is called
- Better memory-space utilization
 - unused routine is never loaded
 - Particularly useful when large amounts of code are infrequently used (e.g., error handling code)
- No special support from OS is required implemented through program (library, API calls)

Dynamic Loading Example in C

- dlopen(): opens a library and prepares it for use
- desym(): looks up the value of a symbol in a given (opened) library.
- dlclose(): closes a DL library


```
#include <dlfcn.h>
int main() {
double (*cosine)(double);
void* handle = dlopen ("/lib/libm.so.6", RTLD LAZY);
 cosine = dlsym(handle, "cos");
 printf ("%f\n", (*cosine)(2.0));
 dlclose(handle);
```

Dynamic Loading

Disk image Memory content After B() called After C() called After C() ends Init Function A() { B(); **Function A() Function A() Function A() Function A()** Function B() { C(); **Function B() Function B() Function B()** Function C() { **Function C()**

Static Linking

- Static linking: libraries are combined by the loader into the program in-memory image
 - Waste memory: duplicated code
 - Faster during execution time
- *Static linking + Dynamic loading
 - Still can't prevent duplicated code



Memory

main ()

Libc.lib

main ()


Libc.lib

main ()

Libc.lib

Dynamic Linking

- Dynamic linking: Linking postponed until execution time
 - Only one code copy in memory and shared by everyone
 - A stub is included in the program in-memory image for each lib reference
 - Stub call -> check if the referred lib is in memory if not, load the lib ->execute the lib
 - DLL (Dynamic link library) on Windows



Review Slides (1)

- 3 types of address binding?
 - compile-time
 - load-time
 - execution-time
- logical address? physical address?
 - virtual -> physical mapping?
- dynamic loading? static loading?
- dynamic linking? static linking?

Outline

- How to refer memory in a program?
 - address binding
- How to load a program into memory?
 - static/dynamic loading and linking
- How to move a program between mem. & disk?
 - swap
- How to allocate memory?
 - paging, segment

Swapping


- A process can be swapped out of memory to a backing store, and later brought back into memory for continuous execution
 - Also used by midterm scheduling, different from context switch
- Backing store a chunk of disk, separated from file system, to provide direct access to these memory images
- Why Swap a process:
 - Free up memory
 - Roll out, roll in: swap lower-priority process with a higher one

Swapping (cont'd)

- Swap back memory location
 - If binding is done at compile/load time
 - -> swap back memory address must be the same
 - If binding is done at execution time
 - -> swap back memory address can be different
- A process to be swapped == must be idle
 - Imagine a process that is waiting for I/O is swapped
 - Solutions:
 - Never swap a process with pending I/O
 - I/O operations are done through OS buffers (i.e. a memory space not belongs to any user processes)

Process Swapping to Backing Store

 A major part of swap time is transfer time; total transfer time is directly proportional to the amount of memory swapped



Outline

- How to refer memory in a program?
 - address binding
- How to load a program into memory?
 - static/dynamic loading and linking
- How to move a program between mem. & disk?
 - swap
- How to allocate memory?
 - paging, segment

Contiguous Memory Allocation


Memory Allocation

- Fixed-partition allocation:
 - Each process loads into one partition of fixed-size
 - Degree of multi-programming is bounded by the number of partitions

- Variable-size partition
 - Hole: block of contiguous free memory
 - Holes of various sizes are scattered in memory

Multiple Partition (Variable-Size) Method

- When a process arrives, it is allocated a hole large enough to accommodate it
- The OS maintains info. on each in-use and free-hole
- A freed hole can be merged with another hole to form a larger hole




Dynamic Storage Allocation Problem

- How to satisfy a request of size n from a list of free holes
- First-fit allocate the 1st hole that fits
- Best-fit allocate the smallest hole that fits
 - Must search through the whole list
- Worst-fit allocate the largest hole
 - Must also search through the whole list
- First-fit and best-fit better than worst-fit in terms of speed and storage utilization

Fragmentation

- External fragmentation
 - Total free memory space is big enough to satisfy a request, but is not contiguous
 - Occur in variable-size allocation
- Internal fragmentation
 - Memory that is internal to a partition but is not being used
 - Occur in fixed-partition allocation
- Solution: compaction
 - Shuffle the memory contents to place all free memory together in one large block at execution time
 - Only if the binding is done at execution time



Review Slides (2)

- Swapping?
- Contiguous memory allocation?
 - fixed-size memory allocation?
 - variable-size memory allocation?
 - first-fit, best-fit, worst-fit?
- External & internal fragmentation?
 - compaction?


Non-Contiguous Memory Allocation — Paging

Paging Concept

- Method:
 - Divide physical memory into fixed-sized blocks called frames
 - Divide logical address space into blocks of the same size called pages
 - To run a program of n pages, need to find n free frames and load the program
 - keep track of free frames
 - Set up a page table to translate logical to physical addresses
- Benefit:
 - Allow the physical address space of a process to be noncontiguous
 - Avoid external fragmentation
 - Limited internal fragmentation
 - Provide shared memory/pages

Paging Example

- Page table:
 - Each entry maps to the base address of a page in physical memory
 - A structure maintained by OS for each process
 - Page table includes only pages owned by a process
 - A process cannot access memory outside its space




Address Translation Scheme

- Logical address is divided into two parts:
 - Page number (p)
 - used as an index into a page table which contains base address of each page in physical memory
 - N bits means a process can allocate at most 2^N pages
 - -> 2^N x page size memory size
 - Page offset (d)
 - combined with the base address to define the physical memory address that is sent to the memory unit
 - N bits means the page size is 2^N
 - Ex. 4 KiB = 4096 B = 2 ^ 12
- Physical addr = page base addr + page offset

Address Translation Architecture


- If Page size is 1KB(2^10) & Page 2 maps to frame 5
- Given 13 bits logical address: (p=2,d=20), what is physical addr.?
 - 5*(1KB) + 20 = 1,010,000,000,000 + 0,000,010,100
 - =1,010,000,010,100



Address Translation

- Total number of pages does not need to be the same as the total number of frames
 - Total # pages determines the logical memory size of a process
 - Total # frames depending on the size of physical memory
- E.g.: Given 32 bits logical address, 36 bits physical address, and 4KB page size, what does it mean?
 - Page table size: 2^32 / 2^12 = 2^20 entries
 - Max program memory: 2³² = 4 GiB
 - Total physical memory size: 2^36 = 64 GiB
 - Number of bits for page number: 2^20 pages -> 20bits
 - Number of bits for frame number: 2^24 frames -> 24bits
 - Number of bits for page offset: 4KB page size = 2^12 bytes -> 12

Free Frames



Page / Frame Size

- The page (frame) size is defined by the hardware
 - Typically a power of 2
 - Ranging from 512 bytes to 16MB / page
 - 4KB / 8KB page is commonly used
- Internal fragmentation?
 - Larger page size -> More space waste
- But page sizes have grown over time
 - memory, process, and data sets have become larger
 - Better I/O performance (during page fault)
 - The page table is smaller

Paging Summary

- Paging helps separate user's view of memory and the actual physical memory
- User view's memory: one single contiguous space
 - Actually, user's memory is scatter out in physical memory
- OS maintains a copy of the page table for each process
- OS maintains a frame table for managing physical memory
 - One entry for each physical frame
 - Indicate whether a frame is free or allocated
 - If allocated, to which page of which process or processes

Implementation of Page Table

- Page table is kept in memory
- Page-table base register (PTBR)
 - The physical memory address of the page table
 - The PTBR value is stored in PCB (Process Control Block)
 - Changing the value of PTBR during Context-switch
- With PTBR, each memory reference results in 2 memory reads
 - One for the page table and one for the real address
- The 2-access problem can be solved by
 - Translation Look-aside Buffers (TLB) (HW) which is implemented by Associative memory (HW)

Associative Memory

- All memory entries can be accessed at the same time
 - Each entry corresponds to an associative register
- But number of entries are limited
 - Typical number of entries: 64 ~ 1024
 - Associative memory parallel search

Page #	Frame #

Address translation (A´, A´´)


- If A´ is in associative register, get frame # out.
- Otherwise get frame # from page table in memory

Translation Look-aside Buffer (TLB)

- A cache for page table shared by all processes
- TLB must be flushed after a context switch

Otherwise, TLB entry must has a PID field (address-space identifiers)

(ASIDs))



Effective Memory-Access Time

- 20 ns for TLB search
- 100 ns for memory access
- Effective Memory-Access Time (EMAT)
 - 70% TLB hit-ratio:
 - EMAT = $0.70 \times (20 + 100) + (1-0.70) \times (20+100+100) = 150 \text{ ns}$
 - 98% TLB hit-ratio
 - EMAT = $0.98 \times 120 + 0.02 \times 220 = 122 \text{ ns}$

Review Slides (3)


- memory frame? page? typical page size?
- page table? virtual -> physical translation?
- What is PTBR register? When to update it?
- Memory reads # for each reference?
- HW support for paging speed?
 - associative memory
 - TLB

Memory Protection

- Each page is associated with a set of protection bits in the page table
 - E.g., a bit to define read/write/execution permission
- Common use: valid-invalid bit
 - Valid: the page/frame is in the process logical address space, and is thus a legal page
 - Invalid: the page/frame is not in the process logical address space

Valid-Invalid Bit Example

- Potential issues:
 - Un-used page entry cause memory waste -> use page table length register (PTLR)
 - Process memory may NOT be on the boundary of a page -> memory limit register is still needed




Shared Pages

- Paging allows processes to share common code, which must be reentrant
- Reentrant code (pure code)
 - It never changes during execution
 - text editors, compilers, web servers, etc
- Only one copy of the shared code needs to be kept in physical memory
- Two (several) virtual addresses are mapped to one physical address
- Process keeps a copy of its own private data and code

Shared Pages by Page Table

 Shared code must appear in the same location in the logical address space of all processes



Page Table Memory Structure


- Page table could be huge and difficult to load
 - 4GB (2³²) logical address space with 4KB (2¹²) page
 - -> 1 million (2^20) page table entry
 - Assume each entry need 4 bytes (32bits)
 - -> Total size=4MB
 - Need to break it into several smaller page tables, better within a single page size (i.e. 4KB)
 - Or reduce the total size of page table
- Solutions:
 - Hierarchical Paging
 - Hash Page Tables
 - Inverted Page Table

Hierarchical Paging


- Break up the logical address space into multiple page tables
 - Paged the page table
 - i.e. n-level page table
- Two-level paging (32-bit address with 4KB (2^12) page size)
- 12-bit offset (d) -> 4KB (2^12) page size
- 10-bit outer page number -> 1K (2^10) page table entries
- 10-bit inner page number -> 1K (2^10) page table entries
- 3 memory accesses

ŗ	page number		page offset	
	p_{i}	p_2	d	
	10	10	12	


Two-Level Page Table Example



Two-Level Address Translation



Two-Level Page Table Translation Example




64-bit Address


- How about 64-bit address? (assume each entry needs 4Bytes)
 - 42 (p1) + 10 (p2) + 12 (offset)
 - -> outer table requires 2⁴² x 4B = 16TB contiguous memory!!!
 - 12 (p1)+10 (p2)+10 (p3)+10 (p4)+10 (p5)+12 (offset)
 - -> outer table requires 2^12 x 4B = 16KB contiguous memory
 - -> 6 memory accesses!!!
- Examples:
 - SPARC (32-bit) and Linux use 3-level paging
 - Motorola 68030 (32-bit) use 4-level paging

Hashed Page Table


- Commonly-used for address > 32 bits
- Virtual page number is hashed into a hash table
- The size of the hash table varies
 - Larger hash table -> smaller chains in each entry
- Each entry in the hashed table contains
 - (Virtual Page Number, Frame Number, Next Pointer)
 - Pointers waste memory
 - Traverse linked list waste time & cause additional memory references



Hashed Page Table Address Translation




Improved Hashed Page Table Implementation



Inverted Page Table

- Maintains NO page table for each process
- Maintains a frame table for the whole memory
 - One entry for each real frame of memory
- Each entry in the frame table has
 - (PID, Page Number)
- Eliminate the memory needed for page tables but increase memory access time
 - Each access needs to search the whole frame table
 - Solution: use hashing for the frame table
- Hard to support shared page/memory

Inverted Page Table Addr Translation




Review Slides (4)

- memory protection by page table?
 - valid, invalid bits?
- page table memory structure?
 - hierarchical -> 2-level, 3-level, etc
 - hash table -> linked list
 - inverted page table
- How are pages shared by different processes?


Non-Contiguous Memory Allocation – Segmentation

Segmentation

- Memory-management scheme that supports user view of memory
- A program is a collection of segments. A segment is a logical unit such as:
 - main program
 - function, object
 - local/global variables,
 - stack, symbol table,
 - arrays, etc...



Logical View of Segmentation




Segmentation Table

- Logical address: (seg#, offset)
 - Offset has the SAME length as physical addr.
- Segmentation table maps two-dimensional physical addresses; each table entry has:
 - Base (4 bytes): the start physical addr
 - Limit (4 bytes): the length of the segment
- Segment-table base register (STBR):
 - the physical addr of the segmentation table
- Segment-table length register (STLR):
 - the # of segments


Segmentation Hardware

- Limit register is used to check offset length
- MMU allocate memory by assigning an appropriate base address for each segment
 - Physical address cannot overlap between segments




Address Translation Comparison


- Segment
 - Table entry: (segment base addr., limit)
 - Segment base addr. can be arbitrary
 - The length of "offset" is the same as the physical memory size
- Page:
 - Table entry: (frame base addr.)
 - Frame base addr. = frame number * page size
 - The length of "offset" is the same as page size



Example of Segmentation



Sharing of Segments




Protection & Sharing

- Protection bits associated with segments
 - Read-only segment (code)
 - Read-write segments (data, heap, stack)
- Code sharing occurs at segment level
 - Shared memory communication
 - Shared library
- Share segment by having same base in two segment tables

Segmentation with Paging


Basic Concept

- Apply segmentation in logical address space
- Apply paging in the physical address space




Address Translation

- CPU generates logical address
 - Given to segmentation unit
 - -> produces linear addresses
 - Linear address given to paging unit
 - -> generates physical address in main memory
- Segmentation and paging units form the equivalent of MMU




Example: The Intel Pentium

- Logical address space is divided into 2 partitions:
 - 1st: 8K(2¹³) segments (private), local descriptor table (LDT)
 - 2nd: 8K(2¹³) segments (shared), global descriptor table (GDT)
- Logical address:
 - max # of segments per process = 2¹⁴ = 16K
 - size of a segment <= 2³² = 4GB




Intel Pentium Segmentation

- Segment descriptor
 - Segment base address and length
 - Access right and privileged level




Intel Pentium Paging (Two-Level)

- Page size can be either 4KB or 4MB
 - Each page directory entry has a flag for indication



Example Question

- Let the physical mem size is 512B, the page size is 32B and the logical address of a program can have 8 segments. Given a 12 bits hexadecimal logical address "448", translate the addr. With blow page and segment tables.
- linear addr:010111110, phy addr:001011110



Review Slides (5)

Segmentation vs. Paging?

	Paging	segmentation
Length	Fixed	Varied
Fragmentation	Internal	External
Table entry	Page number → frame number	Seg ID → (base addr, limit length)
View	Physical memory	User program

Paged segmentation?

Reading Material & HW

- Chap 8
- Problem Set:
 - 8.1, 8.3, 8.4, 8.5, 8.12, 8.15, 8.16, 8.20, 8.23
- Interesting Reading:
 - M. Talluri, M. D. Hill, and Y. A. Khalidi. 1995. A new page table for 64-bit address spaces. SIGOPS Oper. Syst. Rev. 29, 5 (December 1995), 184-200.
 - http://pages.cs.wisc.edu/~markhill/papers/sosp95_pageta bles.pdf

Q&A

Thank you for your attention