# Package 'FAIBCompiler'

July 11, 2019

Title FAIB compilers **Version** 0.0.0.9000

**Description** Home for VRI and PSP compilers

<b>License</b> Apache License (== 2.0)   file LICE	NSE						
Encoding UTF-8							
LazyData true							
<b>Roxygen</b> list(markdown = TRUE)							
RoxygenNote 6.1.1							
Imports methods,  dplyr, data.table, fpCompare, rmarkdown, sp, bcmaps, raster, rgdal, rgeos, nlme, spatstat, jsonlite, openxlsx, haven, SIndexR, FAIBOracle, FAIBBase  Suggests knitr  R topics documented:  ageByForester							
applyDWB							
auxiTreeCompiler							
boredAgeCalculator_Bore							
boredAgeCalculator_Crted boredAgeCalculator_Phys							
	1						

44

Index

boredAgeCalculator_Prorated	8
boredAgeCalculator_Total	
compilerPathSetup	10
DWBCompiler	10
DWBGenerator_BEC	11
DWBGenerator_FIZ	12
getDWBSeries	13
heightSmry_byC	14
loadASCII	14
logAdjustment	15
logAttributesLongForm	16
logFileProducer	17
logMatrixAdjustment	18
lookupCheck	19
mergeAllVolTrees	20
mergeOAData	20
netVolumeCalculator	21
prj_ID2BEC	22
prj_ID2Grp	23
readHandHeld	23
readHandHeld_mod	24
regBA_WSV	25
regRatioDataSelect	
riskGroupDeriver	
siteAgeCompiler	
siteAgeSummary	
siteToolsSpeciesConvertor	
SiteTools_HTBoredAge2SI	
SiteTools_Y2BH	
smallTreeVolSmry	
speciesComp_byC	
stumpVolSmry	
toWSVRatio	
toWSVRatio_curve	33
treeVolEst_RegRatio	
valueCalculator	
volSmry_byC	
volSmry_byCS	
VRICompiler	
VRIInit_auxTree	
VRIInit_clusterplot	
VRIInit lossFactor	
VRIInit_measuredTree	
VRIInit siteTree	
VRISummaries	
VRIVolTree	
VICE VOLUME	+3

ageByForester 3

5	a	. 10
ageByForester	Site age by e	xperienced forester
agebyrorester	Dire age by co	iperienced joresier

### **Description**

This function derives the site age based on experienced forester. It is equivalent to vri\_age macro in original SAS compiler.

### Usage

```
ageByForester(projectID, sampleNumber, sampleTypeCode)
```

### **Arguments**

```
projectID character, Project ID.
sampleNumber character, Sample number.
sampleTypeCode character, Sample type code.
```

### Value

Age provided by experienced forester

#### Note

Contact Bob Krahn for details

### Author(s)

Yong Luo

ageRangeClassifier	Derive age range code
--------------------	-----------------------

### **Description**

This function derives age range code based on age, species and FIZ. The returned age range code includes: 1-young(immature), 2-older(immature), 3-mature and 4-overmature. This function is equivalent to age\_rng.sas macro.

### Usage

```
ageRangeClassifier(age, species, FIZ)
```

### Arguments

age	numeric.	Usually	laver mean	age.	what does t	his mean?
~6~	,	00000	100 01 11100111	~~~	***************************************	

species character, Tree basic species code, which is SP0 in VRI original data.

FIZ character, BC forest inventory zone.

4 auxiTreeCompiler

#### Value

DWB age range code

#### Author(s)

Yong Luo

applyDWB

Apply decay, waste and breakage percentage to gross merchantable volume-VRI specific

### **Description**

This function calculates merchantable volume after removing decay, waste and breakage in VRI compiler. The function is part of cp\_vegi\_2017.sas to derive tree\_ms7.

#### Usage

applyDWB(treeMS)

### **Arguments**

treeMS

data.table, Compiled full and enhanced trees with percentage of decay, waste and breakage.

### Value

A data table that contains VOL\_NTWB (net volume that waste 2 wood and breakage), VOL\_D (merchantable volume after removing decay), VOL\_DW (merchantable volume after removing decay and waste) and VOL\_DWB (merchantable volume after removing decay, waste and breakage).

### Author(s)

Yong Luo

auxiTreeCompiler

Derive volume components for H-enhanced and non-enhanced trees using external coeff and ratio-VRI specific

### Description

Estimates volume components for H-enhanced and non-enhanced trees using regression and ratio methods. For H-enhanced trees, the whole stem volume and gross merchantable volume are already calculated directly using taper equations; and rest of volume components will be calculated using ratio method in this function. For non-enhanced trees, the whole stem volume is derived using regression equation between basal area and whole stem volume and the rest of volume components will be computed using ratio method in this function.

auxiTreeCompiler 5

### Usage

```
auxiTreeCompiler(fullMeasuredTrees, auxiTrees, clusterPlotHeader,
  fixedCoeff, randomCoeff, ratios)
```

### **Arguments**

fullMeasuredTrees

Compiled tree-level data in vi\_c, which contains full measured trees, enhanced

trees and H-enhanced trees. This data is output of DWBCompiler

auxiTrees data.table, Non-enhanced trees in anxilirary plots, however, it may have en-

hanced trees and H-enhanced trees. An output from VRIInit\_auxTree.

clusterPlotHeader

data.table, Cluster and plot-level information. An output of VRIInit\_clusterplot.

fixedCoeff data.table, Specifies the WSV-BA equations by project group PRJ\_GRP, live and

dead status LV\_D, stand and falling status SF\_COMPILE and species code SP0.

The table can be generated using WSV\_BARegression.

randomCoeff data.table, Specifies the WSV-BA equations by project group PRJ\_GRP, live and

dead status LV\_D, stand and falling status SF\_COMPILE and species code SP0.

The table can be generated using WSV\_BARegression.

ratios data.table, Specifies to WSV ratio by project group PRJ\_GRP, live and dead status

LV\_D, stand and falling status SF\_COMPILE and species code SP0. The table can

be generated using toWSVRatio.

#### Value

A list of four tables: 1. fullenhancedtrees: full and enhanced trees; 2. HnonenhancedTrees: Height enhanced and non-enhanced trees;

#### Note

The data selection procedure for regression has been standardized as following:

- 1. Start from vi\_c, which has all trees have minimum information of DBH and Height;
- 2. Select all the full, enhanced and H-enhanced trees;
- 3. Remove observations in Audit plots and have zero whole stem volume;
- 4. Select the latest observation for each tree by live\_dead status. A tree's identity is considered same when it is from same proj\_id, samp\_no and plot.

The data selection for ratio has been standardized as following:

- 1. Start from the that used for regression;
- 2. Select all the full and enhanced trees;
- 3. Select the trees with DBH  $\geq$  10cm

#### Author(s)

boredAgeCalculator\_Bore

Derive bored age using office and field bored age

### Description

This function is to derive bore age based on either office bored age (officeBoredAge) or field bored age (fieldBoredAge). When both bore age information are available, the function takes officeBoredAge as priority. The function is one of the four functions that derive bored age using different method. The rests are boredAgeCalculator\_Total, boredAgeCalculator\_Phys and boredAgeCalculator\_Prorated.

### Usage

```
boredAgeCalculator_Bore(officeBoredAge, fieldBoredAge)
## S4 method for signature 'numeric,numeric'
boredAgeCalculator_Bore(officeBoredAge,
    fieldBoredAge)
## S4 method for signature 'numeric,missing'
boredAgeCalculator_Bore(officeBoredAge)
## S4 method for signature 'missing,numeric'
boredAgeCalculator_Bore(fieldBoredAge)
```

### Arguments

```
officeBoredAge numeric, Office bored age, which is measured in lab by professionals. fieldBoredAge numeric, Field bored age, estimated in field by field crew.
```

#### Value

bored age

#### Author(s)

Yong Luo

#### See Also

 $bored Age Calculator\_Phys\ bored Age Calculator\_Phys\ bored Age Calculator\_Prorated$ 

boredAgeCalculator\_Crted

Derive age at breast height

### Description

This function uses site tools to derive age at breast height for the bored age that is not taken at breast height, i.e., 1.3 m. The process was documented in BC VRI Sample Data Compilation Process.

#### Usage

```
boredAgeCalculator_Crted(boredAge, boredHeight, treeHeight, species, FIZ)

## S4 method for signature 'numeric,numeric,numeric,character,character'
boredAgeCalculator_Crted(boredAge,
   boredHeight, treeHeight, species, FIZ)
```

#### **Arguments**

boredAge numeric, Age at bored height boredHeight numeric, Height at the bore core.

treeHeight numeric, Total tree height

species character, Species code, must be consistent with the species code in site tools.

Can be derived using siteToolsSpeciesConvertor.

FIZ character, Forest inventory zone.

#### Value

Tree age at breast height (1.3 m). For the estimated age  $\leq 0.1$ , the bored age will be used as breast age and a warning message will be given.

#### Author(s)

Yong Luo

boredAgeCalculator\_Phys

Derive bored age using physiological age

### Description

This function is to derive bore age based on physiological age (physAge). The function is one of the four functions that derive bored age using different method. The rests are boredAgeCalculator\_Bore, boredAgeCalculator\_Total and boredAgeCalculator\_Prorated.

#### Usage

```
boredAgeCalculator_Phys(physAge)
## S4 method for signature 'numeric'
boredAgeCalculator_Phys(physAge)
```

### **Arguments**

physAge numeric, Pysiological age.

#### Value

bored age

#### Author(s)

Yong Luo

#### See Also

 $bored Age Calculator\_Total\ bored Age Calculator\_Phys\ bored Age Calculator\_Prorated$ 

boredAgeCalculator\_Prorated

Derive bored age using pro-rated age

### **Description**

This function is to derive bore age based on diameter at bore (boreDiameter), bark thickness (barkThickness), pro-rated ring length (ringLength\_prorated) and pro-rated ring count (ringCount\_prorated). The function is one of the four functions that derive bored age using different method. The rests are boredAgeCalculator\_Bore, boredAgeCalculator\_Total and boredAgeCalculator\_Phys.

```
boredAgeCalculator_Prorated(ringLength_prorated, ringCount_prorated,
   boreDiameter, barkThickness)

## S4 method for signature 'numeric,numeric,numeric,numeric'
boredAgeCalculator_Prorated(ringLength_prorated,
   ringCount_prorated, boreDiameter, barkThickness)

## S4 method for signature 'numeric,numeric,numeric,missing'
boredAgeCalculator_Prorated(ringLength_prorated,
   ringCount_prorated, boreDiameter)
```

#### **Arguments**

```
ringLength_prorated
```

numeric, Pro-rated ring length in cm

ringCount\_prorated

numeric, Pro-rated ring count

boreDiameter numeric, Diameter at bore in cm

barkThickness numeric, Bark thickness in mm. If missing, 0.05 is used in the function.

#### Value

bored age

#### Author(s)

Yong Luo

#### See Also

 $bored Age Calculator\_Total\ bored Age Calculator\_Phys\ bored Age Calculator\_Prorated$ 

boredAgeCalculator\_Total

Derive bored age using total age

### **Description**

This function is to derive bore age based on total age (totalAge). The function is one of the four functions that derive bored age using different method. The rests are boredAgeCalculator\_Bore, boredAgeCalculator\_Phys and boredAgeCalculator\_Prorated.

### Usage

```
boredAgeCalculator_Total(totalAge)
## S4 method for signature 'numeric'
boredAgeCalculator_Total(totalAge)
```

### **Arguments**

totalAge numeric, Total tree age, ie., age at height of 0.

#### Value

bored age

### Author(s)

Yong Luo

#### See Also

 $bored Age Calculator\_Total\ bored Age Calculator\_Phys\ bored Age Calculator\_Prorated$ 

DWBCompiler

compilerPathSetup

Setup an output path of the compiler

### **Description**

This function does two things: 1. create a folder that will store compiled data; 2. return a path that directs the compiled folder.

#### Usage

```
compilerPathSetup(compilationPath = ".")
```

### **Arguments**

compilationPath

character, Specifies a path to store whole compilation process. If missing, the current work directory will be used.

#### Value

Four paths will be returned as following:

- raw\_from\_oracle Path to save all data that read from both oracle and txt database without merging.
- compilation\_sa Path to save merged data for key tables (i.e., vi\_a to vi.g) from both oracle and txt database.
- compilation\_db Path to save compiled outputs.
- compilation\_archive Path to archive all compilation process.

#### Note

Could overwrite the existing output folder, depending on user's choise, i.e., yes or no.

### Author(s)

Yong Luo

DWBCompiler

Compile decay, waste and breakage for standard tables-VRI specific

### Description

This function compiles decay, waste and breakage for standard tables in VRI compiler. The function is equivalent to dwb\_vri\_2017.sas.

DWBGenerator\_BEC 11

#### Usage

```
DWBCompiler(treeMS, siteAge, treeLossFactors, equation)
## S4 method for signature 'data.table,data.table,data.table,character'
DWBCompiler(treeMS,
    siteAge, treeLossFactors, equation)
## S4 method for signature 'data.table,data.table,data.table,missing'
DWBCompiler(treeMS,
    siteAge, treeLossFactors)
```

### Arguments

treeMS data.table, Tree-level data that has been compiled whole stem volume and gross

merchantable volume for full and enhanced trees.

siteAge data.table, Cluster-level summaries of age and height. This table is an output

from siteAgeSummary

treeLossFactors

data.table, The tree loss factor data, an output of VRIInit\_lossFactor. In this

funtion, this table provides loss indicator.

equation character, Specifies whether the compiler is based on KFIZ or KBEC. Default is

set as KBEC.

#### Value

A compiled volume after removing decay, waste and breakage; a log file

#### Author(s)

Yong Luo

DWBGenerator\_BEC

Collect decay, waste and breakage factor in BEC routine

### Description

This function is to collect the dead, waste and breakage factor from lookup table and join them into tree data. Instead of reading the lookup table from disk, the function uses hard-coded the lookup table. This function is equivalent to dwb\_v3.sas macro. For FIZ routine, the decay, waste and breakage are collected using funtion DWBGenerator\_FIZ

```
DWBGenerator_BEC(DBH, height, species, meanAge, BEC, riskGroup, adjustID)

## S4 method for signature

## 'numeric, numeric, character, numeric, character, character'

DWBGenerator_BEC(DBH,
   height, species, meanAge, BEC, riskGroup, adjustID)
```

12 DWBGenerator\_FIZ

### **Arguments**

DBH numeric, Tree DBH. height numeric, Tree height.

species character, Tree basic species code, which is SP0 in VRI original data.

meanAge numeric, Mean site age.

BEC character, BC BEC zone.

riskGroup character, Specifies the risk group. It must be one of 1, 2 or 3. It can be derived

from riskGroupDeriver.

adjustID character, Adjustment identifier. Blank is no adjustment; QCI is queen char-

lottes; WET is wetbelt and GLD\_NW golden?.

#### Value

A list of decay, waste and breakage percentage.

#### Author(s)

Yong Luo

DWBGenerator\_FIZ

Collect decay, waste and breakage factor in FIZ routine

### **Description**

This function is to collect the dead, waste and breakage factor from lookup table and join them into tree data. Instead of reading the lookup table from disk, the function uses hard-coded the lookup table. This function is equivalent to second part of dwb\_fct.sas macro. For BEC routine, the decay, waste and breakage are collected using funtion DWBGenerator\_BEC

### Usage

```
DWBGenerator_FIZ(DBHClass, tabNumber, riskGroup)
## S4 method for signature 'numeric,character,character'
DWBGenerator_FIZ(DBHClass,
  tabNumber, riskGroup)
```

### **Arguments**

DBHClass numeric, Tree DBH class. Currently, The function is capatable to the DBH class

with 5 cm interval. It can be derived using DBHClassifier.

tabNumber character, This character consist of 4 numbers. The first two number is the

species number, and the last is the series number.

riskGroup character, Specifies the risk group. It must be one of 1, 2 or 3. It can be derived

from riskGroupDeriver.

#### Value

A list of decay, waste and breakage percentage.

getDWBSeries 13

#### Author(s)

Yong Luo

getDWBSeries Get local DWB series

### **Description**

Join local DWB (old/imperical factors) by species, PSYUB, ageRangeClass and FIZ. This function is the first part of dwb\_fct.sas.

#### Usage

```
getDWBSeries(species, ageRangeClass, PSYUB, FIZ, source)

## S4 method for signature 'character, character, character, character, character'
getDWBSeries(species,
    ageRangeClass, PSYUB, FIZ, source)

## S4 method for signature 'character, character, character, missing, character'
getDWBSeries(species,
    ageRangeClass, PSYUB, source)

## S4 method for signature 'character, character, missing, character, character'
getDWBSeries(species,
    ageRangeClass, FIZ, source)
```

### **Arguments**

species character, Tree basic species code, which is SP0 in VRI original data.

ageRangeClass character, The classified age range into 1 to 4. Output from ageRangeClassifier.

PSYUB character, Unique PSYU+PSYU\_BLK code.

FIZ character, BC forest inventory zone.

source character, Series source, must one of local, zonal and reversing Zonal. local

is based on species, PSYUB and ageRangeClass; zonal is based on FIZ, species and ageRangeClass; and reversingZonal is based on reversing FIZ zones, i.e.,

changing interior to coastal and changing coastal to interior.

### Value

DWB series, a two number character.

### Author(s)

14 loadASCII

heightSmry\_byC

Summarize mean and lorry's height by cluster-VRI specific

#### **Description**

Summarizes mean and lorry's height by cluster for standing trees, standing + live trees, and standing + live + non-broken top trees. The function is improved version to calculate mean height in vol\_ha\_2017.sas by outputing lorey's height. For both fixed and variable area plots, the function computes mean height by using plot weight (PLOT\_WT) weighted height. For lorey's height computation, the function treats variable and fixed area plots differently. Specifically, the function uses the mean height as lorey's height for variable plots, while uses height that weighted both by plot weight (PLOT\_WT) and basal area (BA\_TREE) for fixed area plots.

### Usage

```
heightSmry_byC(treeMC)
## S4 method for signature 'data.table'
heightSmry_byC(treeMC)
```

#### **Arguments**

treeMC

data.table, Compiled tree-level data that contains both measured trees and counted trees.

### Value

A table contains computed mean height MN or MEAN and lorey's height LRY for all standing trees ALL, standing and live trees 1 and standing and non-broken top trees 2. The output is equevalent to height table in original compiler.

#### Author(s)

Yong Luo

loadASCII

Load the data from ASCII files

### **Description**

This function is to read the data from ASCII files (in txt format).

```
loadASCII(txtLocation, saveThem = FALSE, savePath)
```

logAdjustment 15

#### **Arguments**

txtLocation character, Specifies the location of ASCII files.

saveThem logical, Specifies whether the loaded data should be saved or returned. The

default value is FALSE, which means the function will not save files for you.

savePath character, Specifies the path that directs to the VRI original data soruce, i.e.,

//Mayhem/GIS\_TIB/RDW/RDW\_Data2/Work\_Areas/VRI\_ASCII\_PROD/vri\_sa.

#### Value

no files

#### Author(s)

Yong Luo

### **Examples**

logAdjustment

Adjust log length - VRI specific

### **Description**

The function is to adjust the log length to fit actual height. This function is equivalent to log\_adj\_new macro in original VRI compiler

### Usage

```
logAdjustment(treeData, stumpHeight)
## S4 method for signature 'data.table,numeric'
logAdjustment(treeData, stumpHeight)
## S4 method for signature 'data.table,missing'
logAdjustment(treeData)
```

### Arguments

treeData data.table, Must have tree data information. The table is an output of VRIInit\_measuredTree. stumpHeight numeric, Length of stump. As default, this arguement is set as 0.3 m.

#### Value

Data table that contains the adjusted log length

#### Note

Please see Bob for details about input files

### Author(s)

Yong Luo

logAttributesLongForm Transpose wide form table to long form table-VRI specific

### Description

This function transposes wide form outputs to long form outputs. This function is not included in the VRI compiler anymore.

### Usage

```
logAttributesLongForm(treeData, maximumLogNO)
## S4 method for signature 'data.table,numeric'
logAttributesLongForm(treeData,
    maximumLogNO)
## S4 method for signature 'data.table,missing'
logAttributesLongForm(treeData,
    maximumLogNO)
```

### Arguments

treeData data.table, an output from logValueCalculator function, i.e., tree\_ms6. This

table currently has top diameter (LOG\_D\_X), length (LOG\_L\_X), volume (LOG\_V\_X), merchantable volume (LOG\_VM\_X), grade (LOG\_G\_X), sound percentage (LOG\_S\_X)

and value (LOG\_c\_x). X is log number from 1 to maximum log number.

maximumLogNO numeric, determine the maximum number of logs. In VRI compiler, it is 9.

Therefore, 9 is default.

#### Value

A data table and a log file

### Author(s)

logFileProducer 17

logFileProducer To display a table to log file

### **Description**

Simple tool to display a table to log file.

### Usage

```
logFileProducer(reason, action, displayTable, displayColumn,
  changedVariable, fromTo)
 ## S4 method for signature
## 'character, character, data.table, character, character, character'
logFileProducer(reason,
  action, displayTable, displayColumn, changedVariable, fromTo)
 ## S4 method for signature
## 'character, character, data.table, missing, character, character'
logFileProducer(reason,
  action, displayTable, changedVariable, fromTo)
 ## S4 method for signature
## 'character,character,data.table,character,missing,missing'
logFileProducer(reason,
  action, displayTable, displayColumn)
 ## S4 method for signature
## 'character, character, data.table, missing, missing, missing'
logFileProducer(reason,
  action, displayTable)
```

### Arguments

reason character, Reason to trigger an action.

action character, Specifies action from one of removed, no and changed.

displayTable data.table, A table of interest

displayColumn character, Specifies which column(s) will be displayed in the log file.

changedVariable,

charcater, Specifies the variable that has been modified, must be present if action

is changed.

fromTo character, This is two vectors character. Specifies columns that before and after

alteration. Must be present when action is set as changed.

#### Value

A tring of text

#### Author(s)

Yong Luo

logMatrixAdjustment Adjust log length matrix

### **Description**

This function is to adjust log length matrix based on tree height, minimum log length and default log length. This function is equivalent to vol\_tree\_log\_validation macro in original sas compiler.

```
logMatrixAdjustment(logLengthMatrix, height, stumpHeight, logMinLength,
  logDefaultLength)
  ## S4 method for signature 'data.table,numeric,numeric,numeric'
logMatrixAdjustment(logLengthMatrix,
 height, stumpHeight, logMinLength, logDefaultLength)
  ## S4 method for signature 'data.table,numeric,missing,numeric,numeric'
logMatrixAdjustment(logLengthMatrix,
 height, logMinLength, logDefaultLength)
 ## S4 method for signature 'data.table,numeric,numeric,missing,numeric'
log {\tt MatrixAdjustment} (log {\tt LengthMatrix},
 height, stumpHeight, logDefaultLength)
  ## S4 method for signature 'data.table,numeric,numeric,numeric,missing'
logMatrixAdjustment(logLengthMatrix,
 height, stumpHeight, logMinLength)
  ## S4 method for signature 'data.table,numeric,missing,missing,numeric'
logMatrixAdjustment(logLengthMatrix,
 height, logDefaultLength)
  ## S4 method for signature 'data.table,numeric,missing,numeric,missing'
logMatrixAdjustment(logLengthMatrix,
 height, logMinLength)
  ## S4 method for signature 'data.table,numeric,missing,missing,missing'
logMatrixAdjustment(logLengthMatrix,
 height)
```

lookupCheck 19

### **Arguments**

logLengthMatrix

data.table, A matrix of log length for each tree, NA is accepted in the matrix. The order of log from bottom to top must be presented from left to right in the

table

height numeric, Tree height

stumpHeight, numeric, Stump height. If missing, 0.3 m is used.

logMinLength numeric, Minimum log length. If missing, 3 m is used.

 ${\tt logDefaultLength}$ 

numeric, Default log length. If missing, 5 m is used.

### Value

A data.table that contains the matrix of adjusted log length

#### Author(s)

Yong Luo

lookupCheck

Test whether the lookup table is updated

### **Description**

Reports whether a lookup table is updated. This function is highly recommended before proceed the VRI compiler.

### Usage

```
lookupCheck(lookupName, lookupPath)
## S4 method for signature 'character, character'
lookupCheck(lookupName, lookupPath)
## S4 method for signature 'character, missing'
lookupCheck(lookupName)
```

#### **Arguments**

lookupName character, Specifies the name of lookup table.
lookupPath character, Path that directs to lookup tables.

#### Value

Not value returned. A warning message is given if the lookup table is changed.

### Author(s)

20 mergeOAData

mergeAllVolTrees

Merge all volume trees-VRI specific

#### **Description**

Merge all the volume trees, including full trees (fully-measure trees in IPC), enhanced trees (fully-measured trees in auxi plots), H-enhanced trees (Height measured in auxi plots) and non-enhanced trees (only DBH measured in auxi plots). The function is part of  $vol_ha_2017$ . sas and modified dramatically in R compiler.

### Usage

```
mergeAllVolTrees(treeMS, treeAX)
## S4 method for signature 'data.table,data.table'
mergeAllVolTrees(treeMS, treeAX)
```

### **Arguments**

treeMS data.table, Compiled full, enhanced and H-enhanced trees. This data should be

listed in vi\_c table. This data is an output of DWBCompiler

treeAX data.table, Non-enhanced trees in anxilirary plots (vi\_i). Supposedly, the table

only contains non-enhanced tree list. However, some enhanced and H-enhanced

trees also been stored in this dataset. An output from VRIInit\_auxTree.

#### Value

A data table that contains all volume trees without duplicates. Equivalent to tree\_vb table.

### Author(s)

Yong Luo

mergeOAData

Merge oracle and ascii data for vi\_(a, ..i)

### **Description**

This function is to merge oracle and ascii data before the VRI compiler

```
mergeOAData(oracleSourcePath, asciiSourcePath, fizmapPath, fizmapName,
  fizmapFormat, outputPath)
```

netVolumeCalculator 21

### **Arguments**

oracleSourcePath

character, Specifies the path that stores data from oracle data base. In VRI com-

piler, this should be the savePath for loadVGIS.

asciiSourcePath

character, Specifies the path that stores data from ascii data base. In VRI com-

piler, this should be the savePath for loadASCII.

fizmapPath character, Specifies the path to forest inventory zone map. By default, it is set to

//spatialfiles2.bcgov/work/for/vic/hts/dam/workarea/data/infrastructure,

which is maintained by FAIB employee.

fizmapName character, Specifies the name of forest inventory zone map. By default, it is set

to FIZ\_REG\_COMPARTMENT, which is maintained by FAIB employee.

fizmapFormat character, Specifies the format of forest inventory zone map. Currently, it can

be specified as gdb for geodatabase format and shp for shapefile format. By

default, it is set to gdb, which is maintained by FAIB employee.

outputPath character, Specifies the path to save your outputs. If missing, the current working

directory will be choosed.

#### Value

no item returned

#### Author(s)

Yong Luo

netVolumeCalculator

Calcualtes total net volume and merchantable volume-VRI specific

### **Description**

This function calculates total net volume and net merchantable volume for each tree based on ground called sound percentage. From the second column to the last column, the grossVolMatrix table should have same dimensions (i.e., number of rows and columns) of netFactorMatrix and grossMerchVolMatrix if they are provided. Furthermore, be aware of the correspondingness among the matrix. This function is part of log\_valu\_2017.sas.

```
netVolumeCalculator(grossVolMatrix, grossMerchVolMatrix, netFactorMatrix)
```

```
## S4 method for signature 'data.table,data.table,data.table'
netVolumeCalculator(grossVolMatrix,
   grossMerchVolMatrix, netFactorMatrix)
```

```
## S4 method for signature 'missing,data.table,data.table'
netVolumeCalculator(grossMerchVolMatrix,
```

22 prj\_ID2BEC

```
netFactorMatrix)

## S4 method for signature 'data.table,missing,data.table'
netVolumeCalculator(grossVolMatrix,
    netFactorMatrix)

## S4 method for signature 'data.table,data.table,missing'
netVolumeCalculator(grossVolMatrix,
    grossMerchVolMatrix)
```

#### **Arguments**

grossVolMatrix data.table, Calculated gross volume for each log. The first column of this table is the volume for the stump. If missing, the function calculates the total net merchantable volume.

grossMerchVolMatrix

data.table, Calculated gross merchantable volume for each log. If missing, all the merchantable volume is assigned as 0.

netFactorMatrix

data.table, Ground call for sound percentage. If missing, the net factoring will be assigned as 100.

#### Value

Data table that contains total net volume (VOL\_NET) and total net merchantable volume (VOL\_NETM) for each tree.

### Author(s)

Yong Luo

prj\_ID2BEC

Assign BEC based on project ID

### **Description**

This function takes lookup table that connects project id to BEC zone and joins BEC zone by project id. The function uses a hardcoded lookup table vri\_bec. The function is equivalent to group\_bec.sas.

### Usage

```
prj_ID2BEC(projectID)
## S4 method for signature 'character'
prj_ID2BEC(projectID)
```

#### **Arguments**

projectID character, Specifies project ID.

prj\_ID2Grp 23

#### Value

BEC, Unknown will be return if project id does have any match in lookup table.

#### Author(s)

Yong Luo

prj\_ID2Grp

Group project ID into project group

### Description

This function takes lookup table that connect project id to project group and joins project group by project id. The function uses hardcoded lookup table vri\_grp. The function is equivalent to group\_prj.sas.

### Usage

```
prj_ID2Grp(projectID)
## S4 method for signature 'character'
prj_ID2Grp(projectID)
```

### **Arguments**

projectID character, Specifies project ID.

### Value

Project group, Unknown will be return if project id does have any match in lookup table.

#### Author(s)

Yong Luo

readHandHeld

load json data from handheld and save tables into target folder

### **Description**

This function is to load JSON file data from FAIB new handheld.

```
readHandHeld(fileName, savePath = getwd(), saveFormat = "rdata",
   saveName = "myHandHeldFile", overWrite = FALSE)
```

24 readHandHeld\_mod

#### **Arguments**

fileName character, JSON file name.

savePath character, A folder path user wants to save all the outputs. Default is the current

work directory.

saveFormat character, Specifies the format user wants to save. Currently, the function sup-

ports xlsx and rdata. Default is rdata.

saveName character, Specifies the save name.

overWrite logical, Determine if the file with same name as user specifies will be overwrit-

ten. Default is FALSE.

#### Value

No value will be returned. All the outputs will be saved in a target folder.

#### Author(s)

Yong Luo

#### **Examples**

readHandHeld\_mod

load json data from handheld and save tables into target folder

### **Description**

This function is to load JSON file data from FAIB new handheld.

### Usage

```
readHandHeld_mod(fileName, savePath = getwd(), saveFormat = "rdata",
   saveName = "myHandHeldFile", overWrite = FALSE)
```

### **Arguments**

fileName character, JSON file name.

savePath character, A folder path user wants to save all the outputs. Default is the current

work directory.

saveFormat character, Specifies the format user wants to save. Currently, the function sup-

ports xlsx and rdata. Default is rdata.

 $regBA\_WSV$  25

saveName character, Specifies the save name.

overWrite logical, Determine if the file with same name as user specifies will be overwrit-

ten. Default is FALSE.

#### Value

No value will be returned. All the outputs will be saved in a target folder.

#### Author(s)

Yong Luo

#### **Examples**

regBA\_WSV

To fit basal area and whole stem volume regression using mixed effect model

### **Description**

This function takes the selected data for fitting regression model between basal area and whole stem volume using mixed effect model. The models are fitted based on strata of BEC+SP0+LV\_D

### Usage

```
regBA_WSV(inputData, needCombs)
```

### Arguments

inputData data.table, The data for fitting regression.

needCombs data.table, The combinations of BEC+SP0+LV\_D are needed to derive coeffi-

cients.

### Value

coefficient table

### Author(s)

26 riskGroupDeriver

regRatioDataSelect Select the data for regression and ratio

### **Description**

This function selects the data for fitting regression model between basal area and whole stem volume, and for ratios to whole stem volume in VRI compiler. The regreesion method is used for derive whole stem volume for the trees that just have DBH information. The ratio method is used to derive netted merchantable volume for the trees that do not have call grading information. The data selection should be done annually at the end of every March to allow newer and higher quaulity data enter the data.

### Usage

regRatioDataSelect(sampledata, alltreedata)

### **Arguments**

sampledata data.table, The data contains the sample level information.

alltreedata data.table, The is the data pool which contains the full/enhanced trees and H-

enhanced trees.

#### Value

Selected data for regression and ratio.

### Author(s)

Yong Luo

riskGroupDeriver

Derive risk group for standard sample compilation/data

### **Description**

will refine. This function is equivalent to risk\_grp.sas macro.

riskGroupDeriver(species, pathIndex, series, height, method)

```
## S4 method for signature 'character,character,character,numeric,character'
riskGroupDeriver(species,
  pathIndex, series, height, method)
```

```
## S4 method for signature 'character,character,missing,missing,character'
riskGroupDeriver(species,
  pathIndex, series, height, method)
```

siteAgeCompiler 27

#### **Arguments**

species character, Tree basic species code, which is SP0 in VRI original data.

pathIndex character, A character with length of 8, consists of 0 or 1.

series character, DWB series. It is a length of 2 number character and can be derived

using getDWBSeries function.

height numeric, Total tree height.

method character, Specifies the method between FIZ and KBEC to categorize the risk

group. The FIZ method derives risk group by species, pathIndex, series and height. KBEC method derives the risk group using species and pathIndex.

#### Value

Risk group, which is character

### Author(s)

Yong Luo

siteAgeCompiler Compile breast age, total age, and site index where possible-VRI specific

### **Description**

This function takes site age tree data ie., vi\_h, an output of VRIInit\_siteTree to compute the breast height age, total age, and site index where possible. This function is equivalent to site\_age.sas. The function heavily depends on site tools program.

### Usage

```
siteAgeCompiler(siteAgeData)
## S4 method for signature 'data.table'
siteAgeCompiler(siteAgeData)
```

### Arguments

 ${\tt siteAgeData} \qquad {\tt data.table, Site age \ data \ with \ plot \ header \ information. \ An \ output \ from \ VRIInit\_siteTree}$ 

function.

### Value

A data table and a log file.

#### Author(s)

siteAgeSummary

Summarize site age data by cluster and cluster/species-VRI specific

### **Description**

This function takes compiled site age tree data, an output of siteAgeCompiler, to derive mean age and height results. The compiled data must have breast height age, total age, and site index. This function is equivalent to mean\_htl.sas.

### Usage

```
siteAgeSummary(cpldSiteAgeData)
## S4 method for signature 'data.table'
siteAgeSummary(cpldSiteAgeData)
```

### **Arguments**

cpldSiteAgeData

data.table, Compiled site age tree data, an output of siteAgeCompiler.

### Value

Two data tables: cl\_ah is the age/height summary at cluster level and spc\_ah is the age/height summary at cluster and species level

### Author(s)

Yong Luo

siteToolsSpeciesConvertor

Convert VRI species code to site tools species code

### **Description**

This function converts BC VRI species code to site tools species code. The convertion is based on a hardcoded lookup table spv\_frd.

### Usage

```
siteToolsSpeciesConvertor(species)
## S4 method for signature 'character'
siteToolsSpeciesConvertor(species)
```

#### **Arguments**

species

character, Species code in VRI data sets.

#### Value

Converted species codes that can be recognized by site tools program. NA is the species that failed to be converted.

#### Author(s)

Yong Luo

SiteTools\_HTBoredAge2SI

Calculate site index using site tools

### **Description**

This function calculates site index based on bored age (boredAge), tree height (height), species (species) and region (ICRegion) using site tools program. This function is equivalent to sindex\_httoage.sas.

### Usage

```
SiteTools_HTBoredAge2SI(boredAge, height, species, ICRegion, ageType,
    estType)

## S4 method for signature
## 'numeric,numeric,character,character,numeric,numeric'
SiteTools_HTBoredAge2SI(boredAge,
    height, species, ICRegion, ageType, estType)
```

### **Arguments**

boredAge	numeric, Age at bored height.
height	numeric, Total tree height.
species	character, Species code, must be consistent with the species code in site tools, which can be converted from the original species code by using siteToolsSpeciesConvertor.
ICRegion	character, Must be either I (interior) and C (coastal). IC regions can be derived using BEC2IC.

numeric, Must be either 0 or 1. 0 stands for total age, for which site index is

calculated for 50 years of total tree age. While 1 stands for breast height age,

for which site index is calculated for 50 year old at breast height.

estType numeric, Defines how the site tools estimate site index. Valued as 0 and 1, 0 is

interative and while 1 is directive. Default is 1, which is directive.

#### Value

Site index

ageType

### Author(s)

30 smallTreeVolSmry

SiteTools_Y2BH	Derive years to breast height using site tools	
----------------	--	--

### **Description**

Derive years to breast height based on species (species), region (ICRegion) and site index (siteIndex) using site tools. This function is equivalent to sindex\_httoage.sas.

### Usage

```
SiteTools_Y2BH(species, ICRegion, siteIndex)
## S4 method for signature 'character,character,numeric'
SiteTools_Y2BH(species, ICRegion,
    siteIndex)
```

### **Arguments**

species character, Species code, must be consistent with the species code in site tools,

which can be converted from the original species code by using siteToolsSpeciesConvertor.

ICRegion character, Must be either I (interior) and C (coastal). IC regions can be derived

using BEC2IC function.

siteIndex numeric, Site index. Defined as tree height at 50 years old.

#### Value

Years to breast height

#### Author(s)

Yong Luo

smallTreeVolSmry	Summarizes the volume for small trees - VRI specific	
------------------	--	--

### **Description**

Calculates and summarizes volume of small trees at both cluster/species level and cluster. This function is equivalent to sml\_tree.sas in original compiler.

```
smallTreeVolSmry(smallTreeData, smallTreePlotHeader)
## S4 method for signature 'data.table,data.table'
smallTreeVolSmry(smallTreeData,
    smallTreePlotHeader)
```

speciesComp\_byC 31

### **Arguments**

```
smallTreeData data.table, Small tree data. This data is from card f, i.e., vi_f.

smallTreePlotHeader

data.table, Plot header data for stump and small tree data. The data is from card e, i.e., vi_e.
```

#### Value

Two tables: stmp\_c is summarized volume at cluster level; stmp\_cs is summarized volume at cluster/species level.

### Author(s)

Yong Luo

speciesComp\_byC

Calculates species composition based on cluster/species summary

### **Description**

Calculates species composition at cluster level based on cluster/species summary. The cluster/species-level summaries is an output of volSmry\_byCS function. This function is equivalent to sp\_comp. sas in original compiler.

#### Usage

```
speciesComp_byC(CSSmryTable, basedOn, speciesMaxNO, smallTreeCompile)

## S4 method for signature 'data.table,character,numeric,logical'
speciesComp_byC(CSSmryTable,
  basedOn, speciesMaxNO, smallTreeCompile)

## S4 method for signature 'data.table,character,numeric,missing'
speciesComp_byC(CSSmryTable,
  basedOn, speciesMaxNO)
```

### **Arguments**

CSSmryTable data.table, Summarized volume components for both measured and counted

trees at cluster and species level. See volSmry\_byCS for details.

based0n character, Specifies which component is used for species composition summary.

speciesMaxNO numeric, Maximum number of species entries to calculate.

smallTreeCompile

logical, Defines whether the function is used for calculate species composition

for small trees. If missing, FALSE is used.

#### Value

A data table that contains species composition at cluster level.

32 toWSVRatio

### Author(s)

Yong Luo

stumpVolSmry

Summarizes the volume for stumps - VRI specific

### Description

Calculates stump volume at cluster/species level and cluster. This function is equivalent to stmpvol.sas in original compiler.

### Usage

```
stumpVolSmry(stumpData, stumpPlotHeader)
## S4 method for signature 'data.table,data.table'
stumpVolSmry(stumpData, stumpPlotHeader)
```

### Arguments

```
stumpData data.table, Stump data. This data is from card g, i.e., vi_g.

stumpPlotHeader

data.table, Plot header data for stump and small tree data. The data is from card e, i.e., vi_e.
```

#### Value

Two tables: stmp\_c is summarized volume at cluster level; stmp\_cs is summarized volume at cluster/species level.

### Author(s)

Yong Luo

toWSVRatio

To toWSV ratio for each of strata

### Description

This function takes the selected data for derive ratio for each of strata by BEC+SP0+LV\_D

```
toWSVRatio(inputData, needCombs, minDBH = 10, minObs = 30)
```

toWSVRatio\_curve 33

#### **Arguments**

inputData data.table, The data for deriving ratios, that must contain full and enhanced trees. needCombs

data.table, The combinations of BEC+SP0+LV\_D are needed to derive coeffi-

minDBH numeric, The minimum DBH for selecting trees to derive ratios. If missing, 10

cm will be used.

minObs numeric, The minimum samples size for a stratum. If missing, 30 observations

will be used.

#### Value

ratio table

#### Author(s)

Yong Luo

toWSVRatio\_curve

To toWSV ratio for each of strata

### Description

This function takes the selected data for derive ratio for each of strata by BEC+SP0+LV\_D

### Usage

```
toWSVRatio_curve(inputData, needCombs, minDBH = 10, minObs = 30)
```

### Arguments

inputData data.table, The data for deriving ratios, that must contain full and enhanced trees.

needCombs data.table, The combinations of BEC+SP0+LV\_D are needed to derive coeffi-

cients.

minDBH numeric, The minimum DBH for selecting trees to derive ratios. If missing, 10

cm will be used.

minObs numeric, The minimum samples size for a stratum. If missing, 30 observations

will be used.

### Value

ratio table

#### Author(s)

34 valueCalculator

treeVolEst\_RegRatio

Estimate volume for H-enhanced and non-enhanced trees-VRI specific

### Description

This function estimates the volumes for JH-enhanced and non-enhanced trees using BA-WSV equation and toWSV ratio methods. For H-enhanced trees, the whole stem volume and gross merchantable volume are already calculated directly using taper equations; and rest of volume components will be calculated using ratio method in this function. For non-enhanced trees, the whole stem volume is derived using regression equation between basal area and whole stem volume and the rest of volume components will be computed using ratio method in this function.

#### Usage

```
treeVolEst_RegRatio(nonVolTrees, fixedCoeffTable, randomCoeffTable,
  ratioTable)
```

#### **Arguments**

nonVolTrees

data.table, H-enhanced trees and non-enhanced trees.

fixedCoeffTable

data.table, Specifies the WSV-BA equations by project group PRJ\_GRP, live and dead status LV\_D, stand and falling status SF\_COMPILE and species code SP0. The table can be generated using WSV\_BARegression.

randomCoeffTable

data.table, Specifies the WSV-BA equations by project group PRJ\_GRP, live and dead status LV\_D, stand and falling status SF\_COMPILE and species code SP0. The table can be generated using WSV\_BARegression.

ratioTable

data.table, Specifies toWSV ratio by project group PRJ\_GRP, live and dead status LV\_D, stand and falling status SF\_COMPILE and species code SP0. The table can be generated using toWSVRatio.

#### Value

A data table that has compiled non volume trees.

#### Author(s)

Yong Luo

valueCalculator

Calcualte tree value-VRI specific

### **Description**

This function calculates tree value for each tree based on ground called grade. From the second column to the last column, the grossVolMatrix table should have same dimensions (i.e., number of rows and columns) of callGradeMatrix and grossMerchVolMatrix if they are provided. Furthermore, be aware of the correspondingness among the matrix. In the function, two lookup table are hardcoded (i.e., spv\_spc and sp\_cost). This function is part of the log\_valu\_2017.sas.

volSmry\_byC 35

#### Usage

```
valueCalculator(species, grossVolMatrix, grossMerchVolMatrix,
   callGradeMatrix)

## S4 method for signature 'character,data.table,data.table,data.table'
valueCalculator(species,
   grossVolMatrix, grossMerchVolMatrix, callGradeMatrix)
```

### Arguments

species character, Species codes in BC inventory system.

grossVolMatrix data.table, Calculated gross volume for each log. The first column of this table

is the volume for the stump. If missing, the function calculates the total net

merchantable volume.

grossMerchVolMatrix

data.table, Calculated gross merchantable volume for each log. If missing, all

the merchantable volume is assigned as 0.

callGradeMatrix

data.table, Ground call grading table.

#### Value

Data table that contains net value (VAL\_NET) and net merchantable value (VAL\_MER).

#### Author(s)

Yong Luo

volSmry\_byC

Summarize volume components at cluster level-VRI specific

### **Description**

This function summarizes the cluster-level volume components using cluster/species-level summaries. The cluster/species-level summaries is an output of volSmry\_byCS function.

### Usage

```
volSmry_byC(volSmryByCS)
## S4 method for signature 'data.table'
volSmry_byC(volSmryByCS)
```

### **Arguments**

volSmryByCS data.table, Summarized volume components for both measured and counted

trees. See volSmry\_byCS for details.

#### Value

A data table

36 volSmry\_byCS

#### Author(s)

Yong Luo

volSmry\_byCS Summarize volume components per hectare by cluster and species-VRI specific

**Description** 

Summarizes volume components per hectare by cluster and species. The function is last part of vol\_ha\_2017.sas.

#### Usage

```
volSmry_byCS(treeMC, utilLevel, weirdUtil, equation)
## S4 method for signature 'data.table,numeric,character,character'
volSmry_byCS(treeMC,
  utilLevel, weirdUtil, equation)
## S4 method for signature 'data.table,missing,character,character'
volSmry_byCS(treeMC,
  weirdUtil, equation)
## S4 method for signature 'data.table,numeric,missing,character'
volSmry_byCS(treeMC,
  utilLevel, equation)
## S4 method for signature 'data.table,numeric,numeric,character'
volSmry_byCS(treeMC,
  utilLevel, weirdUtil, equation)
## S4 method for signature 'data.table,numeric,character,missing'
volSmry_byCS(treeMC,
  utilLevel, weirdUtil)
## S4 method for signature 'data.table, missing, missing, missing'
volSmry_byCS(treeMC)
```

#### **Arguments**

treeMC data.table, Tree-level compiled data for all volume trees.

utilLevel numeric, Utilization levels. Default is 4.

weirdUtil character, Weird util. Default is No. Otherwise need to be specified as a number. equation character, Specifies whether the compiler is based on KBEC or KFIZ. Default is

KBEC.

#### Value

A data table summarizes volume components by cluster and species. Equevalent to smy\_cs.

VRICompiler 37

#### Author(s)

Yong Luo

VRICompiler

VRI compiler - VRI specific

### Description

This function compiles VRI data by calling specific VRI functions. Unlike the original compiler (i.e., SAS compiler), the R version compiler hardcodes all the lookup tables in the compilation process. Please refer the descriptions for lookup table to see whether they are same as the original lookup table.

### Usage

```
VRICompiler(oracleUserName, oraclePassword,
  asciiTxtPath = "//albers/gis_tib/VRI/RDW/RDW_Data2/Work_Areas/VRI_ASCII_PROD/vri_raw",
  compilationPath = "//albers/gis_tib/VRI/RDW/RDW_Data2/Work_Areas/VRI_ASCII_PROD/RCompilation",
  fizmapPath = "//spatialfiles2.bcgov/work/for/vic/hts/dam/workarea/data/infrastructure",
  fizmapName = "FIZ_REG_COMPARTMENT", fizmapFormat = "gdb",
  equation = "KBEC", walkThru = TRUE, logMinLength = 0.1,
  stumpHeight = 0.3, breastHeight = 1.3, UTOPDIB = 10,
  utilLevel = 4, weirdUtil = "No")
```

### **Arguments**

oracleUserName character, User name to access to oracle database.

oraclePassword character, Password to access to oracle database.

asciiTxtPath character, Path to ascii txt files. By default, the arguement is specified to //albers/gis\_tib/VRI/RDV

However, user can modify.

compilationPath

character, Specifies the path that stores all the data/processes. By specifying this, four folders will be created to record all the data/processes. Specifically, raw\_from\_oracle stores the data just after oracle and ascii without editing; compilation\_sa stores key data (not all) that after editing and before volume and age compilation; compilation\_db stores compiled results for volume and age compilation at both tree level and cluater level; Archive\_YYYYMMDD achives all the data mentioned above for the future use or reference. By default, this path is set

as//albers/gis\_tib/VRI/RDW/RDW\_Data2/Work\_Areas/VRI\_ASCII\_PROD/RCompilation,

which is consistent with our rdw system.

fizmapPath character, Specifies the path to forest inventory zone map. By default, it is set to

//spatialfiles2.bcgov/work/for/vic/hts/dam/workarea/data/infrastructure,

which is maintained by FAIB employee.

fizmapName character, Specifies the name of forest inventory zone map. By default, it is set

to FIZ\_REG\_COMPARTMENT, which is maintained by FAIB employee.

be specified as gdb for geodatabase format and shp for shapefile format. By

fizmapFormat character, Specifies the format of forest inventory zone map. Currently, it can

default, it is set to gdb, which is maintained by FAIB employee.

38 VRICompiler

equation character, Specifies the taper equation that is used for compiler. Currently supports BEC-based (KBEC) and FIZ-based (KFIZ). walkThru logical, Speciefies whether the data had been collected using work through method. Default is TRUE, if it is not specified. numeric, Specifies minimum length of log when doing log length adjustment, logMinLength see logMatrixAdjustment for details. If missing 0.1 is used. stumpHeight numeric, Stump height. If missing 0.3 is used. breastHeight numeric, Breast height. If missing 1.3 is used. UTOPDIB numeric, Threshold inside-bark diameter for merchantable volume. If missing, UTOPDIB is 10. utilLevel numeric, Specifies utilization level in summrizing tree volumes at cluster and species level. Default is 4. weirdUtil character, Specifies weird utilization in summarizing tree volumes at cluster and species level. Default is no, if missing. Otherwise, a number should be provided.

#### Value

This function compiles data and save outputs in compilationPaths\$compilation\_db and no file is returned.

#### Note

Improvements include:

- 1. specifies trees in B plots as height enhanced trees
- 2. removes the sas-dependent sindex functions
- 3. introduce the SIndexR package

Currently, the compiler supports compilation for the below sample types:

- Q: Regular VRI sample with five point clusters design
- T: ??, sample protocol and sample design are same as Q samples
- B: ??, same plot layout as Q sample, with height is measured for all trees and no call grading information
- M: CMI sample, with all trees have call grading information in the field
- L: LiDAR project, same plot layout and same design but without call grading information
- Y: YSM plots, population between 15 and 50 years
- F: NFI plots, trees measured all DBH, height and call grading
- N: NVAF plots
- A: VRI audit plots

### Author(s)

Yong Luo

#### References

VRI compiler manual

VRIInit\_auxTree 39

VRIInit\_auxTree

Load and select auxiliary plot trees-VRI specific

#### **Description**

This function loads and selects auxiliary data (vi\_i, cardi) based on cluster/plot header.

#### Usage

```
VRIInit_auxTree(clusterplotHeader, dataSourcePath)
```

### **Arguments**

clusterplotHeader

data.table, Cluster and plot level attributes, an output from VRIInit\_clusterplot.

dataSourcePath character, Specifies the path that directs to the VRI original data soruce, i.e., //Mayhem/GIS\_TIB/RDW/RDW\_Data2/Work\_Areas/VRI\_ASCII\_PROD/vri\_sa.

#### Value

A data table that contains auxiliary plot tree data.

### Author(s)

Yong Luo

VRIInit\_clusterplot

Load and select cluster and plot level data- VRI specific

### **Description**

This function prepares the cluster/plot-level inputs for VRI compiler. Specifically, it standardizes names for the variables; reports and removes the duplicate observations at cluster, cluster/plot.

#### Usage

```
VRIInit_clusterplot(dataSourcePath)
```

### **Arguments**

dataSourcePath character, Specifies the path that directs to the VRI original data soruce, i.e., //Mayhem/GIS\_TIB/RDW/RDW\_Data2/Work\_Areas/VRI\_ASCII\_PROD/vri\_sa.

### Value

A data table that contains key information at cluster/plot level and compiler log file.

### Author(s)

40 VRIInit\_measuredTree

VRIInit\_lossFactor

Load and select trees that have loss factor information-VRI specific

#### **Description**

This function loads and selects trees that have loss factor information (vi\_d, cardd) based on selected trees from vi\_c.

### Usage

VRIInit\_lossFactor(fullMeasuredTrees, dataSourcePath)

#### **Arguments**

fullMeasuredTrees

data.table, Selected trees in vi\_c, which includes full, enhanced and H-enhanced trees. An output of VRIInit\_measuredTree.

dataSourcePath character, Specifies the path that directs to the VRI original data soruce, i.e., //Mayhem/GIS\_TIB/RDW/RDW\_Data2/Work\_Areas/VRI\_ASCII\_PROD/vri\_sa.

#### Value

A data table that contains loss factor data. A log file documents the detailed process

### Author(s)

Yong Luo

VRIInit\_measuredTree Load and select fully measured tree data-VRI specific

#### **Description**

This function selects the tree-level data from vi\_c (cardc) based on selected cluster/plot headers. Additionally, the function calculates basal area and tree per ha factor.

### Usage

VRIInit\_measuredTree(clusterplotHeader, dataSourcePath, walkThru = TRUE)

### Arguments

walkThru

clusterplotHeader

data.table, Cluster and plot-level attributes, an output from VRIInit\_clusterplot.

dataSourcePath character, Specifies the path that directs to the VRI original data soruce, i.e.,

 $// May hem/GIS\_TIB/RDW/RDW\_Data2/Work\_Areas/VRI\_ASCII\_PROD/vri\_sa.$ 

logical, Indicates whether walkthrough sampling protocal is used, Tree weight is determined by walkthrough method. In walkthrough method, a tree is identified as NA (no walkthrough applied), 0 for out tree (not counted), and W for double counted tree.

VRIInit\_siteTree 41

#### Value

A data table that contains tree-level information. A log file that describes the detailed process.

### Author(s)

Yong Luo

VRIInit\_siteTree

Load and select site trees-VRI specific

### **Description**

This function connects site tree data (vi\_h, cardh) to selected cluster/plot-level data. Site tree data is located in  $//Mayhem/GIS\_TIB/RDW/RDW\_Data2/Work\_Areas/VRI\_ASCII\_PROD/vri\_sa$ 

### Usage

VRIInit\_siteTree(clusterplotHeader, dataSourcePath)

### **Arguments**

clusterplotHeader

data.table, contains cluster/plot-level attributes, an output from VRIInit\_clusterplot.

dataSourcePath character, Specifies the path that directs to the VRI original data soruce, i.e., //Mayhem/GIS\_TIB/RDW/RDW\_Data2/Work\_Areas/VRI\_ASCII\_PROD/vri\_sa.

### Value

A data table that contains site tree data information. A log file documents the detailed process

#### Note

VRI specific

#### Author(s)

42 VRISummaries

VRISummaries	Summarize the tree-level data at cluster or cluster/species level-VRI specific

### **Description**

Summarizes the compiled tree data (including both enhanced tree data and non-enhanced tree data) at cluster level. This function is equevalent to the summary part in sas compiler in cp\_vegi\_2017.sas. Different from the original compiler, this function outputs the summaries by summarized components, rather than putting all together.

### Usage

### Arguments

allVolumeTrees data.table, All tree data from vi\_c and vi\_i that have been compiled with tree volume.

clusterPlotHeader

data.table, Cluster and plot-level information. An output of VRIInit\_clusterplot.

utilLevel numeric, Utilization levels.

weirdUtil character, Weird util. Default is No. Otherwise need to be specified as a number.

equation character, Specifies whether the compiler is based on KBEC or KFIZ.

### Value

Cluster and species-level volume summaries; cluster-level volume summaries; cluster-level height summaries; cluster-level species composition summaries and log file.

#### Author(s)

VRIVolTree 43

VRIVolTree	Calcualte tree volume-VRI specific	

### **Description**

This function use BEC(or FIZ) and species-specific taper equation to calculate tree volume. Before calculation, the function adjusts height for broken top trees: scenario 1 (D scenario): availability of DBH, DIB at broken height; scenario 2 (H scenario): availability of projected tree height in the field. This functions also assigns the volume multiplier adjustment. The function is equivalent to vir\_vol\_tree\_2011 macro in orignal SAS compiler.

### Usage

### **Arguments**

_	
treeData	data.table, An output from VRIInit_measuredTree function, i.e., vi_c data.
equation	character, Specifies which taper equation form will be used to calculate diameter inside bark for a given height. Must be either KBEC or KFIZ3. If missing, default is KBEC
logMinLength	numeric, Specifies a minimum length for a log.
stumpHeight	numeric, Specifies stump height. If missing, 0.3 m will be used.
breastHeight	numeric, Specifies breast height. 1.3 m will be used when this arguement is missing.
UTOPDIB	numeric, Specifies minimum merchantable inside bark diameter. 10 cm is used as a default.

### Value

A data table

### Author(s)

## **Index**

```
ageByForester, 3
                                                                                                                          getDWBSeries, 13, 27
ageRangeClassifier, 3, 13
                                                                                                                          getDWBSeries,character,character,character,character,character,character
applyDWB, 4
                                                                                                                                                (getDWBSeries), 13
                                                                                                                          getDWBSeries, character, character, character, missing, char
auxiTreeCompiler, 4
                                                                                                                                                (getDWBSeries), 13
BEC2IC, 29, 30
                                                                                                                          getDWBSeries, character, character, missing, character, char
boredAgeCalculator_Bore, 6, 7-9
                                                                                                                                                (getDWBSeries), 13
boredAgeCalculator_Bore, missing, numeric-method
                                                                                                                          heightSmry_byC, 14
                     (boredAgeCalculator_Bore), 6
bored Age Calculator\_Bore, numeric, missing-metho \textbf{\textit{bl}} eight Smry\_by C, data.table-method
                     (boredAgeCalculator_Bore), 6
                                                                                                                                                (heightSmry_byC), 14
boredAgeCalculator_Bore, numeric, numeric-method
                                                                                                                          loadASCII, 14, 21
                     (boredAgeCalculator_Bore), 6
                                                                                                                          loadVGIS, 21
boredAgeCalculator_Crted, 7
boredAgeCalculator_Crted, numeric, numeric, numeric, numeret, etharacter-method
                                                                                                                          logAdjustment,data.table,missing-method
                     (boredAgeCalculator_Crted), 7
                                                                                                                                                (logAdjustment), 15
boredAgeCalculator_Phys, 6, 7, 8, 9
                                                                                                                          logAdjustment,data.table,numeric-method
bored Age Calculator\_Phys, numeric-method
                                                                                                                                                (logAdjustment), 15
                     (boredAgeCalculator_Phys), 7
                                                                                                                          logAttributesLongForm, 16
boredAgeCalculator_Prorated, 6-8, 8, 9
boredAgeCalculator_Prorated, numeric, n
                                                                                                                                                (logAttributesLongForm), 16
                     (boredAgeCalculator_Prorated),
                                                                                                                          logAttributesLongForm, data.table, numeric-method
boredAgeCalculator_Prorated, numeric, n
                                                                                                                          logFileProducer, 17
                     (boredAgeCalculator_Prorated),
                                                                                                                          logFileProducer, character, character, data.table, character
                                                                                                                                                (logFileProducer), 17
boredAgeCalculator_Total, 6-9, 9
                                                                                                                          logFileProducer, character, character, data.table, character
boredAgeCalculator_Total, numeric-method
                                                                                                                                                (logFileProducer), 17
                     (boredAgeCalculator_Total), 9
                                                                                                                          logFileProducer, character, character, data.table, missing
                                                                                                                                                (logFileProducer), 17
compilerPathSetup, 10
                                                                                                                          logFileProducer, character, character, data.table, missing
DBHClassifier, 12
                                                                                                                                                (logFileProducer), 17
DWBCompiler, 5, 10, 20
                                                                                                                          logMatrixAdjustment, 18, 38
DWBCompiler, data.table, data.table, data.table, bbgMathtexAddent, data.table, numeric, missing, missing.
                     (DWBCompiler), 10
                                                                                                                                                (logMatrixAdjustment), 18
DWBCompiler, data.table, data.table, data.table, linightaing invedthost ment, data.table, numeric, missing, missing
                     (DWBCompiler), 10
                                                                                                                                                (logMatrixAdjustment), 18
DWBGenerator_BEC, 11, 12
                                                                                                                          logMatrixAdjustment,data.table,numeric,missing,numeric
DWBGenerator_BEC, numeric, numeric, character, numeric, challogyMaetr, iokAdrjaustæme, roth)a it &cter-method
                     (DWBGenerator_BEC), 11
                                                                                                                          logMatrixAdjustment, data.table, numeric, missing, numeric
DWBGenerator_FIZ, 11, 12
                                                                                                                                                (logMatrixAdjustment), 18
```

(DWBGenerator\_FIZ), 12

DWBGenerator\_FIZ,numeric,character,character-inegMadrixAdjustment,data.table,numeric,numeric,missing

(logMatrixAdjustment), 18

INDEX 45

```
logMatrixAdjustment,data.table,numeric,numerisipemmeolsSpmessessess@omeethodr,7,28,29,30
                          (logMatrixAdjustment), 18
                                                                                                                                                  siteToolsSpeciesConvertor,character-method
logMatrixAdjustment,data.table,numeric,numeric,numeri(s,intuenTeoroilcs-SqueetdriosetSconvertor), 28
                         (logMatrixAdjustment), 18
                                                                                                                                                  smallTreeVolSmry, 30
lookupCheck, 19
                                                                                                                                                  smallTreeVolSmry,data.table,data.table-method
lookupCheck, character, character-method
                                                                                                                                                                            (smallTreeVolSmry), 30
                         (lookupCheck), 19
                                                                                                                                                  speciesComp_byC, 31
lookupCheck,character,missing-method
                                                                                                                                                  speciesComp_byC,data.table,character,numeric,logical-me
                         (lookupCheck), 19
                                                                                                                                                                            (speciesComp_byC), 31
                                                                                                                                                  speciesComp_byC,data.table,character,numeric,missing-me
mergeAllVolTrees, 20
                                                                                                                                                                            (speciesComp_byC), 31
mergeAllVolTrees,data.table,data.table-method<sub>stumpVolSmry</sub>,32
                          (mergeAllVolTrees), 20
                                                                                                                                                  stumpVolSmry,data.table,data.table-method
mergeOAData, 20
                                                                                                                                                                            (stumpVolSmry), 32
netVolumeCalculator, 21
                                                                                                                                                  toWSVRatio, 5, 32, 34
netVolumeCalculator,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,data.table,da
                         (netVolumeCalculator), 21
(netVolumeCalculator), 21
                                                                                                                                                  valueCalculator, 34
net Volume Calculator, data. \ table, missing, data. \ table \ or, character, data. \ table, d
                          (netVolumeCalculator), 21
                                                                                                                                                                            (valueCalculator), 34
netVolumeCalculator, missing, data.table, data.table, data.table, data.table
                         (netVolumeCalculator), 21
                                                                                                                                                  volSmry_byC,data.table-method
                                                                                                                                                                            (volSmry_byC), 35
prj_ID2BEC, 22
                                                                                                                                                  volSmry_byCS, 31, 35, 36
prj_ID2BEC,character-method
                                                                                                                                                  volSmry_byCS,data.table,missing,character,character-me
                         (prj_ID2BEC), 22
                                                                                                                                                                            (volSmry_byCS), 36
prj_ID2Grp, 23
                                                                                                                                                  volSmry_byCS, data.table, missing, missing, missing-method
prj_ID2Grp,character-method
                                                                                                                                                                            (volSmry_byCS), 36
                         (prj_ID2Grp), 23
                                                                                                                                                  volSmry_byCS,data.table,numeric,character,character-me
                                                                                                                                                                            (volSmry_byCS), 36
readHandHeld, 23
                                                                                                                                                  volSmry_byCS,data.table,numeric,character,missing-metho
readHandHeld_mod, 24
                                                                                                                                                                            (volSmry_byCS), 36
regBA_WSV, 25
                                                                                                                                                  volSmry_byCS, data.table, numeric, missing, character-method
regRatioDataSelect, 26
                                                                                                                                                                            (volSmry_byCS), 36
riskGroupDeriver, 12, 26
risk Group Deriver, character, character, character, numeric, numeri
                                                                                                                                                                            (volSmry_byCS), 36
                          (riskGroupDeriver), 26
riskGroupDeriver, character, character, missing, missing, character-method VRIInit_auxTree, 5, 20, 39
                         (riskGroupDeriver), 26
                                                                                                                                                  VRIInit_clusterplot, 5, 39, 39, 40–42
                                                                                                                                                  VRIInit_lossFactor, 11, 40
siteAgeCompiler, 27, 28
                                                                                                                                                  VRIInit_measuredTree, 15, 40, 40, 43
siteAgeCompiler,data.table-method
                                                                                                                                                  VRIInit_siteTree, 27, 41
                         (siteAgeCompiler), 27
                                                                                                                                                  VRISummaries, 42
siteAgeSummary, 11, 28
                                                                                                                                                  VRISummaries, data.table, data.table, numeric, character, ch
siteAgeSummary,data.table-method
                                                                                                                                                                            (VRISummaries), 42
                          (siteAgeSummary), 28
                                                                                                                                                  VRIVolTree, 43
SiteTools_HTBoredAge2SI, 29
SiteTools_HTBoredAge2SI,numeric,numeric,character,character,numeric,numeric-method (SiteTools_HTBoredAge2SI) 29 WSV_BARegression, 5, 34
                          (SiteTools_HTBoredAge2SI), 29
SiteTools_Y2BH, 30
SiteTools_Y2BH, character, character, numeric-method
                         (SiteTools_Y2BH), 30
```