Modeling and Verification with SPIN

Wishnu Prasetya

wishnu@cs.uu.nl

www.cs.uu.nl/docs/vakken/pv

Overview

- Architecture & a bit more about SPIN
- SPIN's modeling language
- Examples of models in SPIN

 Acknowledgement: some slides are taken and adapted from Theo Ruys's SPIN Tutorials.

Spin and Promela

- SPIN = Simple Promela Interpreter
- Promela = Process Meta Language
 - Is a modelling language! (not a language to build an application)


- Strong features :
 - Powerful constructs to synchronize concurrent processes
 - Cutting edge model checking technology
 - Simulation to support analysis (of the models)

SPIN


 Concurrency is a hot area again, now that we all use multi-core CPUs.

Other applications:

- AnWeb: a system for automatic support to web application verification, Di Sciascio et al, in 14th conf. on Soft. Eng. and knowledge eng., 2002.
- Privacy and Contextual Integrity: Framework and Applications, Barth et al, in IEEE Symposium on Security and Privacy, 2006.



(X)SPIN Architecture



System, process, and action.

- A <u>system</u> in SPIN consists of a set of interacting and concurrent processes.
- Each process is sequential, but possibly nondeterministic.
- Each process is built from <u>atomic actions</u> (transition).
- Concurrent execution is modeled by interleaving.
- Fairness can be impossed.

Example

```
byte x = 1;
active proctype P1() { x++; assert (x==2) ; }
active proctype P2() { (x==1); x--; }
```

(using a global variable to synchronize)

Data types

• Bit 0,1

Bool true, false

• Byte 0..255

• Short -2¹⁵ .. 2¹⁵-1

• Int -2³¹ .. 2³¹-1

• Pid 0..255

Mtype 0..255 // user-def. enumeration

• Chan 0..255

- One dimensional array
- Record

What you don't have...

- No sophisticated data types
- No methods; you have macro
- There are only 2 levels of scope:
 - global var (visible in the entire sys)
 - <u>local</u> var (visible only to the process that contains the declaration)
 - there is no inner blocks

(Enabledness) Expression

- This process has 3 atomic actions.
- The action "y==0"
 - only enabled in a state where the expression is true
 - it can only be executed when it is enabled; the effect is skip.
 - so, as long as it is disabled, the process will <u>block</u>
 - if it is not enabled in the current state, a transition in another process may make it enabled in the next state.
 - even if it is enabled in the current state, there is no guarantee the action will be selected for execution; but there is a way in SPIN to impose fairness.

Example

Use it to <u>synchronize</u> between processes :

```
byte x=0 , y=0

active proctype P { x++ ; (y>0) ; x-- }

active proctype Q { (x>0) ; y++ ; (x==0) ; y-- }
```

• // both will terminate, but forcing Q to finish last

Multiprogramming is tricky....

 E.g. one or more processes can become stuck (deadlocked):

```
byte x=0 , y=0

active proctype P { x++ ; (y>0) ; x-- ; (y==0) }

active proctype Q { y++ ; (x>0) ; (x==0) ; y-- }
```

(6 potential executions...)

Processes can also synchronize with channels

```
chan c = [3] of \{byte\};
active proctype producer() {
 do
  :: c!0
  od
active proctype consumer() {
 do
 :: c?x
 od
```

Channels

```
mtype = { DATA, ack }
```

```
chan c = [0] of {bit};

chan d = [2] of {mtype, bit, byte};

chan e[2] = [1] of {bit};
```

- for exchanging messages between processes
- finite sized and <u>asynchronously</u>, unless you set it to size 0 → <u>synchronous</u> channel
- Syntax :

```
c! 0 sending over channel c; blocking if c is full
c? x receives from c, transfer it to x; blocking if c is empty
d? DATA, b, y match and receives
```

There are some <u>more</u> exotic channel operations: checking empty/full, testing head-value, copying instead of receiving, sorted send, random receive ... → check out the Manual

Conditional

```
<u>if</u>
:: stmt₁
:: ...
:: stmt<sub>n</sub>
<u>fi</u>
```

```
<u>if</u>
:: stmt<sub>1</sub>
:: ...
:: else -> ...
<u>fi</u>
```

- The alternatives do not have to be atomic!
- The first action in an alternative acts as its "guard", which determines
 if the alternative is enabled on a given state.
- Non-deterministically choose one enabled alternatives.
- If there is none, the entire IF blocks.
- "else" is a special expression that is enabled if all other alternatives block.

loop: do-statement

```
<u>do</u>
∷ stmt₁
∷ ...
∷ stmt<sub>n</sub>
<u>od</u>
```

- Non-deterministic, as in IF
- If no alternative is enabled, the entire loop blocks.
- Loop on forever, as long as there are enabled alternatives when the block cycle back.
- To exit you have explicitly do a <u>break.</u>

Break, syntax, etc

```
<u>do</u>
:: { (i>0) ; i-- }
:: { (i==0) ; break }
<u>do</u>
```

```
do

:: (i>0) \rightarrow i--

:: (i==0) \rightarrow break

do
```

```
do
:: { i-- ; (i>0) }
:: break
do
```

A process is allowed to be non-deterministic; can be handy for modeling.

```
active proctype consumer() {
    do
    :: c ? x;
    :: c ? x; x= corrupted; // to model occasional corrupted data
    od
}
```

Label and jump

```
LO: (x==0);
if
:: ... goto LO;
:: ...
fi
```

Labels can also be useful in specification, e.g.

 Referring to labels as above goes actually via a mechanism called "remote reference", which can also be used to inspect the value of local variables for the purpose of specification.

Exception/Escape

- S unless E
- Statement! Not to be confused with LTL "unless".

 If E ever becomes enabled during the execution of S, then S is aborted and the execution continues with E.

More precisely... check manual.

Predefined variables in Promela

- _pid
- _nr_pr
- np_
- _last
- else

timeout

- (local var) current process' instantiation number the number of active processes
- true when the model is not in a "progress state"

the pid of process that executed last

true if no statement in the <u>current process</u> is executable

true if no statement in the system is executable

. . .

Timeout

```
<u>do</u>
:: c?x → ...
:: timeout → break
<u>od</u>
```

- <u>timeout</u> becomes executable if there is no other process the system is executable/enabled
 - so, it models a global timeout
 - useful as a mechanism to avoid deadlock
 - beware of statements that are always executable.

Expressing local correctness with assertions

```
active proctype P ...
active proctype Q { ...; assert (x==0 && y==0) }
```

(here it implies that when Q terminates, x and y should be 0)

But we can also express global invariant!

 Thanks to built-in non-determinism in the interleaving semantics, we can also use assertion to specify a global invariant!

```
byte x=0 , y=0

active proctype P { x++ ; (y>0) ; x-- }

active proctype Q { (x>0) ; y++ ; (x==0) ; y--}

active proctype Monitor { assert ((x==0 || x==1)) }
```

// implying that at any time during the run x is either 0 or 1


Deadlock checking, free.

- When a system comes to a state where it has no enabled transition, but one of its processes is not in its terminal (end) state:
 - Deadlocked, will be reported by SPIN
 - But sometimes you want to model that this is ok → suppress it via the invalid-endstate option.
- The terminal state of a process P is by default just P's textual end of code.
- You can specify additional terminal states by using end-label:
 - Of the form "end_1", "end_blabla" etc

Expressing progress requirement

- We can mark some states as progress states
 - Using "progress*" labels
- Any infinite execution must pass through each progress state infinitely many often by any infinite execution; else violation.
- We can ask SPIN (with an option) to verify no such violation exists (non-progress cycles option).

Example



Self-stabilizing leader election in a ring.

Problem-1: Leader Election (LE).

for time to time a ring of processes need to appoint a 'leader'. A centralized decision is undesired.

Problem-2: Self-Stabilizing (SS).

It can start from any state.

A solution: (see left) → relies on the nondeterminism of concurrency.

The processes in Promela

```
#define N 4
byte x[N];
active proctype P0 ( ) {
  do
  :: x[N-1] < x[0] -> x[0] = x[N-1];
  od
proctype P(byte i) {
  do
  :: x[i-1] != x[i] -> x[i] = x[i-1] ;
  od
```

- Why use bytes?
- Should we enable the default end-state checking?
- How to instantiate the P(i)'s ?

Creating processes and init { ... }

```
init {
   byte i = 1 ;
   do
   :: i<N -> { run P(i) ; i++ ; }
   :: i>=N -> break ;
   od
}
```

Put this in atomic { ... }; Be aware of what it means!

Unfortunately, this is not quite right yet. The array x is by default initialized to 0. How can we quantify over 'all' possible values of its elements?

Using non-determinism to quantify over your data

```
init {
  // initializing the array x
  byte i = 0; byte v;
  do
  :: i>=N -> break ;
  :: i<N ->
       v = 0;
       do
       :: V<N -> V++ ;
       :: break
       od ;
       x[i] = v ;
       i++ ;
  od ;
   .... // now create the processes as in the
previous slide
```

How to express the specification?

```
assert (x[i] == x[0])
```


(not really capturing what you mean...)

Using timeout to specify end-state

```
active proctype monitor() {
   byte i ;
   timeout ->
   i = 0 ;
   do
   :: i>=N -> break ;
   :: i<N -> assert(x[i]==x[0]) ; i++ ;
   od
}
```

- Does express: if the system 'stabilizes', all values in x are the same.
- But we still can't express that it *will* stabilize. How can we do it? \rightarrow later.

Example: Alternating bit protocol



- imperfect "connections", but corrupted data can be detected (e.g. with checksum etc).
- Possible solution: send data, wait for a positive acknowledgement before sending the next one.
 - Just 1 bit is needed for the ack, hence the "bit" in the name.


You can think of several ways to work it out...

- A note on reliable full-duplex transmission over half-duplex links, K. A. Bartlett, R. A. Scantlebury, P. T. Wilkinson, Communications of the ACM, Vol 12, 1969.
 - NPL Protocol
 - M<2 Protocol (we'll discuss this one)
- For more, check out:

http://spinroot.com/spin/Man/Exercises.html


e.g. Go-Back-N Sliding Window Protocol

M<2 Protocol, Sender part




State 1 is the **starting state**, and its **accepting state** in the sense when the sender is in this state, it assumes the last data package it sent has been successfully received by the receiver, and so it fetches a new data package to send.

M<2 Protocol, Receiver part



Scenario: 1x error, corrected



Though each automaton is simple, the combined (and concrete) behavior is quite complex; ≈ 100 states in my (abstract) SPIN model (there are more explicit states, if we take the "data" into count).

Modeling in Promela

```
chan S2R = [BufSize] of { bit, byte } ;
chan R2S = [BufSize] of { bit } ;
proctype Sender (chan in, chan out) { ... }
proctype Receiver(chan in, chan out) { ... }
init {
       run Sender(R2S, S2R);
       run Receiver(S2R, R2S)
```

Modelling in SPIN

```
proctype Receiver(chan in, out) {
   show byte rd ; /* received data */
   show bit cbit ; /* control bit */
   <u>do</u>
   :: in ? cbit, rd ;
      <u>if</u>
      :: (cbit == 1) -> out!1
       :: (cbit == 0) -> out!1
       :: printf("MSC: ERROR1\n"); out!0
      fi
                     od
                           customer 1:1
                                customer 2:2
                          1!REQ1 11
```

So, how big the channels should be? Is 0 good enough?

A different style, with "goto"

```
proctype Sender(chan in, out) {
   show byte data ; /* message data */
   show bit cbit ; /* received control bit */
   S1: data = (data+1) % MAX; out!1,data; goto S2;
   S2: in ? cbit ;
       <u>if</u>
       :: (cbit == 1) -> goto S1
       :: (cbit == 0) -> goto S3
       :: printf("MSC: AERROR1\n") -> goto S4
       fi;
   S3: out!1,data ; goto S2 ;
   S4: out!0,data ; goto S2 ;
```

Specification, with assertions?

Each data package, if accepted by the receiver, is accepted exactly once!

- This time, not possible with assertions (at least not without the help of 'something else').
- In LTL (to be discussed later), we can try something along this line:
 - $\square(Receiver@S3 \rightarrow (Receiver@rd == Sender@data))$
- But this still does not quite express the above.

Specification, using shadow variables

Each data package, if accepted by the receiver, is accepted exactly once!


- Extend the model with 'shadow variables'
 - Are used purely for expressing specifications
 - Must <u>not</u> influence the original behavior
- In our case:
 - exploit that sender generates new data by data+1
 - introduce a shadow variable "last" → previously accepted data
 - Impose this <u>assertion</u> on the acceptance state (of Receiver):

current data to be accepted = last + 1

Extending the model

```
proctype Receiver(chan in, out) {
   show byte rd ; /* received data
   show bit cbit; /* contro show byte last
   do
                                  assert (rd == (last+1) % MAX);
   :: in?cbit,rd;
      progress:
                                  last = rd;
      :: (cbit == 1), -> out!1
      :: (cbit == 0) -> out!1
      :: printf("MSC: ERROR1\n") ; out!0
      fi
   od
```

2x successive errors



Ok... but suppose we still want to verify these:

But, if error does not occur twice successively then: every pck sent, if accepted, is accepted exactly once.

If no error occur, every data sent will eventually be accepted.

The first can be expressed simply by constraining the model, namely how it simulates error.

The 2nd one can't be expressed with just assertions and shadow variables.

Alternative: LTL.