# Information in EventMetaData and 'Error event'

- 1, Storing data in EventMetaData object by online DAQ
- 2, Definition of 'Error event' and how to avoid the event
- 2-1, Pocket DAQ case

S. Yamada (KEK)

## 1, Storing data in EventMetaData object by online DAQ


#### Member variables of EventMetaData

```
Rev. 28703 (framework/dataobjects/include/EventMetaData.h)

private:
unsigned int m_event; /**< Event number ('normal' data has values > 0). */
int m_run; /**< Run number (usually > 0, run-independent MC has run == 0). */
int m_subrun; /**< Sub-run number, increases indicate recovery from DAQ-internal trouble without change to detector constants.

Not supposed to be used by offline analysis. */
int m_experiment; /**< Experiment number. (valid values: [0, 1023], run-independent MC has exp == 0) */
int m_production; /**< Unique identifier of the production of the event. */
unsigned long long int m_time; /**< Time in ns since epoch (1970-01-01). */
std::string m_parentLfn; /**< LFN of the parent file */
double m_generatedWeight; /**< Generated weight. */
unsigned int m_errorFlag; /**< Indicator of error conditions during data taking, ORed combination of EventErrorFlag values. */
```

Red variables are supposed to be stored in EventMetadata by Raw2DsModule.cc of online DAQ program at an HLT input server. Currently m time and m production are not filled yet.



### What daq/rfarm/event/modules/src/Raw2DsModule.cc is doing:

#### Fill values in each variable as follows:

```
evtmetadata->setExperiment(sndhdr.GetExpNum()); // -> Added at rev. 8338
evtmetadata->setRun(sndhdr.GetRunNum()); // -> Added at rev. 8701
evtmetadata->setSubrun(sndhdr.GetSubRunNum()); // -> Added at rev. 28343
evtmetadata->setEvent(sndhdr.GetEventNumber()); // -> Added at rev. 8338
if (error_flag) evtmetadata->addErrorFlag(EventMetaData::c_B2LinkCRCError); // Added at rev. 18569
```

### Pocket DAQ case:

- ➤ There is no HLT input server and filling EventMetaData is done by DeSerializerPC.cc not Raw2DsModule.cc.
- > EventMetaData->getErrorFlag() can work if you use the DAQ program for data-taking after rev. 29676.

## 2, Definition of 'Error event' and how to avoid the event

### Type of errors

'Error event' in this slides means that its EventMetaData.m\_errorFlag is nonzero.


In EventMetaData.h,

```
/** bit-flag format of m_error_flag */
enum EventErrorFlag {
    c_B2LinkCRCError = 0x1, /**< Belle2link CRC error is detected in the event */
    c_HLTError = 0x2 /**< Error is returned from HLT modules. */
};</pre>
```

As of Jun. 2016, only c\_B2LinkCRCError is implemented if using rev. 18569 or later.

### What is 'm errorFlag = c B2LinkCRCError = 0x1'

- Data-corruption during B2link data transfer is detected by CRC check.
- -> m\_errorFlag = 1
- Data-corruption during B2link data transfer is not detected by CRC check.
- -> m\_errorFlag = 0



### How to avoid CRC 'error events':

call getErrorFlag() of EventMetaData:

```
event(){
...

if( EventMetaData->getErrorFlag() == 0 ){
    // No CRC error
}else{
    // CRC error event }
... }
```

If the ver. of your DAQ program is old: (PocketDAQ before 29676, Belle2DAQ before rev. 18569)

You need to check every Raw\*\*\* objects except for RawPXD.

```
For data taken with older DAQ program, you need to check each
Raw*** object like the following; (*** is
COPPER/SVD/CDC/TOP/ARICH/KLM )

StoreArray<Raw***> raw_ ***array;
for (int i = 0; i < raw_ *** array.getEntries(); i++) {
  for (int k = 0; k < raw_ *** array[i]->GetNumEntries(); j++) {
    if (raw_***array[i]->GetEventCRCError(k)!=0){
        // CRC Error event!!
    }
}
```

## Test program to check error flag in EventMetaData in .(s)root files

```
$ cd ${BELLE2_LOCAL_DIR}/daq/rawdata/examples $ basf2 CheckErrorEvent.py —i <.sroot file>
```

```
[INFO] CheckErrorEvent: initialize() started.
[INFO] CheckErrorEvent: initialize() done.
[INFO] SeqRootInput: beginRun called.
[INFO] Begin of new run
[INFO] Processed: 1 runs, 1 events
[INFO] Processed: 1 runs, 2 events
...
[INFO] Processed: 1 runs, 7000 events
[INFO] Seq File 1 closed
[INFO] SeqRootInput: 7984 events read with total bytes of 113506 kB
[INFO] SeqRootInput: event rate = 10.2758 (KHz)
[INFO] SeqRootInput: flow rate = 146.088 (MB/s)
[INFO] SeqRootInput: event size = 14.2167 +- 1.26828 (kB)
[INFO] SeqRootInput: endRun done.
```

**Event CRC error 0 CPRs 0 Events** 

[INFO] Reading StreamerInfo [INFO] SeqRootInput: initialized.

-> In this case, No CRC 'error events' stored in EventMetaData are detected.

end