
CS162 Operating Systems and Systems Programming Lecture 14

Memory 2: Virtual Memory (Con't), Caching and TLBs


March 9th, 2021
Profs. Natacha Crooks and Anthony D. Joseph http://cs162.eecs.Berkeley.edu

Recall: General Address translation




- Consequently, two views of memory:
 - View from the CPU (what program sees, virtual memory)
 - View from memory (physical memory)
 - Translation box (Memory Management Unit or MMU) converts between the two views
- Translation ⇒ much easier to implement protection!
 - If task A cannot even gain access to task B's data, no way for A to adversely affect B
 - Extra benefit: every program can be linked/loaded into same region of user address space

Recall: How to Implement Simple Paging?




- Page Table (One per process)
 - Resides in physical memory
 - Contains physical page and permission for each virtual page (e.g., Valid bits, Read, Write, etc)
- Virtual address mapping
 - Offset from Virtual address copied to Physical Address
 - » Example: 10 bit offset \Rightarrow 1024-byte pages
 - Virtual page # is all remaining bits
 - » Example for 32-bits: 32-10 = 22 bits, i.e., 4 million entries
 - » Physical page # copied from table into physical address
 - Check Page Table bounds and permissions

Recall: Simple Page Table Example




Recall: What about Sharing?




Recall: Where is page sharing used?

- The "kernel region" of every process has the same page table entries
 - The process cannot access it at user level
 - But on U->K switch, kernel code can access it AS WELL AS the region for THIS user
 What does the kernel need to do to access other user processes?
- Different processes running same binary!
 - Execute-only, but do not need to duplicate code segments
- User-level system libraries (execute only)
- Shared-memory segments between different processes
 - Can actually share objects directly between processes
 - » Must map page into same place in address space!
 - This is a limited form of the sharing that threads have within a single process


Summary: Paging



Summary: Paging



Summary: Paging



Recall: How big do things get?

- 32-bit address space => 2³² bytes (4 GB)
 - Note: "b" = bit, and "B" = byte
 - And for memory:

```
» "K"(kilo) = 2^{10} = 1024 ≈ 10³ (But not quite!): Sometimes called "Ki" (Kibi) 
» "M"(mega) = 2^{20} = (1024)² = 1,048,576 ≈ 10⁶ (But not quite!): Sometimes called "Mi" (Mibi) 
» "G"(giga) = 2^{30} = (1024)³ = 1,073,741,824 ≈ 10⁶ (But not quite!): Sometimes called "Gi" (Gibi)
```

- Typical page size: 4 KB
 - how many bits of the address is that? (remember $2^{10} = 1024$)
 - Ans 4KB = $4 \times 2^{10} = 2^{12} \Rightarrow 12$ bits of the address
- So how big is the simple page table for each process?
 - $-2^{32}/2^{12} = 2^{20}$ (that's about a million entries) x 4 bytes each => 4 MB
 - When 32-bit machines got started (vax 11/780, intel 80386), 16 MB was a LOT of memory
- How big is a simple page table on a 64-bit processor (x86_64)?
 - $-2^{64}/2^{12} = 2^{52}$ (that's 4.5×10^{15} or 4.5 exa-entries)×8 bytes each = 36×10^{15} bytes or 36 exa-bytes!!!! This is a ridiculous amount of memory!
 - This is really a lot of space for only the page table!!!
- The address space is sparse, i.e. has holes that are not mapped to physical memory
 - So, most of this space is taken up by page tables mapped to nothing


Lec 13.12

Recall: Page Table Discussion

- What needs to be switched on a context switch?
 - Page table pointer and limit
- What provides protection here?
 - Translation (per process) and dual-mode!
 - Can't let process alter its own page table!
- Analysis
 - Pros
 - » Simple memory allocation
 - » Easy to share
 - Con: What if address space is sparse?
 - » E.g., on UNIX, code starts at 0, stack starts at $(2^{31}-1)$
 - » With IK pages, need 2 million page table entries!
 - Con: What if table is really big?
 - » Not all pages used all the time ⇒ would be nice to have working set of page table in memory
- Simple Page table is way too big!
 - Does it all need to be in memory?
 - How about multi-level paging?
 - or combining paging and segmentation


How to Structure a Page Table

Page Table is a map (function) from VPN to PPN



- Simple page table corresponds to a very large lookup table
 - VPN is index into table, each entry contains PPN
- What other map structures can you think of?
 - Trees?
 - Hash Tables?

Fix for sparse address space: The two-level page table



Example: x86 classic 32-bit address translation




Figure 4-2. Linear-Address Translation to a 4-KByte Page using 32-Bit Paging

- Intel terminology: Top-level page-table called a "Page Directory"
 - With 'Page Directory Entries'
- CR3 provides physical address of the page directory
 - This is what we have called the "PageTablePtr" in previous slides
 - Change in CR3 changes the whole translation table!




Administrivia

- Midterm 2: Coming up on Thursday 3/18 5-6:30PM (two weeks from today)
 - Topics: up and including Lecture 16: Scheduling, Deadlock, Address Translation, Virtual Memory, Caching, TLBs, Demand Paging
 - Lecture 16 will be released early
 - Will REQUIRE you to have your zoom proctoring setup working again
 - » You must have screen sharing (entire desktop not just the browser), audio unmuted, and your camera working
 - » Make sure to get your setup debugged and ready!
- Review Session: 3/16 (5-7pm)
 - Details TBA



What is in a Page Table Entry (PTE)?

- What is in a Page Table Entry (or PTE)?
 - Pointer to next-level page table or to actual page
 - Permission bits: valid, read-only, read-write, write-only
- Example: Intel x86 architecture PTE:
 - Address same format as prior slides (10, 10, 12-bit offset)
 - Intermediate page tables called "Directories"




- P: Present (same as "valid" bit in other architectures)
- W: Writeable
- U: User accessible
- PWT: Page write transparent: external cache write-through
- PCD: Page cache disabled (page cannot be cached)
 - A: Accessed: page has been accessed recently
 - D: Dirty (PTE only): page has been modified recently
 - PS: Page Size: PS=1 \Rightarrow 4MB page (directory only). Bottom 22 bits of virtual address serve as offset


Examples of how to use a PTE

- How do we use the PTE?
 - Invalid PTE can imply different things:
 - » Region of address space is actually invalid or
 - » Page/directory is just somewhere else than memory
 - Validity checked first
 - » OS can use other (say) 31 bits for location info
- Usage Example: Demand Paging
 - Keep only active pages in memory
 - Place others on disk and mark their PTEs invalid
- Usage Example: Copy on Write
 - UNIX fork gives copy of parent address space to child
 - » Address spaces disconnected after child created
 - How to do this cheaply?
 - » Make copy of parent's page tables (point at same memory)
 - » Mark entries in both sets of page tables as read-only
 - » Page fault on write creates two copies
- Usage Example: Zero Fill On Demand
 - New data pages must carry no information (say be zeroed)
 - Mark PTEs as invalid; page fault on use gets zeroed page
 - Often, OS creates zeroed pages in background


Sharing with multilevel page tables



Summary: Two-Level Paging




Summary: Two-Level Paging




Multi-level Translation: Segments + Pages

- What about a tree of tables?
 - Lowest level page table ⇒ memory still allocated with bitmap
 - Higher levels often segmented
- Could have any number of levels. Example (top segment):



- What must be saved/restored on context switch?
 - Contents of top-level segment registers (for this example)
 - Pointer to top-level table (page table)

What about Sharing (Complete Segment)?



Multi-level Translation Analysis

Pros:

- Only need to allocate as many page table entries as we need for application
 » In other wards, sparse address spaces are easy
- Easy memory allocation
- Easy Sharing
 - » Share at segment or page level (need additional reference counting)

• Cons:


- One pointer per page (typically 4K 16K pages today)
- Page tables need to be contiguous
 - » However, the 10b-10b-12b configuration keeps tables to exactly one page in size
- Two (or more, if >2 levels) lookups per reference
 - » Seems very expensive!



Recall: Dual-Mode Operation

- Can a process modify its own translation tables? NO!
 - If it could, could get access to all of physical memory (no protection!)
- To Assist with Protection, Hardware provides at least two modes (Dual-Mode Operation):
 - "Kernel" mode (or "supervisor" or "protected")
 - "User" mode (Normal program mode)
 - Mode set with bit(s) in control register only accessible in Kernel mode
 - Kernel can easily switch to user mode; User program must invoke an exception of some sort to get back to kernel mode (more in moment)
- Note that x86 model actually has more modes:
 - Traditionally, four "rings" representing priority; most OSes use only two:
 - » Ring 0 \Rightarrow Kernel mode, Ring 3 \Rightarrow User mode
 - » Called "Current Privilege Level" or CPL
 - Newer processors have additional mode for hypervisor ("Ring I")
- Certain operations restricted to Kernel mode:
 - Modifying page table base (CR3 in x86), and segment descriptor tables
 - » Have to transition into Kernel mode before you can change them!
 - Also, all page-table pages must be mapped only in kernel mode

Making it real: x86 Memory model with segmentation (16/32-bit)



Lec 13.30


X86 Segment Descriptors (32-bit Protected Mode)

- Segments are implicit in the instruction (e.g., code segments) or part of the instruction
 - There are 6 registers: SS, CS, DS, ES, FS, GS
- What is in a segment register?
 - A pointer to the actual segment description:



Segment Register

- G/L selects between GDT and LDT tables (global vs local descriptor tables)
- RPL: Requestor's Privilege Level (RPL of CS ⇒ Current Privilege Level)
- Two registers: GDTR/LDTR hold pointers to global/local descriptor tables in memory
 - Descriptor format (64 bits): 131




- G: Granularity of segment [Limit Size] (0: 16bit, 1: 4KiB unit)
- DB: Default operand size (0: 16bit, 1: 32bit)
 - A: Freely available for use by software
 - P: Segment present
- DPL: Descriptor Privilege Level: Access requires Max(CPL,RPL) < DPL
 - S: System Segment (0: System, 1: code or data)
- Type: Code, Data, Segment

How are segments used?

- One set of global segments (GDT) for everyone, different set of local segments (LDT) for every process
- In legacy applications (16-bit mode):
 - Segments provide protection for different components of user programs
 - Separate segments for chunks of code, data, stacks
 - » RPL of Code Segment ⇒CPL (Current Privilege Level)
 - Limited to 64K segments
- Modern use in 32-bit Mode:
 - Even though there is full segment functionality, segments are set up as "flattened", i.e., every segment is 4GB in size
 - One exception: Use of GS (or FS) as a pointer to "Thread Local Storage" (TLS)
 - » A thread can make accesses to TLS like this: mov eax, gs(0x0)
- Modern use in 64-bit ("long") mode
 - Most segments (SS, CS, DS, ES) have zero base and no length limits
 - Only FS and GS retain their functionality TLS

X86_64: Four-level page table!



Lec 13.33

From x86_64 architecture specification





Figure 4-8. Linear-Address Translation to a 4-KByte Page using 4-Level Paging

- All current x86 processor support a 64-bit operation
- 64-bit words (so ints are 8 bytes) but 48-bit addresses

Larger page sizes supported as well



Linear Address
47 39 38 30 29 0

PML4 Directory Ptr Offset

30

Page-Directory-Pointer Table

PDPTE with PS=1
9

PML4E

40

CR3

Figure 4-9. Linear-Address Translation to a 2-MByte Page using 4-Level Paging

Figure 4-10. Linear-Address Translation to a 1-GByte Page using 4-Level Paging

- Larger page sizes (2MB, IGB) make sense since memory is now cheap
 - Great for kernel, large libraries, etc.
 - Use limited primarily by internal fragmentation...

IA64: 64bit addresses: Six-level page table?!!?


12 bits 9 bits 9 bits 9 bits 9 bits 7 bits 9 bits 64bit Virtual Virtual P2 index Virtual P3 index Virtual P4 index Virtual P1 index Virtual Virtual P6 index Address: Offset P5 index

No!

Too slow
Too many almost-empty tables

Alternative: Inverted Page Table

- With all previous examples ("Forward Page Tables")
 - Size of page table is at least as large as amount of virtual memory allocated to processes
 - Physical memory may be much less
 - » Much of process space may be out on disk or not in use




- Answer: use a hash table
 - Called an "Inverted Page Table"
 - Size is independent of virtual address space
 - Directly related to amount of physical memory
 - Very attractive option for 64-bit address spaces
 - » PowerPC, UltraSPARC, IA64
- Cons:
 - Complexity of managing hash chains: Often in hardware!
 - Poor cache locality of page table

Address Translation Comparison

	Advantages	Disadvantages
Simple Segmentation	Fast context switching (segment map maintained by CPU)	External fragmentation
Paging (Single-Level)	No external fragmentation Fast and easy allocation	Large table size (~ virtual memory) Internal fragmentation
Paged Segmentation	Table size ~ # of pages in virtual memory Fast and easy allocation	Multiple memory references per page access
Multi-Level Paging		
Inverted Page Table	Table size ~ # of pages in physical memory	Hash function more complex No cache locality of page table



How is the Translation Accomplished?




- The MMU must translate virtual address to physical address on:
 - Every instruction fetch
 - Every load
 - Every store

3/4/21

- What does the MMU need to do to translate an address?
 - I-level Page Table
 - » Read PTE from memory, check valid, merge address
 - » Set "accessed" bit in PTE, Set "dirty bit" on write
 - 2-level Page Table
 - » Read and check first level
 - » Read, check, and update PTE
 - N-level Page Table ...
- MMU does *Page Table Tree Traversal* to translate each address Crooks & Joseph CS162 © UCB Spring 2021 Lec 13.40

Where and What is the MMU?



- The processor requests READ Virtual-Address to memory system
 - Through the MMU to the cache (to the memory)
- Some time later, the memory system responds with the data stored at the physical address (resulting from virtual \rightarrow physical) translation
 - Fast on a cache hit, slow on a miss
- So what is the MMU doing?
- On every reference (I-fetch, Load, Store) read (multiple levels of) page table entries to get physical frame or FAULT
 - Through the caches to the memory
 - Then read/write the physical location


Recall: CS61c Caching Concept



- Cache: a repository for copies that can be accessed more quickly than the original
 - Make frequent case fast and infrequent case less dominant
- Caching underlies many techniques used today to make computers fast
 - Can cache: memory locations, address translations, pages, file blocks, file names, network routes, etc...
- Only good if:
 - Frequent case frequent enough and
 - Infrequent case not too expensive
- Important measure: Average Access time =
 (Hit Rate x Hit Time) + (Miss Rate x Miss Time)

Recall: In Machine Structures (eg. 61C) ...

Caching is the key to memory system performance



Average Memory Access Time (AMAT)


3/4/21

HitRate =
$$90\% = > AMAT = (0.9 \times 1) + (0.1 \times 101) = 11.1 \text{ ns}$$

HitRate =
$$99\%$$
 => AMAT = $(0.99 \times 1) + (0.01 \times 101) = 2.01$ ns

MissTime_{L1} includes HitTime_{L1} +MissPenalty_{L1} \equiv HitTime_{L1} +AMAT_{L2} Crooks & Joseph CS162 © UCB Spring 2021 Lec 13.43


Another Major Reason to Deal with Caching




- Cannot afford to translate on every access
 - At least three DRAM accesses per actual DRAM access
 - Or: perhaps I/O if page table partially on disk!
- Even worse: What if we are using caching to make memory access faster than DRAM access?
- Solution? Cache translations!
 - Translation Cache: TLB ("Translation Lookaside Buffer")

 Crooks & Joseph CS162 © UCB Spring 2021 Lec 13.44

Why Does Caching Help? Locality!



- Temporal Locality (Locality in Time):
 - Keep recently accessed data items closer to processor
- Spatial Locality (Locality in Space):
 - Move contiguous blocks to the upper levels




Recall: Memory Hierarchy

• Caching: Take advantage of the principle of locality to:


3/4/21

- Present the illusion of having as much memory as in the cheapest technology
- Provide average speed similar to that offered by the fastest technology



How do we make Address Translation Fast?


- Cache results of recent translations!
 - Different from a traditional cache
 - Cache Page Table Entries using Virtual Page # as the key



Translation Look-Aside Buffer

- Record recent Virtual Page # to Physical Frame # translation
- If present, have the physical address without reading any of the page tables !!!
 - Even if the translation involved multiple levels
 - Caches the end-to-end result
- Was invented by Sir Maurice Wilkes prior to caches
 - When you come up with a new concept, you get to name it!
 - People realized "if it's good for page tables, why not the rest of the data in memory?"
- On a *TLB miss*, the page tables may be cached, so only go to memory when both miss


Caching Applied to Address Translation



- Question is one of page locality: does it exist?
 - Instruction accesses spend a lot of time on the same page (since accesses sequential)
 - Stack accesses have definite locality of reference
 - Data accesses have less page locality, but still some...
- Can we have a TLB hierarchy?
 - Sure: multiple levels at different sizes/speeds



What kind of Cache for TLB?



- Remember all those cache design parameters and trade-offs?
 - Amount of Data = N * L * K
 - Tag is portion of address that identifies line (w/o line offset)
 - Write Policy (write-thru, write-back), Eviction Policy (LRU, ...)


How might organization of TLB differ from that of a conventional instruction or data cache?

• Let's do some review ...

A Summary on Sources of Cache Misses

- Compulsory (cold start or process migration, first reference): first access to a block
 - "Cold" fact of life: not a whole lot you can do about it
 - Note: If you are going to run "billions" of instruction, Compulsory Misses are insignificant
- Capacity:
 - Cache cannot contain all blocks access by the program
 - Solution: increase cache size
- Conflict (collision):
 - Multiple memory locations mapped to the same cache location
 - Solution I: increase cache size
 - Solution 2: increase associativity
- Coherence (Invalidation): other process (e.g., I/O) updates memory

How is a Block found in a Cache?




- Block is minimum quantum of caching
 - Data select field used to select data within block
 - Many caching applications don't have data select field
- Index Used to Lookup Candidates in Cache
 - Index identifies the set
- Tag used to identify actual copy
 - If no candidates match, then declare cache miss

Review: Direct Mapped Cache

- Direct Mapped 2^N byte cache:
 - The uppermost (32 N) bits are always the Cache Tag The lowest M bits are the Byte Select (Block Size = 2^{M})
- Example: I KB Direct Mapped Cache with 32 B Blocks
 - Index chooses potential block
 - Tag checked to verify block
- Byte select chooses byte within block 31 **Cache Tag Cache Index Byte Select** Ex: 0x01 Ex: 0x00 Ex: 0x50 Valid Bit **Cache Tag Cache Data** Byte 31 Byte 1 Byte 0 0x50Byte 63 Byte 33 Byte 32 **Byte 1023** Byte 992 | 31


Review: Set Associative Cache

- N-way set associative: N entries per Cache Index
 - N direct mapped caches operates in parallel
- Example: Two-way set associative cache
 - Cache Index selects a "set" from the cache
 - Two tags in the set are compared to input in parallel



Review: Fully Associative Cache


- Fully Associative: Every block can hold any line
 - Address does not include a cache index
 - Compare Cache Tags of all Cache Entries in Parallel
- Example: Block Size=32B blocks
 - We need N 27-bit comparators
 - Still have byte select to choose from within block



Where does a Block Get Placed in a Cache?

• Example: Block 12 placed in 8 block cache

32-Block Address Space:



Direct mapped:

block 12 can go only into block 4 (12 mod 8)


Block 0 1 2 3 4 5 6 7 no.



block 12 can go anywhere in set 0

(12 mod 4) Block 0 1 2 3 4 5 6

no.



0 1 2 3

Fully associative:

block 12 can go anywhere

Block 0 1 2 3 4 5 6 7 no.

Which block should be replaced on a miss?

- Easy for Direct Mapped: Only one possibility
- Set Associative or Fully Associative:
 - Random
 - LRU (Least Recently Used)
- Miss rates for a workload:

	2-way		4-w	ay ay	8-way		
Size	LRU Random		LRU Random		LRU Random		
16 KB	5.2%	5.7%	4.7%	5.3%	4.4%	5.0%	
64 KB	1.9%	2.0%	1.5%	1.7%	1.4%	1.5%	
256 KB	1.15%	1.17%	1.13%	1.13%	1.12%	1.12%	


Review: What happens on a write?

- Write through: The information is written to both the block in the cache and to the block in the lower-level memory
- Write back: The information is written only to the block in the cache
 - Modified cache block is written to main memory only when it is replaced
 - Question is block clean or dirty?
- Pros and Cons of each?
 - WT:
 - » PRO: read misses cannot result in writes
 - » CON: Processor held up on writes unless writes buffered
 - WB:
 - » PRO: repeated writes not sent to DRAM processor not held up on writes
 - » CON: More complex Read miss may require writeback of dirty data

Questions about caches?

- How does operating system behavior affect cache performance?
- Switching threads?
- Switching contexts?
- Cache design? What addresses are used?
- What does our understanding of caches tell us about TLB organization?

What TLB Organization Makes Sense?



- Needs to be really fast
 - Critical path of memory access
 - » In simplest view: before the cache
 - » Thus, this adds to access time (reducing cache speed)
 - Seems to argue for Direct Mapped or Low Associativity
- However, needs to have very few conflicts!
 - With TLB, the Miss Time extremely high! (PT traversal)
 - Cost of Conflict (Miss Time) is high
 - Hit Time dictated by clock cycle
- Thrashing: continuous conflicts between accesses
 - What if use low order bits of page as index into TLB?
 - » First page of code, data, stack may map to same entry
 - » Need 3-way associativity at least?
 - What if use high order bits as index?
 - » TLB mostly unused for small programs

TLB organization: include protection

- How big does TLB actually have to be?
 - -Usually small: 128-512 entries (larger now)
 - -Not very big, can support higher associativity
- Small TLBs usually organized as fully-associative cache
 - Lookup is by Virtual Address
 - Returns Physical Address + other info
- What happens when fully-associative is too slow?
 - Put a small (4-16 entry) direct-mapped cache in front
 - Called a "TLB Slice"
- Example for MIPS R3000:

Virtual Address	Physical Address	Dirty	Ref	Valid	Access	ASID
0xFA00	0x0003	Υ	N	Υ	R/W	34
0x0040	0x0010	N	Υ	Υ	R	0
0x0041	0x0011	N	Υ	Υ	R	0

Example: R3000 pipeline includes TLB "stages"


MIPS R3000 Pipeline

Inst Fetch		Dcd/ Reg		ALU / E.A		Memory	Write Reg	
TLB	I-Cac	he	RF	Operation			WB	
				E.A.	TLB	D-Cache		

TLB

64 entry, on-chip, fully associative, software TLB fault handler

Virtual Address Space




Example: Pentium-M TLBs (2003)

- Four different TLBs
 - Instruction TLB for 4K pages
 - » 128 entries, 4-way set associative
 - Instruction TLB for large pages
 - » 2 entries, fully associative
 - Data TLB for 4K pages
 - » 128 entries, 4-way set associative
 - Data TLB for large pages
 - » 8 entries, 4-way set associative
- All TLBs use LRU replacement policy
- Why different TLBs for instruction, data, and page sizes?

Intel Nahelem (2008)

- LI DTLB
 - 64 entries for 4 K pages and
 - 32 entries for 2/4 M pages,
- LI ITLB
 - 128 entries for 4 K pages using 4-way associativity and
 - 14 fully associative entries for 2/4 MiB pages
- unified 512-entry L2 TLB for 4 KiB pages, 4-way associative.

Current Intel x86 (Skylake, Cascade Lake)



Current Example: Memory Hierarchy


- Caches (all 64 B line size)
 - L1 I-Cache: 32 <u>KiB</u>/core, 8-way set assoc.
 - L1 D Cache: 32 KiB/core, 8-way set assoc., 4-5 cycles load-to-use, Write-back policy
 - L2 Cache: I MiB/core, 16-way set assoc., Inclusive, Write-back policy, 14 cycles latency
 - L3 Cache: I.375 MiB/core, I I-way set assoc., shared across cores, Non-inclusive victim cache, Write-back policy, 50-70 cycles latency
- TLB
 - L1 ITLB, 128 entries; 8-way set assoc. for 4 KB pages
 - » 8 entries per thread; fully associative, for 2 MiB / 4 MiB page
 - L1 DTLB 64 entries; 4-way set associative for 4 KB pages
 - » 32 entries; 4-way set associative, 2 MiB / 4 MiB page translations:
 - » 4 entries; 4-way associative, IG page translations:
 - L2 STLB: 1536 entries; 12-way set assoc. 4 KiB + 2 MiB pages
 - » 16 entries; 4-way set associative, 1 GiB page translations:




What happens on a Context Switch?

- Need to do something, since TLBs map virtual addresses to physical addresses
 - Address Space just changed, so TLB entries no longer valid!
- Options?
 - Invalidate TLB: simple but might be expensive
 - » What if switching frequently between processes?
 - Include ProcessID in TLB.
 - » This is an architectural solution: needs hardware
- What if translation tables change?
 - For example, to move page from memory to disk or vice versa...
 - Must invalidate TLB entry!
 - » Otherwise, might think that page is still in memory!
 - Called "TLB Consistency"


Putting Everything Together: Address Translation



Putting Everything Together: TLB




Putting Everything Together: Cache



Page Fault

- The Virtual-to-Physical Translation fails
 - PTE marked invalid, Priv. Level Violation, Access violation, or does not exist
 - Causes a Fault / Trap
 - » Not an interrupt because synchronous to instruction execution
 - May occur on instruction fetch or data access
 - Protection violations typically terminate the instruction
- Other Page Faults engage operating system to fix the situation and retry the instruction
 - Allocate an additional stack page, or
 - Make the page accessible Copy on Write,
 - Bring page in from secondary storage to memory demand paging
- Fundamental inversion of the hardware / software boundary

Next Up: What happens when ...



Summary (1/3)

- Page Tables
 - Memory divided into fixed-sized chunks of memory
 - Virtual page number from virtual address mapped through page table to physical page number
 - Offset of virtual address same as physical address
 - Large page tables can be placed into virtual memory
- Multi-Level Tables
 - Virtual address mapped to series of tables
 - Permit sparse population of address space
- Inverted Page Table
 - Use of hash-table to hold translation entries
 - Size of page table \sim size of physical memory rather than size of virtual memory

Summary (2/3)

- The Principle of Locality:
 - Program likely to access a relatively small portion of the address space at any instant of time.
 - » Temporal Locality: Locality in Time
 - » Spatial Locality: Locality in Space
- Three (+1) Major Categories of Cache Misses:
 - Compulsory Misses: sad facts of life. Example: cold start misses.
 - Conflict Misses: increase cache size and/or associativity
 - Capacity Misses: increase cache size
 - Coherence Misses: Caused by external processors or I/O devices
- Cache Organizations:
 - Direct Mapped: single block per set
 - Set associative: more than one block per set
 - Fully associative: all entries equivalent

Summary (3/3)

- "Translation Lookaside Buffer" (TLB)
 - Small number of PTEs and optional process IDs (< 512)
 - Fully Associative (Since conflict misses expensive)
 - On TLB miss, page table must be traversed and if located PTE is invalid, cause Page Fault
 - On change in page table, TLB entries must be invalidated
 - TLB is logically in front of cache (need to overlap with cache access)
- Next Time: What to do on a page fault?