### CS330: Operating Systems

Locking

#### Recap: Strategy to handle race conditions in OS

| Contexts executing critical sections | Uniprocessor systems | Multiprocessor systems                       |
|--------------------------------------|----------------------|--|
| System calls                         | Disable preemption   | Locking                                      |
| System calls,<br>Interrupt handler   | Disable interrupts   | Locking + Interrupt<br>disabling (local CPU) |
| Multiple interrupt<br>handlers       | Disable interrupts   | Locking + Interrupt<br>disabling (local CPU) |

#### Locking example: pthread mutex

```
pthread_mutex _t lock; // Initialized using pthread_mutex_init
static int counter = 0;
void *thfunc(void *)
 int ctr = 0;
 for(ctr=0; ctr<100000; ++ctr){
   pthread_mutex_lock(&lock); // One thread acquires lock, others wait
                                  // Critical section
   counter++;
   pthread_mutex_unlock(&lock); // Release the lock
```

#### Design issues of locks

```
pthread_mutex _t lock; // Initialized using pthread_mutex_init
static int counter = 0;
```

- Efficiency of lock and unlock operations
- Lock acquisition delay vs. wasted CPU cycles
- Fairness of the locking scheme

```
counter++; // Critical section

pthread_mutex_unlock(&lock); // Release the lock
}
```

# Lock ADT

unlock(L)

lock(L)

// Return  $\Rightarrow$  Lock acquired

// Return  $\Rightarrow$  Lock released

lock(L2) Critical Section unlock(L2)

Lock(L1) Critical Section unlock(L2)

lock t \*L1, L2;

Critical Section

lock(L1)

unlock(L1)

#### Lock ADT: Efficiency

```
lock_t *L;
lock(L)
 // Return \Rightarrow Lock acquired
unlock(L)
 // Return \Rightarrow Lock released
```

- Efficiency of lock/unlock operations directly influence performance
- Implementation choices?

#### Lock ADT: Efficiency

```
lock t*L;
lock(L)
 // Return \Rightarrow Lock acquired
unlock(L)
 // Return \Rightarrow Lock released
```

- Efficiency of lock/unlock operations directly influence performance
- Implementation choices?
- Hardware assisted implementations
  - Use hardware synchronization primitives like atomic operations

#### Lock ADT: Efficiency

```
lock t*L;
lock(L)
 // Return \Rightarrow Lock acquired
unlock(L)
 // Return \Rightarrow Lock released
```

- Efficiency of lock/unlock operations directly influence performance
- Implementation choices?
- Hardware assisted implementations
  - Use hardware synchronization primitives like atomic operations
- Software locks are implemented without assuming any hardware support
  - Not used in practice because of high overheads

#### Design issues of locks

```
pthread_mutex _t lock; // Initialized using pthread_mutex_init
static int counter = 0;
```

- Efficiency of lock and unlock operations
- Hardware-assisted lock implementations are used for efficiency
- Lock acquisition delay vs. wasted CPU cycles
- Fairness of the locking scheme

```
counter++; // Critical section
pthread_mutex_unlock(&lock); // Release the lock
}
```

#### Lock: busy-wait (spinlock) vs. Waiting

lock(L) //Acquired

Critical section lock(L) //Lock is busy. Reschedule or Spin?

unlock(L) Critical section unlock(L)

#### Lock: busy-wait (spinlock) vs. Waiting

T1 T2 lock(L) //Acquired

Critical section

unlock(L) Critical section

unlock(L)

 With busy waiting, context switch overheads saved, wasted CPU cycles due to spinning

lock(L) //Lock is busy. Reschedule or Spin?

- Busy waiting is prefered when critical section is small and the context executing the critical section is not rescheduled (e.g., due to I/O wait)

#### Design issues of locks

```
pthread_mutex _t lock; // Initialized using pthread_mutex_init
static int counter = 0;
```

- Efficiency of lock and unlock operations
- Hardware-assisted lock implementations are used for efficiency
- Lock acquisition delay vs. wasted CPU cycles
- Use waiting locks and spinlocks depending on the requirement
- Fairness of the locking scheme

#### Fairness

- Given *N* threads contending for the lock, number of unsuccessful attempts for lock acquisition for all contending threads should be same
- Bounded wait property
  - Given N threads contending for the lock, there should be an upper bound on the number of attempts made by a given context to acquire the lock

#### Design issues of locks

```
pthread_mutex_t lock; // Initialized using pthread_mutex_init
```

- Efficiency of lock and unlock operations
- Hardware-assisted lock implementations are used for efficiency
- Lock acquisition delay vs. wasted CPU cycles
- Use waiting locks and spinlocks depending on the requirement
- Fairness of the locking scheme
- Contending threads should not starve for the lock

```
pthread_mutex_unlock(&lock); // Release the lock
}
```

```
    lock_t *L = 0; // Initial value - Does this implementation work?

2. lock(L)
   while(*lock);
   *lock = 1;
 7. unlock(L)
8. {
    *lock = 0;
10.
```

```
Does this implementation work?
 1. lock_t *L = 0; // Initial value -
                                 - No, it does not ensure mutual exclusion
2. lock(L)
                                    Why?
   while(*lock);
   *lock = 1;
 7. unlock(L)
8. {
    *lock = 0;
10.
```

```
lock_t *L = 0; // Initial value
   lock(L)
    while(*lock);
    *lock = 1;
    unlock(L)
8. {
     *lock = 0;
10.
```

- Does this implementation work?
- No, it does not ensure *mutual exclusion*
- Why?
  - Single core: Context switch between line #4 and line #5
  - Multicore: Two cores exiting the
     while loop by reading lock = 0

```
lock_t *L = 0; // Initial value
   lock(L)
    while(*lock);
    *lock = 1;
    unlock(L)
8. {
     *lock = 0;
10.
```

- Does this implementation work?
- No, it does not ensure *mutual exclusion*
- Why?
  - Single core: Context switch between line #4 and line #5
  - Multicore: Two cores exiting the while loop by reading lock = 0
- Core issue: Compare and swap has to happen atomically!

#### Spinlock using atomic exchange

```
lock_t *L = 0; // Initial value
lock(L)
  while(atomic_xchg(*L, 1));
unlock(L)
  *lock = 0;
```

- Atomic exchange: exchange the value of memory and register atomically
- atomic\_xchg (int \*PTR, int val) returnsthe value at PTR before exchange
- Ensures mutual exclusion if "val" is stored on a register
- No fairness guarantees

#### Spinlock using XCHG on X86

```
lock(lock_t *L)
 asm volatile(
 "mov $1, %%rax;"
 "loop: xchg %%rax, (%%rdi);"
 "cmp $0, %%rax;"
  "jne loop;"
  ::: "memory");
unlock(int *L) { *L = 0;}
```

- XCHG R, M ⇒ Exchange value of register R and value at memory address
   M
  - *RDI* register contains the lock argument
  - Exercise: Visualize a context switch between any two instructions and analyse the correctness

#### Spinlock using compare and swap

```
lock_t *L = 0; // Initial value
lock(L)
 while( CAS(*L, 0, 1) );
 unlock(L)
  *lock = 0;
```

- Atomic compare and swap: perform the condition check and swap atomically
- CAS (int \*PTR, int cmpval, int newval)
   sets the value of PTR to newval if cmpval is equal to value at PTR. Returns
   0 on successful exchange
- No fairness guarantees!

#### CAS on X86: cmpxchg

## cmpxchg source[Reg] destination [Mem/Reg] Implicit registers : rax and flags

```
    if rax == [destination]
    then
    flags[ZF] = 1
    [destination] = source
    else
    flags[ZF] = 0
    rax = [destination]
```

- "cmpxchg" is not atomic in X86, should be used with a "lock" prefix

#### Spinlock using CMPXCHG on X86

```
lock(lock t *L)
asm volatile(
   "mov $1, %%rcx;"
  "loop: xor %%rax, %%rax;"
  "lock cmpxchg %%rcx, (%%rdi);"
   "jnz loop;"
   ::: "rcx", "rax", "memory");
unlock(lock_t ^*L) { ^*L = 0;}
```

Value of RAX (=0) is compared
against value at address in register
RDI and exchanged with RCX (=1), if
they are equal

Exercise: Visualize a context switch between any two instructions and analyse the correctness

#### Load Linked (LL) and Store conditional (SC)

- LoadLinked (R, M)
  - Like a normal load, it loads R with value of M
  - Additionally, the hardware keeps track of future stores to M
- StoreConditional (R, M)
  - Stores the value of R to M if no stores happened to M after the execution of LL instruction (after execution, R = 1)
  - Otherwise, store is not performed (after execution R=0)
- Supported in RISC architectures like mips, risc-v etc.

#### Spinlock using LL and LC

```
lock_t *L = 0;
lock(lock_t *L)
{
    while(LoadLinked(L) ||
    !StoreConditional(L, 1));
}
unlock(lock t *L) { *L = 0;}
lock: LL R1, (R2); //R2 = lock address
BNEQZ R1, lock;
ADDUI R1, R0, #1; //R1 = 1
SC R1, (R2)
BEQZ R1, lock
```

- Efficient as the hardware avoids memory traffic for unsuccessful lock acquire attempts
- Context switch between LL and SC results in SC to fail

#### Spinlocks: reducing wasted cycles

- Spinning for locks can introduce significant CPU overheads and increase energy consumption
- How to reduce spinning in spinlocks?

#### Spinlocks: reducing wasted cycles

- Spinning for locks can introduce significant CPU overheads and increase energy consumption
- How to reduce spinning in spinlocks?
- Strategy: Back-off after every failure, exponential back-off used mostly

```
lock( lock_t *L) {
    u64 backoff = 0;
    while(LoadLinked(L) || !StoreConditional(L, 1)){
        if(backoff < 63) ++backoff;
        pause(1 << backoff); // Hint to processor
}</pre>
```

#### Fairness in spinlocks

- Spinlock implementations discussed so far are not fair,
  - no bounded waiting
- To ensure fairness, some notion of ordering is required
- What if the threads are granted the lock in the order of their arrival to the lock contention loop?
  - A single lock variable may not be sufficient
  - Example solution: Ticket spinlocks

#### Atomic fetch and add (xadd on X86)

#### xadd R, M


```
TmpReg T = R + [M]
R = [M]
[M] = T
```

- Example: M = 100; RAX = 200
- After executing "lock xadd %RAX, M", value of RAX = 100, M = 300
- Require lock prefix to be atomic

#### Ticket spinlocks (OSTEP Fig. 28.7)


```
void lock(struct lock_t *L){
struct lock t{
                                                long myturn = xadd(\&L \rightarrow ticket, 1);
         long ticket;
                                                while(myturn != L \rightarrow turn)
         long turn;
                                                      pause(myturn - L \rightarrow turn);
};
void init lock (struct lock t*L){
                                           - Example: Order of arrival: T1 T2 T3
  L \rightarrow ticket = 0; L \rightarrow turn = 0;
                                           - T1 (in CS): myturn = 0, L = \{1, 0\}
void unlock(struct lock_t *L){
                                           - T2: myturn = 1, L = \{2, 0\}
      L \rightarrow turn++;
                                           - T3: myturn = 2, L = \{3,0\}
                                           - T1 unlocks, L = \{3, 1\}. T2 enters CS
```

#### Ticket spinlock




- Local variable "myturn" is equivalent to the order of arrival
- If a thread is in CS ⇒ Local Turn must be same as "Turn"
- Threads waiting = Ticket Turn

#### Ticket spinlock



- Value of turn incremented on lock release
- Thread which arrived just after the current thread enters the CS
- When a new thread arrives, it gets the lock after the other threads ahead of the new thread acquire and release the lock

#### Ticket spinlock



- Ticket spinlock guarantees bounded waiting
- If N threads are contending for the lock and execution of the CS consumes T cycles, then bound = N \* T (assuming negligible context switch overhead)

#### Ticket spinlock (with yield)

```
void lock(struct lock_t *L){
  long myturn = xadd(&L → ticket, 1);
  while(myturn != L → turn)
      sched_yield();
}
```

- Why spin if the thread's turn is yet to come?
- Yield the CPU and allow the thread with ticket (or other non contending threads)
- Further optimization
  - Allow the thread with
     "myturn" value one less than
     "L→ turn" to continue spining