Chapter 3
Transport Layer



Computer Networking: A Top-Down Approach
8^{th} edition
Jim Kurose, Keith Ross
Pearson, 2020

Transport layer: overview

Our goal:

- understand principles behind transport layer services:
  - multiplexing, demultiplexing
  - reliable data transfer
  - flow control
  - congestion control
- learn about Internet transport layer protocols:
  - UDP: connectionless transport
  - TCP: connection-oriented reliable transport
  - TCP congestion control

Transport layer: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control

Transport services and protocols

- provide *logical communication* between application processes running on different hosts
- transport protocols actions in end systems:
  - sender: breaks application messages into *segments*, passes to network layer
  - receiver: reassembles segments into messages, passes to application layer
- two transport protocols available to Internet applications
  - TCP, UDP



Transport Layer Actions

Sender:

- is passed an application-layer message
- determines segment header fields values
- creates segment
- passes segment to IP





Transport Layer Actions



Receiver:

- receives segment from IP
- checks header values
- extracts application-layer message
- demultiplexes message up to application via socket

Two principal Internet transport protocols

- **TCP:** Transmission Control Protocol
  - reliable, in-order delivery
  - congestion control
  - flow control
  - connection setup
- **UDP:** User Datagram Protocol
  - unreliable, unordered delivery
  - no-frills extension of “best-effort” IP
- services not available:
  - delay guarantees
  - bandwidth guarantees



Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control

Multiplexing/demultiplexing

multiplexing at sender:

handle data from multiple sockets, add transport header (later used for demultiplexing)

demultiplexing at receiver:

use header info to deliver received segments to correct socket



How demultiplexing works

- host receives IP datagrams
  - each datagram has source IP address, destination IP address
  - each datagram carries one transport-layer segment
  - each segment has source, destination port number
- host uses *IP addresses & port numbers* to direct segment to appropriate socket

- Two kinds of ports:
  - (a) Reserved ports (A few 1000s from the lower end). Well known ports (TCP: #80/HTTP; #179/BGP; #20,21/FTP UDP: #520/RIP;
  - (b) Free ports (Talk to your system admin to get one.)



TCP/UDP segment format

Connectionless demultiplexing

Recall:

- when creating socket, must specify *host-local* port #

- when creating datagram to send into UDP socket, must specify
  - destination IP address
  - destination port #

when receiving host receives *UDP* segment:

- checks destination port # in segment
- directs UDP segment to socket with that port #

IP/UDP datagrams with *same dest. port #,* but different source IP addresses and/or source port numbers will be directed to *same socket* at receiving host

Connectionless demultiplexing: an example



Connection-oriented demultiplexing

- TCP socket identified by 4-tuple:
  - source IP address
  - source port number
  - dest IP address
  - dest port number
- demux: receiver uses *all four values (4-tuple)* to direct segment to appropriate socket
- server may support many simultaneous TCP sockets:
  - each socket identified by its own 4-tuple
  - each socket associated with a different connecting client

Connection-oriented demultiplexing: example



Three segments, all destined to IP address: B,
dest port: 80 are demultiplexed to *different* sockets

Summary

- Multiplexing, demultiplexing: based on segment, datagram header field values
- **UDP:** demultiplexing using destination port number (only)
- **TCP:** demultiplexing using 4-tuple: source and destination IP addresses, and port numbers
- Multiplexing/demultiplexing happen at *all* layers

Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control

UDP: User Datagram Protocol

- "no frills," "bare bones" Internet transport protocol
- "best effort" service, UDP segments may be:
  - lost
  - delivered out-of-order to app
- *connectionless:*
  - no handshaking between UDP sender, receiver
  - each UDP segment handled independently of others

Why is there a UDP?

- no connection establishment (which can add RTT delay)
- simple: no connection state at sender, receiver
- small header size
- no congestion control
  - UDP can blast away as fast as desired!
  - can function in the face of congestion

UDP: User Datagram Protocol

- UDP use:
  - streaming multimedia apps (loss tolerant, rate sensitive)
  - DNS
  - SNMP
  - HTTP/3
- if reliable transfer needed over UDP (e.g., HTTP/3):
  - add needed reliability at application layer
  - add congestion control at application layer

UDP segment header



UDP segment format

Summary: UDP

- "no frills" protocol:
  - segments may be lost, delivered out of order
  - best effort service: "send and hope for the best"
- UDP has its plusses:
  - no setup/handshaking needed (no RTT incurred)
  - can function when network service is compromised
  - helps with reliability (checksum)
- build additional functionality on top of UDP in application layer (e.g., HTTP/3)

Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control

Principles of reliable data transfer

- Packets are transmitted over unreliable channels which can corrupt the packets, deliver the same packet more than once (duplication), deliver the packets out of order, even cause packet loss.
- Automatic Repeat Request (ARQ) protocols are used to provide reliable data transfer.
- Reliable data transfer requires feedback from the receiver to the sender (Acknowledgement)
- Sequence numbers are used to solve the problem of out of order and duplicate packets.
- Timers are used to solve the problem of lost packets

Stop-and-wait operation



(a) no loss



(b) packet loss

- Main idea is to send a packet, start a timer, wait for an acknowledgement. If the timer times out before receiving ACK, retransmit

Stop-and-wait operation

Any duplicate packet (at the receiver) or duplicate ACK (at the sender) will be discarded



(c) ACK loss



(d) premature timeout/ delayed ACK

Performance Stop-and-wait

- U_{sender}: *utilization* – fraction of time sender busy sending

- example: 1 Gbps link, 15 ms prop. delay, 8000 bit packet
  - time to transmit packet into channel:

$$D_{trans} = \frac{L}{R} = \frac{8000 \text{ bits}}{10^9 \text{ bits/sec}} = 8 \text{ microsecs}$$

Stop-and-wait operation



Stop-and-wait operation

$$U_{sender} = \frac{L / R}{RTT + L / R}$$

$$= \frac{.008}{30.008}$$

$$= 0.00027$$



- 270Kbps throughput over 1 Gbps link
- Stop-and-wait protocol performance stinks!
- Protocol limits performance of underlying infrastructure (channel)

Pipelined protocols operation

pipelining: sender allows multiple, “in-flight”, yet-to-be-acknowledged packets

- range of sequence numbers must be increased
- buffering at sender and/or receiver



(a) a stop-and-wait protocol in operation (b) a pipelined protocol in operation

Pipelining: increased utilization



3-packet pipelining increases utilization by a factor of 3!

$$U_{sender} = \frac{3L / R}{RTT + L / R} = \frac{.0024}{30.008} = 0.00081$$

Pipelined protocols: overview

Go-back-N:

- sender can have up to N unacked packets in pipeline
- receiver only sends *cumulative ack*
  - doesn't ack packet if there's a gap
- sender has timer for oldest unacked packet
  - when timer expires, retransmit *all* unacked packets

Selective Repeat:

- sender can have up to N unack'ed packets in pipeline
- rcvr sends *individual ack* for each packet
- sender maintains timer for each unacked packet
  - when timer expires, retransmit only that unacked packet

Go-Back-N: sender

- sender: "window" of up to N, consecutive transmitted but unACKed pkts
  - k-bit seq # in pkt header
- *cumulative ACK:* ACK(*n*): ACKs all packets up to, including seq # *n*
  - on receiving ACK(*n*): move window forward to begin at *n+1*
- timer for oldest in-flight packet
- *timeout(n):* retransmit packet n and all higher seq # packets in window
- ACK-only: always send ACK for correctly-received packet so far, with highest *in-order* seq #
  - may generate duplicate ACKs
- on receipt of out-of-order packet:
  - can discard (don't buffer) or buffer: an implementation decision
  - re-ACK pkt with highest in-order seq #

Go-Back-N in action

Any out of order packet (at the receiver) or duplicate ACK (at the sender) will be discarded



Selective repeat

- receiver *individually* acknowledges all correctly received packets
  - buffers packets, as needed, for eventual in-order delivery to upper layer
- sender times-out/retransmits individually for unACKed packets
  - sender maintains timer for each unACKed pkt
- sender window
  - *N* consecutive seq #s
  - limits seq #s of sent, unACKed packets

Selective repeat: sender and receiver

sender

data from above:

- if next available seq # in window, send packet

timeout(*n*):

- resend packet *n*, restart timer

ACK(*n*) in [expected ACK sq# window]:

- mark packet *n* as received
- if n smallest unACKed packet, advance window base to next unACKed seq #

receiver

packet *n* in [expected received sq# window]

- send ACK(*n*)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order packets), advance window to next not-yet-received packet

packet *n* with sq# in the previous window

- ACK(*n*)

otherwise:

- ignore

Selective Repeat in action



Q: what happens when ack2 arrives?

Selective repeat: a dilemma!

example:

- seq #s: 0, 1, 2, 3 (base 4 counting)
- window size=3

- receiver sees no difference in two scenarios!
- duplicate data accepted as new in (b)

Q: what relationship between seq # size and window size to avoid problem in (b)?

A: Window size should be equal to or less than half the seq # space.



Performance of Sliding Window when No Errors

- Say that Tx and Rx have agreed on a window size W.
- Let L be the frame size. Then, if t_T = RTT + L/R is the total elapsed time to send a data frame and to receive the corresponding ACK,

then the sender will send

  - If $WL/R \leq t_T$, then send W frames or
  - If $WL/R > t_T$, the "link" will be full and the time to send the frames will be greater than t_T, which does not make sense. So, we will have an upper bound of $W_{upper\text{-}bound} = t_T/t_I$, where t_I is the time to transmit one frame, i.e., ($t_I = L/R$)

- Hence the utilization is: $U = \min(1, Wt_I/t_T)$

Ideal Window Size for 100% utilization : $W_{upper\text{-}bound} = t_T/t_I$

Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- Principles of congestion control
- TCP congestion control

TCP: overview RFCs: 793,1122, 2018, 5681, 7323

- point-to-point:
  - one sender, one receiver
- reliable, in-order *byte steam:*
  - no "message boundaries"
- full duplex data:
  - bi-directional data flow in same connection
  - MSS: maximum segment size
- cumulative ACKs
- pipelining:
  - TCP congestion and flow control set window size
- connection-oriented:
  - handshaking (exchange of control messages) initializes sender, receiver state before data exchange
- flow controlled:
  - sender will not overwhelm receiver

TCP segment structure



TCP sequence numbers, ACKs

Sequence numbers:

- byte stream "number" of first byte in segment's data

Acknowledgements:

- seq # of next byte expected from other side
- cumulative ACK

Q: how receiver handles out-of-order segments

- *A:* TCP spec doesn't say, - up to implementor
- Two choices:
  - Discard (inefficient)
  - Buffer (used in practice)



TCP sequence numbers, ACKs



simple telnet scenario

TCP Sender (simplified)

event: data received from application

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
  - think of timer as for oldest unACKed segment
  - expiration interval: **`TimeOutInterval`**

event: timeout

- retransmit segment that caused timeout
- restart timer

event: ACK received

- if ACK acknowledges previously unACKed segments
  - update what is known to be ACKed
  - start timer if there are still unACKed segments

TCP Receiver: ACK generation [RFC 5681]

Event at receiver	*TCP receiver action*
arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
arrival of in-order segment with expected seq #. One other segment has ACK pending	immediately send single cumulative ACK, ACKing both in-order segments
arrival of out-of-order segment higher-than-expect seq. # . Gap detected	immediately send *duplicate ACK,* indicating seq. # of next expected byte
arrival of segment that partially or completely fills gap	immediate send ACK, provided that segment starts at lower end of gap

TCP: retransmission scenarios



lost ACK scenario



premature timeout

TCP: retransmission scenarios



cumulative ACK covers
for earlier lost ACK

TCP fast retransmit

TCP fast retransmit

if sender receives 3 additional ACKs for same data ("triple duplicate ACKs"), resend unACKed segment with smallest seq #

- likely that unACKed segment lost, so don't wait for timeout

Receipt of three duplicate ACKs indicates 3 segments received after a missing segment – lost segment is likely. So retransmit!



Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- Principles of congestion control
- TCP congestion control

TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?



receiver protocol stack

TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?



TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?





receiver protocol stack

TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?



receiver protocol stack

flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast

TCP flow control

- TCP receiver "advertises" free buffer space in **`rwnd`** field in TCP header
  - **`RcvBuffer`** size set via socket options (typical default is 4096 bytes)
  - many operating systems autoadjust **`RcvBuffer`**
- sender limits amount of unACKed ("in-flight") data to received **`rwnd`**
- guarantees receive buffer will not overflow



TCP receiver-side buffering

TCP flow control

- TCP receiver "advertises" free buffer space in **`rwnd`** field in TCP header
  - **`RcvBuffer`** size set via socket options (typical default is 4096 bytes)
  - many operating systems autoadjust **`RcvBuffer`**
- sender limits amount of unACKed ("in-flight") data to received **`rwnd`**
- guarantees receive buffer will not overflow



TCP segment format

TCP Connection Establishment: 3-way handshake

- Use these fields to understand the opening of a conn.
  - Connection request (SYN)
  - Initial Sequence Number (ISN)
  - Acknowledgement (ACK)
  - Receive window size

TCP Connection Establishment: 3-way handshake



TCP Connection Establishment: 3-way handshake

- SYN segment from client to server
  - SYN = 1
  - A random initial Seq# (ISN)
  - RWND is undefined (defined later …)
  - Options
- SYN+ACK segment from server to client
  - SYN = 1
  - A random initial Seq# (ISN)
  - ACK = 1 (server acks the received SYN segment)
  - Ack Seq.#: The sequence # of first data byte to be received
  - RWND: Receive window size
- ACK from client to server
  - ACKs the second SYN segment
  - RWND

TCP: closing a connection

- client, server each close their side of connection
  - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
  - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled



Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control

Principles of congestion control

Congestion:

- informally: "too many sources sending too much data too fast for *network* to handle"
- manifestations:
  - long delays (queueing in router buffers)
  - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!

congestion control: too many senders, sending too fast

flow control: one sender too fast for one receiver

Approaches towards congestion control

End-end congestion control:

- no explicit feedback from network
- congestion *inferred* from observed loss, delay
- approach taken by TCP



Approaches towards congestion control

Network-assisted congestion control:

- routers provide *direct* feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control

TCP congestion control: AIMD

- *approach:* senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

Additive Increase

increase sending rate by 1 maximum segment size every RTT until loss detected

Multiplicative Decrease

cut sending rate in half at each loss event



AIMD sawtooth behavior: *probing* for bandwidth

TCP AIMD: more

Multiplicative decrease detail: sending rate is

- Cut in half on loss detected by triple duplicate ACK (TCP Reno)
- Cut to 1 MSS (maximum segment size) when loss detected by timeout (TCP Tahoe)

Why AIMD?

- AIMD – a distributed, asynchronous algorithm – has been shown to:
  - optimize congested flow rates network wide!
  - have desirable stability properties

TCP congestion control: details



TCP sending behavior:

- *roughly:* send `cwnd` bytes, wait RTT for ACKS, then send more bytes

$$\text{TCP rate} \approx \frac{\texttt{cwnd}}{\text{RTT}} \text{ bytes/sec}$$

- TCP sender limits transmission: **`LastByteSent- LastByteAcked` ≤ `Min (cwnd,rwnd)`**
- `cwnd` is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

TCP slow start

- when connection begins, increase rate exponentially until first loss event:
  - initially **`cwnd`** = 1 MSS
  - double **`cwnd`** every RTT
  - done by incrementing **`cwnd`** for every ACK received
- *summary:* initial rate is slow, but ramps up exponentially fast



TCP: from slow start to congestion avoidance

Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.



Implementation:

- variable **ssthresh**
- on loss event, **ssthresh** is set to 1/2 of **cwnd** just before loss event

* Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive/

TCP: Congestion Avoidance

- Once the congestion window (cwnd) reaches the slow start threshold (ssthresh), the TCP connection goes into congestion avoidance (CA) phase.

- In CA, the sender will increase its congestion window by 1 MSS when all the segments in the previous cwnd have been Acked.



TCP: detecting, reacting to loss

- loss indicated by timeout:
  - cwnd set to 1 MSS;
  - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
  - dup ACKs indicate network capable of delivering some segments
  - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to 1 (timeout or 3 duplicate acks)

TCP Reno vs Tahoe



TCP throughput

- avg. TCP thruput as function of window size, RTT?
  - ignore slow start, assume there is always data to send
- W: window size (measured in bytes) where loss occurs
  - avg. window size (# in-flight bytes) is ¾ W
  - avg. thruput is 3/4W per RTT

$$\text{avg TCP thruput} = \frac{3}{4}\frac{W}{RTT} \text{ bytes/sec}$$



TCP CUBIC

- Is there a better way than AIMD to "probe" for usable bandwidth?
- Insight/intuition:
  - W_{max}: sending rate at which congestion loss was detected
  - congestion state of bottleneck link probably (?) hasn't changed much
  - after cutting rate/window in half on loss, initially ramp to to W_{max} *faster*, but then approach W_{max} more *slowly*



TCP CUBIC

- K: point in time when TCP window size will reach W_{max}
  - K itself is tuneable
- increase W as a function of the *cube* of the distance between current time and K
  - larger increases when further away from K
  - smaller increases (cautious) when nearer K
- TCP CUBIC default in Linux, most popular TCP for popular Web servers



F'2016 Final: Assuming **TCP Reno** is the protocol experiencing the behavior shown in the figure, answer the following questions.



a. Identify the intervals of time when TCP slow start is operating.

b. Identify the intervals of time when TCP congestion avoidance is operating.

c. After the 16th transmission round, is segment loss detected by a triple duplicate ACK or by a timeout?

d. After the 22nd transmission round, is segment loss detected by a triple duplicate ACK or by a timeout?

e. What is the initial value of *ssthresh* at the first transmission round?

f. What is the value of *ssthresh* at the 18th transmission round?

g. What is the value of *ssthresh* at the 24th transmission round?

h. During what transmission round is the 70th segment sent?

i. Assuming a packet loss is detected after the 26th round by the receipt of a triple duplicate ACK, what will be the values of the congestion window size and of *ssthresh*?

j. Suppose TCP Tahoe is used (instead of TCP Reno), and assume that triple duplicate ACKs are received at the 16th round. What are the *ssthresh* and the congestion window size at the 19th round?

Answers:

a. 1—6 and 23--26

b. 6--16 and 17--22

c. Triple dup. ACK

d. Timeout

e. 32

f. 21 **g. 13** **h. 7th** **i. 4, 4** **j. 21, 4**