ObitTalk User Documentation

Obit: Merx mollis mortibus nuper

Version: 1.5 January 5, 2010

Abstract

This documents describes the ObitTalk interface to AIPS and Obit Software. ObitTalk is a python package which allows running AIPS and Obit tasks and scripts and direct access to astronomical data using Obit. Obit implements multiple data types, currently AIPS and FITS data. Most of the material in this document is also available in the on–line documentation. This document assumes familiarity with python and with AIPS and radio astronomical techniques. The difference with AIPS and POPS usage is explained.

Contents

1.1	Introd	uction						
1.2	Obtaining Software							
1.3	Startin	ng ObitTalk						
	1.3.1	Startup Script						
1.4	Object	z-orientation for POPS users						
	1.4.1	Data objects						
	1.4.2	Tasks						
	1.4.3	$functions = verbs \dots \dots$						
1.5	ObitV	iew Image Display						
1.6	ObitM	less Task Message Display						
1.7		alk Basics						
	1.7.1	Tasks						
	1.7.2	Asynchronous Tasks						
	1.7.3	Disk Numbers and Task Executation						
	1.7.4	Scripts						
	1.7.5	Task logs						
	1.7.6	ObitTalk/Obit routines						
	1.7.7	Messages and error handling						
	1.7.8	Lock and Parameter Files						
	1.7.9	Modifying Data Headers						
	1.7.10	Object parameter lists						
	1.7.11	Accessing UV Data						
1.8		el Processing						
	1.8.1	Multi-threading						
	1.8.2	Cluster Nodes						
1.9	Exam	bles						
	1.9.1	Display AIPS Catalog						
	1.9.2	Create Python Image Object						
	1.9.3	Display Data Header						
	1.9.4	Display an Image						
	1.9.5	Image Pixel Access						
	1.9.6	Run an AIPS task						
	1.9.7	Run an Obit task						
	1.9.8	Table Access						
	1.9.9	Table Row Data						
	1.9.10	Writing to a History						
	1.9.11	Modify Visibility Data						
		Write Quantized FITS image						
		Image Gaussian Fitting						

	1.9.14 Subtract a CLEAN model from UV Data	
1.10	Obit classes and utility packages with python interfaces	39
1.11	OTObit Functions	41
	1.11.1 AIPSHelp	42
	1.11.2 AllDest	42
	1.11.3 AMcat	42
	1.11.4 AUcat	42
	1.11.5 Acat	43
	1.11.6 ClearErr	43
	1.11.7 Fdir	43
	1.11.8 ObitHelp	43
	1.11.9 PrintHistory	44
	1.11.10 ShowErr	44
	1.11.11 alldest	44
	1.11.12 altswitch	44
	1.11.13 clearstat	44
	1.11.14 copyInputs	45
	1.11.15 day2dhms	45
	1.11.16 dhms2day	45
	1.11.17 explain	45
	1.11.18 getFITS	45
	1.11.19 getname	46
	1.11.20 go	46
	1.11.21 imhead	46
	1.11.22 imlod	46
	1.11.23 imstat	47
	1.11.24 imtab	47
	1.11.25 inputs	47
	1.11.26 new Display	47
	1.11.27 setname	48
	1.11.28 set2name	48
	1.11.29 set3name	48
	1.11.30 set4name	48
	1.11.31 setoname	48
	1.11.32 setwindow	49
	1.11.33 tabdest	49
	1.11.34 tget	49
	1.11.35 tput	49
	1.11.36 tvlod	49
	1.11.37 tvstat	50
	1.11.38 uvTabSave	50
	1.11.39 uvlod	50
	1.11.40 uvtab	51
	1.11.41 window	51
	1.11.42 zap	51
1.12	OTObit Data	51
	Remote Usage	52
-	1 13 1 Ohit Talk Server	52

	1.13.2	Remote data directories	52
	1.13.3	ObitScript class	54
1.14	Local	Python Data Interface Classes	59
	1.14.1	Obit python Image class	30
	1.14.2	Obit python UV class	75
	1.14.3	Obit python OTF class	92
	1.14.4	Obit python Table Class)7
1.15	ObitTa	alk Data Classes	12
	1.15.1	AIPSUVData	12
	1.15.2	AIPSImage	14
	1.15.3	FITSUVData	16
	1.15.4	FITSImage	17

1.1 Introduction

ObitTalk is derived from the ParselTongue project at JIVE and provides a scripting and interactive command line interfaces to astronomical data and processing software. In particular, AIPS and FITS data structures as used in the AIPS and Obit software packages are supported as well as AIPS tasks and Obit tasks and other python enabled software.

Obit is intended as an environment optimized for the development and evaluation of new data processing algorithms. As such, it is not a full featured data processing system. However, with the interoperability of Obit and AIPS, the ObitTalk interface to both Obit and AIPS does present the user with a full featured data processing environment for radio interferometry. This utility package facilitates the access to data and images from python as well as various interactive features. The details of the functions in this package are given later. Many of these functions have equivalents in POPS although adapted to python.

AIPS tasks will use the AIPS XAS TV which must be started separately. Obit tasks and ObitTalk use the ObitView image display and/or the ObitMess task message server each of which must also be started independently. If AIPS is not available, ObitTalk still can work using FITS or AIPS files.

ObitTalk can start tasks or scripts either locally or on a remote machine which has an ObitTalk-Server process running. Some remote data access is supported through the AIPSUVData, AIPSImage, FITSUVData and FITSImage classes. Currently other python functions only work interactively locally or remotely using the ObitScript class.

Tasks, scripts and more detailed access to and manipulation of data are available. These are described briefly below and methods of obtaining more detailed descriptions are described.

This document contains both tutorial and reference material. New users should read the first few sections; later sections are mostly for reference.

1.2 Obtaining Software

Obit and related software is available from http://www.cv.nrao.edu/~bcotton/Obit.html. At present there is no system of stable releases so using the anonymous CVS interface is recommended. Obit depends heavily on third party software which is descriped on this page. Support of the Obit package is extremely limited. The components of the Obit/ObitTalk package are:

- Obit
 Basic Obit package and the support for radio interferometry
- ObitSD
 Obit "On The Fly" (OTF) single dish imaging package.
- ObitView Image display used by Obit.
- ObitMess
 Task message display server used by ObitTalk.
- ObitTalk
 Scripting and interactive interface to Obit software.

These software packages come with installation instructions and config scripts to build them.

1.3 Starting ObitTalk

The operation of ObitTalk is influenced by the values of a number of environment variables to specify the locations of directories with python modules, data directories and Obit and AIPS task documentation and executable files. Some of these are set to standard values by the ObitTalk startup script with the exception of the AIPS startup values; other environment variables may need to be set using the script, setup.sh or setup.csh - depending on your shell, which is generated by the Obit installation procedure. If the AIPS shell variables AIPS_ROOT and AIPS_VERSION are previously set by an AIPS startup script no further action needs to be taken to use AIPS. If you wish to use python modules not in one of the standard location, set PYTHONPATH to include the directories. For example, using tcsh and setting PYTHONPATH to use modules in both directories pointed to by myPython1 and myPython2:

% setenv PYTHONPATH "\$myPython1": "\$myPython2"

Custom setups can be implemented using an ObitTalk startup script as discussed below.

If you wish to use the ObitView image display or the ObitMess task message window, you can start them before ObitTalk. If ObitView is in your path:

% ObitView &

will start the display server. If this fails to start the display, see the discussion of ObitView below. ObitMess can be started in the same fashion; see sections 1.5 and 1.6 for more details.

Then, if the script ObitTalk is in your path:

% ObitTalk [scriptname]

should start ObitTalk. Likewise, for asynchronous display of task messages the ObitMess server must also be started.

If the environment variables AIPS_ROOT and AIPS_VERSION are defined, or an .obitrc.py startup script file is found, ObitTalk will make AIPS tasks and data available. If the optional scriptname is given, then the python interpreter will do some simple AIPS initialization and execute the python script "scriptname". If no script is specified then ObitTalk will ask for your AIPS number and do its AIPS initialization (if AIPS is available) and go into an interactive python session. The python prompts are:

>>>

1.3.1 Startup Script

When ObitTalk starts it looks for a startup script named .obitrc.py in either the users home directory or the current working directory (the latter has priority). If found, it is executed as python code. This can be used to define the AIPS and Obit setups. The following startup script fragment shows how to define AIPS tasks and data, Obit tasks and FITS data directories. This can be used to define both local and remote data directories; see section 1.13.2 for a discussion of defining data directories on remote systems. This example startup script can be found in \$OBIT/share/scripts/obitrc.py or /usr/share/obit/scripts/.

```
# Startup script
print "Executing startup script "
import ObitTalkUtil
```

```
AIPS_VERSION = "31DEC06/"
# Define OBIT_EXEC for access to Obit Software
             = None # (def /usr/lib/obit/bin)
OBIT_EXEC
OBIT_EXEC
             = "/export/data_1/users/bcotton/Software.dir/SVN/ObitInstall/ObitSystem/Obit/"
# Define AIPS directories (URL, disk name)
# URL = None for local disks
aipsdirs = [ \
    (None, "/export/data_1/aips/DATA/SMEAGLE_1"), \
    (None, "/export/data_1/aips/DATA/SMEAGLE_2"), \
    (None, "/export/data_1/aips/DATA/SMEAGLE_3"), \
    (None, "/export/data_2/aips/DATA/SMEAGLE_4"), \
    (None, "/export/data_2/aips/DATA/SMEAGLE_5"), \
    (None, "/export/data_2/aips/DATA/SMEAGLE_6"), \
    (None, "/export/data_2/bcotton/SMEAGLE_7")]
# Define FITS directories (URL, disk name)
# URL = None for local disks
fitsdirs = [ \
    (None, "/export/data_1/users/bcotton/Software.dir/AIPS/FITS")]
# setup environment
ObitTalkUtil.SetEnviron(AIPS_ROOT=AIPS_ROOT, AIPS_VERSION=AIPS_VERSION, \
                        OBIT_EXEC=OBIT_EXEC, \
                        aipsdirs=aipsdirs, fitsdirs=fitsdirs)
# List directories
ObitTalkUtil.ListAIPSDirs()
ObitTalkUtil.ListFITSDirs()
# Any other customization goes here
```

1.4 Object-orientation for POPS users

Many of the differences between AIPS/POPS and ObitTalk are because the latter is generally object—oriented. "Object—oriented" in this context means little more than variables are more substantial than the floats and strings and simple arrays of POPS variables (although these also exist). A python (hence ObitTalk) variable is a relatively arbitrary thing and can be a scalar number, string, an array or list of variables or the interface to a dataset such as an image or uv data.

In ObitTalk, the interface to a data set is assigned to a variable and this variable is used to specify operations in a way not very different from INNAME, INCLASS, INDISK, INSEQ ... are used to specify a dataset in POPS. This allows having an arbitrary number of such data objects while avoiding the conflicts in usage of INNAME... in POPS.

The usual object—oriented syntax is that "class methods" (functions which can operate on an object) are invoked like this:

```
>>> object.function(arguments)
```

where "object" is the python object, "function" is the function name and arguments are the additional arguments, the object is implicitly an argument, by convention called "self" in python. In python documentation of function interfaces, "self" appears as the first argument of the function although it is invoked as shown above. As a convenience to POPS users many of these functions are also implemented in the more traditional procedural form, for instance, the following produce the same result:

```
>>> myTask.explain()
or
>>> explain(myTask)
```

1.4.1 Data objects

ObitTalk uses Obit to access the external (i.e. disk) representations of datasets and Obit allows multiple "native" data representations. At present AIPS and FITS (as practiced by AIPS) external representations are supported. (Note, the old style random groups FITS for UV data as written by AIPS task FITTP is NOT supported but the tables format written by FITAB is.) The distinction between external representations is largely hidden except for the process of creating ("instantiation" in computerese) the interface object in which its representation must be specified. For example, to create an interface object to an AIPS image described by the strings Aname (AIPS Name), Aclass (AIPS class), and integers disk (AIPS disk number) and seq (AIPS sequence number):

>>> myImage=Image.newPAImage(''myImage'', Aname, Aclass, disk, seq, exists, err) where exists is True if the image is expected to previously exist and False otherwise. Messages and error conditions are registered in err (defined at ObitTalk startup) and any error messages can be viewed by:

>>> ShowErr(err)

Thereafter the variable myImage is used to access the AIPS image but beyond this point, it is largely irrelevant if the underlying file is an AIPS or FITS (or other) format. For instance, the header can be displayed:

Туре	Pixels	Coord value	at Pixel	Coord incr	Rotat
RASI	N 164	5 55 30.80561	78.00	-5e-05	0.00
DECSI	N 167	39 48 49.1650	87.00	5e-05	0.00
STOKES	3	IPol	1.00	1	0.00
FREQ	1	4.2826e+10	1.00	4e+06	0.00

```
Coordinate equinox 2000.0 Coordinate epoch 2000.00 Observed RA 5 55 30.80561 Observed Dec 39 48 49.1650 no. Comp 200 Clean Beam 0.001 x 0.001 asec, PA 0.0 deg. Rest freq 0 Vel type: LSR, wrt radio Alt ref value 0 wrt pixel 1.00
```

In this sense, objects can have members (other objects) or functions which operate on the object. For instance, the "header" of myImage which is referred to as an ImageDescriptor in ObitTalk is referenced as myImage.Desc and the function which destroys the object as well as its external representation is myImage.Zap() (functions are denoted with parenthess even if there are no arguments. Note the names of variables are arbitrary and "myImage" could as well be "Judy" and are used in error and other informative messages.

Local disk numbers in AIPS data files have the same meaning as in POPS. FITS disk numbers correspond to the directories pointed to by the environment variables \$FITS, \$FITS01, \$FITS02.... FITS disk 0 has a special meaning in which the filename is either relative to the current working directory or a full path to the file. Disk numbers may also be defined on remote computers.

1.4.2 Tasks

An important type of object in ObitTalk is the Task object. This object defines the interface to tasks (parameters, documentation, etc.) Currently, interfaces to AIPS tasks and Obit tasks are supported. Tasks have the same meaning as in POPS and are programs that run independently of the python process and are generally compiled Fortran or C programs. In order to run a task, a task object is first created; at this point AIPS or Obit needs to be specified but after the object is created the type of task is relatively minor. One difference between POPS and python is that the final single quote around a POPS string causes it to be converted to upper case whereas no case conversion is done in python. If you want a AIPS file name or class which contains upper case letters, you must type it that way. Tasks may have output as well as input parameters.

If tasks are run synchronously (using the task_obj.go() syntax), a python RunTime exception will be thrown if the task finishes in other than a normal completion, either detects an uncorrectable problem or aborts. In any mode of running an Obit task, the output parameter "retCode" will have a value of 0 if the task terminated normally without detecting a problem and -1 otherwise. Note: this value will be -999 during the task execution.

Tasks functions

There are a number of common task functions which can be invoked from a task object. These functions also have a short version to simplify typing. For example:

```
>>> myTask.i
is equivalent to
>>> myTask.inputs()
```

These common task functions and the short form are explained in the following:

- inputs (short i)

 This function is to list the current values of the tasks input parameters with a short description.
- outputs (short o)
 This function is to list the current values of the tasks output parameters with a short description.
- help (short h)
 This function is to list the help documentation for the task.
- explain (short e)

 This function is to list any extended documentation for the task.

- go (short g)

 This function starts the task in synchronous mode using the current input parameters.
- abort (short a)

 This function aborts the task. A "Control C" while running a task synchronously has the same effect.
- wait (short w)

 This function suspends operations pending the completion of the task.

Arrays in AIPS Tasks

The main difference between Obit and AIPS tasks as well as a major difference between POPS and python is that array indexing in POPS arrays is one relative whereas in python indexing is zero relative. In other words, the first element of array parm in POPS is parm(1) and in python it is parm[0] (also note the parentheses and square brackets). Since the AIPS documentation describes array values by their one relative indices, using zero relative addressing is a serious potential source of trouble; aparm(3) in POPS is aparm[2] in python. To avoid this problem, ObitTalk adds a extra, unused, element at the beginning of each array to keep the indexing consistent with AIPS documentation. To enforce this scheme, ObitTalk does not allow you to modify the first element of an array. This causes an additional problem, that you cannot set a AIPS task array parameter as:

```
>>> AIPStaskObj.ArrayParm = [1,2,3,4] # Fails
Instead, there are two options, using slicing of the parameter array:
>>> AIPStaskObj.ArrayParm[1:] = [1,2,3,4] # OK
or using the AIPSList class:
>>> AIPStaskObj.ArrayParm = AIPSList([1,2,3,4]) # OK
Multidimensional arrays can be set
>>> AIPStaskObj.Array2DParm = AIPSList([[1,2,3,4],[5,6,7,8]]) # OK
(Note the double square brackets).
```

Arrays in Obit Tasks

Arrays in Obit task array parameters have zero—relative indexing so statements like >>> ObitTaskobj.ArrayParm = [1,2,3,4] # OK work as expected.

Examples

```
An example of creating a task object named im to run AIPS task IMEAN is:

>>> im=AIPSTask("IMEAN")

The parameters of the task can then be set:

>>> im.inname='07030+51396'; im.inclass='PCUBE'; im.indisk=1; im.inseq=2

>>> im.BLC=AIPSList([10,10]); im.TRC=AIPSList([100,100])

The Inputs can be reviewed:

>>> im.i

IMEAN: Task to print the mean, rms and extrema in an image

Adverbs Values Comments
```

dohist	-1.0	<pre>True (1.0) do histogram plot. = 2 => flux on x axis</pre>
userid	0.0	User ID. 0=>current user 32000=>all users
inname	07030+51396	Image name (name)
inclass	PCUBE	Image name (class)
inseq	2.0	Image name (seq. #)
indisk	1.0	Disk drive #
blc	10.0, 10.0, 0.0, 0.0, 0.0, 0.0, 0.0	Bottom left corner of image 0=>entire image
trc	100.0, 100.0, 0.0, 0.0, 0.0, 0.0, 0.0	Top right corner of image 0=>entire image
nboxes	0.0	No. of ranges for histogram.
pixrange	0.0, 0.0	Min and max range for hist.
functype	0.0, 0.0	'LG' => do log10 plot of #
		samples, else linear
pixavg	0.0	Estimate of mean noise value
pixstd	0.0	Estimate of true noise rms < 0 => don't do one
		= 0 => 2-passes to get
docat	1.0	Put true RMS in header
ltype	3.0	Type of labeling: 1 border,
		2 no ticks, 3 - 6 standard,
		7 - 10 only tick labels
		<pre><0 -> no date/time</pre>
outfile		Name of output log file,
dotv	-1.0	No output to file if blank > 0 Do plot on the TV, else
dotv	-1.0	make a plot file
grchan	0.0	Graphics channel 0 => 1.
and the task i		Graphics channel 0 -> 1.
	run:	
>>> im.g	TVT-17 (7 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	
	k IMEAN (release of 31DECO2) begins	
	tial guess for PIXSTD taken from ACTNOISE	
7	ge= 07030+51396 .PCUBE . 2 1 xywind=	
	n and rms found by fitting peak in histog	
	n=-3.1914E-06 Rms= 2.7893E-04 **** from	nistogram
	n and rms found by including all data: n= 1.8295E-05 Rms= 5.2815E-04 JY/BEAM ov	17/9/2 pivola
	x density = 2.0006E-01 Jy. beam area =	-
	imum=-1.5441E-03 at 164 180 1 1	13.33 pixeis
	pos: RA 07 02 04.303 DEC 51 51 23.18	
	pos: IPOL 1400.000 MHZ	
	imum= 4.0180E-02 at 93 159 1 1	
	pos: RA 07 03 36.211 DEC 51 47 11.65	
	pos: IPOL 1400.000 MHZ	
	urns adverbs to AIPS	




Figure 1.1: Screenshot of ObitView window.

IMEAN2: Appears to have ended successfully

IMEAN2: smeagle 31DEC06 TST: Cpu= 0.0 Real= 0

1.4.3 functions = verbs

In addition to tasks, ObitTalk allows POPS verb—like functionality by means of functions using data interface objects. This allows access to headers, data values and unlike POPS, access to much of the high level functionality in the Obit class libraries as well as all of the functionality of python. Numerous operations which in POPS require tasks can be performed by ObitTalk functions. Examples are the conversions between AIPS and FITS types (functions imlod, uvlod, imtab, uvtab). Much of the POPS functionality is implemented in ObitTalk functions.

1.5 ObitView Image Display

While AIPS tasks can use the AIPS TV, the image display used by ObitTalk and Obit tasks is ObitView which is run as an independent program. ObitView can be used as an image browser independently of ObitTalk. To display image myImage on a running ObitView simply:

>>> tvlod(myImage)

A screen shot of the ObitView window is shown in Figure 1.1.

ObitView uses the xmlrpc protocols to communicate between tasks and as such allows communication between different computers by means of the internet. Parts of this protocol involve fixed port numbers which means that only a single ObitView can run on a given computer using a given port number. An attempt to start a second will fail with a "can't bind" message. By default

port 8765 is used but others may be used as well. For instance to use port 8888, start ObitView as follows

% ObitView -port 8888 &

Then ObitTalk can be told to use this port by:

>>> newDisplay(8888)

Obit tasks which use the display have a parameter dispURL which should be set to "http://localhost:8888/RPC2" to use the new display.

If the display is running on a machine on which the data is not visible, use "http://myhost:port/RPC2" where myhost is the network name and port is the port number (usually 8765), Example, to set the display on a task object named task:

>>> task.dispURL="http://canis.cv.nrao.edu:8765/RPC2"

When a remote process displays on an ObitView display, it first copies the image as a compressed FITS image to the display which saves the file in its current working directory as ObitDisplay-FITS.fits.gz. It is useful to start ObitView from a directory where it is both possible and desirable to write these temporary files.

If there is trouble connecting to the display server port (e.g. firewall, address translation) and you have ssh login access between the relevant hosts then it is possible to use ssh port forwarding through the secure connection. From the command shell on the client side (as seen by ObitView) issue:

% ssh -L localport:host:hostport user@host

where localport is the local port number (typically 8765 for ObitView), host is the host on which the ObitView process is running and host port is the port on host that the target ObitView is watching. Then, give the task or ObitTalk on the client end (again as seen by ObitView) a url for itself other than localhost; this will cause the file to be transmitted. For instance if the result of the shell "hostname" command is "smeagle" create an ObitTalk display:

>>> newDisplay(URL="http://smeagle:8765/RPC2")

A tylod should then cause to image to be displayed on the host specified in the ssh command.

ObitView is used by ObitTalk and Obit tasks to display images and perform some interactive operations such as specifying CLEAN boxes. ObitView gives much more control over the display of an image than is possible in the AIPS TV. Once an image is loaded, all of the display controls are available; there is extensive online help.

When an interactive CLEAN box or other window setting session begins, a RequestBox dialog appears with the image displayed overlaid by the current CLEAN window. The radio buttons at the top of this dialog specify what action is to be taken by the calling program when the "OK" button on the bottom is hit and the calling program resumes. These options are:

- Continue
 - Continue with the edited window.
- Abort
 - Shutdown immediately.
- Quit Operation

Terminate the current operation and continue/shutdown in an orderly fashion. For a simple CLEAN, this means stop the clean here and do whatever component restoration/flattening operations were requested. If this command is given in a CLEAN as part of a self-calibration cycle, the current CLEAN is terminated and the self-calibration continues. If this command

is given at the end of a self–calibration cycle then the self-calibration proceeds as if it were converged.

• Turn Off TV

No more displays of the image. Inside a CLEAN this causes no more displays during the current CLEAN but this does not affect displays in some outer operation (e.g. self calibration). If the TV display is turned off in one CLEAN of a self—calibration loop then it is turned off in subsequent CLEANs.

• View Field

If the image is a multi-facet image, then the display (with possible editing of its CLEAN window) of another facet is requested by this option and the facet number (1-relative) entered in the text box labeled "Request field"

If editing of the window displayed is desired, then the "Clear" button deletes the current window (not normally needed) and the "Edit" button puts the display in window editing mode. The message dialog appears with detailed instruction about editing. To exit editing mode hit the "d" or "D" button.

When all editing of the window is complete, the "OK" button causes the calling program to resume with the specified operation and the edited window. The "Cancel" button is like "OK" except that any editing of the window is discarded.

There are several types of boxes used by Obit CLEANing and these are shown in different colors (subject to some user selection). Not all types are always used. The types of CLEAN boxes are:

• "Inner" boxes

These are the traditional CLEAN window boxes specifying the regions in which components may be selected.

• "Inner" unboxes

Specifies regions in which components are NOT to be selected. Used in the autoCenter mode.

• "Outer" boxes

Specifies regions inside of which the autoWindow algorithm is allowed to place Inner boxes. For multi–facet images these generally correspond to the region of the facet to be used when the image is flattened.

The program timeout (length of time ObitView will wait before sending a program the default response, i.e. "Continue") can be set using the "Options" menu. The default timeout is infinite but can be specified to a finite period. The actual minimum is 5 seconds to give time to actually respond interactively and any activity on the editing dialog disables the timeout for that instance.

1.6 ObitMess Task Message Display

The ObitMess server is used in order to display task messages and to provide user input for tasks running asynchronous. Use of this faculity is described in Section 1.7.2. To be used in an ObitTalk session, is must be started independently.

Like ObitView, ObitMess uses the xmlrpc protocols to communicate with ObitTalk and as such allows communication between different computers by means of the internet. Parts of this protocol involve fixed port numbers which means that only a single ObitMess can run on a given computer using a given port number. An attempt to start a second will fail with a "can't bind" message.

By default port 8777 is used but others may be used as well. For instance to use port 8889, start ObitMess as follows

% ObitMess -port 8889 &

Then ObitTalk can be told to use this port when starting a task (myTask) by:

```
>>> tw=go(mytask, URL="http://localhost:8889/RPC2")
```

If there is trouble connecting between ObitTalk and the message server port (e.g. firewall, address translation) and you have ssh login access between the relevant hosts then it is possible to use ssh port forwarding through the secure connection. From the command shell on the client side (as seen by ObitMess) issue:

```
% ssh -L localport:host:hostport user@host
```

where localport is the local port number (typically 8777 for ObitMess), host is the host on which the ObitMess process is running and host port is the port on host that the target ObitMess is watching.

When ObitMess is started a window will appear with the label "Obit task message server" and a Quit button. Additional windows will be produced as needed. Only hit the "Quit" button when you are through with the message server.

1.7 ObitTalk Basics

Obit consists of class libraries and a number of prepackaged tasks similar to AIPS tasks. The classes are implemented in c but there are python bindings to much of the high-level functionality allowing python scripts a high degree of flexibility in accessing and manipulating data. ObitTalk can execute Obit Tasks and functions as well as AIPS tasks but not POPS verbs.

Obit can support multiple physical data formats as long as they are uniquely mapable to a common data model. Above a data access level, the underlying physical data representation is (mostly) hidden. Currently, AIPS and FITS (as practiced by AIPS) are supported. Only FITS format OTF data is supported. AIPS and Obit tasks (mostly) are completely interoperable and may be mixed.

Data objects generally have a "descriptor" member, e.g. each Image has an ImageDesc giving the "header" information. These can be accessed by conversion to and from a python dict (dictionary) in the relevant Descriptor class function. An example of an AIPS image in catalog slot 2 of AIPS disk 2:

```
>>> indisk=2
```

>>> image=getname(2,indisk)

>>> dict = image.Desc.Dict

Or, the function Header will display the contents in a human readable form:

```
>>> image.Header()
```

Note: function imhead(image) is a different path to the same end.

Catalogs in AIPS data directories can be viewed using the functions Acat(), AMcat(), AUcat() for all, image and uv entries; there are numerous optional arguments an explaination of which can be obtained by

```
>>> help(Acat)
```

Acat(disk=None, first=1, last=1000, Aname=None, Aclass=None, Aseq=0, giveList=False)
Catalog listing of AIPS files on disk disk

The class remembers the last disk accessed

```
Strings use AIPS wild cards:
        blank => any
              => one of any character
             => arbitrary string
    If giveList then return list of CNOs
    disk
              = AIPS disk number to list
    first
              = lowest slot number to list
    last
              = highest slot number to list
              = desired AIPS name, using AIPS wildcards, None -> don't check
    Aname
              = desired AIPS class, using AIPS wildcards, None -> don't check
    Aclass
    Aseq
              = desired AIPS sequence, 0=> any
    giveList = If true, return list of CNOs matching
   Directories in FITS "disks" can be displayed by Fdir
>>> help(Fdir)
Fdir(disk=None, dir=None)
    Catalog listing of FITS files on disk disk
    The class remembers the last disk accessed
    disk
              = AIPS disk number to list
              = relative or abs. path of directory, def. = cwd
    dir
                Only used if disk == 0
```

1.7.1 Tasks

Following are lists of tasks available through ObitTalk.

AIPS Tasks

• All AIPS tasks

Obit Tasks

- AutoFlag Radio interferometry data editing software
- Calib Calibrate visibility data (amp & phase)
- CLCal Apply gain solutions to a CL table
- Convol Convolve images
- CubeClip Remove insignificant pixels from 3D cube
- CubeVel Flux weighted velocity image from 3D cube
- Feather Task to feather together images
- FndSou Task to generate a source catalog from an image
- GetJy Determine calibrator flux densities
- **HGeom** Task to make an image consistent with another image
- IDIin Read IDI format UV data

- Imager Radio interferometry imaging task
- IonCal Low frequency Field Based calibration
- IonImage Low frequency Field Based calibration and imaging
- IonMovie Make a movie of ionospheric phase from an SN table
- IonSF Convert Ion. movie to 2D structure func (distance, time)
- Lister Listing of data and calibration tables
- MednFlag Automated UV flagging about a median value
- Ringer Fit rings to SiO maser cubes
- noFQId Set FqIDs in continuum data to 1
- SCMap Interferometry self calibration imaging
- SetJy Modify SoUrce (SU) table
- SNCor Modify visibility gain (AIPS SN) table
- SNFilt Fits for instrumental phases in SN table.
- SNSmo Smooth visibility gain (AIPS SN) table
- Split Split multi-source UV data to single source
- SplitCh Split UV data to multiple channels
- Squint VLA beam squint correcting imaging software
- Squish Compress image cube along third axis
- SubImage Task to copy a sub region of an image
- TabCopy Task to one or more tables
- Template Task to print the mean, rms and extrema in an image
- UVBLAvg Baseline dependent time and/or frequency averaging
- UVCopy Copy UV data
- UVSim Simulate UV data
- UVSub Task to subtract a clean model from a uv data base
- VL2VZ Convert VL (survey catalog) table to VZ table
- VLSSFix Corrects residual geometry in low frequency images

Obit SD Tasks:

• CCBCalib Calibrate GBT CCB OTF format data

- CCBFix Strip bad data from post-lobotomy GBT CCB data
- OTFImage Image OTF format data

To see task documentation either a python task object may first be created and its documentation viewed, or more directly:

```
AIPSHelp("AIPS_task_name")
or
ObitHelp("Obit_task_name")
    To create a task object:
>>> im=AIPSTask("IMEAN")
to create an AIPS task object for task IMEAN, or
>>> fe=ObitTask("Feather")
```

to create an Obit Task object for Feather. Note the names of the objects are arbitrary.

Task parameters can be set using the form object.parameter=value:

```
>>> im.inname="MY FILE"
```

where the parameter names are subject to minimum match and tab completion. Array values are given in square brackets "[]", the usual form for a python list. AIPS array values are indexed 1-relative and Obit arrays 0-relative but this is largely transparent. Note: unlike POPS, ALL strings are case sensitive. There are convenience functions setname, set2name and setoname to copy the name information to a task object for the first and second input objects and the output object:

```
>>> setname (myImage, im)
```

Task parameters can be reviewed using the inputs() function:

```
>>> im.inputs()
or
>>> inputs(im)
```

Note: there is NO minimum match on functions but there is tab completion and you must give the parentheses.

POPS style help can be viewed:

```
>>> im.help()
or
>>> help(im)
or EXPLAIN (if available) by:
>>> im.explain()
or
>>> explain(im)
    Tasks can be run using the go function:
>>> im.go()
```

The above form of the go function runs synchronously and does not return until the task finishes. Log messages will appear in the screen; if logging to a file is desired, set the name of the file (relative or full path) on the task object's logFileMember:

```
>>> im.logFile="myLog.log"
```

After a task is run which generates output values, these can be viewed using the outputs function:




Figure 1.2: Message window for Obit task Template after completion.

>> im.outputs()

and the values can be accessed through the task parameter. The task functions work for both AIPS and Obit tasks. Obit tasks have an output parameter "retCode" which will have a value of -999 until the task completes without detecting a problem After such a completion, the value will be 0.

1.7.2 Asynchronous Tasks

If the ObitMess message server is running and the doWait parameter on the task (or script) object is set to False, it is possible to execute asynchronously:

```
>> window = go(TaskObj)
```

If TaskObj.doWait==True, the task is run synchronously with messages written to the python command window. When a task is run asynchronously (TaskObj.doWait=False), a new ObitMess window with a scrolling text box will appear on the screen; the task messages will appear in this window and the task can be controlled from this window. If the task accepts terminal input, then this text can be entered into the text box below the message box, one line at a time and hitting the Enter key. If the window is expecting user input, the status becomes "Awaiting user input" and the task will suspend until the response is typed into the response line and the Enter key hit. The task status shown at the bottom of this window gives "Running", "Finished" and there are buttons that allow aborting the task, saving the messages in a text file or closing the window.

A screen shot of a message window is shown in Figure 1.2.

The TaskWindow object returned when an asynchrous task is started can be used to suspend python operations until the task completes:

```
>> window.wait()
```

or abort the task:

>> window.abort()

Tasks (or scripts) can also be run asynchronously without a runtime display of the messages. This is done using the MsgBuf argument to the go function which will then execute the task (or

script) and save the messages. In this case the go function returns a TaskMsgBuffer. The task messages can be saved to a logfile or obtained from the TaskMsgBuffer object:

```
>> buffer = go(myTask,MsgBuf=True)
>> buffer.wait()
>> messages = buffer.Messages()
TaskMsgBuffer objects also have an abort function.
```

1.7.3 Disk Numbers and Task Executation

"Data disks" as defined in ObitTalk include the information about the location of the data and ObitTalk will attempt to execute the task where the data defined for it resides. This means that disk numbers cannot be defaulted as then ObitTalk cannot decide where to execute the task or tell if all data reside on the same host. For Obit Tasks operating on FITS files, disk 0 has a special meaning, that the filename given is relative to the current working directory.

1.7.4 Scripts

Scripts can be executed locally directly as a command line argument to ObitTalk or interactively using the ObitScript class. When a script is executed from the command line, there is no prompt for the AIPS user number which must be supplied by the script. To use all features of the Obit python interface, a full initialization of Obit is also needed. An example python fragment in a script given on the command line initializing Obit for user 100 is the following:

```
# Initialize Obit for AIPS user 100
user=100
from OTObit import *
AIPS.AIPS.userno=user
OSystem.PSetAIPSuser (user)
err=0Err.OErr()
```

Scripts can run from an interactive ObitTalk session (started with no arguments) and can be run synchronously or asynchronously and either locally or remotely using the ObitScript class.

1.7.5 Task logs

Messages from running AIPS or Obit tasks will appear in the python window if the task is being run synchronously or in the Task Window if run asynchronously. Each Task window has a button that allows writing the contents into a file; otherwise the logging messages are lost when the window closes. If logging to a file is desired, set the name of the file (relative or full path) on the task object's logFileMember:

```
>>> im.logFile=''myLog.log''
```

This will cause the messages to be logged as the task runs.

1.7.6 ObitTalk/Obit routines

ObitTalk has python binding to the Obit c library that allow access to data and many high level functions. Thus, scripts or interactive use can be controlled by data values in files. (Note: in general functions which manipulate data require that the data be visible locally whereas tasks and the ObitTalk Data classes do not).

Control parameters to Obit (c) routines are largely passed in an InfoList structure (a type of associative array similar to a python dict) but many of the python interface routines take care of this detail and their parameters are passed through a python dictionary. Details are available via the python help command. Use of ObitTalk routines is described below.

1.7.7 Messages and error handling

In ObitTalk error handling and messages use the OErr class. ObitTalk defines a variable err at startup for this purpose. Python functions bound to Obit routines which can generate either messages or error conditions are passed an OErr argument. Messages are generally not shown until explicitly requested, this allows suppressing messages when necessary.

Note: if an error condition is indicated on err and has not been cleared and/or messages displayed, then subsequent functions passed err will simply return without-performing their function.

OErr functions include:

- ShowErr(err) Display any messages and clear any error conditions.
- OErr.PClear(err) Clear Obit error stack err and error condition
- OErr.PIsErr(err) Tells if an error condition exists
- OErr.PLog(err, eCode, message) Add message To Obit Error/message stack err
- OErr.PSet(err) Set Obit error flag
- OErr.printErr(err) Prints Obit error/message stack
- OErr.printErrMsg(err, message='Error') Prints Obit error stack and throws runtime exception on error
- OErr.OErrIsA(err) Tells if object thinks it's a Python ObitErr

Each OErr message has a severity level:

- OErr.Info Informative message
- OErr.Warn Warning message (not an error)
- OErr.Traceback Traceback information from c routines.
- **OErr.MildError** Error (but may not be serious)
- OErr.Error Error message
- OErr.StrongError Serious error
- OErr.Fatal Program cannot continue

1.7.8 Lock and Parameter Files

ObitTalk uses files in /tmp to indicate that resources are allocated and for input and output parameter files for ObitTasks. If problems occur then these files may not be properly disposed of and may need to be deleted by hand. These will have names like Obit_pops_no_pid (e.g. Obit3.5942) indicating an allocated "POPS number" or ObitTask_Input.pops_no (e.g. SCMapInput.1) indicating the input parameter file to an Obit Task (SCMap).

1.7.9 Modifying Data Headers

The Obit/python interface can be used to modify data headers through the Descriptor classes (ImageDesc, UVDesc, etc). The actual memory resident structure is a c structure which can be translated to and from a python dict. The general procedure is

1. Open the object Read/Write

```
>>> help(x.Open)
Open(self, access, err, blc=None, trc=None) method of Image.Image instance
    Open an image persistent (disk) form

self = Python Image object
    access = access READONLY (1), WRITEONLY (2), READWRITE(3)
    err = Python Obit Error/message stack
    blc = if given and a list of integers (min 2) giving
    bottom left corner (1-rel) of subimage
    trc = if given and a list of integers (min 2) giving
    top right corner (1-rel) of subimage
```

- 2. Obtain the descriptor in python dict form using the x.Desc.Dict function.
- 3. Modify the contents of the dict making sure to maintain its structure, format of date strings and data types.
- 4. Update the Descriptor using a x.Dest.Dict = dict type statement
- 5. Update descriptor in external representation using the data object's UpdateDesc function.

6. Close object

An example is shown in the following in which the value of "observer" is changed from "Axxxx" to "my code":

```
>>> x=getname(17)
AIPS Image W3
                       VLA
                              1 1
>>> imhead(x)
AIPS Image Name: W3
                             Class: VLA
                                           seq:
                                                       1 disk:
Object: W3
Observed: 1992-07-17 Telescope: VLA
                                         Created: 2006-09-25
Observer: Axxxx
                    Instrument: VLA
               -0.018 Maximum =
Minimum =
                                         2.452 JY/BEAM
```

```
Type
       Pixels
               Coord value
                              at Pixel
                                          Coord incr
                                                      Rotat
RA---SIN
          320
               2 25 36.44334
                                161.00
                                            -1.72914
                                                      0.00
DEC--SIN
          320 62 6 11.2407
                                161.00
                                            1.72914
                                                      -0.35
                  8.6697e+09
FREQ
           1
                                 1.00
                                         6.05469e+06
                                                      0.00
STOKES
           1
                  IPol
                                 1.00
                                                       0.00
_____
Coordinate equinox 2000.0 Coordinate epoch 2000.00
             2 25 36.44334 Observed Dec 62 6 11.2407
no. Comp
              1
Clean Beam
            6.99984 x
                        6.99984 asec, PA
                                            0.0 deg.
Rest freq
                   O Vel type: Observer, wrt
                                           Optical
Alt ref value
              1.1704e+05 wrt pixel
                                     16.00
Maximum version number of AIPS CC tables is 1
Maximum version number of AIPS HI tables is 1
>>> x.Open(Image.READWRITE,err)
>>> d=x.Desc.Dict
>>> d["observer"]
'Axxxx
>>> d["observer"]="my code"
>>> x.UpdateDesc(err)
>>> x.Close(err)
>>> imhead(x)
AIPS Image Name: W3
                           Class: VLA
                                        seq:
                                                   1 disk:
Object: W3
Observed: 1992-07-17 Telescope: VLA
                                      Created: 2006-09-25
                   Instrument: VLA
Observer: my code
Minimum =
              -0.018 Maximum =
                                      2.452 JY/BEAM
Type
    Pixels
               Coord value at Pixel
                                          Coord incr
                                                      Rotat
                              161.00
                                          -1.72914
RA---SIN
          320
              2 25 36.44334
                                                    0.00
          320 62 6 11.2407
DEC--SIN
                               161.00
                                            1.72914
                                                      -0.35
FREQ
           1
                  8.6697e+09
                                 1.00
                                         6.05469e+06
                                                    0.00
                  IPol
                                 1.00
                                                       0.00
STOKES
           1
_____
Coordinate equinox 2000.0 Coordinate epoch 2000.00
Observed RA
             2 25 36.44334 Observed Dec 62 6 11.2407
no. Comp
              1
Clean Beam
            6.99984 x
                        6.99984 asec, PA
                                            0.0 deg.
                   O Vel type: Observer, wrt Optical
Rest freq
              1.1704e+05 wrt pixel
Alt ref value
Maximum version number of AIPS CC tables is 1
Maximum version number of AIPS HI tables is 1
```

1.7.10 Object parameter lists

It is frequently necessary to pass parameters to Obit functions to control their behavior. These are sometimes explicit arguments of python functions but in other cases they are passed through

the InfoList member of the object. This is particularly used for data selection and calibration parameters. An InfoList is conceptually similar to a python dict structure although less flexible. An InfoList is a list of labeled data items, each item is a scalar or an array of a given data type. The data types supported are int, long (explicitly 32 bit in c), float, double (explicitly 64 bit in c), boolean and strings. More details can be obtained by viewing the help function on the class.

Obit data (and other) objects will have an InfoList member which can generally be accessed through the List member. Conversion to and from python dict structures is by means of the Dict member of the InfoList class. Simple access to entries in an InfoList are through the set and get functions.

```
set(self, name, value, ttype=None) method of InfoList.InfoList instance
   Save a value in an InfoList
   Set an entry in an InfoList, possibly redefining its type and dimension
            = input Python InfoList
   name
             = name of desired entry
            = value to save, either a scalar integer, float, boolean or string
   value
               or a 1D array of one of these types
               Type and dimensionality determined from value unless ttype is set
              = data type, "double", "long", None=>type of value
    ttype
get(self, name) method of InfoList.InfoList instance
   Retrieve a value from an InfoList
   returns python list containing data:
   0 - return code, 0=0K else failed
    1 - name
   2 - type
        int=1, oint=3, long=4, float=9, double=10, string=13, boolean=14
   3 - dimension array as list, e.g. [1,1,1,1,1] for scalar
    4 - data array
   self
             = input Python InfoList
   name
             = name of desired entry
   Usage of these functions as shown in the following in which x is an Obit data object.
>>> x.List.set("fvalue",1.234)
>>> x.List.get("fvalue")
[0, 'fvalue', 9, [1, 1, 1, 1], [1.2339999675750732]]
>>> x.List.set("farray",[1.234,4.567,7.890])
>>> x.List.get("farray")
[0, 'farray', 9, [3, 1, 1, 1], [1.2339999675750732, 4.5669999122619629, 7.8899998664855957]]
>>> x.List.set("darray",[1.234,4.567,7.890],"double")
>>> x.List.get("darray")
[0, 'darray', 10, [3, 1, 1, 1], [1.234, 4.5670000000000002,
    7.889999999999997]]
>>> x.List.Dict
{'DISK': [2, [1, 1, 1, 1], [1]], 'FileType': [2, [1, 1, 1, 1],
```

'fvalue': [9, [1, 1, 1, 1], [1.2339999675750732]],

1.7.11 Accessing UV Data

There are a number of Obit Class functions that perform highlevel operations of uv data sets (UV objects) in the CleanVis, UVImager, and UVSelfCal classes. For details, import these classes and view the help documentation. Visibility data can be read from and written to data objects using the UV ReadVis and WriteVis functions employing objects of the UVVis class.

The selection, calibration and editing of visibility data can be controlled by setting parameters on the InfoList member of the UV data object. Many of these are set using the interface to highlevel class functionality, but for a given parameter which is not part of the class function interface definition, the value can be set directly through the InfoList (see section 1.7.10). A complete list of the UV data selection/calibration/editing parameters follows.

- doCalSelect boolean scalar Select/calibrate/edit data?
- Stokes string (4,1,1)
 Selected output Stokes parameters: ""⇒ no translation,"I ","V ","Q ", "U ", "IQU ",
 "IQUV", "IV ", "RR ", "LL ", "RL ", "LR ", "HALF" = RR,LL, "FULL"=RR,LL,RL,LR.
 [default ""] In the above 'F' can substitute for "formal" 'I' (both RR+LL).
- BChan int scalar
 First spectral channel (1-rel) selected. [def all]
- EChan int scalar Highest spectral channel (1-rel) selected. [def all]
- BIF int scalar First IF (1-rel) selected. [def all]
- EIF int scalar Highest IF (1-rel) selected. [def all]
- doPol int scalar
 > 0 ⇒ calibrate polarization.
- doCalib int scalar $> 0 \Rightarrow$ calibrate, $2 \Rightarrow$ also calibrate Weights
- gainUse int scalar SN/CL table version number, $0 \Rightarrow$ use highest
- flagVer int scalar Flag table version, $0 \Rightarrow$ use highest, $< 0 \Rightarrow$ none

- BLVer int scalar BL table version, $0 > \text{use highest}, < 0 \Rightarrow \text{none}$
- BPVer int scalar Band pass (BP) table version, 0 ⇒use highest
- Subarray int scalar Selected subarray, <= 0 ⇒all [default all]
- dropSubA bool scalar Drop subarray info?
- FreqID int scalar Selected Frequency ID, <= 0 ⇒all [default all]
- timeRange float (2,1,1) Selected timerange in days.
- UVRange float (2,1,1) Selected UV range in kilowavelengths.
- InputAvgTime float scalar Input data averaging time (sec). Used for fringe rate decorrelation correction.
- Sources string (?,?,1)
 Source names selected unless any starts with a '-' in which case all are deselected (with '-' stripped).
- souCode string (4,1,1) Source Cal code desired,
 - '' \Rightarrow any code selected
 - '* ' \Rightarrow any non blank code (calibrators only)
 - '-CAL' \Rightarrow blank codes only (no calibrators)
- Qual int scalar Source qualifier, -1 [default] = any
- Antennas int (?,1,1) a list of selected antenna numbers, if any is negative then the absolute values are used and the specified antennas are deselected.
- corrType int scalar Correlation type, 0=cross corr only, 1=both, 2=auto only.
- passAll bool scalar

 If True, pass along all data when selecting/calibration even if it's all flagged. Data deselected
 by time, source, antenna etc. is not passed.
- doBand int scalar Band pass application type $< 0 \Rightarrow$ none:
 - 1. If = 1 then all the bandpass data for each antenna will be averaged to form a composite bandpass spectrum, this will then be used to correct the data.

- 2. If = 2 the bandpass spectra nearest in time (in a weighted sense) to the uv data point will be used to correct the data.
- 3. If = 3 the bandpass data will be interpolated in time using the solution weights to form a composite bandpass spectrum, this interpolated spectrum will then be used to correct the data.
- 4. If = 4 the bandpass spectra nearest in time (neglecting weights) to the uv data point will be used to correct the data.
- 5. If = 5 the bandpass data will be interpolated in time ignoring weights to form a composite bandpass spectrum, this interpolated spectrum will then be used to correct the data.
- Smooth float (3,1,1) specifies the type of spectral smoothing
 - Smooth[0] = type of smoothing to apply:
 - * $0 \Rightarrow \text{no smoothing}$
 - * $1 \Rightarrow \text{Hanning}$
 - * $2 \Rightarrow Gaussian$
 - $* 3 \Rightarrow Boxcar$
 - * $4 \Rightarrow \text{Sinc (i.e. } \sin(x)/x)$
 - Smooth[1] = the "diameter" of the function, i.e. width between first nulls of Hanning triangle and sinc function, FWHM of Gaussian, width of Boxcar. Defaults (if < 0.1) are 4, 2, 2 and 3 channels for Smooth[0] = 1 4.
 - Smooth[2] = the diameter over which the convolving function has value in channels. Defaults: 1, 3, 1, 4 times Smooth[1] used when
- SubScanTime float scalar

{Optional} if given, this is the desired time (days) of a sub scan. This is used by the selector to suggest a value close to this which will evenly divide the current scan. $0 \Rightarrow$ Use scan average. This is only useful for ReadSelect operations on indexed ObitUVs.

As an example of the data selection usage, to specify that only autocorrelations are desired in UV data object myUV in subsequent operations:

```
>>> myUV.List.set('corrType',2)
```

1.8 Parallel Processing

ObitTalk and Obit tasks implement some basic aspects of parallel processing. These include using multiple cores and/or processors with shared memory in a computer using multi-threading and distributing tasks across nodes of a cluster or workstations on a LAN. These are described in the following sections.

1.8.1 Multi-threading

Many of the more expensive operation in Obit allow using multiple processors/cores which share memory. The technique of multi-threading is used for this. Obit tasks which support multi-threading have a parameter, nThreads, giving the maximum number of threads to allow in a parallel operation. In general, this should not be more than the actual number of processors/corees

available but may be fewer if multiple tasks are to be run using threading or the particular task executation cannot make good use of more than a given number of threads. Threading in functions called from scripts can be invoked as in the following example of allowing two parallel threads.

```
>>> # Allow multiple threads
```

1.8.2 Cluster Nodes

ObitTalk can start parallel, independent processes on multiple nodes of a cluster of workstations on a network; these can be either tasks or ObitScripts. Executation is initiated on the node/workstation on which the data disks are defined. See sections 1.7.3 and 1.13 for more details.

1.9 Examples

The following give simple examples of using ObitTalk.

1.9.1 Display AIPS Catalog

```
The examine your AIPS image catalog on disk 7

>>> AMcat(7)

AIPS Directory listing for disk 7

1 CYG A 74 MHz.MODEL . 1 MA 13-Apr-2004 10:25:32
```

1.9.2 Create Python Image Object

```
To create a python object for the AIPS image in slot 1 and name it "x": >>> x=getname(1,7)
AIPS Image CYG A 74 MHz MODEL 7 1
```

1.9.3 Display Data Header

To view the image header of x:

```
>>> imhead(x)
```

AIPS Image Name: CYG A 74 MHz Class: MODEL seq: 1 disk: 7

Object: 3C405

Observed: 2001-01-19 Telescope: VLA Created: 2001-03-03

Observer: AD441 Instrument: VLA

Minimum = -25 Maximum = 4638.2 JY/BEAM

Туре	Pixels	Coord value	at Pixel	Coord incr	Rotat
RASI	N 512	19 59 28.35406	256.00	-5	0.00
DECSI	N 512	40 44 2.0862	257.00	5	0.32
FREQ	1	7.38e+07	1.00	1.55029e+06	0.00
STOKES	1	IPol	1.00	1	0.00

```
Coordinate equinox 2000.0 Coordinate epoch 2000.00 Observed RA 19 59 28.35406 Observed Dec 40 44 2.0862 no. Comp 697
```

>>> OSystem.PAllowThreads(2) # 2 threads max.

```
Clean Beam 24.9998 x 24.9998 asec, PA 0.0 deg.

Rest freq 0 Vel type: Observer, wrt Optical

Alt ref value 0 wrt pixel 0.00

Maximum version number of AIPS CC tables is 1

Maximum version number of AIPS HI tables is 1
```

1.9.4 Display an Image

To display image x in ObitView:

```
>>> tvlod(x)
```

Note: if ObitTalk thinks something has gone wrong with the image display, the python object may need to be recreated. To recreate the default image display:

>>> newDisplay()

1.9.5 Image Pixel Access

Access to arrays of image pixel values is through the FArray class. Images can be read into or written from FArray objects which can be manipulated in many ways. See help(FArray) for details. In the following the pixel array in an image is read and several operations are performed.

```
>>> # Create image object from AIPS catalog entry
>>> x = Image.newPAImage("Swan", "Cygnus A", "J2000", 1, 1, True, err)
>>> ShowErr(err)
                                # Check for errors
>>> x.Open(Image.READONLY,err) # Open image
>>> x.Read(err)
                                # Read plane
>>> pixels=x.FArray
                                # python FArray object from image
                                # Display Mean of pixel values
>>> pixels.Mean
49.573715209960938
>>> pixels.RMS
                                # Display RMS of pixel values
4.758549690246582
>>> FArray.PSMul(pixels, 5.0)
                                # Scale all pixels by 5
>>> pixels.Mean
                                # Display new mean
247.86857604980469
>>> x.Close(err)
                                # Close image
                                # Display (0-rel) pixel [100,100]
>>> pixels.get(100,100)
8.0
>>> pixels.set(3.1415926,100,100) # set value of pixel [100,100]
>>> pixels.get(100,100)
                                # See new value
3.1415925025939941
```

1.9.6 Run an AIPS task

```
To run AIPS task IMEAN on x and view the values returned:
```

```
dohist
             -1.0
                                                       True (1.0) do histogram plot.
                                                       = 2 \Rightarrow flux on x axis
              0.0
                                                       User ID. 0=>current user
 userid
                                                         32000=>all users
 inname
             CYG A 74 MHz
                                                       Image name (name)
 inclass
             MODEL
                                                       Image name (class)
 inseq
              1.0
                                                       Image name (seq. #)
              7.0
                                                       Disk drive #
 indisk
 blc
             0.0, 0.0, 0.0, 0.0, 0.0, 0.0, 0.0
                                                       Bottom left corner of image
                                                         0=>entire image
             0.0, 0.0, 0.0, 0.0, 0.0, 0.0, 0.0
                                                       Top right corner of image
 trc
                                                         0=>entire image
 nboxes
              0.0
                                                       No. of ranges for histogram.
             0.0, 0.0
                                                       Min and max range for hist.
 pixrange
                                                       'LG' => do log10 plot of #
functype
                                                       samples, else linear
              0.0
                                                       Estimate of mean noise value
 pixavg
 pixstd
              0.0
                                                       Estimate of true noise rms
                                                          < 0 => don't do one
                                                          = 0 => 2-passes to get
              1.0
                                                       Put true RMS in header
 docat
 ltype
              3.0
                                                       Type of labeling: 1 border,
                                                       2 no ticks, 3 - 6 standard,
                                                       7 - 10 only tick labels
                                                       <0 -> no date/time
 outfile
                                                       Name of output log file,
                                                       No output to file if blank
             -1.0
                                                       > 0 Do plot on the TV, else
 dotv
                                                       make a plot file
              0.0
                                                       Graphics channel 0 => 1.
 grchan
                  # Execute task
>>> imean.g
IMEAN1: Task IMEAN (release of 31DECO2) begins
IMEAN1: Image= CYG A 74 MHz.MODEL .
                                                             1 512 512
                                      1 7
                                             xywind=
                                                        1
IMEAN1: Mean and rms found by fitting peak in histogram:
IMEAN1: Mean= 4.8010E-02 Rms= 4.7438E+00 **** from histogram
IMEAN1: Mean and rms found by including all data:
IMEAN1: Mean= 1.8457E+00 Rms= 6.0963E+01 JY/BEAM over
                                                           262144 pixels
IMEAN1: Flux density = 1.7080E+04 Jy.
                                         beam area = 28.33 pixels
IMEAN1: Minimum=-2.5000E+01 at
                                 59 145
                                             1
IMEAN1: Skypos: RA 20 00 55.087 DEC 40 34 45.54
IMEAN1: Maximum= 4.6382E+03 at 252 256
IMEAN1: Skypos: RA 19 59 30.116 DEC 40 43 57.20
IMEAN1: Skypos: IPOL 73.800 MHZ
IMEAN1: returns adverbs to AIPS
IMEAN1: Appears to have ended successfully
IMEAN1: smeagle
                     31DEC06 TST: Cpu=
                                              0.0 Real=
```

>>> imean.	o # Examine outputs	
Adverbs	Values	Comments
pixavg	0.0480099283159	Estimate of mean noise value
pixstd	4.74377298355	Estimate of true noise rms
		< 0 => don't do one
		= 0 => 2-passes to get

1.9.7 Run an Obit task

To run Obit task FndSou on an image, x, containing multiple sources to generate a source catalog (use sf.h for detailed help):

```
>>> sf=ObitTask("FndSou")
>>> setname(x.sf)
>>> sf.outDisk=1
>>> sf.NGauss=20
                     # Max. number of sources (islands)
>>> sf.CutOff=2
                     # Minimum pixel brightness to consider
>>> sf.Retry=1
                    # Try multiple components if residuals exceed this
>>> sf.doMult=True
                    # Allow using multiple Gaussians per source
>>> sf.doWidth=True # Fix width
>>> sf.Parms=[2., 5., 0., 1]
>>> sf.RMSsize=50
                     # Size of window to use to determine image RMS
>>> sf.prtLv=1
                    # Some diagnostic output
                  # Generate VL table
>>> sf.doVL=True
>>> sf.i
                   # Display inputs
FndSou: Task to fit Gaussian models to an image by least-squares
           Values
Adverbs
                                                   Comments
                                                 -----
DataType
            AIPS
                                                  FITS" or "AIPS" type of input
inName
           1400+208
                                                  Image Name (Name) 1
 inClass
            ICLEAN
                                                  Image Name (Class) 1
 inSeq
              1
                                                  Image Name (Seq. #) 1
 inDisk
               1
                                                  Disk drive # 1
 inFITS
                                                  Filename 1 if FITS image
 BLC
         0, 0, 0, 0, 0, 0
                                                  Bottom left corner of image
                                                    0=>entire image
            0, 0, 0, 0, 0, 0
 TRC
                                                  Top right corner of image
                                                    0=>entire image
 doVL
            True
                                                  Convert to VL table?
doPBCorr
                                                  PB correction to VL table?
            False
 asize
            25.0
                                                  antenna diam. for PB corr.
           False
                                                  Catalog residual map?
 doResid
 outName
                                                  Output Image Name
outClass
                                                  Output Image Class
 outSeq
               0
                                                  Output Image Seq. #
 outDisk
                                                  output Disk drive
                                                  Output Filename if FITS image
 outFITS
 NGauss
              20
                                                  Max. Number of islands
```

```
NPass
                1
                                                     Number of passes through resid.
CutOff
              2.0
                                                     Flux cutoff level
Retry
              1.0
                                                     Retry level
                                                     Sort Order of output ' '=RA
 Sort
                                                     Printer disk file to save
 OutPrint
doMult
                                                     >0 => fit multiple peaks
             True
 doWidth
             True
                                                     >0 => fit widths
 Gain
             0.05
                                                     Amp-dependent part of retry
                                                     and warning levels
             2.0, 5.0, 0.0, 1.0, 0.0
 Parms
                                                     Components constraints
                                                      [0] flux < Parms[0]
                                                      [1] widths>Parms[1] cells
                                                      [2] peaks>Parms[2] cells
                                                     outside fitting region
                                                      [3] if >0 don't allow Gauss
                                                     smaller than CLEAN beam
 RMSsize
               50
                                                     Size of region to determine RMS
                                                     Debug print level
prtLv
>>> sf.g
                      # run task
** Message: info
                      : FndSou Begins
** Message: info
                      : Date/Time: 2007-10-11 13:47:51
                      : Found 23 islands pass 1
** Message: info
** Message: info
                      : Successfully fitted 20 components
** Message: info
                      : Attempt to break O islands into multiple
```

: O Attempts to break islands failed

: 0 components rejected for low peak

: 0 fits hit iteration limit

Found 23 islands in 1 passes

** Message: info

** Message: info

** Message: info

Successfully fitted 20 components

Attempt to break 0 islands into multiple

- O Attempts to break islands failed
- O components rejected for low peak
- O fits hit iteration limit

. . .

** Message: info : FndSou Ends

** Message: info : Date/Time: 2007-10-11 13:47:58

1.9.8 Table Access

To create a python object from the VL table created in the previous example and display its contents using the Catalog module utility PVLPrint:

```
>>> import Catalog
>>> vltab=x.NewTable(Table.READONLY, "AIPS VL",1,err)
>>> Catalog.PVLPrint(vltab,x,err)
>>> ShowErr(err) # Display any error messages
```

Listing of fitted VL table values

Fitted sizes in asec, Peak, Flux, IRMS in mJy, residual values relative to Peak Error estimates (asec, mJy, deg) given under value

		RA		De	C	Peak	Flux	IRMS	Fit Maj F	it min
1	13 43	56.1032	22	18	21.163	3666.31	4806.81	90.186	104.886	80.000
		1.80			1.12	93.92	123.13		3.021	1.822
2	13 48	14.5900	24	15	57.461	5508.17	5917.91	87.870	85.951	80.000
		0.82			0.81	89.29	95.93		1.442	1.253
3	13 48	51.8784	26	35	44.011	2742.81	3484.55	77.721	98.355	82.667
		1.60			1.69	81.18	103.13		3.143	2.266
4	13 49	39.0137	21	07	29.926	13631.90	13820.04	112.454	81.104	80.000
		0.41			0.40	112.83	114.39		0.676	0.658
5	13 50	58.3986	15	51	55.507	2479.43	2733.85	91.272	88.209	80.000
		1.94			1.88	93.20	102.76		3.473	

1.9.9 Table Row Data

In the following example, the header of an AIPS CC (Clean Components) table is converted to a dict and printed and the first few rows are read into a python dict structure and printed.

```
>>> imDict=x.Desc.Dict
>>> xinc = abs(imDict['cdelt'][0])  # X Cell spacing
>>> yinc = abs(imDict['cdelt'][1]) # Y Cell spacing
>>> cctab=x.NewTable(Table.READONLY, "AIPS CC", 1, err)
>>> thead=cctab.Desc.Dict
>>> thead
          # Display contents of python dict
{'repeat': [1, 1, 1, 1], 'nrow': 114, 'dim1': [1, 1, 1, 1],
'sortOrder2': 0, 'sortOrder1': 0, 'dim2': [1, 1, 1, 1],
'dim0': [1, 1, 1, 1], 'version': 1, 'lrow': 16, 'Table name': 'AIPS CC',
'FieldName': ['FLUX', 'DELTAX', 'DELTAY', '_status'],
'type': [9, 9, 9, 2], 'FieldUnit': ['JY', 'DEGREES', 'DEGREES', '']}
>>> cctab.Open(Table.READONLY,err)
>>> ShowErr(err) # Display any error messages
                           # Loop over first 4 rows printing
>>> for i in range(1,5):
       row = cctab.ReadRow(i, err)
                                       # Read row i (1-rel)
       xcell = row["DELTAX"][0]/xinc # X position in cells
       ycell = row["DELTAY"][0]/yinc # Y position in cells
       flux = row["FLUX"][0]
                                       # Flux
       print "%5d %5.2f %5.2f %10.2f" % (i,xcell, ycell,flux)
   1 -16.00 6.00
                      1260.95
   2 -47.00 16.00
                       646.20
   3 -16.00 5.00
                       626.66
   4 -46.00 16.00
                       527.65
>>> cctab.Close(err)
                                       # Close table
```

1.9.10 Writing to a History

The following example writes a timestamp and a comment into a image processing history and then prints the history.

```
>>> hi = x.History(Image.READWRITE, err)
                                           # Extract history object from image
>>> r=hi.Open(History.READWRITE, err)
                                           # Open history
>>> hi.TimeStamp(" Start Obit "+ObitSys.pgmName,err) # Timestamp
>>> r=hi.WriteRec(-1, "Some comment", err)
                                           # write comment
>>> r=hi.Close(err)
                                           # Close
>>> OErr.printErrMsg(err, "Error with history")# Error test
>>> PrintHistory(x)
                                           # Show history
History for AIPS: Image: Cygnus A. J2000.1.1
    2 -----
    3 /Begin "HISTORY" information found in fits tape header by IMLOD
 1553
             / 2007-10-11T21:12:11 Start Obit ObitPython
 1554 Some comment
```

1.9.11 Modify Visibility Data

The UV functions ReadVis and WriteVis read and write single visibility records in the form of python UVVis objects which contain the following members:

- u u coordinate (lambda)
- v v coordinate (lambda)
- w w coordinate (lambda)
- time Visibility time in days since 0 h on reference day
- ant1 antenna 1 of baseline
- ant2 antenna 2 of baseline
- vis visibilities as list of tuples (vis, wt) as (complex, float)

The visibilities are in the order defined in the data descriptor:

- jlocs 0-rel axis order: Stokes' parameters
- incs Increment in data: Stokes (in floats)
- **jlocf** 0-rel axis order: Frequency
- incf Increment in data: Frequency (in floats)
- **jlocif** 0-rel axis order: IF
- incif Increment in data: IF (in floats)

The following example uses the UVVis class to read the records in a UV data file, multiply the complex visibilities by 2.0 and the weights by 0.5. To specify data selection, calibration and editing to be applied to data as it is read, see section 1.7.11.

```
# Input AIPS file
x = UV.newPAUV("inUV", "RX_Tau", "IF2", 1, 1, True, err, nvis=1)
x.Open(UV.READONLY, err)
OErr.printErrMsg(err, "Error with input image")
# Output AIPS file
y = UV.newPAUV("outUV", "RX_Tau", "Copy", 1, 1, False, err, nvis=1)
UV.PClone(x, y, err)
y.Open(UV.WRITEONLY, err)
OErr.printErrMsg(err, "Error with output image")
# Get information about data
                                      # Number of visibilities
nvis = x.Desc.Dict["nvis"]
jstok = x.Desc.Dict["jlocs"]
                                      # Order in data of Stokes
nstok = x.Desc.Dict["inaxes"][jstok] # Number of Stokes (polarizations)
stokinc = x.Desc.Dict["incs"]/3
                                      # Increment between Stokes in vis
jfreq = x.Desc.Dict["jlocf"]
                                      # Order in data of Frequency
nfreq = x.Desc.Dict["inaxes"][jfreq] # Number of Frequencies
freqinc = x.Desc.Dict["incf"]/3
                                      # Increment between channels in vis
     = x.Desc.Dict["jlocif"]
                                      # Order in data of IF
jif
nif = x.Desc.Dict["inaxes"][jif] # Number of IFs
ifinc = x.Desc.Dict["incif"]/3
                                     # Increment between IFs in vis
# Loop over input file
for i in range(0, nvis):
   # read to UVVis
    v = x.ReadVis(err)
   vlist = v.vis # array of tuples (complex vis, float weight)
   # Multiply each vis by two, multiply weight by 0.5
   # Loop over IF
   for iif in range (0, nif):
        # Loop over Frequency channel
        for ifreq in range (0, nfreq):
            # Loop over Stokes
            for istok in range (0, nstok):
                indx = istok*stokinc + ifreq*freqinc + iif*ifinc
                # Extract visibility tuple
                tup = vlist[indx]
                vlist[indx] = (2.0*tup[0],tup[1]*0.5) # multiply/replace
   # Write data to output
   y.WriteVis(v, err)
    OErr.printErrMsg(err, "Error copying file")
# Close files
x.Close(err)
y.Close(err)
OErr.printErrMsg(err, "Error closing file")
```

1.9.12 Write Quantized FITS image

The following example reads an AIPS image and writes a integerized FITS image with the pixel values truncated at a set fraction of the RMS "noise" in the image. This operation creates an image which is more compressible but with a controlled loss of precision. Note: in practice is is better to use the ObitTalk function imtab as it is simpler to use and will also copy tables; this example is given to show how to access images in ObitTalk.

```
# Specify input and output
inDisk
         = "INPUT IMAGE"
Aname
Aclass
         = "CLASS"
Aseq
        = 1
outDisk = 1
outFile = "Quantized.fits"
# Create Images
          = Image.newPAImage("Input image", Aname, Aclass, inDisk, Aseq, True, err)
# Note: inImage can also be created using getname(cno,disk)
outImage = Image.newPFImage("Output image",
                                               outFile, outDisk, False, err)
Image.PClone(inImage, outImage, err)
                                       # Same structure etc.
OErr.printErrMsg(err, "Error initializing")
# Fraction of RMS
fract = 0.25
# Copy to quantized integer image with history
inHistory = History.History("history", inImage.List, err)
Image.PCopyQuantizeFITS (inImage, outImage, err, fract=fract, inHistory=inHistory)
OErr.printErrMsg(err, "Writing to FITS")
```

1.9.13 Image Gaussian Fitting

Fitting of Gaussians to an image over a large area can be performed by task FndSou and over more limited areas using the ImageFit class function Fit. This function takes an image and a FitRegion which defines the fitting area of the image and the initial set of values defining the Gaussians to be fit. Image class functions TVFit and GaussFit provide a simplified interface to the fitting routines.

The following is an example of an interactive model fitting session, a screen shot of the ObitView window after the fitting region and model are specified is shown in figure 1.3

```
>>> # Define image
>>> x=Image.newPAImage("image","3C84","PennAr",1,1,True,err)
>>> # Interactively set fitting region followed by fitting
>>> fr = x.TVFit(x,disp,err)
```

The image will be loaded to the display, hit the "edit" button on the RequestBox, then specify the region to fit on the display with a rectangular box, followed by circular boxes to mark Gaussian components initial locations and initial sizes; instructions are given in the ObitView Message Box. When done, hit "d" and then "OK" on the bottom of the RequestBox. Example results:

```
Model fit for 3C84
RA 3 19 47.73316 ( 0.518 asec), pixel 131.441 ( 0.259)
```




Figure 1.3: Screenshot of ObitView window specifying fitting region with model.

```
Dec
      41 30 36.7370 (
                         0.594 asec), pixel 116.772 (
                                                           0.297)
Peak Flux density
                    0.0109 (0.000725) JY/BEAM
Integrated Flux density
                          0.0164 (0.00109) Jy
Fitted Major axis
                    15.148 (
                                1.13) asec,
                                                7.574 (
                                                           0.33) pixels
                    11.228 (
Fitted Minor axis
                               0.661) asec,
                                                5.614 (
                                                           0.33) pixels
Fitted Position angle -36.995 (
                                    7.84) deg
Deconvolved model
Deconvolved Major axis
                           10.8 (
                                     1.12) asec,
                                                     5.385 (
                                                               0.814) pixels
                           3.55 (
Deconvolved Minor axis
                                     1.63) asec,
                                                     1.776 (
                                                               0.814) pixels
                             143.01 (
                                         5.49) deg
Deconvolved Position angle
```

Image class function GaussFit can be used for noninteractive fitting. The defaults are generally adequate for a single source near the reference pixel. Both TVFit and GaussFit return a FitRegion object.

```
Additional functionality can be obtained by using ImageFit functions directly, first >>> import ImageFit, FitRegion, FitModel
The ImageFit.Fit function is described in the following:
```

```
Resultant model left in FitRegion reg
inImageFit = Python ImageFit object
image = ObitImage to be fitted
reg = Fit region defining what is to be fitted and initial guess
err = Python Obit Error/message stack
input = input parameter dictionary
```

```
Input dictionary entries:
  fitImage Image to be fitted
  fitRegion FitRegion to be fitted
 MaxIter int Maximum number of iterations [def. 10 per fitted parameter]
           int Message level, 0=>none [def 0]
  PosGuard float Distance (cells) from edge to allow center [def no bound]
  FluxLow float Lower bounds on Flux density [def no bound]
           float Major axis upper bound (cells) [def no bound]
  GMaiUp
  GMajLow float Major axis lower bound (cells) [def no bound]
           float Minor axis upper bound (cells) [def no bound]
  GMinUp
  GMinLow float Minor axis lower bound (cells) [def no bound]
   A FitRegion can be created interactively using the image viewer and FitRegion.PSetup():
PSetup(inImage, disp, err)
   Interactive initial definition of fitting region
  Interactively allows the user to set the region of the image
  to be fitted and the initial model.
  The fitting region is first specified with a rectangular window
  and then the initial models to be fitted with circular windows.
  Returns FitRegion, leaves image pixel array on inImage
    image = image to be fitted
    disp
           = image display to use
           = Obit Error/message stack
    err
   Fitted models can then be viewed on the screen or written to a file by FitRegion.Print()
 Print(self, ImDesc, file=None)
      Display human readable contents
               = object with Model to display
      self
      ImDesc
               = Image Descriptor with Beam, etc.
      file
               = if present, the name of a file into which to write
                 the information rather than displaying it on the screen
or, can be accessed in python using the array of FitModel objects in the FitRegion.
```

1.9.14 Subtract a CLEAN model from UV Data

The following python script fragment subtracts the Fourier transform of a CLEAN model, multiplied by 0.5 from one uv data set and writes another. Several steps are necessary to create a SkyModel from an image mosaic containing a single image. Then, control parameters are entered into the input dict for SkyModel.PSubUV which is used to perform the operation. The input and output data are all FITS files with names inFile, inModel, outFile on FITS "disks" inDisk and outDisk. Note: this operation is also performed by task UVSub.

```
import SkyModel, ImageMosaic
# Set data
inData = UV.newPFUV("Input uv data", inFile, inDisk, True, err)
inImage = Image.newPFImage("Input image",inModel, inDisk, True, err)
outData = UV.newPFUV("Output uv data", outFile, outDisk, False, err)
```

```
OErr.printErrMsg(err, "Error initializing")
# Make Image Mosaic with a single image
mosaic = ImageMosaic.newObit("Mosaic", 1, err)
OErr.printErrMsg(err, "Error making mosaic")
# Add image to mosaic
ImageMosaic.PSetImage(mosaic, 0, inImage)
# Make SkyModel from mosaic
model = SkyModel.PCreate("SkyModel", mosaic)
OErr.printErrMsg(err, "Error making SkyModel")
# Control parameters to input dict, most defaulted
Input = SkyModel.UVSubInput
Input['InData']
                    = inData
                               # Input uv data
Input['SkyModel']
                               # SkyModel
                    = model
Input['OutData']
                   = outData # output uv data
Input['doCalSelect'] = False
                               # No calibration or data selection
Input['Stokes']
                   = ', '
                               # No conversion of Stokes
                    = 0.5
                               # Multiply model FT by 0.5
Input['Factor']
Input['Mode']
                               # Fastest FT type (DFT or Grid)
                    = 0
Input['Type']
                    = 0
                               # Use CLEAN model from CC table
Input['CCVer']
                              # Use CC table 2 (array of 1 per image)
                    = [2]
# Subtract Fourier transform of sky model from inData, write outData
SkyModel.PSubUV(err, Input)
OErr.printErrMsg(err, "Error subtracting")
```

1.10 Obit classes and utility packages with python interfaces

There are a number of Obit functions with high level python interfaces. To see more details import and view the help for each:

```
>>> import History
>>> help(History)
```

Obit/AIPS/Radio Interferometry/Image classes and utilities

- AIPSDir AIPS directory class
- CArray Complex array class
- Catalog Source catalog class
- CleanImage Image CLEAN
- CleanVis Visibility based CLEAN
- ConvUtil Image convolution utilities
- FArray float array class

- FArrayUtil FArray utilities
- FeatherUtil Image feathering utilities
- FFT Fast Fourier Transform class
- FInterpolate Float array interpolator
- FITSDir FITS directory routines
- FitModel Source fitting model
- FitRegion Source fitting region
- **History** History class
- ImageDesc Image Descriptor (header)
- ImageMosaic Image Mosaic class
- Image Image class
- ImageFit Image fitting class
- ImageUtil Image utilities
- InfoList Obit associative array for control info
- IonCal Ionospheric calibration
- MergeCal Partial fix for screwed up VLBA cal. data
- MosaicUtil Image mosaicing utilities
- OData Base Data (image, UV, OTF) class
- ODisplay Interface to ObitView display
- **OErr** Obit message/error class
- **OPlot** Ploting interface
- OSystem Obit System class
- OWindow (CLEAN) image window class
- SkyGeom Celestial geometry
- SkyModel Sky model class
- SpectrumFit Spectrum fitting class
- TableDesc Table descriptor (header) class
- TableList Table list for data object (Image, UVData, OTF)
- Table Class

- Table Util Table utilities
- TaskWindow Task message window class
- TimeFilter Time filtering class
- UVDesc UV data descriptor (header)
- UVGSolve UV gain solutions
- UVImager UV data imager class
- UV UV data class
- UVSelfCal UV Self calibration class
- UVSoln2Cal UV SN to CL table routines.
- UVVis UV visibility access class
- VLACal VLA calibration utilities
- ZernikeUtil Zernike polynomial utilities

Single dish/OTF imaging classes and utilities. These require the ObitSD python directory in the PYTHONPATH.

- CCBUtil GBT CCB utility package
- CleanOTF Single dish (Hogbom) CLEAN
- CleanOTFRec Single dish record based CLEAN
- GBTDCROTF Convert GBD DCR data to OTF format
- GBTUtil Utilities for GBT data
- OTFDesc OTF Descriptor
- OTFGetAtmCor OTF Atmospheric correction utilities
- OTFGetSoln OTF calibration solution utilities
- **OTF** OTF ("On the Fly") data
- OTFRec OTF record access class
- OTFSoln2Cal Utilities to convert OTF solution to calibration tables
- OTFUtil OTF Utilities
- PARUtil Utilities for GBT Mustang (Penn Array) data

1.11 OTObit Functions

The following are functions available from OTObit which are all automatically imported when ObitTalk in started.

1.11.1 AIPSHelp

```
AIPSHelp(Task)
   Give Help for AIPS task Task
           = AIPSTask name to give (e.g. "IMEAN")
   Task
1.11.2 AllDest
AllDest(disk=None, Atype=' ', Aname='
                                               ', Aclass=' ', Aseq=0)
   Delete AIPS files matching a pattern
   Strings use AIPS wild cards:
       blank => any
       , ? ,
            => one of any character
            => arbitrary string
             = AIPS disk number, 0=>all
   disk
             = AIPS entry type, 'MA' or 'UV'; ' => all
   Atype
             = desired AIPS name, using AIPS wildcards, None -> don't check
   Aname
             = desired AIPS class, using AIPS wildcards, None -> don't check
             = desired AIPS sequence, 0=> any
   Aseq
1.11.3 AMcat
AMcat(disk=1, first=1, last=1000)
   Catalog listing of AIPS Image files on disk disk
   Strings use AIPS wild cards:
       blank => any
            => one of any character
       "*" => arbitrary string
   If giveList then return list of CNOs
            = AIPS disk number to list
   disk
   first
            = lowest slot number to list
             = highest slot number to list
   last
   Aname
            = desired name, using AIPS wildcards, None -> don't check
   Aclass = desired class, using AIPS wildcards, None -> don't check
          = desired sequence, 0=> any
   Aseq
   giveList = If true, return list of CNOs matching
1.11.4 AUcat
AUcat(disk=1, first=1, last=1000)
   Catalog listing of AIPS UV data files on disk disk
   Strings use AIPS wild cards:
       blank => any
       '?' => one of any character
        "*" => arbitrary string
```

If giveList then return list of CNOs
disk = AIPS disk number to list
first = lowest slot number to list
last = highest slot number to list
Aname = AIPS desired name, using AIPS wildcards, None -> don't check
Aclass = AIPS desired class, using AIPS wildcards, None -> don't check
Aseq = AIPS desired sequence, 0=> any
giveList = If true, return list of CNOs matching

1.11.5 Acat

Acat(disk=1, first=1, last=1000) Catalog listing of AIPS files on disk disk The class remembers the last disk accessed Strings use AIPS wild cards: blank => any ,,, => one of any character => arbitrary string If giveList then return list of CNOs disk = AIPS disk number to list first = lowest slot number to list last = highest slot number to list = desired AIPS name, using AIPS wildcards, None -> don't check Aname Aclass = desired AIPS class, using AIPS wildcards, None -> don't check = desired AIPS sequence, 0=> any giveList = If true, return list of CNOs matching

1.11.6 ClearErr

ClearErr(err=<C OErr instance>)
Print any errors and clear stack

err = Python Obit Error/message stack, default is OTObit version

1.11.7 Fdir

Fdir(disk=None, dir=None)

Catalog listing of FITS files on disk disk

The class remembers the last disk accessed disk = AIPS disk number to list dir = relative or abs. path of directory, def. = cwd

Only used if disk == 0

1.11.8 ObitHelp

ObitHelp(Task)
Give Help for OBIT task Task

```
Task = ObitTask name to give (e.g. "Feather")
```

1.11.9 PrintHistory

```
PrintHistory(ObitObj, hiStart=1, hiEnd=1000000, file=None)
Display history log or write to file
```

Reads selected history records and displays with "more"

ObitObj = Python Obit object with history
err = Python Obit Error/message stack

hiStart = if given the first (1-rel) history record hiEnd = if given the highest (1-rel) history record

file = if present, the name of a file into which to write the history rather than displaying it on the screen

1.11.10 ShowErr

```
ShowErr(err=<C OErr instance>)
    Print any errors and clear stack
```

err = Python Obit Error/message stack, default of OTObit version

1.11.11 alldest

```
alldest(Aname='.*', Aclass='.*', Atype='.?', Adisk=0, Aseq=0, test=False)
   Delete AIPS files matching a pattern
```

Uses regular expression matching for strings

Note: "+" values are escaped

Clears any status before deleting

Aname = AIPS file name , " " => any
Aclass = AIPS class name, " " => any

Atype = 'MA', 'UV' or any

Adisk = AIPS disk number, 0=> any

Aseq = AIPS sequence number; 0=> any

test = if true only list and not delete

1.11.12 altswitch

altswitch(inImage)

Switch frequency and velocity

Algorithm lifted from AIPS AU7.FOR

inImage = Python Image object, created with getname, getFITS

1.11.13 clearstat

clearstat(o, code=4)

Clear status of AIPS catalog entry

1.11.14 copyInputs

copyInputs(inTask, outTask)

Copy values from one task object to another

Copies parameter values from inTask to outTask which are in both the inTask and outTask $_{\rm input_list.}$

Need not be the same task.

inTask = Task object to copy from
outTask = Task object to copy to

1.11.15 day2dhms

```
day2dhms(tim)
```

convert a time in days to a string as d/hh:mm:ss.s

Returns time as string: "d/hh:mm:ss.s" tim time in days

1.11.16 dhms2day

dhms2day(st)

convert a time string in d/hh:mm:ss.s to days

Returns time in days st time string as "d/hh:mm:ss.s"

1.11.17 explain

explain(TaskObj)

Give explanation for a task if available

TaskObj = Task object whose inputs to list

1.11.18 getFITS

getFITS(file, disk=1, Ftype='Image')
 Return Obit object for FITS file in file on disk

file = FITS file name
disk = FITS disk number

Ftype = FITS data type: 'Image', 'UV'

1.11.19 getname

getname(cno, disk=1)

Return Obit object for AIPS file in cno on disk

cno = AIPS catalog slot number

disk = AIPS disk number

1.11.20 go

go(TaskObj, MsgBuf=False, URL="http://localhost:8777/RPC2")
 Execute task

Returns TaskWindow object if run asynchronously (doWait=True) or the task message log if run synchronously (doWait=False)

The wait() function on the TaskWindow will hang until the task finishes

TaskObj = Task object to execute

If doWait member is true run synchronously,

else run with messages in a separate Message window

MsgBuf = if true and TaskObj.doWait=False run asynchronously

 $using \ a \ Task {\tt MsgBuffer}$

URL = URL of ObitMess message server if MsgBuf=False

1.11.21 imhead

imhead(ObitObj)

List header

ObitObj = Obit or ObitTalk data object

1.11.22 imlod

imlod(filename, inDisk, Aname, Aclass, Adisk, Aseq, err)
Load FITS Image data to AIPS

Read a ImageTAB FITS Image data file and write an AIPS data set

filename = name of FITS file
inDisk = FITS directory number
Aname = AIPS name of file
Aclass = AIPS class of file

Aseq = AIPS sequence number of file

Adisk = FITS directory number

err = Python Obit Error/message stack

returns AIPS Image data object

1.11.23 imstat

```
imstat(inImage, blc=[1, 1, 1, 1, 1], trc=[0, 0, 0, 0, 0])
    Get statistics in a specified region of an image plane
   Returns dictionary with statistics of selected region with entries:
                = Mean value
       RMSHist = RMS value from a histogram analysis
       RMS
               = Simple RMS value
               = maximum value
       Max
       MaxPos = pixel of maximum value
              = minimum value
       Min
       MinPos = pixel of minimum value
             = Python Image object, created with getname, getFITS
1.11.24 imtab
imtab(inImage, filename, outDisk, err, fract=None, quant=None,
        exclude=['AIPS HI', 'AIPS PL', 'AIPS SL'], include=['AIPS CC'],
       headHi=False))
   Write Image data as FITS file
   Write a Image data set as a integer FITAB format file
   History written to header
    inImage
              = Image data to copy
   filename = name of FITS file
    inDisk
            = FITS directory number
    err
              = Python Obit Error/message stack
   fract
              = Fraction of RMS to quantize
              = quantization level in image units, has precedence over fract
   quant
                None or <= 0 => use fract.
    exclude
              = List of table types NOT to copy
                NB: "AIPS HI" isn't really a table and gets copied anyway
    include
               = List of table types to copy
               = if True move history to header, else leave in History table
   headHi
   returns FITS Image data object
1.11.25 inputs
inputs(TaskObj)
   List task inputs
               = Task object whose inputs to list
    TaskObj
```

1.11.26 newDisplay

newDisplay(port=8765, URL=None)
Recreate display to another display server

```
port = port number on local machine
  URL = Full URL (e.g. http://localhost:8765/RPC2)

1.11.27 setname
setname(inn, out)
```

Supports both FITS and AIPS

Copies Data type and file name, disk, class etc

Copy file definition from inn to out as in...

inn = Obit data object, created with getname, getFITS

out = ObitTask object,

1.11.28 set2name

set2name(in2, out)

Copy file definition from in2 to out as in2...

Supports both FITS and AIPS

Copies Data type and file name, disk, class etc

in2 = Obit data object, created with getname, getFITS

out = ObitTask object,

1.11.29 set3name

set3name(in3, out)

Copy file definition from in3 to out as in3...

Supports both FITS and AIPS

Copies Data type and file name, disk, class etc

in3 = Obit data object, created with getname, getFITS

out = ObitTask object,

1.11.30 set4name

set4name(in4, out)

Copy file definition from in4 to out as in4...

Supports both FITS and AIPS

Copies Data type and file name, disk, class etc

in4 = Obit data object, created with getname, getFITS

out = ObitTask object,

1.11.31 setoname

setoname(inn, out)

Copy file definition from inn to out as outdisk...

Supports both FITS and AIPS

Copies Data type and file name, disk, class etc

```
inn = Obit data object, created with getname, getFITS
    out = ObitTask object,
1.11.32 setwindow
setwindow(w, out)
   Set BLC and TRC members on out from OWindow w
   Uses first window in first field on w which must be a rectangle
   This may be set interactively using tvlod
        = OWindow object
   out = ObitTask object, BLC and TRC members [0] and [1] are modified
1.11.33 tabdest
tabdest(ObitObj, tabType, tabVer)
       Delete a table
       Deletes associated tables
       ObitObj = Python Obit object with tables
                = Table type, NB AIPS tables names start with "AIPS"
       tabType
                   e.g. "AIPS CC"
       tabVer
                 = table version, 0=> highest, <0 => all
1.11.34 tget
tget(inn, file=None)
   Restore task object from disk
   Restore values in task object
         = task name, or a task object of the desired type
            in the latter case, the input object will NOT be modified
   file = optional file name, the default is <task_name>.pickle
            in the current working directory
1.11.35 tput
tput(to, file=None)
   save task object
   save values in task object
         = task object to save
   file = optional file name, the default is <task_name>.pickle
```

1.11.36 tvlod

tvlod(image, window=None)
 display image

in the current working directory

```
image = Obit Image, created with getname, getFITS
    window = Optional window for image to edit
1.11.37 tvstat
tvstat(inImage)
   Set region in an image using the display and tell mean, rms
   Returns dictionary with statistics of selected region with entries:
               = Mean value
       RMSHist = RMS value from a histogram analysis
               = Simple RMS value
       RMS
               = maximum value
       Max
       MaxPos = pixel of maximum value
             = minimum value
       MinPos = pixel of minimum value
    inImage = Python Image object, created with getname, getFITS
1.11.38 uvTabSave
  uvTabSave(inUV, filename, outDisk, err, \
      exclude=['AIPS HI', 'AIPS_AN', 'AIPS FQ', 'AIPS PL', 'AIPS SL'],\
      include=[])
       Write UV data tables (but not data) to a FITS file
       Write tables associated with UV data set as a FITAB format file
       History written to header
       inUV
                  = UV data to copy
       filename = name of FITS file
       inDisk = FITS directory number
                  = Python Obit Error/message stack
       err
       exclude
                  = List of table types NOT to copy
                    NB: "AIPS HI" isn't really a table and gets copied anyway
                  = List of table types to copy (FQ, AN always done )
       returns FITS UV data object
1.11.39 uvlod
uvlod(filename, inDisk, Aname, Aclass, Adisk, Aseq, err)
   Load FITS UV data to AIPS
   Read a UVTAB FITS UV data file and write an AIPS data set
   filename = name of FITS file
   inDisk
            = FITS directory number
   Aname
            = AIPS name of file
   Aclass
             = AIPS class of file
   Aseq
             = AIPS sequence number of file
            = FITS directory number
    Adisk
```

= Python Obit Error/message stack

err

1.11.40 uvtab

```
uvtab(inUV, filename, outDisk, err, compress=False,
       exclude=['AIPS HI', 'AIPS AN', 'AIPS FQ', 'AIPS SL', 'AIPS PL'],
       include=[], headHi=False)
    Write UV data as FITS file
   Write a UV data set as a FITAB format file
   History written to header
    inUV
               = UV data to copy
   filename = name of FITS file
    inDisk
               = FITS directory number
               = Python Obit Error/message stack
              = List of table types NOT to copy
   exclude
                 NB: "AIPS HI" isn't really a table and gets copied anyway
               = List of table types to copy (FQ, AN always done )
    include
                 Exclude has presidence over include
               = if True move history to header, else leave in History table
   headHi
   returns FITS UV data object
```

1.11.41 window

window(image)

```
Make a window object for an image

Returns OWindow object
image = Obit image object

1.11.42 zap

zap(o)
Zap object o

Delete Image, UV or OTF data files
Removes all external components (files)
o = Obit Data object to delete
```

1.12 OTObit Data

The OTObit environment contains a number of useful pieces of information concerning your current session. These should all be imported into the scripting or interactive environment at startup.

```
AIPSdisks = ['/usr/AIPS/DATA/GOLLUM_1', '/usr/AIPS/DATA/GOLLUM_2', '/u...
Adisk = 1
FITSdisks = ['/usr/AIPS/FITS']
Fdisk = 1
ObitSys = <C OSystem instance>
```

```
dir = None
disp = <C ODisplay instance> ObitView
dsk = 'DA10'
err = <C OErr instance>
nAIPS = 8
nFITS = 1
popsno = 1
userno = 103
```

1.13 Remote Usage

In order to run tasks or scripts or access data on a remote machine, an ObitTalkServer must be running on the remote host and the client ObitTalk must be told the URL of the remote server and the list of directory names on the remote host.

1.13.1 ObitTalkServer

The target host machine must have installed AIPS and Obit systems. Remote access is provided through a ObitTalkServer process which can be started once the initial AIPS processes are run to define the standard AIPS directories. Note: this does NOT include the AIPS data directories \$DA01 The default is for ObitTalkServer to watch port 8000 although this can be modified in the ObitTalkServer script. The xmlrpc URL of this server process is then 'http://mymachine.org:8000/RPC2' where mymachine.org is a suitable network name for the host. The host must allow client access to port 8000.

```
An example of creating a remote AIPSImage is:

>>> ai=AIPSImage("3C43", "PCube", disk, 1)

This can then be displayed on a running ObitView by either:

>>> tvlod(ai)

to display of the current ObitView display, or

>>> ai.display(url)
```

where url is the optional url of an ObitView server. Note: if url is not specified and the local ObitView server is the default, the default server display will be used; this is likely to seldom be the desired effect so you should use the second form and give the url of you ObitView as seen by the remote server.

1.13.2 Remote data directories

The set of AIPS data directories on a machine depends on a number of factors, login name, user number, system configuration files as well as command line arguments. Due to this complexity, the current configuration of ObitTalk does not allow an automated discovery of these directories and they must be explicitly supplied. After the ObitTalk startup has initialized the local data directories, remote AIPS directories can be defined:

```
>>> url = 'http://mymachine.org:8000/RPC2'
>>> dirname = '/export/data_1/aips/DATA/MINE_1'
>>> disk = len(AIPS.AIPS.disks)
>>> AIPS.AIPS.disks.append(AIPS.AIPSDisk(url, disk, dirname))
```

This directory will then be accessable as disk disk. Note: to define an additional local AIPS disk, set url to None. The function AIPSCat(disk) will give a directory listing of this directory, tasks and the AIPSUVData and AIPSImage classes can access data in these directories. For a task to use remote data, all "disks" specified must be on the same host. Disk numbers on the task object will automatically be translated to the local numbers on the remote host. Note: ObitTalk uses disks to determine where a task is to be run so NO disk numbers may be defaulted. Example usage follows:

```
>>> url='http://192.168.1.140:8000/RPC2'
>>> dirname='/export/data_1/aips/DATA/VINO_1'
>>> disk = len(AIPS.AIPS.disks)
>>> AIPS.AIPS.disks.append(AIPS.AIPSDisk(url, disk, dirname))
>>> t=ObitTask("Template")
>>> t.DataType='AIPS'
>>> t.inDisk=disk
>>> t.inName='0319+415'
>>> t.inClass='IClean'
>>> t.inSeq=1
>>> t.g
[1, '** Message: info
                           : TEMPLATE Begins']
[1, '** Message: info
                           : TEMPLATE: mean -0.000005 RMS 0.000736']
[1, '** Message: info
                           : TEMPLATE Ends']
or an AIPS task:
>>> AIPS.AIPS.disks.append(AIPS.AIPSDisk(url, disk, dirname))
>>> im=AIPSTask("imean")
>>> im.indisk=disk
>>> im.inname='0319+415'
>>> im.inclass='IClean'
>>> im.inseq=1
>>> im.g
IMEAN1: Task IMEAN (release of 31DEC05) begins
IMEAN1: Initial guess for PIXSTD taken from ACTNOISE inheader
IMEAN1: Image= 0319+415
                           .IClean.
                                      1 1
                                            xywind=
                                                               397
                                                                    397
IMEAN1: Mean and rms found by fitting peak in histogram:
IMEAN1: Mean=-1.7323E-05 Rms= 7.2413E-04 **** from histogram
IMEAN1: Mean and rms found by including all data:
IMEAN1: Mean=-4.8774E-06 Rms= 7.3894E-04 JY/BEAM over
                                                           20441 pixels
IMEAN1: Flux density = -5.3379E-03 Jy.
                                         beam area = 18.68 pixels
IMEAN1: Minimum=-2.4419E-03 at 397 350
IMEAN1: Skypos: RA 03 20 09.53788 DEC 41 26 27.4046
IMEAN1: Maximum= 2.8951E-03 at 300 378
IMEAN1: Skypos: RA 03 20 12.14383 DEC 41 26 35.8283
IMEAN1: Skypos: IPOL 4860.100 MHZ
IMEAN1: returns adverbs to AIPS
IMEAN1: Appears to have ended successfully
IMEAN1: vino
                     31DEC05 TST: Cpu=
                                             0.0 Real=
```

Note: since the task definition is likely obtained from the client host, be sure the versions of Obit and AIPS are compatable.

1.13.3 ObitScript class

Any file containing python instructions can be fed to ObitTalk as a command line argument in a non interactive session. Scripts can also be use in interactice sessions using the ObitScript class. The ObitScript class allows defining scripts that can be executed either locally or remotely on a host with a running ObitTalkServer. Scripts are similar to tasks and share many properties like synchronous or asynchronous operation. Scripts may use all Obit classes with python bindings for data local to the host on which it is executing and has all the task and remote data access available interactively. Note: before a script can be run on a remote machine, the AIPS data directories on the remote host must be entered into list of disks as described above.

Scripts are text strings containing valid commands. Note: the script must follow python indentention rules, a backslash n (cannot be said in latex) indicates a line break. Scripts can be supplied as simple strings, a list of strings or the name of a file containing the text of the script. An example usage follows

```
>>> import ObitScript
>>> script = \
>>>
        'im=Image.newPAImage("image","0900+398III","IClean",1,23,True,err)\n'+ \
        'im.Header(err)\n'
>>> s=ObitScript.ObitScript("myScript", script=script)
>>> s.i # Show script text
Listing of script myScript
im=Image.newPAImage("image","0900+398III","IClean",1,23,True,err)
im.Header(err)
>>> s.g
** Message: info
                      : myScript Begins
User 100
AIPS Image Name:
                 0900+398III Class: IClean seq:
                                                       23 disk:
                                                                    1
Object: 0900+398
Observed: 2005-04-04 Telescope: VLA
                                          Created: 2007-02-09
Observer: AP452
                     Instrument: VLA
Minimum =
              -0.74624 Maximum =
                                         33.584 JY/BEAM
Type
       Pixels
                 Coord value
                                 at Pixel
                                              Coord incr
                                                           Rotat
           256
                 9 9 33.38948
                                   129.00
                                                      -20
                                                            0.00
RA---SIN
DEC--SIN
           256 42 53 47.3748
                                   129.00
                                                      20
                                                            0.00
                    7.3794e+07
FREQ
             1
                                     1.00
                                             1.46484e+06
                                                            0.00
                                     1.00
STOKES
                    IPol
                                                        1
                                                             0.00
Coordinate equinox 2000.0 Coordinate epoch 2000.00
Observed RA
               9 0 0.00000 Observed Dec 39 47 60.0000
Phase shifted in X
                        1.836 in Y
                                        3.096
no. Comp
Clean Beam
              76.3171 x
                           71.8424 asec, PA
                                              -68.5 deg.
                     O Vel type: Observer, wrt
Rest freq
                                                 Optical
Alt ref value
                         0 wrt pixel
Maximum version number of AIPS CC tables is 1
Maximum version number of AIPS HI tables is 1
```

** Message: info : myScript Ends

The execution of a script is done by wrapping the script in Obit initialization and shutdown code and writting it to a disk file in /tmp where it is fed as the command line input to ObitTalk. If the ObitScript object member debug is set to True then a copy of the script file will be saved.

The following describes the ObitScript class and can be obtained online by:

```
>>> help(ObitScript)
```

DESCRIPTION

This module provides the ObitScript class.

This class allows running Obit/python scripts either locally or remotely

ObitScripts are derived from Task and share most of execution properties. In particular, ObitScripts can be executed either locally or remotely. In this context a script is a character string containing a sequence of ObitTalk or other python commands and may be included when the script object is created or attached later.

An example:

script="import OSystem
print 'Welcome user',OSystem.PGetAIPSuser()
"

CLASSES

class ObitScript(Task.Task)

This class implements running Obit/python Script

The ObitScript class, handles client-side script related operations. Actual script operations are handled by server-side proxies. For local operations, the server-side functionality is implemented in the same address space but remote operation is through an xmlrpc interface.

An ObitScript has an associated proxy, either local or remote. A proxy is a module with interface functions, local proxies are class modules from subdirectory Proxy with the same name (i.e. ObitScript) and the server functions are implemented there. Remote proxies are specified by a URL and a proxy from the xmlrpclib module is used.

Method resolution order:

ObitScript
Task.Task
MinimalMatch.MinimalMatch

```
Methods defined here:
__call__(self)
__getattr__(self, name)
__init__(self, name, **kwds)
    Create ObitScript task object
   Creates Script Object.
   name = name of script object
   Optional Keywords:
                = Script to execute as string or list of strings
        script
        file
                = Name of text file containing script
       URL
                = URL on which the script is to be executed
                  Default = None = local execution
        AIPSDirs = List of AIPS directories on URL
                  Default = current AIPS directories on url
       FITSDirs = List of FITS directories on URL
                  Default = current FITS directories on url
        AIPSUser = AIPS user number for AIPS data files
                  Default is current
        version = AIPS version string, Default = current
   Following is a list of class members:
                = URL of execution server, None=Local
                = Proxy for URL
       proxy
        script = Script as text string
        userno = AIPS user number
        AIPSDirs = List of AIPS directories on URL
       FITSDirs = List of FITS directories on URL
        AIPSUser = AIPS user number for AIPS data files
        version = AIPS version string
        _message_list = messages from Script execution
__setattr__(self, name, value)
abort(self, proxy, tid, sig=15)
    Abort the script specified by PROXY and TID.
   Calls abort function for task tid on proxy.
   None return value
   proxy = Proxy giving access to server
   tid = Task id in pid table of process to be terminated
          = signal to sent to the task
    sig
explain(self)
   List script
```

```
feed(self, proxy, tid, banana)
   Feed the script a BANANA.
   Pass a message to a running script's sdtin
            = Proxy giving access to server
            = Script task id in pid table of process
   bananna = text message to pass to script input
finished(self, proxy, tid)
   Determine if script has finished
   Determine whether the script specified by PROXY and TID has
   finished.
   proxy = Proxy giving access to server
   tid = Task id in pid table of process
go(self)
   Execute the script.
   Writes task input parameters in the task parameter file and
   starts the task synchronously returning only when the task
   terminates. Messages are displayed as generated by the task,
    saved in an array returned from the call and, if the task
   member logFile is set, written to this file.
help(self)
   List script.
inputs(self)
   List script
messages(self, proxy=None, tid=None)
   Return task messages
   Returns list of messages and appends them to the object's
   message list.
   proxy = Proxy giving access to server
        = Task id in pid table of process
outputs(self)
   Not defined.
spawn(self)
   Spawn the script.
   Starts script asynchronously returning immediately
   Messages must be retrieved calling messages.
   Returns (proxy, tid)
```

```
wait(self, proxy, tid)
       Wait for the script to finish.
       proxy = Proxy giving access to server
             = Task id in pid table of process
  Data and other attributes defined here:
  AIPSDirs = []
  FITSDirs = []
  debug = False
  doWait = False
  isbatch = 32000
  logFile = ''
  msgkill = 0
  proxy = <module 'LocalProxy' from '/export/users/bcotton/share/obittal...</pre>
  script = ''
  url = None
  userno = 0
  version = 'TST'
  Methods inherited from MinimalMatch.MinimalMatch:
  __repr__(self)
class ObitScriptMessageLog
  Methods defined here:
  __init__(self)
  zap(self)
      Zap message log.
```

Data and other attributes defined here:

userno = -1

1.14 Local Python Data Interface Classes

Local and remote script execution data access is allowed through the direct python bindings to the data classes. These classes are Image, UV (radio interferometric data), and OTF (radio single dish "On-the-Fly" data) which are all derived from the base OData class. Most of the top level class functionality, e.g. making an image from a data set, are available through these classes. The online documentation for these classes can be obtained by

```
>>> help(Image)
>>> help(UV)
>>> import OTF; help(OTF)
```

Class members are accessed as using the "object_name.value" form as

```
>>> header=uv.Desc.Dict
```

to get the "header" from uv data uv as a python dict. Class functions (have "self" as an argument are called as

```
>>> uv.Header(err)
```

Note, "self" not included directly in the argument. Functions which do not have "self" as an argument (usually have names starting with 'P') need to include the class:

```
>>> UV.PHeader(uv, err)
```

All data ojects have a Descriptor (the "Desc" member) which can be read and written (requires open and close of data object). Conversion between the c memory resident forms and a python dict is by means of the "Dict" member of the descriptor classes:

```
>>> d=uv.Desc.Dict
>>> d
{'origin': 'Obit
                   ', 'jlocr': 4, 'obsdat': '1996-11-16', 'equinox': 2000.0,
'observer': 'AC473
'ptype': ['UU-L-SIN', 'VV-L-SIN', 'WW-L-SIN', 'BASELINE', 'TIME1
'ilocid': -1, 'obsdec': 30.2984147222, 'xshift': 0.0, 'ilocws': -1,
'jlocd': 5, 'restFreq': 0.0, 'ilocsu': -1, 'nvis': 1594634, 'ilocb': 3,
'ilocv':1, 'ilocw': 2, 'iloct': 4, 'ilocu': 0, 'nrparm': 5, 'instrume': 'VLA',
'epoch':2000.0, 'isort': 'TB', 'VelDef': 0, 'inaxes': [3, 2, 30, 1, 1, 1, 0],
'yshift': 0.0, 'ilocit': -1, 'object': 'MCFIELD',
'ctype': ['COMPLEX ', 'STOKES ', 'FREQ
                                           ', 'IF
                                                                                '],
'cdelt': [1.0, -1.0, 97656.25, 1.0, 1.0, 1.0, 0.0], 'jlocif': 3,
'JDObs': 2450403.5, 'date': '2007-07-07', 'ilocfq': -1, 'jlocf': 2, 'VelReference': 3,
'ncorr': 60, 'jlocc': 0, 'crpix': [1.0, 1.0, 16.0, 1.0, 1.0, 1.0, 1.0], 'jlocs': 1,
'name': 'AIPS UV data', 'teles': 'VLA
                                      ', 'altRef': 125100.0,
'numVisBuff': 0, 'naxis': 6, 'crota': [0.0, 0.0, 0.0, 0.0, 0.0, 0.0, 0.0],
'bunit':'UNCALIB', 'firstVis': 0, 'altCrpix': 16.0, 'obsra': 195.75129125000001,
'crval': [1.0, -1.0, 316562500.0, 1.0, 195.75129125000001, 30.2984147222, 0.0]}
```

1.14.1 Obit python Image class

The interface to Images use FArray objects to store the pixel data. The FArray class allows efficient pixel manipulation and knows about magic value blanking of pixels. The data arrays in memory can also be access for use with NumPy. Further functions are available in python modules ImageUtil, CleanImage, ConvUtil, ImageMosaic, MosaicUtil and Feather modules The following describes the Image class.

```
NAME
    Image - Python Obit Image class
DESCRIPTION
    This class contains an astronomical image and allows access.
    An ObitImage is the front end to a persistent disk resident structure.
    Magic value blanking is supported, blanked pixels have the value
    OBIT_MAGIC (ObitImageDesc.h).
    Pixel data are kept in an FArray structure which is how Python acceses the data.
    There may be associated tables (e.g. "AIPS CC" tables).
    Both FITS and AIPS cataloged images are supported.
    Image Members with python interfaces:
    exist
              - True if object previously existed prior to object creation
    InfoList - used to pass instructions to processing
    ImageDesc - Astronomical labeling of the image Member Desc
              - Container used for pixel data Member FArray
    PixBuf
              - memory pointer into I/O Buffer
    Additional Functions are available in ImageUtil.
CLASSES
    OData.OData(OData.ODataPtr)
        Image
    class Image(OData.OData)
       Python Obit Image class
       Additional Functions are available in ImageUtil.
      Method resolution order:
           Image
           OData.OData
           OData.ODataPtr
      Methods defined here:
       Clone(self, outImage, err)
           Make a copy of a object but do not copy the actual data
```

This is useful to create an Image similar to the input one.

= Python Image object

self

```
outImage = Output Python Image object, must be defined
           = Python Obit Error/message stack
Close(self, err)
    Close an image persistent (disk) form
              = Python Image object
    self
              = Python Obit Error/message stack
    err
Copy(self, outImage, err)
   Make a deep copy of input object.
   Makes structure the same as self, copies data, tables
    self = Python Image object to copy
    outImage = Output Python Image object, must be defined
           = Python Obit Error/message stack
GetPlane(self, array, plane, err)
    Read an image persistent (disk) form to an (optional) specified FArray
    The data to be read is specified in the InfoList member as modified by plane
    self = Python Image object
    array = Python FArray to accept data, if None use inImage buffer
    plane = array of 5 integers giving (1-rel) pixel numbers
          = Python Obit Error/message stack
Header(self, err)
    Write image header on output
           = Python Obit Image object
          = Python Obit Error/message stack
ImageIsA(self)
    Tells if input really a Python Obit Image
    return true, false (1,0)
          = Python UV object
    self
Info(self, err)
    Get underlying data file info
    self
           = Python Obit Image object
    err
          = Python Obit Error/message stack
Open(self, access, err, blc=None, trc=None)
    Open an image persistent (disk) form
    self
          = Python Image object
```

```
access = access READONLY (1), WRITEONLY (2), READWRITE(3)
              = Python Obit Error/message stack
    err
              = if given and a list of integers (min 2) giving
    blc
    bottom left corner (1-rel) of subimage
              = if given and a list of integers (min 2) giving
    top right corner (1-rel) of subimage
PutPlane(self, array, plane, err)
    Write an image persistent (disk) form from an (optional) specified FArray
    The data to be written is specified in the InfoList member as modified by plane
          = Python Image object
    self
             = Python FArray to provide data, if None use inImage buffer
              = array of 5 integers giving (1-rel) pixel numbers
    plane
              = Python Obit Error/message stack
Read(self, err)
    Read an image persistent (disk) form
    The data to be read is specified in the InfoList mamber
    Uses FArray member as buffer.
              = Python Image object
    err
              = Python Obit Error/message stack
ReadFA(self, array, err)
    Read an image persistent (disk) form to a specified FArray
    The data to be read is specified in the InfoList member
          = Python Image object
    array = Python FArray to accept data
           = Python Obit Error/message stack
ReadPlane(self, err, blc=None, trc=None)
    Read an image plane into the FArray
    Reads the plane specified by blc, trc
    into the FArray associated with the image
    self
            = Python Image object
             = Python Obit Error/message stack
    err
    blc
            = if given and a list of integers (min 2) giving
               bottom left corner (1-rel) of subimage
             = if given and a list of integers (min 2) giving
    trc
               top right corner (1-rel) of subimage
    returns Python FArray from Image with data read
```

Scratch(self, err)

Create a scratch file suitable for accepting the data to be read from self

```
= Python Image object
    err
              = Python Obit Error/message stack
UpdateDesc(self, err, Desc=None)
    Update any disk resident structures about descriptor
    self
              = Python Image object
    err
              = Python Obit Error/message stack
    Desc
              = Descriptor, if None then use current descriptor
                Contents can be accessed throuth the Dict member
Write(self, err)
    Write an image persistent (disk) form
    The data to be written is specified in the InfoList member
    Uses FArray member as buffer.
    self
              = Python Image object
              = Python Obit Error/message stack
    err
WriteFA(self, array, err)
    Write an image persistent (disk) form from a specified FArray
    The data to be written is specified in the InfoList member
             = Python Image object
    self
              = Python FArray to write
    array
              = Python Obit Error/message stack
    err
WritePlane(self, imageData, err)
    Write an image plane.
    Writes the plane specified by blc, trc on image infoList
    Checks if the current FArray on Image is compatable with
    imageData.
    self
              = Python Image object
    imageData = Python FArray with data to write
              = Python Obit Error/message stack
    err
__del__(self)
__getattr__(self, name)
__init__(self, name)
__repr__(self)
__setattr__(self, name, value)
```

A scratch Image is more or less the same as a normal Image except that it is

automatically deleted on the final unreference.

```
cast(self, toClass)
    Casts object pointer to specified class
    self
             = object whose cast pointer is desired
    toClass = Class string to cast to ("ObitImage")
Methods inherited from OData.OData:
CopyTables(self, outOData, exclude, include, err)
    Copy Tables from one OData to another
    self
              = Python OData object
    outOData
                 = Output Python OData object, must be defined
    exclude = list of table types to exclude (list of strings)
    has priority
    include
            = list of table types to include (list of strings)
              = Python Obit Error/message stack
    err
Dirty(self)
    Mark OData as needing a header update to disk file
    self
             = Python OData object
FullInstantiate(self, access, err)
    Fully instantiate an OData by opening and closing
    return 0 on success, else failure
    self = Python OData object
    access = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE
              = Python Obit Error/message stack
    err
GetHighVer(self, tabType)
    Get highest version number of a specified Table
            returns highest tabType version number, 0 if none.
         = Python OData object
    tabType = Table type, e.g. "OTFSoln"
GetName(self)
    Tells OData object name (label)
    returns name as character string
    self = Python OData object
History(self, access, err)
    Return the associated History
```

```
self
             = Python OData object
             = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE
   access
             = Python Obit Error/message stack
   err
IsScratch(self)
   Tells if OData is a scratch object
   return true, false (1,0)
          = Python OData object
   self
NewTable(self, access, tabType, tabVer, err, numOrb=0,
       numPCal=3, numIF=1, numPol=1, numTerm=0, numChan=1,
       numTones=1, numBand=1, numTabs=1, npoly=1, numCoef=5, noParms=0)
   Return the specified associated table
   Table will be created if necessary.
   self
            = Python OData object
   access = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE
   tabType = Table type, e.g. "AIPS AN"
   tabVer = table version, if > 0 on input that table returned,
   if 0 on input, the highest version is used.
             = Python Obit Error/message stack
   Optional parameters, values only used if table created
   numOrb
            = Number of orbital parameters (AN)
   numPCal = Number of polarization parameters (AN)
           = Number of IFs (FQ, SN, CL, BP, BL, TY, CQ)
   numIF
   numPol
            = Number of Stokes' (SN, CL, BP, BL, PC, TY, GC, MC, IM)
   numTerm = Number of terms in model polynomial (CL)
   numChan = Number of spectral channels (BP)
   numTomes = Number of Phase cal tones (PC)
   numTabs = Number of ??? (GC)
   numCoef = Number of polynomial coefficents (NI)
   numBand = Number of Bands(?) (IM, GC)
   npoly = number of polynomial terms (IM)
   noParms = Number of parameters in CC table model
   maxis1-5 = Dimension of axes of IDI data matrix
ODataIsA(self)
   Tells if input really a Python Obit OData
   return true, false (1,0)
         = Python OData object
Rename(self, err, newFITSName=None, newAIPSName=' ',
       newAIPSClass=' ', newAIPSSeq=0)
   Rename underlying files
          = Python OData object
   self
```

```
For FITS files:
          newFITSName = new name for FITS file
          For AIPS:
          newAIPSName = New AIPS Name (max 12 char) Blank => don't change.
          newAIPSClass = New AIPS Class (max 6 char) Blank => don't change.
          newAIPSSeq = New AIPS Sequence number, 0 => unique value
      UpdateTables(self, err)
          Update any disk resident structures about the current tables
          Returns 0 on success
                   = Python Image object
          self
                   = Python Obit Error/message stack
       Zap(self, err)
          Delete underlying files and the basic object.
                    = Python OData object
          self
                    = Python Obit Error/message stack
          err
       ZapTable(self, tabType, tabVer, err)
          Destroy specified table
          Returns 0 on success
          self = Python OData object
          tabType = Table type, e.g. "AIPS CC"
          tabVer = table version, integer
                  = Python Obit Error/message stack
          err
FUNCTIONS
   ObitName(ObitObject)
       Return name of an Obit object or input if not an Obit Object
   PClone(inImage, outImage, err)
       Make a copy of a object but do not copy the actual data
       This is useful to create an Image similar to the input one.
        inImage = Python Image object
       outImage = Output Python Image object, must be defined
                 = Python Obit Error/message stack
   PClone2(inImage1, inImage2, outImage, err)
       Make a copy of a object but do not copy the actual data
        inImage1 = Python Image object to clone
        inImage2 = Python Image object whose geometry is to be used
```

= Python Obit Error/message stack

err

```
outImage = Output Python Image object, must be defined,
                will be defined as Memory only
    err
              = Python Obit Error/message stack
PCloneMem(inImage, outImage, err)
   Make a Memory only clone of an Image structure
    This is useful for temporary structures
             = Python Image object
    outImage = Output Python Image object, must be defined
              = Python Obit Error/message stack
PClose(inImage, err)
   Close an image persistent (disk) form
              = Python Image object
              = Python Obit Error/message stack
PCompare(in1Image, in2Image, err, plane=[1, 1, 1, 1, 1])
    Compare a plane of two images
    returns list [max. abs in1Image, max abs difference, RMS difference]
    in1Image = Python Image object
    in2Image = Python Image object, on output, the FArray contains the difference.
              = Python Obit Error/message stack
             = plane to compare
    plane
PCopy(inImage, outImage, err)
   Make a deep copy of input object.
   Makes structure the same as inImage, copies data, tables
            = Python Image object to copy
    outImage = Output Python Image object, must be defined
              = Python Obit Error/message stack
    err
PCopyQuantizeFITS(inImage, outImage, err, fract=0.25, quant=None, inHistory=None)
    Make a copy of an image quantizing to a 16 or 32 bit integer
        FITS image
    inImage
              = Python Image object
    outImage = Output Python Image object, must be defined
               but not fully created
    err
             = Python Obit Error/message stack
    fract
              = quantization level as a fraction of the plane min. RMS
              = quantization level in image units, has precedence over fract
    quant
                None or <= 0 => use fract.
    inHistory = if given a History object to copy to the output FITS header
```

```
PCopyTables(inImage, outImage, exclude, include, err)
    Copy Tabeles from one image to another
             = Python Image object
    inImage
    outImage = Output Python Image object, must be defined
    exclude = list of table types to exclude (list of strings)
               has priority
    include = list of table types to include (list of strings)
    err
             = Python Obit Error/message stack
PDirty(inImage)
   Mark Image as needing a header update to disk file
               = Python Image object
    inImage
PFArray2FITS(inArray, outFile, err, outDisk=1, oDesc=None)
   Write an FArray to a FITS image
    Very rudimentary header attached
    Returns image object
    inArray = Python FArray object
    outFile = Name of FITS file
    outDisk = FITS disk number
    oDesc
            = None or ImageDescriptor to be written
             = Python Obit Error/message stack
    err
PFArray2Image(inArray, outImage, err)
    Attach an FArray to an image and write it
    Very rudimentary header attached
    inArray = Python Image object
    outImage = Python Image to write
    err
             = Python Obit Error/message stack
PFullInstantiate(inImage, access, err)
    Fully instantiate an Image by opening and closing
   return 0 on success, else failure
    inImage = Python Image object
    access = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE
             = Python Obit Error/message stack
    err
PGetBeam(inImage)
    Return Beam attached to Image
    returns Beam with image pixel data
    inImage = Python Image object
```

```
PGetDesc(inImage)
    Return the member ImageDesc
   returns ImageDesc as a Python Dictionary
    inImage
             = Python Image object
PGetFArray(inImage)
    Return FArray used to buffer Image data
   returns FArray with image pixel data
    inImage = Python Image object
PGetHighVer(inImage, tabType)
    Get highest version number of a specified Table
    returns highest tabType version number, 0 if none.
    inImage = Python Image object
   tabType = Table type, e.g. "OTFSoln"
PGetList(inImage)
   Return the member InfoList
    returns InfoList
    inImage = Python Image object
PGetName(inImage)
   Tells Image object name (label)
   returns name as character string
    inImage = Python Image object
PGetPixBuf(inImage)
    Return python memory buffer for pixel array in memory
    inImage
            = Python Image object
PGetPlane(inImage, array, plane, err)
    Read an image persistent (disk) form to an (optional) specified FArray
    The data to be read is specified in the InfoList member as modified by plane
    inImage = Python Image object
   array
            = Python FArray to accept data, if None use inImage buffer
            = array of 5 integers giving (1-rel) pixel numbers
    plane
             = Python Obit Error/message stack
    err
PGetTable(inImage, access, tabType, tabVer, err, noParms=0)
```

Return (create) the specified associated table

Specific table types are recognized and the appropriate constructor called, these may have additional parameters. This allows creating new tables of the appropriate type. returns Python Obit Table = Python Image object inImageaccess = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE tabType = Table type, e.g. "AIPS AN", or "OTFSoln" tabVer = table version, if > 0 on input that table returned, if 0 on input, the highest version is used. = Python Obit Error/message stack err noParms = Number of parameters in CC table model PGetTableList(inImage) Return the member tableList returns tableList inImage = Python Image object PHeader(inImage, err) Print image descriptor inImage= Python Image object = Python Obit Error/message stack err PImageGetTable(inImage, access, tabType, tabVer, err) Obsolete use PGetTable PIsA(inImage) Tells if input really a Python Obit Image return True, False (1,0) inImage = Python Image object PIsScratch(inImage) Tells if Image is a scratch object return true, false (1,0) inImage = Python Image object POpen(inImage, access, err, blc=None, trc=None) Open an image persistent (disk) form inImage = Python Image object = access READONLY (1), WRITEONLY (2), READWRITE(3) access = Python Obit Error/message stack err = if given and a list of integers (min 2) giving blc bottom left corner (1-rel) of subimage = if given and a list of integers (min 2) giving trc

top right corner (1-rel) of subimage

PPutPlane(inImage, array, plane, err) Write an image persistent (disk) form from an (optional) specified FArray The data to be written is specified in the InfoList member as modified by plane inImage = Python Image object = Python FArray to provide data, if None use inImage buffer array = array of 5 integers giving (1-rel) pixel numbers plane err = Python Obit Error/message stack PRead(inImage, err) Read an image persistent (disk) form The data to be read is specified in the InfoList mamber Uses FArray member as buffer. inImage = Python Image object err = Python Obit Error/message stack PReadFA(inImage, array, err) Read an image persistent (disk) form to a specified FArray The data to be read is specified in the InfoList member inImage = Python Image object = Python FArray to accept data array = Python Obit Error/message stack err PReadPlane(inImage, err, blc=None, trc=None) Read an image plane into the FArray Reads the plane specified by blc, trc into the FArray associated with the image inImage= Python Image object = Python Obit Error/message stack err = if given and a list of integers (min 2) giving blc bottom left corner (1-rel) of subimage = if given and a list of integers (min 2) giving trc top right corner (1-rel) of subimage returns Python FArray from Image with data read PScratch(inImage, err) Create a scratch file suitable for accepting the data to be read from inImage A scratch Image is more or less the same as a normal Image except that it is automatically deleted on the final unreference. inImage = Python Image object

= Python Obit Error/message stack

err

```
PSetBeam(inImage, beam)
    Replace the Beam attached to an Image
              = Python Image object
    inImage
    beam
              = Python Beam Image to attach
PSetFArray(inImage, array)
    Replace the FArray on an Image
    inImage
              = Python Image object
    array
             = Python FArray to attach
PSwapAxis(inImage, err, ax1=3, ax2=4)
    Swap axes on an image
   The order of two adjacent axes may be swapped if the dimensionality
    of at least one of them is 1
    inImage = Image whose axes are to be swapped
            = Python Obit Error/message stack
    err
            = first (1-rel) axis number
    ax1
           = second (1-rel) axis number
    ax2
PUnref(inImage)
   Decrement reference count
   Decrement reference count which will destroy object if it goes to zero
   Python object stays defined.
    inImage
            = Python Image object
PUpdateDesc(inImage, err, Desc=None)
    Update external representation of descriptor
    inImage = Python Image object
          = Python Obit Error/message stack
            = Image descriptor, if None then use current descriptor
    Desc
PUpdateTables(inImage, err)
    Update any disk resident structures about the current tables
    inImage
             = Python Image object
              = Python Obit Error/message stack
    err
PWrite(inImage, err)
    Write an image persistent (disk) form
   The data to be written is specified in the InfoList member
    Uses FArray member as buffer.
    inImage
            = Python Image object
```

= Python Obit Error/message stack err PWriteFA(inImage, array, err) Write an image persistent (disk) form from a specified FArray The data to be written is specified in the InfoList member inImage = Python Image object array = Python FArray to write = Python Obit Error/message stack err PWritePlane(Image, imageData, err) Write an image plane. Writes the plane specified by blc, trc on image infoList Checks if the current FArray on Image is compatable with imageData. = Python Image object Image imageData = Python FArray with data to write = Python Obit Error/message stack err PZap(inImage, err) Delete underlying files and the basic object. = Python Image object inImage = Python Obit Error/message stack err PZapTable(inImage, tabType, tabVer, err) Destroy specified table inImage = Python Image object tabType = Table type, e.g. "AIPS CC" tabVer = table version, integer err = Python Obit Error/message stack input(inputDict) Print the contents of an input Dictionary inputDict = Python Dictionary containing the parameters for a routine newObit(name, filename, disk, exists, err) Create and initialize an Image structure Create, set initial access information (full image, plane at a time) and if exists verifies the file. Returns the Python Image object name = name desired for object (labeling purposes) filename = name of FITS file disk = FITS directory number

exists = if true then the file is opened and closed to verify err = Python Obit Error/message stack

newPACNO(disk, cno, exists, err, verbose=True)

Create and initialize an AIPS based Image structure

Create, set initial access information (full image, plane at a time) and if exists verifies the file.

Returns the Python Image object

isOK member set to indicate success

disk = AIPS directory number
cno = AIPS catalog number

exists = if true then the file is opened and closed to verify

err = Python Obit Error/message stack

verbose = If true any give error messages, else suppress

newPAImage(name, Aname, Aclass, disk, seq, exists, err, verbose=True)
 Create and initialize an AIPS based Image structure

Create, set initial access information (full image, plane at a time) and if exists verifies the file.

Returns the Python Image object

isOK member set to indicate success

name = name desired for object (labeling purposes)

Aname = AIPS name of file Aclass = AIPS class of file

seq = AIPS sequence number of file

disk = FITS directory number

exists = if true then the file is opened and closed to verify

err = Python Obit Error/message stack

verbose = If true any give error messages, else suppress

newPFImage(name, filename, disk, exists, err, verbose=True)
 Create and initialize an FITS based Image structure

Create, set initial access information (full image, plane at a time) and if exists verifies the file.

isOK member set to indicate success

Returns the Python Image object

name = name desired for object (labeling purposes)

filename = name of FITS file
disk = FITS directory number

exists = if true then the file is opened and closed to verify

err = Python Obit Error/message stack

verbose = If true any give error messages, else suppress

1.14.2 Obit python UV class

Further utilities are available in the SkyModel, IonCal, CleanVis UVSelfCal, UVGSolve, UVImager, and UVSoln2Cal python modules. The following describes the UV class.

NAME

UV - Python Obit inteferometer (UV) data class

This class contains interoferometric data and allows access.

```
DESCRIPTION
```

An ObitUV is the front end to a persistent disk resident structure. There maybe (usually are) associated tables which either describe the data or contain calibration and/or editing information. Both FITS (as Tables) and AIPS cataloged data are supported. Most access to UV data is through functions as the volume of the data is inappropriate to be processed directly in python. UV Members with python interfaces: exist - True if object previously existed prior to object creation List - used to pass instructions to processing - Astronomical labeling of the data TableList - List of tables attached - memory pointer into I/O Buffer Data selection, calibration and editing parameters on List member: "doCalSelect" bool (1,1,1) Select/calibrate/edit data? string (4,1,1) Selected output Stokes parameters: "Stokes" ","V ","Q ", "U ", "=> no translation,"I "IQU ", "IQUV", "IV ", "RR ", "LL ", "RL ", "LR ", "HALF" = RR,LL, "FULL"=RR,LL,RL,LR. [default " In the above 'F' can substitute for "formal" 'I' (both RR+LL). "BChan" int (1,1,1) First spectral channel selected. [def all] "EChan" int (1,1,1) Highest spectral channel selected. [def all] "BIF" int (1,1,1) First "IF" selected. [def all] "ETF" int (1,1,1) Highest "IF" selected. [def all] "doPol" int (1,1,1) > 0 -> calibrate polarization. "doCalib" int (1,1,1) >0 -> calibrate, 2=> also calibrate Weights "gainUse" int (1,1,1) SN/CL table version number, 0-> use highest "flagVer" int (1,1,1) Flag table version, 0-> use highest, <0-> none "BLVer" int (1,1,1) BL table version, 0> use highest, <0-> none "BPVer" int (1,1,1) Band pass (BP) table version, 0-> use highest "Subarray" int (1,1,1) Selected subarray, <=0->all [default all] "dropSubA" bool (1,1,1) Drop subarray info? "FreqID" int (1,1,1) Selected Frequency ID, <=0->all [default all] "timeRange" float (2,1,1) Selected timerange in days. "UVRange" float (2,1,1) Selected UV range in kilowavelengths. "InputAvgTime" float (1,1,1) Input data averaging time (sec).

used for fringe rate decorrelation correction.
"Sources" string (?,?,1) Source names selected unless any starts with

```
a '-' in which case all are deselected (with '-' stripped).
"souCode" string (4,1,1) Source Cal code desired, ' ' => any code selected
                              '* ' => any non blank code (calibrators only)
                              '-CAL' => blank codes only (no calibrators)
            int (1,1,1) Source qualifier, -1 [default] = any
"Qual"
"Antennas" int (?,1,1) a list of selected antenna numbers, if any is negative
           then the absolute values are used and the specified antennas are deselected.
"corrtype" int (1,1,1) Correlation type, 0=cross corr only, 1=both, 2=auto only.
"passAll" bool (1,1,1) If True, pass along all data when selecting/calibration
                             even if it's all flagged,
                             data deselected by time, source, antenna etc. is not passed.
           int (1,1,1) Band pass application type <0-> none
"doBand"
     (1) if = 1 then all the bandpass data for each antenna
        will be averaged to form a composite bandpass
        spectrum, this will then be used to correct the data.
     (2) if = 2 the bandpass spectra nearest in time (in a weighted
        sense) to the uv data point will be used to correct the data.
     (3) if = 3 the bandpass data will be interpolated in time using
        the solution weights to form a composite bandpass spectrum,
        this interpolated spectrum will then be used to correct the
        data.
     (4) if = 4 the bandpass spectra nearest in time (neglecting
        weights) to the uv data point will be used to correct the
        data.
     (5) if = 5 the bandpass data will be interpolated in time ignoring
        weights to form a composite bandpass spectrum, this
        interpolated spectrum will then be used to correct the data.
"Smooth" float (3,1,1) specifies the type of spectral smoothing
   Smooth(1) = type of smoothing to apply:
      0 => no smoothing
      1 => Hanning
      2 => Gaussian
      3 => Boxcar
       4 \Rightarrow Sinc (i.e. sin(x)/x)
    Smooth(2) = the "diameter" of the function, i.e.
       width between first nulls of Hanning triangle
       and sinc function, FWHM of Gaussian, width of
       Boxcar. Defaults (if < 0.1) are 4, 2, 2 and 3
       channels for Smooth(1) = 1 - 4.
    Smooth(3) = the diameter over which the convolving
       function has value - in channels.
      Defaults: 1, 3, 1, 4 times Smooth(2) used when
"SubScanTime" float scalar [Optional] if given, this is the
    desired time (days) of a sub scan. This is used by the
    selector to suggest a value close to this which will
    evenly divide the current scan.
```

This is only useful for ReadSelect operations on indexed ObitUVs.

0 => Use scan average.

```
CLASSES
   OData.OData(OData.ODataPtr)
       UV
    class UV(OData.OData)
       Python Obit inteferometer (UV) data class
      UV Members with python interfaces:
      List
               - used to pass instructions to processing
      TableList - List of tables attached
      Desc
               - Astronomical labeling of the data
                - memory pointer into I/O Buffer
       VisBuf
      Method resolution order:
          IJV
           OData.OData
           OData.ODataPtr
       Methods defined here:
       Clone(self, outUV, err)
           Make a copy of a object but do not copy the actual data
           This is useful to create an UV similar to the input one.
                = Python UV object
           self
           outUV = Output Python UV object, must be defined
                  = Python Obit Error/message stack
       Close(self, err)
           Close a UV persistent (disk) form
           returns 0 on success, else failure
                   = Python UV object
           self
                     = Python Obit Error/message stack
       Copy(self, outUV, err)
          Make a deep copy of input object.
           Makes structure the same as self, copies data, tables
                 = Python UV object to copy
           outUV = Output Python UV object, must be defined
                  = Python Obit Error/message stack
       Header(self, err)
           Write image header on output
                 = Python Obit UV object
           self
```

```
= Python Obit Error/message stack
    err
Info(self, err)
    Get underlying data file info
           = Python Obit UV object
    err
           = Python Obit Error/message stack
Open(self, access, err)
    Open a UV data persistent (disk) form
    Returns 0 on success, else failure
    self = Python UV object
    access = access READONLY (1), WRITEONLY (2), READWRITE(3)
           = Python Obit Error/message stack
Read(self, err)
    Read a UV persistent (disk) form
    Reads into buffer attached to UV data, use VisBuf for access
    Returns 0 on success, else failure
          = Python UV object
    err
           = Python Obit Error/message stack
Scratch(self, err)
    Create a scratch file suitable for accepting the data to be read from self
    A scratch UV is more or less the same as a normal UV except that it is
    automatically deleted on the final unreference.
    self
              = Python UV object
              = Python Obit Error/message stack
    err
UVIsA(self)
    Tells if input really a Python Obit UV
    return true, false (1,0)
           = Python UV object
    self
UpdateDesc(self, err, Desc=None)
    Update any disk resident structures about descriptor
    self
              = Python UV object
              = Python Obit Error/message stack
    err
              = Descriptor, if None then use current descriptor
    Desc
                Contents can be accessed throuth the Dict member
Write(self, err)
```

Write a UV persistent (disk) form

```
Writes buffer attached to UV data, use VisBuf for access
    returns 0 on success, else failure
              = Python UV object
    self
    err
              = Python Obit Error/message stack
__del__(self)
__getattr__(self, name)
__init__(self, name)
__repr__(self)
__setattr__(self, name, value)
cast(self, toClass)
    Casts object pointer to specified class
             = object whose cast pointer is desired
    toClass = Class string to cast to ("ObitUV")
Methods inherited from OData.OData:
CopyTables(self, outOData, exclude, include, err)
    Copy Tables from one OData to another
              = Python OData object
    outOData
                 = Output Python OData object, must be defined
    exclude = list of table types to exclude (list of strings)
    has priority
    include
             = list of table types to include (list of strings)
              = Python Obit Error/message stack
    err
Dirty(self)
    Mark OData as needing a header update to disk file
    self
             = Python OData object
FullInstantiate(self, access, err)
    Fully instantiate an OData by opening and closing
    return 0 on success, else failure
         = Python OData object
    self
             = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE
    access
              = Python Obit Error/message stack
    err
```

```
GetHighVer(self, tabType)
    Get highest version number of a specified Table
           returns highest tabType version number, 0 if none.
          = Python OData object
    tabType = Table type, e.g. "OTFSoln"
GetName(self)
    Tells OData object name (label)
    returns name as character string
    self = Python OData object
History(self, access, err)
    Return the associated History
            = Python OData object
    self
    access = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE
    err
            = Python Obit Error/message stack
IsScratch(self)
    Tells if OData is a scratch object
    return true, false (1,0)
          = Python OData object
    self
NewTable(self, access, tabType, tabVer, err, numOrb=0,
       numPCal=3, numIF=1, numPol=1, numTerm=0, numChan=1,
       numTones=1, numBand=1, numTabs=1, npoly=1, numCoef=5, noParms=0)
    Return the specified associated table
    Table will be created if necessary.
            = Python OData object
    self
    access = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE
    tabType = Table type, e.g. "AIPS AN"
            = table version, if > 0 on input that table returned,
    tabVer
    if 0 on input, the highest version is used.
    err
              = Python Obit Error/message stack
    Optional parameters, values only used if table created
    numOrb
            = Number of orbital parameters (AN)
    numPCal = Number of polarization parameters (AN)
    numIF
            = Number of IFs (FQ, SN, CL, BP, BL, TY, CQ)
    numPol
            = Number of Stokes' (SN, CL, BP, BL, PC, TY, GC, MC, IM)
    numTerm = Number of terms in model polynomial (CL)
    numChan = Number of spectral channels (BP)
    numTomes = Number of Phase cal tones (PC)
    numTabs = Number of ??? (GC)
    numCoef = Number of polynomial coefficents (NI)
    numBand = Number of Bands(?) (IM, GC)
```

```
npoly
                   = number of polynomial terms (IM)
           noParms = Number of parameters in CC table model
           maxis1-5 = Dimension of axes of IDI data matrix
       ODataIsA(self)
           Tells if input really a Python Obit OData
           return true, false (1,0)
           self = Python OData object
      Rename(self, err, newFITSName=None, newAIPSName='
           newAIPSClass='
                             ', newAIPSSeq=0)
           Rename underlying files
                 = Python OData object
                     = Python Obit Error/message stack
           For FITS files:
           newFITSName = new name for FITS file
           For AIPS:
           newAIPSName = New AIPS Name (max 12 char) Blank => don't change.
           newAIPSClass = New AIPS Class (max 6 char) Blank => don't change.
           newAIPSSeq
                       = New AIPS Sequence number, 0 => unique value
      UpdateTables(self, err)
           Update any disk resident structures about the current tables
           Returns 0 on success
                   = Python OData object
                    = Python Obit Error/message stack
           err
       Zap(self, err)
           Delete underlying files and the basic object.
           self
                    = Python OData object
           err
                    = Python Obit Error/message stack
       ZapTable(self, tabType, tabVer, err)
           Destroy specified table
          Returns 0 on success
           self
                  = Python OData object
           tabType = Table type, e.g. "AIPS CC"
           tabVer = table version, integer
                   = Python Obit Error/message stack
           err
FUNCTIONS
   PClone(inUV, outUV, err)
```

Make a copy of a object but do not copy the actual data This is useful to create an UV similar to the input one. = Python UV object outUV = Output Python UV object, must be defined = Python Obit Error/message stack err PClose(inUV, err) Close an image persistent (disk) form = Python UV object inUV err = Python Obit Error/message stack PCopy(inUV, outUV, err) Make a deep copy of input object. Makes structure the same as inUV, copies data, tables = Python UV object to copy outUV = Output Python UV object, must be defined err = Python Obit Error/message stack PCopyTables(inUV, outUV, exclude, include, err) Copy Tabeles from one image to another inUV = Python UV object outUV = Output Python UV object, must be defined exclude = list of table types to exclude (list of strings) has priority include = list of table types to include (list of strings) = Python Obit Error/message stack err PDirty(inUV) Mark UV as needing a header update to disk file inUV = Python UV object PEditClip(inUV, scratch, outUV, err) Clip raw visibilities control parameters on inUV info member "maxAmp" OBIT_float (1,1,1) Maximum allowed amplitude "oper" OBIT_string (4,1,1) operation type: "flag" flag data with amplitudes in excess of maxAmp "clip" clip amplitudes at maxAmp and preserve phase default is "flag" returns UV data object = Python UV object to clip/flag scratch= True if this is to be a scratch file (same type as inUV) outUV = Predefined UV data if scratch is False, may be inUV ignored if scratch True.

err = Python Obit Error/message stack

PEditClipStokes(inUV, scratch, outUV, err)
Flag visibilities by Stokes

Clip a uv data set. Data with amplitudes of the selected stokes in excess of maxAmp are flagged. Optionally all correlations associated may be flagged. Stokes conversion as needed for test.

Control parameters are on the inUV info member:

"clipStok" OBIT_string (1,1,1) Stokes value to clip (I, Q, U, V, R, L) default = "I"

"flagAll" Obit_bool (1,1,1) if true, flag all associated correlations default = True

"maxAmp" OBIT_float (1,1,1) Maximum allowed amplitude returns UV data object $% \left(1,1,1\right) =\left(1,1,1\right) +\left(1,1,1\right$

inUV = Python UV object to clip/flag

scratch= True if this is to be a scratch file (same type as inUV)

outUV = Predefined UV data if scratch is False, may be inUV ignored if scratch True.

err = Python Obit Error/message stack

PEditFD(inUV, outUV, err)

Frequency-domain editing of UV data - produces FG table

Editing is done independently for each visibility channel. First clipping is done on correlator and Vpol amplitudes. Following this, an average and RMS is determined for each channel in each timeAvg period and a spectral baseline is established for the average values, either using a median window filter (FDwidMW>0) or a linear baseline fit (FDwidMW<=0) to specified channels. Channels with excessive RMSes or residual amplitudes are flagged. Flagging is done by entering the offending data in FG table flagTab on outUV.

Control parameters on inUV info member

"flagTab" OBIT_int (1,1,1) FG table version number [def. 1]
"timeAvg" OBIT_float (1,1,1) Time interval over which to average data to be flagged (days) [def = 1 min.]

"FDmaxAmp" OBIT_float (1,1,1) Maximum average amplitude allowed in the spectrum before fitting. Any channel exceeding this is flagged in advance of the baseline fitting or median filtering, default = infinite

"FDmaxV" OBIT_float (1,1,1) Maximum average amplitude allowed in V polarization; any channel exceeding this is flagged in advance of the baseline fitting or median filtering, Calculates V from difference in amplitudes.

default = infinite

```
An odd number (5) is recommended, default or 0 => linear baseline
      "FDmaxRMS" OBIT_float (2,1,1) Flag all channels having RMS
                values > maxRMS[0] of the channel median sigma.[default = 6.]
                plus maxRMS[1] (default 0.1) of the channel average in quadrature
      "FDmaxRes" OBIT_float (1,1,1) Max. residual flux in sigma allowed for
                channels outside the baseline fitting regions.
                default = 6.
      "FDmaxResBL" OBIT_float (1,1,1) Max. residual flux in sigma allowed for
                channels within the baseline fitting regions.
                Default = FDmaxRes
      "FDbaseSel" OBIT_int (4,*,1) Channel selection to define spectral baseline
                Used only for linear baseline fitting.
                Select groups of channels/IF(s) to fit as sets
                of (Start, end, inc, IF), i.e., chanSel = 6,37,1,0,
                92,123,1,0 for two regions applying to all IFs.
                Channel and IF numbers 1 -rel
                The first group for which the end channel == 0 terminates the list
                Channel increments defaults to 1
                If the IF==0 then the group applies to all IF.
                Default is channels 2 => nchan-1 all IFs
    inUV
           = Python UV object to flag
             Any prior selection and editing is applied.
    outUV = UV data onto which the FG table is to be attached.
             May be the same as inUV.
           = Python Obit Error/message stack
    err
PEditStokes(inUV, outUV, err)
    Stokes editing of UV data, FG table out
       All data on a given baseline/correlator are flagged if the
    amplitude of the datatype "FlagStok" exceeds maxAmp.
    If a fraction of bad baselines on any antenna/channel/IF exceeds
    maxBad, then all data to that correlator is flagged.
    Flagging entries are written into FG table flagTab.
    Results are unpredictable for uncalibrated data.
    Control parameters on info member of inUV:
      "flagStok" OBIT_string (1,1,1) Stokes value to clip (I, Q, U, V, R, L)
                 default = "V"
      "flagTab" OBIT_int
                            (1,1,1) FG table version number [ def. 1]
                NB: this should not also being used to flag the input data!
      "timeAvg" OBIT_float (1,1,1) Time interval over which to determine
                data to be flagged (days) [def = 1 min.]
      "maxAmp" OBIT_float (1,1,1) Maximum VPol allowed
      "maxBad"
                OBIT_float (1,1,1) Fraction of allowed flagged baselines
                to an antenna above which all baselines are flagged.
                [default 0.25]
```

"FDwidMW" OBIT_int (1,1,1) If > 0 the width of the median window in channels.

```
May be the same as inUV.
```

inUV = Python UV object to clip/flag

outUV = UV data onto which the FG table is to be attached.

err = Python Obit Error/message stack

PEditTD(inUV, outUV, err)

Time-domain editing of UV data - produces FG table

Fill flagging table with clipping by RMS values of the real and imaginary parts. All correlations are clipped on each baseline if the RMS is larger than the maximum. The clipping is done independently in each time interval defined by timeAvg.

The clipping level is given by MIN (A, MAX (B,C)) where:

A = sqrt (maxRMS[0]**2 + (avg_amp * maxRMS[1])**2) and avg_amp is the average amplitude on each baseline.

B = median RMS + 3 * sigma of the RMS distribution.

C = level corresponding to 3% of the data.

All data on a given baseline/correlator are flagged if the RMS exceeds the limit. If a fraction of bad baselines on any correlator exceeds maxBad, then all data to that correlator is flagged. In addition, if the offending correlator is a parallel hand correlator then any corresponding cross hand correlations are also flagged. Flagging entries are written into FG table flagTab.

Control parameters on inUV info member

"flagTab" OBIT_int (1,1,1) FG table version number [def. 1]
"timeAvg" OBIT_float (1,1,1) Time interval over which to determine data to be flagged (days) [def = 1 min.]

NB: this should be at least 2 integrations.

"maxRMS" OBIT_float (2,1,1) Maximum RMS allowed, constant plus amplitude coefficient.

"maxBad" OBIT_float (1,1,1) Fraction of allowed flagged baselines [default 0.25]

inUV = Python UV object to clip/flag

outUV = UV data onto which the FG table is to be attached.

May be the same as inUV.

err = Python Obit Error/message stack

PFullInstantiate(inUV, access, err)

Fully instantiate an UV by opening and closing

return 0 on success, else failure

inUV = Python UV object

access = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE

err = Python Obit Error/message stack

PGetDesc(inUV)

Return the member UVDesc

```
returns UVDesc as a Python Dictionary
           = Python UV object
    inUV
PGetFreq(inUV, err)
   Get Frequency information
    inUV
           = Python UV object
              = Python Obit Error/message stack
    err
PGetHighVer(inUV, tabType)
    Get highest version number of a specified Table
   returns highest tabType version number, 0 if none.
    inUV = Python UV object
   tabType = Table type, e.g. "OTFSoln"
PGetList(inUV)
    Return the member InfoList
    returns InfoList
           = Python UV object
PGetName(inUV)
   Tells UV object name (label)
   returns name as character string
           = Python UV object
PGetSubA(inUV, err)
   Get Subarray information
   returns 0 on success, else 1
           = Python UV object
    inUV
              = Python Obit Error/message stack
PGetTable(inUV, access, tabType, tabVer, err, numOrb=0, numPCal=3,
        numIF=1, numPol=1, numTerm=0, numChan=1, numTones=1,
numBand=1, numTabs=1, npoly=1, numCoef=5, maxis1=2, maxis2=1,
        maxis3=1, maxis4=1, maxis5=1)
    Return (create) the specified associated table
    Specific table types are recognized and the appropriate constructor
    called, these may have additional parameters. This allows creating
   new tables of the appropriate type.
   returns Python Obit Table
    inUV
            = Python UV object
    access = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE
```

```
tabType = Table type, e.g. "AIPS AN"
    tabVer
             = table version, if > 0 on input that table returned,
               if 0 on input, the highest version is used.
    err
             = Python Obit Error/message stack
    Optional parameters, values only used if table created
             = Number of orbital parameters (AN)
    numOrb
    numPCal = Number of polarization parameters (AN)
    numIF
            = Number of IFs (FQ, SN, CL, BP, BL, TY, CQ)
    numPol = Number of Stokes' (SN, CL, BP, BL, PC, TY, GC, MC, IM)
    numTerm = Number of terms in model polynomial (CL)
    numChan = Number of spectral channels (BP)
    numTomes = Number of Phase cal tones (PC)
    numTabs = Number of ??? (GC)
   numCoef = Number of polynomial coefficents (NI)
   numBand = Number Bands(?) (IM, GC)
    npoly = number of polynomial terms (IM)
    maxis1-5 = Dimension of axes of IDI data matrix
PGetTableList(inUV)
    Return the member tableList
    returns tableList
          = Python UV object
PGetVisBuf(inUV)
PHeader(inUV, err)
   Print data descriptor
             = Python Obit UV object
    inUV
             = Python Obit Error/message stack
    err
PIsA(inUV)
    Tells if input really a Python Obit UV
   return true, false (1,0)
          = Python UV object
PIsScratch(inUV)
   Tells if UV is a scratch object
   return true, false (1,0)
    inUV
          = Python UV object
PNewUVTable(inUV, access, tabType, tabVer, err)
    Obsolete use PGetTable
POpen(inUV, access, err)
```

```
Open an image persistent (disk) form
    inUV
           = Python UV object
              = access 1=READONLY, 2=WRITEONLY, 3=READWRITE
    access
    err
              = Python Obit Error/message stack
PRename(inUV, err, newFITSName=None, newAIPSName='
        newAIPSClass='
                           ', newAIPSSeq=0)
   Rename underlying files
           = Python UV object
    inUV
              = Python Obit Error/message stack
    err
   For FITS files:
    newFITSName = new name for FITS file
   For AIPS:
    newAIPSName = New AIPS Name (max 12 char) Blank => don't change.
   newAIPSClass = New AIPS Class (max 6 char) Blank => don't change.
    newAIPSSeq = New AIPS Sequence number, 0 => unique value
PScratch(inUV, err)
    Create a scratch file suitable for accepting the data to be read from inUV
    A scratch UV is more or less the same as a normal UV except that it is
    automatically deleted on the final unreference.
    inUV
              = Python UV object
              = Python Obit Error/message stack
    err
PUVInfo(inUV, err)
    Get file info for extant uv data object
   Fills in information on object, useful for scratch files
    inUV
           = Python UV object
           = Python Obit Error/message stack
    err
PUpdateDesc(inUV, err, Desc=None)
    Update external representation of descriptor
           = Python UV object
    inUV
           = Python Obit Error/message stack
    err
           = UV descriptor, if None then use current descriptor
   Desc
             Contents can be accessed throuth the Dict member
PUpdateTables(inUV, err)
    Update any disk resident structures about the current tables
              = Python UV object
    inUV
    err
              = Python Obit Error/message stack
```

```
PUtilAvgF(inUV, outUV, err, scratch=False, NumChAvg=0, doAvgAll=False, ChanSel=None)
    Average A UV data set in Frequency
    returns Averaged UV data object
           = Python UV object to copy
             Any selection editing and calibration applied before average.
    outUV = Predefined UV data if scratch is False, ignored if
             scratch is True.
    err
           = Python Obit Error/message stack
    scratch = True if this is to be a scratch file (same type as inUV)
    NumChAvg = Number of channels to average, [def.0 = all]
    doAvgAll = If TRUE then average all channels and IF.
    ChanSel = Groups of channels to consider (relative to channels &
                IFs selected by BChan, EChan, BIF, EIF)
                (start, end, increment, IF) as array of tuples
                where start and end at the beginning and ending
                channel numbers (1-rel) of the group to be included,
                increment is the increment between selected channels
                and IF is the IF number (1-rel)
                default increment is 1, IF=0 means all IF.
                Default is all channels in each IF.
                Example [(3,14,1,0),(25,30,1,0)] averages channels
                3 through 14 and 25 through 30 in each IF.
PUtilAvgT(inUV, outUV, err, scratch=False, timeAvg=1.0)
    Average A UV data set in Time
    returns Averaged UV data object
          = Python UV object to copy
             Any selection editing and calibration applied before average.
    outUV = Predefined UV data if scratch is False, ignored if
             scratch is True.
           = Python Obit Error/message stack
    err
    scratch = True if this is to be a scratch file (same type as inUV)
    timeAvg = Averaging time in min
PUtilCopyZero(inUV, scratch, outUV, err)
    Copy a UV data set replacing data by zero, weight 1
    returns UV data object
           = Python UV object to copy
    scratch= True if this is to be a scratch file (same type as inUV)
    outUV = Predefined UV data if scratch is False
             ignored if scratch True.
           = Python Obit Error/message stack
    err
PUtilCount(inUV, err, timeInt=1440.0)
```

Each new source starts a new interval returns a dist with entries: numTime = Number of time intervals numCorr = Number of Correlations per vis Count = Number of good correlation/visibilities Bad = Number of flagged correlation/visibilities Source = Source ID per interval (or 0 if no source ID) LST = Average LST (days) per interval inUV = Python UV object to copy Any selection editing and calibration applied before average. = Python Obit Error/message stack err timeInt = interval in min (max 500 intervals) PUtilIndex(inUV, err, maxScan=None, maxGap=None) Indexes a uv data inUV = Python UV object to index = Python Obit Error/message stack maxScan = max. scan length in min. [def. long] maxGap = max. scan gap in min. [def. long] PUtilUVWExtrema(inUV, err) Get UV coverage information returns array [0]=maximum baseline length (in U,V), [1] = maximum W inUV = Python UV object = Python Obit Error/message stack err PUtilVisCompare(in1UV, in2UV, err) Compares the visibilites in in1UV with those in in2UV returns RMS real, imaginary parts/amplitude = Numerator Python UV object in1UV = Denominator Python UV object in2UV err = Python Obit Error/message stack PUtilVisDivide(in1UV, in2UV, outUV, err) Divides the visibilites in in1UV by those in in2UV outUV = in1UV / in2UV in1UV = Numerator Python UV object, no calibration/selection = Denominator Python UV object in2UV outUV = Output python UV object = Python Obit Error/message stack

Count data values by interval in a UV dataset

PUtilVisSub(in1UV, in2UV, outUV, err) Subtracts the visibilites in in2UV from those in in1UV outUV = in1UV - in2UV in1UV = First python UV object, no calibration/selection = Second python UV object, calibration allowed in2UV = Output Python UV object, may be same as in1UV outUV = Python Obit Error/message stack err PZap(inUV, err) Delete underlying files and the basic object. inUV = Python UV object = Python Obit Error/message stack err PZapTable(inUV, tabType, tabVer, err) Destroy specified table Returns 0 on success inUV= Python UV object tabType = Table type, e.g. "AIPS AN" tabVer = table version, integer err = Python Obit Error/message stack newPACNO(disk, cno, exists, err, verbose=True, nvis=1000) Create and initialize an AIPS based UV structure Create, set initial access information and if exists verifies the file. Sets buffer to hold 1000 vis. Returns the Python UV object isOK member set to indicate success disk = AIPS directory number = AIPS catalog number cno exists = if true then the file is opened and closed to verify = Python Obit Error/message stack verbose = If true any give error messages, else suppress = Number of visibilities read/written per call nvis newPAUV(name, Aname, Aclass, disk, seq, exists, err, verbose=True, nvis=1000) Create and initialize an AIPS based UV structure Create, set initial access information (full image, plane at a time) and if exists verifies the file. Sets buffer to hold 1000 vis. Returns the Python UV object isOK member set to indicate success = name desired for object (labeling purposes)

```
Aname = AIPS name of file
Aclass = AIPS class of file
```

seq = AIPS sequence number of file

disk = FITS directory number

exists = if true then the file is opened and closed to verify

err = Python Obit Error/message stack

verbose = If true any give error messages, else suppress
nvis = Number of visibilities read/written per call

newPFUV(name, filename, disk, exists, err, verbose=True, nvis=1000)
Create and initialize an FITS based UV structure

Create, set initial access information (full image, plane at a time) and if exists verifies the file.

Sets buffer to hold 1000 vis.

Returns the Python UV object

isOK member set to indicate success

name = name desired for object (labeling purposes)

filename = name of FITS file
disk = FITS directory number

exists = if true then the file is opened and closed to verify

err = Python Obit Error/message stack

verbose = If true any give error messages, else suppress
nvis = Number of visibilities read/written per call

1.14.3 Obit python OTF class

To access the OTF class, your PYTHONPATH variable should include the ObitSD/python directory before the Obit/python directory. Then in ObitTalk:

```
>>>> import OTF
```

to make the OTF classes available. Further functions are available in the OTFUtil, CCBUtil, Clean-OTF, Clean-OTFRec,GBTDCROTF, OTFGetAtmCor, OTFGetSoln, and OTFSoln2Cal python modules. The following describes the OTF class.

NAME

OTF - Python Obit "On-the-fly" (OTF) single dish data class

DESCRIPTION

This class contains single dish data and allows access.

An ObitOTF is the front end to a persistent disk resident structure.

There maybe (usually are) associated tables which either describe

the data or contain calibration and/or editing information.

OTF Members with python interfaces:

List - used to pass instructions to processing

Desc - Astronomical labeling of the image

TableList - List of tables attached

```
RecBuf
          - memory pointer into I/O Buffer
```

Additional Functions are available in OTFUtil, OTFSoln2Cal, OTFGetSoln, OTFGetAtmCor, CleanOTF

There are a number of utility routines in this module which take control parameters in the form of python dictionaries (e.g. AtmCal, Clean, Concat, Image, ResidCal, Soln2Cal, Split) which each have defined dictionaries with default values and names of the routine and "Input" appended.

Care should he taken not to change the data types of the entries in these dictionaries.

These dictionaries can be listed in semi human readable form using the OTF.input function.

```
Data selection, calibration and editing parameters on List member
  "doCalSelect" bool (1,1,1) Select/calibrate/edit data?
  "doCalib"
                int (1,1,1) > 0 \rightarrow calibrate,
  "gainUse"
                int (1,1,1) SN/CL table version number, 0-> use highest
  "flagVer"
                int (1,1,1) Flag table version, 0-> use highest, <0-> none
  "BChan"
                int (1,1,1) First spectral channel selected. [def all]
  "EChan"
                int (1,1,1) Highest spectral channel selected. [def all]
  "Targets"
                string (?,?,1) Target names selected. [def all]
  "timeRange"
                float (2,1,1) Selected timerange in days. [def all]
  "Scans"
                int (2,1,1) Lowest and highest selected scan numbers. [def all]
                int (?,1,1) a list of selected feed numbers, [def all.]
  "Feeds"
                bool (1,1,1) If true keep cal-on data, otherwise drop [def True.]
  "keepCal"
OData.OData(OData.ODataPtr)
    OTF
```

CLASSES

```
class OTF(OData.OData)
```

Python Obit "On-the-fly" (OTF) single dish data class

This class contains single dish data and allows access. An ObitOTF is the front end to a persistent disk resident structure. There maybe (usually are) associated tables which either describe the data or contain calibration and/or editing information.

OTF Members with python interfaces:

- used to pass instructions to processing

- Astronomical labeling of the image

TableList - List of tables attached

- memory pointer into I/O Buffer

Method resolution order:

OTF

```
OData.ODataPtr
Methods defined here:
Clone(self, outOTF, err)
    Make a copy of a object but do not copy the actual data
    This is useful to create an OTF similar to the input one.
          = Python OTF object
    outOTF = Output Python OTF object, must be defined
           = Python Obit Error/message stack
    err
Close(self, err)
    Close a OTF persistent (disk) form
    returns 0 on success, else failure
             = Python OTF object
    self
              = Python Obit Error/message stack
    err
Copy(self, outOTF, err)
    Make a deep copy of input object.
    Makes structure the same as self, copies data, tables
           = Python OTF object to copy
    outOTF = Output Python OTF object, must be defined
           = Python Obit Error/message stack
    err
Header(self, err)
    Write image header on output
    self
           = Python Obit OTF object
    err
           = Python Obit Error/message stack
Info(self, err)
    Get underlying data file info
    self
           = Python Obit OTF object
           = Python Obit Error/message stack
NewTable(self, access, tabType, tabVer, err, numDet=1,
        numPoly=0, numParm=0)
    Return the specified associated table
    self
            = Python OTF object
    access = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE
    tabType = Table type, e.g. "OTFSoln"
    tabVer
             = table version, if > 0 on input that table returned,
```

OData.OData

```
if 0 on input, the highest version is used.
    err
              = Python Obit Error/message stack
    Optional parameters, values only used if table created
    numDet
             = Number of Detectors (OTFCal, OTFSoln, OTFScanData)
    numPoly = Number of polynomial terms (OTFCal, OTFSoln)
    numParm
              = Number of model parameters (OTFModel)
OTFIsA(self)
    Tells if input really a Python Obit OTF
    return true, false (1,0)
    self
           = Python OTF object
Open(self, access, err)
    Open a OTF data persistent (disk) form
    Returns 0 on success, else failure
          = Python OTF object
    access = access READONLY (1), WRITEONLY (2), READWRITE(3)
           = Python Obit Error/message stack
Read(self, err)
    Read a OTF persistent (disk) form
    Reads into buffer attached to OTF data, use VisBuf for access
    Returns 0 on success, else failure
           = Python OTF object
    self
           = Python Obit Error/message stack
    err
ReadRec(self, err)
    Read a OTF persistent (disk) form
    Returns OTFRec structure from next record
          = Python OTF object
    self
          = Python Obit Error/message stack
    err
Scratch(self, err)
    Create a scratch file suitable for accepting the data to be read from self
    A scratch OTF is more or less the same as a normal OTF except that it is
    automatically deleted on the final unreference.
              = Python OTF object
    self
    err
              = Python Obit Error/message stack
UpdateDesc(self, err, Desc=None)
    Update any disk resident structures about descriptor
    self
              = Python OTF object
```

```
= Python Obit Error/message stack
    err
              = Descriptor, if None then use current descriptor
    Desc
                Contents can be accessed throuth the Dict member
Write(self, err)
    Write a OTF persistent (disk) form
    Writes buffer attached to OTF data, use VisBuf for access
    returns 0 on success, else failure
    self
              = Python OTF object
              = Python Obit Error/message stack
    err
WriteRec(self, outRec, err)
    Write a OTF persistent (disk) form
    Writes buffer attached to OTF data, use VisBuf for access
    returns 0 on success, else failure
    self
              = Python OTF object
              = OTFRec structure to write
    outRec
              = Python Obit Error/message stack
    err
  __del__(self)
__getattr__(self, name)
__init__(self, name)
__repr__(self)
__setattr__(self, name, value)
cast(self, toClass)
    Casts object pointer to specified class
    self
             = object whose cast pointer is desired
    toClass = Class string to cast to ("ObitOTF")
Methods inherited from OData.OData:
CopyTables(self, outOData, exclude, include, err)
    Copy Tables from one OData to another
    self
              = Python OData object
                 = Output Python OData object, must be defined
    outOData
    exclude
            = list of table types to exclude (list of strings)
    has priority
    include
             = list of table types to include (list of strings)
```

```
= Python Obit Error/message stack
    err
    Mark OData as needing a header update to disk file
    self
             = Python OData object
FullInstantiate(self, access, err)
    Fully instantiate an OData by opening and closing
    return 0 on success, else failure
    self = Python OData object
             = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE
    access
              = Python Obit Error/message stack
GetHighVer(self, tabType)
    Get highest version number of a specified Table
           returns highest tabType version number, 0 if none.
    self
          = Python OData object
    tabType = Table type, e.g. "OTFSoln"
GetName(self)
    Tells OData object name (label)
   returns name as character string
    self = Python OData object
History(self, access, err)
    Return the associated History
            = Python OData object
    self
    access = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE
             = Python Obit Error/message stack
    err
IsScratch(self)
    Tells if OData is a scratch object
    return true, false (1,0)
          = Python OData object
ODataIsA(self)
    Tells if input really a Python Obit OData
   return true, false (1,0)
          = Python OData object
Rename(self, err, newFITSName=None, newAIPSName=' ',
        newAIPSClass='
                           ', newAIPSSeq=0)
   Rename underlying files
```

```
= Python Obit Error/message stack
           err
           For FITS files:
           newFITSName = new name for FITS file
           For AIPS:
           newAIPSName = New AIPS Name (max 12 char) Blank => don't change.
           newAIPSClass = New AIPS Class (max 6 char) Blank => don't change.
           newAIPSSeq = New AIPS Sequence number, 0 => unique value
      UpdateTables(self, err)
           Update any disk resident structures about the current tables
           Returns 0 on success
           self = Python Image object
                   = Python Obit Error/message stack
           err
       Zap(self, err)
           Delete underlying files and the basic object.
                     = Python OData object
           self
                     = Python Obit Error/message stack
           err
       ZapTable(self, tabType, tabVer, err)
           Destroy specified table
          Returns 0 on success
           self
                   = Python OData object
           tabType = Table type, e.g. "AIPS CC"
           tabVer = table version, integer
               = Python Obit Error/message stack
           err
FUNCTIONS
    AtmCal(err, input= AtmCalInput )
        Basic atmospheric calibration.
        Applies Atmospheric calibration and optionally gross pointing offsets
        Returns the version number of the Soln Table on success.
                = Python Obit Error/message stack
        err
                = input parameter dictionary
        input
        Input dictionary entries:
        InData = input Python OTF to calibrate
        solint = solution interval (sec)
        tau0 = zenith opacity (nepers)
       minEl = minimum elevation (deg)
        tTemp = effective atmospheric temperature (per detector)
```

self

= Python OData object

```
tRx
           = Receiver temperature per detector (K)
    calJy = Noise cal value in Jy per detector
    raOff = RA pointing offset (deg)
    decOff = Dec pointing offset (deg)
ClearCal(inOTF, err)
    Delete calibration tables on an OTF
    Removes all OTFSoln and OTFCal tables
    inOTF
            = Extant Python OTF
            = Python Obit Error/message stack
    err
Concat(err, input={'InData': None, 'OutData': None})
    Concatenates OTFs.
    Applies Copies InData to the end of OutData.
    The files must be compatable (not checked)
    err
            = Python Obit Error/message stack
            = input parameter dictionary
    input
    Input dictionary entries:
    InData = Python input OTF to calibrate
    OutData = Python output OTF, must be previously defined
MBBaseCal(err, input=MBBaseCalInput)
    Continuum baseline fitting for multibeam instrument.
   Fit one term, time variable common, atmospheric polynomial and a single offset
    per detector.
    Since the different detectors each have an individual multiplicative term, the
    Atmospheric + offset are places in the the detector's additive term and the
    polynomial is set to zero.
    Scans in excess of 5000 samples will be broken into several.
    Returns the version number of the Soln Table on success.
    err
            = Python Obit Error/message stack
    input
            = input parameter dictionary
    Input dictionary entries:
    InData = input Python OTF to calibrate
    solint = solution interval (sec), entries 4 times per SolInt
    order = polynomial order
    clipsig = Data outside of +/- clipsig ignored [def large]
    plotdet = Detector number (1-rel) to plot per scan [def =-1 = none]
          = minimum elevation (deg)
    gainuse = version number of prior table (Soln or Cal) to apply, -1 is none
    flagver = version number of flagging table to apply, -1 is none
```

Return name of an Obit object or input if not an Obit Object

PClone(inOTF, outOTF, err)

Make a copy of a object but do not copy the actual data

This is useful to create an OTF similar to the input one.

inOTF = Python OTF object

outOTF = Output Python OTF object, must be defined

err = Python Obit Error/message stack

PClose(inOTF, err)

Close an image persistent (disk) form

inOTF = Python OTF object

err = Python Obit Error/message stack

PConcat(inOTF, outOTF, err)

Copy data from inOTF to the end of outOTF

inOTF = Python OTF object

outOTF = Output Python OTF object, must be defined

err = Python Obit Error/message stack

PCopy(inOTF, outOTF, err)

Make a deep copy of input object.

Makes structure the same as inOTF, copies data, tables

inOTF = Python OTF object to copy

outOTF = Output Python OTF object, must be defined

err = Python Obit Error/message stack

PCopyTables(inOTF, outOTF, exclude, include, err)

Copy Tabels from one image to another

inOTF = Python OTF object

outOTF = Output Python OTF object, must be defined

exclude = list of table types to exclude (list of strings)

has priority

include = list of table types to include (list of strings)

err = Python Obit Error/message stack

PDirty(inOTF)

Mark OTF as needing a header update to disk file

inOTF = Python OTF object

PFullInstantiate(inOTF, access, err)

Fully instantiate an OTF by opening and closing

```
return 0 on success, else failure
            = Python OTF object
   inOTF
           = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE
    access
             = Python Obit Error/message stack
PGetDesc(inOTF)
    Return the member OTFDesc
   returns OTFDesc as a Python Dictionary
           = Python OTF object
    inOTF
PGetHighVer(inOTF, tabType)
   Get highest version number of a specified Table
   returns highest tabType version number, 0 if none.
    inOTF
             = Python OTF object
    tabType = Table type, e.g. "OTFSoln"
PGetList(inOTF)
   Return the member InfoList
   returns InfoList
           = Python OTF object
    inOTF
PGetName(inOTF)
   Tells OTF object name (label)
   returns name as character string
    inOTF = Python OTF object
PGetRecBuf(inOTF)
PGetTableList(inOTF)
   Return the member tableList
   returns tableList
    inOTF = Python OTF object
PHeader(inOTF, err)
   Print data descriptor
              = Python Obit OTF object
             = Python Obit Error/message stack
    err
PIsA(inOTF)
    Tells if input really a Python Obit OTF
```

```
return true, false (1,0)
    inOTF
             = Python OTF object
PIsScratch(inOTF)
    Tells if OTF is a scratch object
   return true, false (1,0)
    inOTF
           = Python OTF object
PNewOTFTable(inOTF, access, tabType, tabVer, err, numDet=1, numPoly=0, numParm=0)
   Return the specified associated table
    inOTF
             = Python OTF object
             = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE
    access
    tabType = Table type, e.g. "OTFSoln"
    tabVer
             = table version, if > 0 on input that table returned,
                if 0 on input, the highest version is used.
    err
              = Python Obit Error/message stack
        Optional parameters, values only used if table created
        numDet
                 = Number of Detectors (OTFCal, OTFSoln, OTFScanData)
        numPoly = Number of polynomial terms (OTFCal, OTFSoln)
        numParm = Number of model parameters (OTFModel)
POTFInfo(inOTF, err)
   Get file info for extant uv data object
   Fills in information on object, useful for scratch files
    inOTF
           = Python OTF object
           = Python Obit Error/message stack
POpen(inOTF, access, err)
    Open an image persistent (disk) form
   Returns 0 on success, else failure
            = Python OTF object
    inOTF
    access = access 1=READONLY, 2=WRITEONLY, 3=READWRITE
    err
              = Python Obit Error/message stack
PRename(inOTF, err, newFITSName=None)
   Rename underlying files
            = Python OTF object
    inOTF
              = Python Obit Error/message stack
    err
    For FITS files:
    newFITSName = new name for FITS file
PScratch(inOTF, err)
```

Create a scratch file suitable for accepting the data to be read from inOTF

A scratch OTF is more or less the same as a normal OTF except that it is automatically deleted on the final unreference.

inOTF = Python OTF object

err = Python Obit Error/message stack

PSetTarget(inOTF, Target, Flux, RA, Dec, err) Set target flux density and position

inOTF = Python OTF object

Target = Target name

Flux = Target Flux density

RA = RA in deg at mean equinox and epoch

Dec = Dec in deg at mean equinox and epoch

err = Python Obit Error/message stack

PUpdateDesc(inOTF, err, Desc=None)

Update external representation of descriptor

inOTF = Python OTF object

err = Python Obit Error/message stack

Desc = OTF descriptor, if None then use current descriptor

PUpdateTables(inOTF, err)

Update any disk resident structures about the current tables

inOTF = Python OTF object

err = Python Obit Error/message stack

PZap(inOTF, err)

Delete underlying files and the basic object.

inOTF = Python OTF object

err = Python Obit Error/message stack

PZapTable(inOTF, tabType, tabVer, err)

Destroy specified table

inOTF = Python OTF object

tabType = Table type, e.g. "OTFSoln"
tabVer = table version, integer

err = Python Obit Error/message stack

PolyBLCal(err, input=PolyBLCalInput)

Polynomial baseline fit to residual data

Each solution interval in a scan is median averaged (average of 9 points around the median) and then a polynomial fitted.

```
Returns the version number of the Soln Table on success.
            = Python Obit Error/message stack
    input
            = input parameter dictionary
    Input dictionary entries:
    InData = input Python OTF to calibrate
    solint = solution interval (sec)
    order = polynomial order
    minEl = minimum elevation (deg)
    gainuse = version number of prior table (Soln or Cal) to apply, -1 is none
    flagver = version number of flagging table to apply, -1 is none
ResidCal(err, input=ResidCalInput)
    Determine residual calibration for an OTF.
    Determines a solution table for an OTF by one of a number of techniques using
   residuals from a model image.
    Returns the version number of the Soln Table on success.
            = Python Obit Error/message stack
    input
            = input parameter dictionary
    Input dictionary entries:
    InData = Python input OTF to calibrate
            = Python input model FArray, "None" means do not subtract model image
    ModelDesc= Python input model ImageDesc
    minFlux = Minimum brightness in model
    solint = solution interval (sec)
    solType = solution type:
       "Gain" solve for multiplicative term from "cals" in data.
             (solint, minRMS, minEl, calJy)
       "Offset" Solve for additive terms from residuals to the model.
             (solint, minEl)
       "GainOffset" Solve both gain and offset
             (solint, minRMS, minEl, calJy)
       "Filter" Additive terms from filters residuals to the model.
             (solint, minEl)
        "multiBeam" Multibeam solution
             (solint, minEl)
    minEl = minimum elevation (deg)
    minRMS = Minimum RMS residual to solution
    calJy = Noise cal value in Jy per detector
    gainuse = version number of prior table (Soln or Cal) to apply, -1 is none
    flagver = version number of flagging table to apply, -1 is none
SelfCal(err, ImageInp=ImageInput, Soln2CalInp=Soln2CalInput)
    Self calibrate an OTF
```

Image an OTF, optionally Clean, determine residual calibration,

apply to Soln to Cal table. If the Clean is done, then the CLEAN result is used as the model in the ResidCal, otherwise the dirty image from Image is. = Python Obit Error/message stack ImageInp = input parameter dictionary for Image = input parameter dictionary for Clean, "None"-> no Clean requested CleanInp May be modified to point to the result of the Image step ResidCalInp = input parameter dictionary for ResidCal Will be modified to give correct derived model image Soln2CalInp = input parameter dictionary for Soln2Cal Soln2Cal(err, input=Soln2CalInput) Apply a Soln (solution) table to a Cal (calibration) table. = Python Obit Error/message stack err input = input parameter dictionary Input dictionary entries: InData = Python input OTF to calibrate = Soln table version number to apply, 0-> high oldCal = input Cal table version number, -1 means none, 0->high newCal = output Cal table version number, 0->new Split(err, input=SplitInput) Select and calibrate an OTF writing a new one. Applies calibration and editing/selection to inData and writes outData. = Python Obit Error/message stack err input = input parameter dictionary Input dictionary entries: InData = input Python OTF to calibrate OutData = output Python OTF, must be previously defined average = if true average in frequency gainuse = version number of prior table (Soln or Cal) to apply, -1 is none flagver = version number of flagging table to apply, -1 is none Print the contents of an input Dictionary

input(inputDict)

inputDict = Python Dictionary containing the parameters for a routine There should be a member of the dictionary ('structure') with a value being a list containing:

- 1) The name for which the input is intended (string)
- 2) a list of tuples consisting of (parameter name, doc string) with an entry for each parameter in the dictionary. The display of the the inputs dictionary will be in the order of the tuples and display the doc string after the value. An example:

```
Soln2CalInput={'structure':['Soln2Cal',[('InData','Input OTF'),
                                                ('soln', 'input soln table version'),
                                                ('oldCal', 'input cal table version, -1=none
                                                ('newCal', 'output cal table')]],
                      'InData':None, 'soln':0, 'oldCal':-1, 'newCal':0}
makeImage(err, input=ImageInput)
    Image an OTF.
    Data is convolved and resampled onto the specified grid.
    Image is created and returned on success.
            = Python Obit Error/message stack
    err
    input
            = input parameter dictionary
    Input dictionary entries:
    InData = input Python OTF to image
    OutName = name of output image file
    Disk
           = disk number for output image file
            = center RA (deg)
    ra
           = center Dec (deg)
    dec
            = number of pixels in "x" = RA
    nx
            = number of pixels in 'Y' = dec
    ny
    xCells = Cell spacing in x (asec)
    yCells = Cell spacing in y (asec)
          = minimum summed weight in gridded image [def 0.1]
    minWt
    ConvType= Convolving function Type 0=pillbox,3=Gaussian,4=exp*sinc,5=Sph wave
    ConvParm= Convolving function parameters depends on ConvType
      Type 2 = Sinc, (poor function - don't use)
        Parm[0] = halfwidth in cells,
        Parm[1] = Expansion factor
      Type 3 = Gaussian,
        Parm[0] = halfwidth in cells, [def 3.0]
        Parm[1] = Gaussian with as fraction or raw beam [def 1.0]
      Type 4 = Exp*Sinc
        Parm[0] = halfwidth in cells, [def 2.0]
        Parm[1] = 1/sinc factor (cells) [def 1.55]
        Parm[2] = 1/exp factor (cells) [def 2.52]
        Parm[3] = exp power [def 2.0]
      Type 5 = Spherodial wave
        Parm[0] = halfwidth in cells [def 3.0]
        Parm[1] = Alpha [def 5.0]
        Parm[2] = Expansion factor [not used]
    gainuse = version number of prior table (Soln or Cal) to apply, -1 is none
    flagver = version number of flagging table to apply, -1 is none
    doBeam = Beam convolved with convolving Fn image desired? [def True]
            = Actual instrumental Beam to use, else Gaussian [def None]
    Beam
    Beam
```

```
newPOTF(name, filename, disk, exists, err, nrec=1000)
        Create and initialize an OTF structure
        Create, set initial access information (nrec records)
        and if exists verifies the file.
        Returns the Python OTF object
                 = name desired for object (labeling purposes)
        name
        filename = name of FITS file
        disk
               = FITS directory number
        exists = if true then the file is opened and closed to verify
                = Python Obit Error/message stack
        nrec
                = Number of records read/written per call
DATA
   AtmCalInput = {'InData': None, 'aTemp': [0.0, 0.0], 'calJy': [1.0, 1.0...
   ConcatInput = {'InData': None, 'OutData': None}
    MBBaseCalInput = {'InData': None, 'clipsig': 1e+20, 'flagver': -1, 'ga...
   PolyBLCalInput = {'InData': None, 'flagver': -1, 'gainuse': -1, 'minEl...
   ResidCalInput = {'Clip': 1e+20, 'InData': None, 'Model': None, 'ModelD...
   Soln2CalInput = {'InData': None, 'newCal': 0, 'oldCal': -1, 'soln': 0,...
   SplitInput = {'InData': None, 'OutData': None, 'average': 0, 'flagver'...
1.14.4
        Obit python Table Class
Obit Table class objects can be created as shown in the following:
inUV=UV.newPAUV("UV", "20050415", "LINE", 1, 1, True, err)
tabType="AIPS SU"
tabVer=1
access=UV.READONLY
su = inUV.NewTable(access,tabType,tabVer,err)
If a new table is being created, some optional parameters may be needed depending on the table
type (see help(UV) description of NewTable).
   The table header (descriptor) can be obtained as a python Dict:
h = su.Desc.Dict
   Data from a row in the table can be obtained as a python Dict:
su.Open(access,err)
row1 = su.ReadRow(access,err)
OErr.printErrMsg(err, "Error reading")
su.Close(err)
print "row1",row1
   Note: these dict structures are independent of the underlying data structures.
   The following describes the Obit Table class.
NAME
```

Table - Python Obit Table class

DESCRIPTION

This class contains tabular data and allows access. An ObitTable is the front end to a persistent disk resident structure. Both FITS (as Tables) and AIPS cataloged data are supported. Table Members with python interfaces: InfoList - used to pass instructions to processing Table header keywords for specific table types are available in the keys member of a Table after the table has been opened. These will be updated to disk when the table is closed. CLASSES TablePtr Table class Table(TablePtr) Methods defined here: Close(self, err) Close an table persistent (disk) form Specific table type keywords are written from the "keys" dict member = Python Table object self = Python Obit Error/message stack err Open(self, access, err) Open an table persistent (disk) form Specific table type keywords are written to the "keys" dict member = Python Table object self = access READONLY (1), WRITEONLY (2), READWRITE(3) access = Python Obit Error/message stack err ReadRow(self, rowno, err) Read a specified row in a table and returns as a python Dict = Python Image object self = row number (1-rel) to read rowno = Python Obit Error/message stack WriteRow(self, rowno, rowDict, err) Write an image persistent (disk) form from a specified Dict Writes a single row self = Python Image object

= row number (1-rel) to write

rowno

```
rowDict = Python Dict of same form as returned by PReadRow
                   = Python Obit Error/message stack
          err
      Zap(self, err)
          Delete underlying files and the basic object.
          self
                   = Python Table object
                   = Python Obit Error/message stack
          err
      __del__(self)
      __init__(self, name)
        _____
      Methods inherited from TablePtr:
      __getattr__(self, name)
      __repr__(self)
      __setattr__(self, name, value)
   class TablePtr
      Methods defined here:
      __getattr__(self, name)
      __init__(self, this)
      __repr__(self)
      __setattr__(self, name, value)
FUNCTIONS
   PClone(inTab, outTab)
       Copy the structure of a Table
       inTab
                = input Python Table
               = extant output Python Obit Table or None
       outTab
   PClose(inTab, err)
       Close a table persistent (disk) form
       Specific table type keywords are written from the "keys" dict member
                = Python Table object
       inTab
                = Python Obit Error/message stack
       err
   PConcat(inTab, outTab, err)
```

Copy row data from inTab to the end of outTab

inTab = input Python Obit Table

outTab = extant output Python Obit Table
err = Python Obit Error/message stack

PCopy(inTab, outTab, err)

Copy a Table including persistent forms

inTab = input Python Obit Table

outTab = extant output Python Obit Table
err = Python Obit Error/message stack

PDirty(inTable)

Mark Table as needing a header update to disk file

inTable = Python Table object

PFullInstantiate(inTab, access, err)
Open and close to fully instantiate

return 0 on success, else failure
inTab = input Python Table

access = access code 1=READONLY, 2=WRITEONLY, 3=READWRITE

err = Python Obit Error/message stack

PGetDesc(inTab)

Return the TableDesc from a Table

returns TableDesc

inTab = input Python Table

PGetIODesc(inTab)

Return the TableDesc from a Table's IO member

returns TableDesc from IO member (disk resident version)

if the IO member is not defined a None is returned.

For most reliable results, this routine should be called when the table is opened with Write allowed.

inTab = input Python Table

PGetIOList(inTab)

Return the InfoList from a Table's IO member

returns InfoList from IO member (disk resident version) if the IO member is not defined a None is returned.

For most reliable results, this routine should be called when

the table is opened with Write allowed.

```
inTab
            = input Python Table
PGetList(inTab)
   Return the InfoList from a Table
    returns InfoList
    inTab
            = input Python Table
PGetName(inTab)
    Returns object name (label)
   return name string
            = input Python Table
    inTab
PGetVer(inTab)
   Get table version number
    returns table version number
            = input Python Table
    inTab
PIsA(inTab)
   Tells if object thinks it's a Python Obit Table
   return true, false (1,0)
            = input Python Table
    inTab
POpen(inTab, access, err)
    Open a table persistent (disk) form
    Specific table type keywords are written to the "keys" dict member
    inTab
            = Python Table object
    access = access READONLY (1), WRITEONLY (2), READWRITE(3)
    err
             = Python Obit Error/message stack
PReadRow(inTab, rowno, err)
    Read a specified row in a table and returns as a python Dict
    Dict has keys:
       "Table name" to give the name of the table
       Field named (column labels)
   data are returned as a list of the field data type.
    inTab
             = Python Table object
             = row number (1-rel) to read
    rowno
             = Python Obit Error/message stack
    err
PSort(inTab, colName, desc, err)
    Sort a table by contents of a column
```

```
inTab
                = input Python Obit Table to sort
        colName = Column name (e.g. "Time")
               = if true sort in descending order, else ascending
        err
                 = Python Obit Error/message stack
    PUnref(inTab)
        Decrement reference count
        Decrement reference count which will destroy object if it goes to zero
        Python object stays defined.
                = Python Table object
        inTab
    PWriteRow(inTab, rowno, rowDict, err)
        Write an image persistent (disk) form from a specified Dict
        Writes a single row
        inTab
                = Python Table object
                 = row number (1-rel) to write
        rowno
        rowDict = Python Dict of same form as returned by PReadRow
        err
                  = Python Obit Error/message stack
    PZap(inTab, err)
        Destroy the persistent form of a Table
        inTab
                 = input Python Obit Table
                 = Python Obit Error/message stack
        err
DATA
    READONLY = 1
    READWRITE = 3
    WRITEONLY = 2
```

1.15 ObitTalk Data Classes

The ObitTalk classes AIPSUVData, AIPSImage, FITSUVData and FITSImage allow local or remote access to AIPS and FITS Images and UV data. Functions in these data classes work for data on remote nodes. Details of these class interfaces can be viewed using:

```
>>> help(AIPSUVData)
>>> help(AIPSImage)
>>> help(FITSUVData)
>>> help(FITSImage)
```

1.15.1 AIPSUVData

```
class AIPSUVData(_AIPSData)
This class describes an AIPS UV data set.
```

Methods inherited from _AIPSData:

exists(self)

Check whether this image or data set exists.

Returns True if the image or data set exists, False otherwise.

getrow_table(self, type, version, rowno)
Get a row from an extension table.

Returns row ROWNO from version VERSION of extension table TYPE as a dictionary.

header(self)

Get the header for this image or data set.

Returns the header as a dictionary.

header_table(self, type, version)

Get the header of an extension table.

Returns the header of version VERSION of the extension table TYPE.

table(self, type, version)

table_highver(self, type)

Get the highest version of an extension table.

Returns the highest available version number of the extension table TYPE.

tables(self)

Get the list of extension tables.

verify(self)

Verify whether this image or data set can be accessed.

zap(self)

Destroy this image or data set.

zap_table(self, type, version)

Destroy an extension table.

Deletes version VERSION of the extension table TYPE. If VERSION is 0, delete the highest version of table TYPE. If VERSION is -1, delete all versions of table TYPE.

```
Properties inherited from _AIPSData:
  disk
      Disk where this data set is stored.
      lambdaself
 klass
      Class of this data set.
      lambdaself
 name
      Name of this data set.
      lambdaself
  seq
      Sequence number of this data set.
      lambdaself
 userno
      User number used to access this data set.
      lambdaself
1.15.2 AIPSImage
class AIPSImage(_AIPSData)
  This class describes an AIPS image.
 Methods defined here:
  display(self, dispURL='http://localhost:8765/RPC2')
      Display an image.
      Displays image on ObitView server on dispURL
      dispURL = URL of ObitView server on which to display
      Returns True if successful
 Methods inherited from _AIPSData:
  exists(self)
      Check whether this image or data set exists.
      Returns True if the image or data set exists, False otherwise.
```

getrow_table(self, type, version, rowno)
 Get a row from an extension table.

Returns row ROWNO from version VERSION of extension table TYPE as a dictionary.

header(self)

Get the header for this image or data set.

Returns the header as a dictionary.

header_table(self, type, version)

Get the header of an extension table.

Returns the header of version VERSION of the extension table TYPE .

table(self, type, version)

table_highver(self, type)

Get the highest version of an extension table.

Returns the highest available version number of the extension table TYPE.

tables(self)

Get the list of extension tables.

verify(self)

Verify whether this image or data set can be accessed.

zap(self)

Destroy this image or data set.

zap_table(self, type, version)

Destroy an extension table.

Deletes version VERSION of the extension table TYPE. If VERSION is 0, delete the highest version of table TYPE. If VERSION is -1, delete all versions of table TYPE.

Properties inherited from _AIPSData:

disk

Disk where this data set is stored.

lambdaself

```
klass
     Class of this data set.
      lambdaself
 name
     Name of this data set.
     lambdaself
 seq
      Sequence number of this data set.
      lambdaself
 userno
     User number used to access this data set.
     lambdaself
1.15.3 FITSUVData
class FITSUVData(_FITSData)
 This class describes an FITS UV data set.
 Methods inherited from _FITSData:
  exists(self)
      Check whether this image or data set exists.
      Returns True if the image or data set exists, False otherwise.
  getrow_table(self, type, version, rowno)
      Get a row from an extension table.
      Returns row ROWNO from version VERSION of extension table TYPE
      as a dictionary.
 header(self)
      Get the header for this image or data set.
     Returns the header as a dictionary.
 header_table(self, type, version)
     Get the header of an extension table.
      Returns the header of version VERSION of the extension table
```

TYPE.

```
table(self, type, version)
  table_highver(self, type)
      Get the highest version of an extension table.
      Returns the highest available version number of the extension
      table TYPE.
  tables(self)
      Get the list of extension tables.
  verify(self)
      Verify whether this image or data set can be accessed.
  zap(self)
      Destroy this image or data set.
  zap_table(self, type, version)
      Destroy an extension table.
      Deletes version VERSION of the extension table TYPE. If
      VERSION is 0, delete the highest version of table TYPE.
      VERSION is -1, delete all versions of table TYPE.
 Properties inherited from _FITSData:
  disk
     Disk where this data set is stored.
      lambdaself
  filename
      Filename of this data set.
      lambdaself
1.15.4 FITSImage
class FITSImage(_FITSData)
 This class describes an FITS image.
 Methods inherited from _FITSData:
  exists(self)
      Check whether this image or data set exists.
```

Returns True if the image or data set exists, False otherwise.

```
getrow_table(self, type, version, rowno)
    Get a row from an extension table.
    Returns row ROWNO from version VERSION of extension table TYPE
    as a dictionary.
header(self)
    Get the header for this image or data set.
    Returns the header as a dictionary.
header_table(self, type, version)
    Get the header of an extension table.
    Returns the header of version VERSION of the extension table
    TYPE.
table(self, type, version)
table_highver(self, type)
    Get the highest version of an extension table.
    Returns the highest available version number of the extension
    table TYPE.
tables(self)
    Get the list of extension tables.
verify(self)
    Verify whether this image or data set can be accessed.
zap(self)
    Destroy this image or data set.
zap_table(self, type, version)
    Destroy an extension table.
    Deletes version VERSION of the extension table TYPE. If
    VERSION is 0, delete the highest version of table TYPE. If
    VERSION is -1, delete all versions of table TYPE.
Properties inherited from _FITSData:
disk
    Disk where this data set is stored.
```

lambdaself

${\tt filename}$

Filename of this data set.

lambdaself