

物理实验数学中心

Physics Expeiment Center



Dielectric constant measurement

Li Bin

NJUPT


Purposes:

- 1. Handle the principles and method of the measurement of dielectric constants.
- 2. Learn the method of data processing.

Principles:


1. Measure the dielectric constant of solid dielectrics by alternating current bridge

In the air



$$C_1 = C_0 + C_{B1} + C_{F1}$$

Insert dielectric sample



$$C_2 = C_{\rm C} + C_{\rm B2} + C_{\rm F2}$$

We have these functions:

$$C_{\theta} = \frac{\varepsilon_{\theta} S}{D}$$

$$C_0 = \frac{\varepsilon_0 S}{D} \qquad C_C = \frac{\varepsilon_r \ \varepsilon_0 \ S}{t + \varepsilon_r \ (D-t)}$$

$$C_{\rm B1} = C_{B2} \qquad C_{\rm F1} = C_{\rm F2}$$

$$C_{\text{F1}} = C_{\text{F2}}$$

$$C_{\rm C} = C_2 - C_1 + C_0$$

$$\varepsilon_{r} = \frac{C_{\rm C} \cdot t}{\varepsilon_{0} S - C_{\rm C} (D - t)}$$

2. Calculations of dielectric constant and capacitance:

Vacuum dielectric constant \mathcal{E}_0 , S_0 is plate area, D is distance between plates, the capacitance \mathbb{C} is shown as:

$$C = \frac{\varepsilon_0 S_0}{D} + C_F$$


Set
$$C = y$$
, $\frac{1}{D} = x$

$$y = a + bx$$

We got
$$a = C_F$$
, $b = \varepsilon_0 S_0$
Finally, we have $\varepsilon_0 = b/S_0$

Instruments:

1, Solid electrode



2. Alternating current bridge

We choose 10kHz and read from 'DISPLAY A' section.



3. Solid dielectric sample

Solid samples are disk-shaped PTFE plastics, the material with high temperature resistance, corrosion resistance, high dielectric strength characteristics.



Steps and Contents:

1. Measure the dielectric constant of solid dielectrics by alternating current bridge

- (a). Measure the diameters of the sample as *d*, three times using Vernier caliper. Measure the thickness of sample as *t* three times using micrometer.
- (b). Let the two plates touch each other, and read the starting value of the micrometer as D_0 .
- (c). Set the distance of the plates as 5.500mm. Note that the real value in micrometer should be 5.500mm + D_0 . Read the capacitance data from 'DISPLAY A' section as C1.
- (d). Insert the sample carefully, read the capacitance again as C2.
- (e). Repeat steps (d) and (e) twice.



2. Measure the vacuum dielectric constant and capacitance

Remove the sample, set the palates distance to 1.000,

1.100 ... 1.900 mm, and

Read the corresponding capacitance *C*.

$$C = \frac{\varepsilon_0 S_0}{D} + C_F$$

Set x = 1/D, y = C

Calculate C_F and ε_0 using origin software.

Data processing:

Table I

Starting value
$$D_0 = _{\text{mm}}$$
, Distance $D = _{\text{5.000}}$ mm. $\varepsilon_0 = 8.85 \times 10^{-12} \text{F/m}$

	D/mm	d/mm	t/mm	S/mm ²	C ₀ /pf	C ₁ /pf	C ₂ /pf	C _C /pf	ε _r
1	5.000	44.18	3.95		2.70	18.90	21.73		
2		44.18	3.92			19.00	21.77		
3		44.17	3.94			19.10	21.75		
Average									

d: diameter of sample,t: thickness of sample,

$$S = \pi (d/2)^2$$

$$C_0 = \frac{\varepsilon_0 S}{D}$$

$$C_{\rm C} = C_2 - C_1 + C_0$$

$$\varepsilon_{r} = \frac{C_{\rm C} \cdot t}{\varepsilon_{0} S - C_{\rm C} (D - t)}$$


Table II

D/mm	1.000	1.100	1.200	1.300	1.400	1.500	1.600	1.700	1.800	1.900
1/D(mm-1)										
C/pF	29.75	28.22	26.93	25.95	25.25	24.42	23.44	22.83	22.39	21.78

$$C = \frac{\varepsilon_0 S_0}{D} + C_{\rm F}$$

Set x = 1/D, y = C, calculate ε_0 .

The Slope $K = \varepsilon_0 S_{\theta}$, $\varepsilon_0 = K / S_{\theta}$ The Intercept is C_F . Note: $S_0 = 21.61 \text{ cm}^2$.



END