Best Practices for Property Prediction from Molecular Simulations

Bryce C. Manubay,^{1,*} John D. Chodera,^{2,†} and Michael R. Shirts^{1,‡}

¹University of Colorado

²Computational Biology Program, Sloan Kettering Institute,

Memorial Sloan Kettering Cancer Center, New York, NY 10065, United States

(Dated: July 4, 2016)

This document describes a collected set of best practices for computing various physical properties from molecular simulations of liquid mixtures.

Keywords: best practices; molecular dynamics simulation; physical property computation

TODO LIST

I. PRELIMINARIES

Definitions

11

13

14

- V: Volume
- *U*: Total energy (including potential and kinetic, excluding external energy such as due to gravity, etc)
 - S: Entopy
- N: Number of particles
- T: Temperature
- P: Pressure
- k_B: Boltzmann constant
- β : $(k_B T)^{-1}$
- M: Molar mass
- ρ : Density (M/V)
- H: Enthalpy
 - G: Gibbs Free Energy (free enthalpy)
- A: Helmholtz Free Energy
- μ: Chemical potential
- D: Total dipole moment
- u: reduced energy
- f: reduced free energy

Macroscopically, the quantities V, U, N are constants (assuming the system is not perturbed in any way), as we assume that the fluctuations are essentially zero, and any uncertainty comes from our inability to measure that constant precisly. For a mole of compound (about 18 mL for water), the relative uncertainty in any of these quantites is about 10^{-12} , far lower than any thermodynamics experiment.

[JDC1]: This is a TODO item example.

However, in a molecular simulation, these quantites are not necessarily constant. For example, in a NVT simulation, U is allowed to vary. For a long enough simulation (assuming ergodicity, which can pretty much always be assumed with correct simulations and simple fluids), then the ensemble average value of $U = \langle U \rangle$ will be constant, and in the limit of large simulations/long time will converge to the macroscopic value U; at least, the macroscopic value of that given model, though perhaps not the U for the real system. In an NVT simulation, clearly V is constant. In a NPT simulation, however, V is a variable, and we must estimate what the macroscopic value would be with the ensemble estimate $\langle V \rangle$.

The quantities T,P, and μ are always constants in both simulation in experiment. There are a number of quantities that can be used to ESTIMATE these constants. For example, $\langle \frac{1}{3Nk_B} \sum_i m_i | v_i |^2 \rangle$, where m is the mass of each particle and $|v_i|$ is the magnitude of the velocity of each particle, is an estimator of T, and it's average will be equal to the temperature. But it is not the temperature. This quantity fluctuates, but the tempature remains constant; otherwise the simulation could not be at constant temperature.

Ensemble averages of some quantity X $(\langle X \rangle)$ are assumed to be averages over the appropriate Boltzmann weighting, i.e. in the NVT ensemble with classical statistical mechanics, they would be $\int X(\vec{x},\vec{p})e^{-\beta U(\vec{x},\vec{p})}d\vec{x}d\vec{p}$. We note that in the limit of very large systems, $\langle X \rangle_{NPT}=\langle X \rangle_{NVT}=\langle X \rangle_{\mu VT}$.

Ensemble averages can be computed by one of two ways. First, they can be computed directly, by running a simulation that produces samples with the desired Boltzmann distribution. In that case ensemble averages can be computed as simple averages, $\langle V \rangle = \frac{1}{N} \sum_i V_i$, where the sum round is over all observations. Uncertainties can be estimated in a number of different ways, but usually require estimating the number of uncorrelated samples. Secondly, they can be calculated as reweighted estimates from several different sim-

^{*} email@email.com

[†] john.chodera@choderalab.org

[‡] Corresponding author; michael.shirts@virginia.edu

 $_{77}$ additional notation. We define the reduced potential u= $\beta U(\vec{x})$ in the canonical (NVT) ensemble, $u = \beta U + \beta PV$ in the isobaric-isothermal (NPT) ensemble, and $u=\beta U$ — ₈₀ $\beta N\mu$ in the grand canonical ensemble (similar potentials can be defined in other ensembles). We then define f = $\int e^{-u} dx$, where the integral is over all of the DOF of the system (x for NVT, x, V for NPT, and x, N for. For NPT, we then $_{ exttt{84}}$ have f=eta G, and for NVT we have f=eta A, while for μVT we have $f = -\beta \langle P \rangle V$.

To calculate expectations at one set of parameters gener-87 ated with paramters that give rise to a different set of probability distributions, we start with the definition of an ensem-⁸⁹ ble average given a probability distribution $p_i(x)$.

$$\langle X \rangle_i = \int X(x) p_i(x) dx$$
 (1)

90 We then multiply and divide by $p_i(x)$, to get

$$\langle X \rangle_i = \int X(x) p_i(x) \frac{p_j(x)}{p_j(x)} dx = \int X(x) p_j(x) \frac{p_i(x)}{p_j(x)} dx$$
(2)

91 We then note that this last integral can be estimated by the 92 Monte Carlo estimate

$$\langle X \rangle_i = \int X(x) p_j(x) \frac{p_i(x)}{p_j(x)} dx = \frac{1}{N} \sum_{n=1}^N X(x_n) \frac{p_i(x_n)}{p_j(x_n)}$$
(3)

 $_{
m 93}$ Where the x_k are sampled from probability distribution $^{
m 130}$

We now define the mixture distribution of K other dis- 131 $_{^{96}}$ tributions as: $p_m(x)=\frac{1}{N}\sum_{i=1}^N N_k p_k(x)$, where $N=_{^{97}}\sum_k N_k$. We can construct a sample from the mixture distributions $_{98}$ bution by simply pooling all the samples from k individual 99 simulations. The formula for calculating ensemble averages in a distribution $p_i(x)$ from samples from the mixture distri-101 bution is:

$$\langle X \rangle_i = \sum_{n=1}^N X(x_n) \frac{p_i(x_n)}{\sum k = 1^{N_k} p_k(x_n)} \tag{4}$$

In the case of Boltzmann averages, then $p_i(x) = e^{f_i - u_i(x)}$ where the reduced free energy f is unknown. Reweighting 104 from the mixture distibution becomes.

$$\langle X \rangle_i = \sum_{n=1}^N X(x_n) \frac{e^{f_i - u_i(x_n)}}{\sum_{k=1}^{N_k} e^{f_k - u_k(x)}}$$
 (5) ₁₃₆

which can be seen to be the same formula as the MBAR forby setting X=1, and looking at the K equations obtained by 139 from the Gibbs free energy as: reweighting to the K different distributions.

Finite differences at different temperatures and pressures 110 can be calculated by including states with different reduced

ulations, as $\langle V \rangle$ = $\frac{1}{\sum_i w_i} V_i w_i$ where w_i is a reweighting factor that can be derived from importance sampling theory. To simplify our discussion of reweighting, we use some To simplify our discussion of reweighting, we use some To simplify our discussion of reweighting, we use some To simplify our discussion of reweighting, we use some To simplify our discussion of reweighting, we use some To simplify our discussion of reweighting, we use some To simplify our discussion of reweighting factors are potentials. For example, $u_j(x) = \beta_i U(x) + \beta_i (P_i + \Delta P) V$, The potentials are potentials. For example, $u_j(x) = \beta_i U(x) + \beta_i (P_i + \Delta P) V$, The potentials are potentials. For example, $u_j(x) = \beta_i U(x) + \beta_i (P_i + \Delta P) V$, The potentials are potentials. For example, $u_j(x) = \beta_i U(x) + \beta_i (P_i + \Delta P) V$, The potentials are potentials. For example, $u_j(x) = \beta_i U(x) + \beta_i (P_i + \Delta P) V$, The potentials are potentials. For example, $u_j(x) = \beta_i U(x) + \beta_i (P_i + \Delta P) V$, The potentials are potentials. For example, $u_j(x) = \beta_i U(x) + \beta_i (P_i + \Delta P) V$, The potentials are potentials. For example, $u_j(x) = \beta_i U(x) + \beta_i (P_i + \Delta P) V$, The potentials are potentials. For example, $u_j(x) = \beta_i U(x) + \beta_i (P_i + \Delta P) V$, The potentials are potentials. For example, $u_j(x) = \beta_i U(x) + \beta_i (P_i + \Delta P) V$, The potentials are potentials. For example, $u_j(x) = \beta_i U(x) + \beta_i (P_i + \Delta P) V$, The potentials are potentials. For example, $u_j(x) = \beta_i U(x) + \beta_i (P_i + \Delta P) V$, The potentials are potentials. For example, $u_j(x) = \beta_i U(x) + \beta_i U(x)$ ing at differences in free energy with respect to temperature, $_{\rm II5}$ because $G_2-G_1=\beta_2f_2-\beta_1f_1.$ [MRS: needs to find notes $_{\rm II6}$ on how this was dealt with last time]

> Since with MBAR, one can make the differences as small as one would like (you don't have to actually carry out a simulation at those points), we can use the simplest formulas: 120 central difference for first derivatives:

$$\frac{dA}{dx} \approx \frac{1}{2\Delta x} \left(A(x + \Delta x) - A(x - \Delta x) \right)$$

121 And for 2nd deriatives:

$$\frac{d^2A}{dx^2} \approx \frac{1}{\Delta x^2} \left(A(x + \Delta x) - 2A(x) + A(x - \Delta x) \right)$$

122 Thus, only properties at two additional points need to be evaluated to calculate both first and 2nd derivatives.

Note that if the finite differences are reevaluated using reweighting approaches, it is important that the simulation used generates the correct Boltzmann distribution. If not, 127 reweighted observables will be incorrect, and the results of the finite difference approach will have significant error.

PURE SOLVENT PROPERTIES

Density

Direct calculation

Starting with the equation used to calculate the density 133 experimentally,

$$\rho = \frac{M}{V} \tag{6}$$

(4) We replace the average with the esemble estimate (calculated lated either directly, or with reweighting) to obtain:

$$\rho = \frac{M}{\langle V \rangle} \tag{7}$$

Derivative Estimate

From the differential definition of the Gibbs free energy mula for expectations. The free energies can be obtained $_{_{138}}~dG=~VdP-SdT+\sum_{i}\mu_{i}dN_{i}$ that V can be calculated

$$V = \left(\frac{\partial G}{\partial P}\right)_{T,N} \tag{8}$$

The density can therefore be estimated from the Gibbs free
 energy.

$$\rho = \frac{M}{\left(\frac{\partial G}{\partial P}\right)_{T,N}} \tag{9}$$

The derivative can be estimated using a central difference numerical method utilizing Gibbs free energies reweighted to different pressures.

$$\left(\frac{\partial G}{\partial P}\right)_{T,N} \approx \frac{G_{P+\Delta P} - G_{P-\Delta P}}{2\Delta p}$$
 (10)

145 The density can then finally be estimated.

148

$$\rho \approx \frac{M}{\frac{G_{P+\Delta P} - G_{P-\Delta P}}{2\Delta P}} \tag{11}$$

This can be calculated from the reduced free energy f if desired by simply substituting:

$$\rho \approx \frac{\beta M}{\frac{f_{P+\Delta P} - f_{P-\Delta P}}{2\Delta P}} \tag{12}$$

B. Molar Enthalpy

Section on relation of enthalpy to Gibbs free energy (should we need it). This is not an experimental quantity, but will be helpful in calculating related properties of interest. The enthalpy, H, can be found from the Gibbs free energy, G, by the Gibbs-Helmholtz relation:

$$H = -T^2 \left(\frac{\partial \left(\frac{G}{T} \right)}{\partial T} \right)_{P,N} \tag{13}$$

Transforming the derivative in the Gibbs-Helmholtz relation to be in terms of β instead of T yields:

$$H = -T^{2} \frac{\beta^{2}}{\beta^{2}} \left(\frac{\partial \left(\frac{G}{T} \right)}{\partial T} \frac{\partial T}{\partial \beta} \frac{\partial \beta}{\partial T} \right)_{P,N} \tag{14}$$

Recall that $\beta=\frac{1}{k_BT}$, therefore $\frac{\partial\beta}{\partial T}=-\frac{1}{k_BT^2}$. Substituting these values into the enthalpy equation gives:

$$H = \frac{1}{k_B^3 T^2 \beta^2} \left(\frac{\partial \left(\frac{G}{T} \right)}{\partial \beta} \right)_{P,N} = \frac{1}{k_B} \left(\frac{\partial \left(\frac{G}{T} \right)}{\beta} \right)_{P,N}$$

$$= \frac{\partial f}{\partial \beta}_{P,N} \tag{15}$$

C. Heat Capacity

The definition of the isobaric heat capacity is:

$$C_P = \left(\frac{\partial H}{\partial T}\right)_{P,N} \tag{16}$$

$$=\frac{\partial\left(\frac{\partial f}{\partial \beta}\right)}{\partial T}_{PN}\tag{17}$$

$$=k_B\beta^2\frac{\partial^2 f}{\partial \beta^2} \tag{18}$$

This could be computed by finite differences approach or analytical derivation using MBAR.

The enthalpy fluctuation formula can also be used to calculate C_P [1],

$$C_P = \frac{\langle H^2 \rangle - \langle H \rangle^2}{Nk_B \langle T \rangle^2}.$$
 (19)

(12) $^{_{164}}$ This form is equivalent for isochoric heat capacity, but with $^{_{165}}$ derivatives at constant volume rather than pressure.

Horn et al.[1] suggest a number of vibrational corrections be applied to the calculation of C_P due to a number of approximations made during the simulation of the liquid [1]. The following terms were added as a correction:

$$\left(\frac{\partial E_{vib,l}}{\partial T}\right)_{P} = \left(\frac{\partial E_{vib,l,intra}^{QM}}{\partial T}\right)_{P} + \left(\frac{\partial E_{vib,l,inter}^{QM}}{\partial T}\right)_{P} - \left(\frac{\partial E_{vib,l,inter}^{CM}}{\partial T}\right)_{P} \tag{20}$$

170 where

$$\left(\frac{\partial E_{vib}^{CM}}{\partial T}\right)_{P} = k_{B} n_{vib} \tag{21}$$

171 and

$$\left(\frac{\partial E_{vib}^{QM}}{\partial T}\right)_{P} = \sum_{i=1}^{n_{vib}} \left(\frac{h^{2}v_{i}^{2}e^{\frac{hv_{i}}{k_{B}T}}}{k_{B}T^{2}\left(e^{\frac{hv_{i}}{k_{B}T}} - 1\right)^{2}}\right)$$
(22)

Above, n_{vib} is the number of vibrational modes, h is Planck's constant and v_i is the vibrational frequency of mode i.

D. Isothermal Compressibility

The definition of isothermal compressibility is:

$$\kappa_T = -\frac{1}{V} \left(\frac{\partial V}{\partial P} \right)_T \tag{23}$$

1. First Derivative

Thus, it can be estimated by the finite difference of $\langle V \rangle$

$$\kappa_T = -\frac{1}{2V(T, P)^2} \left(\langle V(P + \Delta P, T) \rangle - \langle V(P - \Delta P) \rangle \right)$$
(24)

178 Or by the finite differences evaluation of:

176

179 180

184

185

186

187

188 189

190

191

192

199

200

$$\kappa_T = -\frac{\left(\frac{\partial^2 G}{\partial P^2}\right)_{T,N}}{\left(\frac{\partial G}{\partial P}\right)_{T,N}} \tag{25}$$

 κ_T can also be estimated from the ensemble average $_{\scriptscriptstyle 206}$ and fluctuation of volume (in the NPT ensemble) or particle ₁₈₃ number (in the μ VT ensemble)[2]:

$$\kappa_T = \beta \frac{\langle \Delta V^2 \rangle_{NTP}}{\langle V \rangle_{NTP}} = V \beta \frac{\langle \Delta N^2 \rangle_{VT}}{\langle N \rangle_{VT}}$$
 (26)

 $\kappa_T = \beta \frac{\langle \Delta V^2 \rangle_{NTP}}{\langle V \rangle_{NTP}} = V \beta \frac{\langle \Delta N^2 \rangle_{VT}}{\langle N \rangle_{VT}}$

 $\left(\frac{\partial S}{\partial P}\right)_{V} = \left(\frac{\partial S}{\partial T}\right)_{V} \left(\frac{\partial T}{\partial P}\right)_{V} = \frac{C_{V}}{T} \left(\frac{\partial T}{\partial P}\right)_{V} = \frac{C_{V}}{T\gamma_{V}}$

Where $\alpha=\frac{1}{V}\left(\frac{\partial V}{\partial T}\right)_P=\left(\frac{\partial lnV}{\partial T}\right)_P$ is the coefficient of thermal expansion. The second term is our triple product

 $\left(\frac{\partial S}{\partial V}\right)_{P} = \left(\frac{\partial S}{\partial T}\right)_{P} \left(\frac{\partial T}{\partial V}\right)_{P} = \frac{C_{P}}{T} \left(\frac{\partial T}{\partial V}\right)_{P} = \frac{C_{P}}{TV\alpha}$

Thus our derivation yields:

rule $\left(\frac{\partial S}{\partial P}\right)_V$ can be expressed as follows.

$$\left(\frac{\partial P}{\partial V}\right)_{S} = \frac{C_{P}\gamma_{V}}{C_{V}V\alpha} \tag{33}$$

Horn et al set out several ways for calculating $\alpha[1]$.

Speed of Sound

The definition of the speed of sound is[3]:

$$c^{2} = \left(\frac{\partial P}{\partial \rho}\right)_{S} = -\frac{V^{2}}{M} \left(\frac{\partial P}{\partial V}\right)_{S} \tag{27}$$

$$c^{2} = \frac{V^{2}}{\beta M} \left[\frac{\left(\frac{\gamma_{V}}{k_{B}}\right)^{2}}{\frac{C_{V}}{k_{B}}} + \frac{\beta}{V \kappa_{T}} \right]$$
 (28)

1. Analytical derivative of density with respect to temperature

$$\alpha = -\frac{dln\langle\rho\rangle}{dT} \tag{34}$$

2. Numerical derivative of densitt over range of T of interest

Same finite differnces approach on ρ can be used as was 215 shown for isothermal compressibility.

Where:

Using the enthalpy-volume fluctuation formula

209

210

$$\gamma_V = \left(\frac{\partial P}{\partial T}\right)_V \tag{29}$$

 γ_V is known as the isochoric pressure coefficient. κ_T is 194 the same isothermal compressibility from section A.1.3

An alternate derivation, applying the triple product rule $_{220}$ derivation can also be used to calculate γ_V . 198 to $\left(\frac{\partial P}{\partial V}\right)_S$ yields the following.

$$\alpha = \frac{\langle VH \rangle - \langle V \rangle \langle H \rangle}{k_B \langle T \rangle^2 \langle V \rangle} \tag{35}$$

Finite differences approximations and/or analytical

$\left(\frac{\partial P}{\partial V}\right)_{G} = \frac{\left(\frac{\partial S}{\partial V}\right)_{P}}{\left(\frac{\partial S}{\partial S}\right)_{CS}}$ (30)

Enthalpy of Vaporization

The definition of the enthalpy of vaporization is[4]:

$$\Delta H_{vap} = H_{gas} - H_{lig} = E_{gas} - E_{lig} + P(V_{gas} - V_{lig})$$
 (36)

If we assume that $V_{gas}>>V_{liq}$ and that the gas is ideal 226 (and therefore kinetic energy terms cancel):

223

224

227

228

236 237

240

241

245

248 249

$$\Delta H_{vap} = E_{gas,potential} - E_{lig,potential} + RT$$
 (37) 232

230 Horn et al [1].

$$\Delta H_{vap} = -\frac{E_{liq,potential}}{N} + RT - PV_{liq} + C$$
 (38)

An alternate, but similar, method is recommended by

In the above equation C is a correction factor for vibra-234 tional energies, polarizability, non-ideality of the gas and 235 pressure. It can be calculated as follows.

$$C_{vib} = C_{vib,intra} + C_{vib,inter} = (E_{vib,QM,qas,intra} - E_{vib,QM,liq,intra}) + (E_{vib,QM,liq,inter} - E_{vib,CM,liq,inter})$$
(39)

sical mechanics, resectively.

$$C_{pol} = \frac{N}{2} \frac{\left(d_{gas} - d_{liq}\right)^2}{\alpha_{p,gas}} \tag{40}$$

Where d_i is the dipole moment of a molecule in phase i242 and $\alpha_{p,gas}$ is the mean polarizability of a molecule in the gas phase.

$$C_{ni} = P_{vap} \left(B - T \frac{dB}{dT} \right) \tag{41}$$

Where B is the second virial coefficient.

$$C_{x} = \int_{P_{ext}}^{P_{vap}} \left[V\left(P_{ext}\right) \left[1 - \left(P - P_{ext}\right) \kappa_{T} \right] - TV\alpha \right] dP \tag{42}$$

Where P_{ext} in the external pressure and $V\left(P_{ext}\right)$ is the 250 volume at P_{ext} .

This is frequently done as a single simulation calculation by assuming the average intramolecular energies remains constant during the phase change, which is rigorously correct for something like a rigid water molecule (intramolecu- 285 lar energies are zero), but less true for something with structural rearrangement between gas and liquid phases.

As discussed by myself and MRS, we have decided to not 286 monly done using said property we have ample reason to 289 tal system dipole moment. 262 not follow classical practice. First of all, the enthalpy data is usually not collected at standard temperature and pressure, 264 but at the saturation conditions of the liquid being vapor-

The QM and CM subscripts stand for quantum and clas- 265 ized [5]. This would require corrections to be made to get the ₂₆₆ property at STP (the process will be explained below) using 267 fitted equations for heat capacity. Not only is this inconve-268 nient, but it adds an unknown complexity to correcting un-269 certainties in the experimental data. Often times the uncer-270 tainties of these "experimental" enthalpies are unrecorded 271 because they are estimated from fitted Antoine equation co-272 efficients [5].

> An additional issue is the necessity of having to use gas 274 phase simulation data in order to validate a parametriza-275 tion process meant for small organic liquids and their mixtures. Following an example of Wang et al. [6] we plan to instead use enthalpy of vaporization calculations as an unbiased means of testing the success of the parametrization. If 279 the parametrization procedure is expanded to use enthalpy of vaporization, corrections can be made to the experimental heat of vaporization in order to get a value at STP using 282 the following equation.

$$\Delta H_{vap}(T) = \Delta H_{vap}^{ref} + \int_{T_{ref}}^{T} \left(C_{P,gas} - C_{P,liq} \right) dT \quad (43)$$

Dielectric Constant

This equation was provided by a literature reference auinitially begin the parametrization process using enthalpy of 287 thored by CJ Fennell[7]. Below, $\epsilon(0)$ is the zero frequency vaporization data. While force field parametrization is com- 288 dielectric constant, V is the system volume and D is the to-

$$\epsilon(0) = 1 + \frac{4\pi}{3k_BT\langle V\rangle} (\langle D^2\rangle - \langle D\rangle^2) \tag{44}$$

BINARY MIXTURE PROPERTIES

290

291

306

309

311

312

313

317

Mass Density, Speed of Sound and Dielectric Constant

The methods for these calculations are the same for a 292 multicomponent system.

1. Activity Coefficient

The definition of chemical potential in a pure substance 296 İS:

$$\mu(T,P) = \left(\frac{\partial G}{\partial N}\right)_{T,P} \tag{45}$$

which is a function of only temperaure and pressure.

Then the definition of the chemical potential μ_i of com- $_{299}$ pound i in a mixture is:

$$\mu_i(T, P, \vec{N}) = \left(\frac{\partial G}{\partial N_i}\right)_{T, P, N_{i+1}} \tag{46}$$

 $_{\mbox{\tiny 301}}$ N_i refers to a molecule of component i and $N_{j\neq i}$ refers to all molecules other than component i, with \vec{N} the vector of all component numbers. Since μ_i is intensive, this is equivalently a function of the vector of mole fractions \vec{x}_i instead of simply of N_i .

For an ideal solution, the chemical potential μ_i can be related to the pure chemical potential by

$$\mu_i(T, P, \vec{x}_i) = \mu(T, P) + k_B T \ln(\gamma_i) \tag{47}$$

By analogy to this form, we can

$$\mu_i(T, P, \vec{x}_i) = \mu(T, P) + k_B T \ln(x_i \gamma_i)$$
 (48)

Where γ_i is the activity coefficient of component i, and is a function of T,P, and $\vec{x_i}$. Rearrangement of the previous equation yields:

$$\gamma_i = \frac{e^{\left(\frac{\mu_i(T, P, \vec{x}_i) - \mu(T, P)}{k_B T}\right)}}{r} \tag{49}$$

lated from simulation, chemical potential differences can. 359

We can calculate the difference $\mu_i(T,P,\vec{x}_i) - \mu(T,P)$ by calculating $\Delta\mu(T,P)_{liquid} - \Delta\mu(T,P)_{gas}$ using a standard alchemical simulation of the pure substance, followed by the calculation of $\mu_i(T, P, \vec{x}_i)_{liquid} - \Delta \mu(T, P, \vec{x}_i)_{gas}$, and assuming that $\Delta\mu(T,P,\vec{x}_i)_{gas} = \Delta\mu(T,P)_{gas}$ (note: there are a few subleties here relating to the $\ln x_i$ factor, but it appears that with alchemical simulations with a only one particle that is allowed to change, this will cancel out (need to 329 follow up).

2. Excess Molar Properties

The general definition of an excess molar property can be stated as follows:

$$y^E = y^M - \sum_i x_i y_i \tag{50}$$

Where y^E is the excess molar quantity, y^M is the mixture guantity, x_i is the mole fraction of component i in the mixture and y_i is the pure solvent quantity. In general, the sim-338 plest methods for calculating excess molar properties for bi-339 nary mixtures will require three simulations. One simulation is run for each pure component and a third will be run for 341 the specific mixture of interest. We note that only one set of ₃₄₂ pure simulations are needed to calculate excess properties 343 at all compositions.

Excess Molar Heat Capacity and Volume

Excess molar heat capacities and volume will be calculated using the methods for the pure quantities in section $_{347}$ A.1 in combination with the general method for excess property calculation above.

4. Excess Molar Enthalpy

Excess molar enthalpy can be calculated using the general relation of molar enthalpy as it relates to Gibbs Free Energy from section A.1 and the generalized method of ecess molar property calculation above or by the following[8]:

$$H^E = \langle E^M \rangle + PV^E - \sum_i x_i \langle E_i \rangle \tag{51}$$

Where $\langle \rangle$ denotes an ensemble average and V^E is calcu-Although chemical potentials cannot be directly calcu- ass lated using the general method of excess molar properties.

- ₃₆₂ [3] R. Lustig, Molecular Simulation **37**, 457 (2011).
- 363 [4] W. et al., Journal of Chemical Theory and Computation **7**, 2151 367 [6] W. et al., Journal of Physical Chemistry B **116**, 7088 (2012).
- $_{365}$ [5] C. et al., Journal of Physical and Chemical Reference Data 32, $_{369}$
- 519 (2003).
- 368 [7] C. Fennell, The Journal of Physical Chemistry B 116, 6936 (2012).
 - 370 [8] D. et al., Fluid Phase Equilibria **289**, 156 (2010).