Best Practices for Property Prediction from Molecular Simulations

Bryce C. Manubay,^{1,*} John D. Chodera,^{2,†} and Michael R. Shirts^{1,‡}

¹University of Colorado

²Computational Biology Program, Sloan Kettering Institute,
Memorial Sloan Kettering Cancer Center, New York, NY 10065, United States

(Dated: July 7, 2016)

This document describes a collected set of best practices for computing various physical properties from molecular simulations of liquid mixtures.

Keywords: best practices; molecular dynamics simulation; physical property computation

TODO LIST

I. PRELIMINARIES

Definitions

10

12

13

- V: Volume
- U: Total energy (including potential and kinetic, excluding external energy such as due to gravity, etc)
- S: Entopy
- N: Number of particles
- T: Temperature
- P: Pressure
- k_B : Boltzmann constant
 - β : $(k_B T)^{-1}$
- M: Molar mass
- ρ : Density (M/V)
- *H*: Enthalpy
- G: Gibbs Free Energy (free enthalpy)
- A: Helmholtz Free Energy
- μ: Chemical potential
- D: Total dipole moment
- *u*: reduced energy
- f: reduced free energy

Macroscopically, the quantities V,U,N are constants (assuming the system is not perturbed in any way), as we assume that the fluctuations are essentially zero, and any uncertainty comes from our inability to measure that constant precisly. For a mole of compound (about 18 mL for water), the relative uncertainty in any of these quantites is about 10^{-12} , far lower than any thermodynamics experiment.

[JDC1]: This is a TODO item example.

However, in a molecular simulation, these quantites are not necessarily constant. For example, in an NVT equilib-38 rium simulation, U is allowed to vary. For a long enough simulation (assuming ergodicity, which can pretty much always be assumed with correct simulations and simple fluids), then the ensemble average value of $U = \langle U \rangle$ will be constant, and in the limit of large simulations/long time will converge to the macroscopic value U; at least, the macroscopic value of that given model, though perhaps not the U for the real system. In an V simulation, clearly U is constant. In an V simulation, however, U is a variable, and we must estimate what the macroscopic value would be with the ensemble average U.

The quantities T, P, and μ are typically constant durso ing the equilibrium simulations and experiments of interest here. There are a number of quantities that can be used to ESTIMATE these constants. For example, $\langle \frac{1}{3Nk_B}\sum_i m_i|v_i|^2\rangle$, where m is the mass of each particle and $|v_i|$ is the magnitude of the velocity of each particle, is an estimate of T, and it's average will be equal to the temperature. But it is not the temperature. This quantity fluctuates, but the tempature remains constant; otherwise the simulation could not be at constant temperature.

To even say that some environmental variable, such as T or P is held constant is not entirely correct. What this means is that such quantities are controlled by an external force in order to hold them at a certain value. In the case of temperature, a thermostat is used. Recalling some basics of chemical engineering controller design, we know that no controller is perfect. Corrections from feedback cannot be made instantanteously, hence there is some variation in the simulation temperature reported. A thermostat constantly modifies the velocities of the particles in simulation in order to achieve the distribution of kinetic energies that would be expected for a simulation at the temperature specified.

Ensemble averages of some quantity X ($\langle X \rangle$) are assumed to be averages over the appropriate Boltzmann

^{*} email@email.com

[†] john.chodera@choderalab.org

[†] Corresponding author; michael.shirts@virginia.edu

₇₄ tistical mechanics, they would be $\int X(\vec{x}, \vec{p})e^{-\beta U(\vec{x}, \vec{p})}d\vec{x}d\vec{p}$. 75 We note that in the limit of very large systems, $\langle X \rangle_{NPT} =$ $\langle X \rangle_{NVT} = \langle X \rangle_{\mu VT}$.

Ensemble averages can be computed by one of two ways. First, they can be computed directly, by running a simulation that produces samples with the desired Boltzmann distribution. In that case ensemble averages can be computed as simple averages, $\langle V \rangle = \frac{1}{N} \sum_{i} V_{i}$, where the sum is over all observations. Uncertainties can be estimated in a number of different ways, but usually require estimating the number of 84 uncorrelated samples. Secondly, they can be calculated as 85 reweighted estimates from several different simulations, as $\langle V \rangle = \frac{1}{\sum_i w_i} V_i w_i$ where w_i is a reweighting factor that can 87 be derived from importance sampling theory.

To simplify our discussion of reweighting, we use some ₈₉ additional notation. We define the reduced potential u=₉₀ $\beta U(\vec{x})$ in the canonical (NVT) ensemble, $u=\beta U+\beta PV$ in the isobaric-isothermal (NPT) ensemble, and $u = \beta U$ – $\beta N\mu$ in the grand canonical ensemble (similar potentials $_{93}$ can be defined in other ensembles). We then define f= $\int e^{-u} dx$, where the integral is over all of the DOF of the system (x for NVT, x, V for NPT, and x, N for μVT . For NPT, we then have $f = \beta G$, and for NVT we have f = βA , while for μVT we have $f = -\beta \langle P \rangle V$.

To calculate expectations at one set of parameters generated with paramters that give rise to a different set of probability distributions, we start with the definition of an ensemble average given a probability distribution $p_i(x)$.

$$\langle X \rangle_i = \int X(x) p_i(x) dx$$
 (1)

We then multiply and divide by $p_i(x)$, to get

$$\langle X \rangle_i = \int X(x) p_i(x) \frac{p_j(x)}{p_j(x)} dx = \int X(x) p_j(x) \frac{p_i(x)}{p_j(x)} dx$$
(2)

103 We then note that this last integral can be estimated by the 104 Monte Carlo estimate

$$\langle X \rangle_i = \int X(x) p_j(x) \frac{p_i(x)}{p_j(x)} dx = \frac{1}{N} \sum_{n=1}^N X(x_n) \frac{p_i(x_n)}{p_j(x_n)}$$
(3)

 $_{ ext{105}}$ Where the x_k are sampled from probability distribution $_{ ext{143}}$ 106 $p_i(x)$

We now define the mixture distribution of K other distribution as: $p_m(x)=\frac{1}{N}\sum_{i=1}^N N_k p_k(x)$, where $N=\sum_k N_k$. 109 We can construct a sample from the mixture distribution by simply pooling all the samples from k individual simu-III lations. The formula for calculating ensemble averages in a distribution $p_i(x)$ from samples from the mixture distribu-113 tion is:

$$\langle X \rangle_i = \sum_{n=1}^{N} X(x_n) \frac{p_i(x_n)}{\sum_{k=1}^{N_k} p_k(x_n)}$$
 (4)

 $_{73}$ weighting, i.e. $\,$ in the NVT ensemble with classical sta- $_{114}$ In the case of Boltzmann averages, then $p_i(x)=e^{f_i-u_i(x)},$ where the reduced free energy f is unknown. Reweighting 116 from the mixture distibution becomes.

$$\langle X \rangle_i = \sum_{n=1}^{N} X(x_n) \frac{e^{f_i - u_i(x_n)}}{\sum_{k=1}^{N_k} e^{f_k - u_k(x)}}$$
 (5)

which can be seen to be the same formula as the MBAR formula for expectations. The free energies can be obtained $_{
m 119}$ by setting X=1, and looking at the K equations obtained by reweighting to the K different distributions.

Finite differences at different temperatures and pressures 122 can be calculated by including states with different reduced potentials. For example, $u_j(x)=\beta_i U(x)+\beta_i(P_i+\Delta P)V$, or $u_j=\frac{1}{k_B(T_i+\Delta T)}U(x)+\frac{1}{k_B(T_i+\Delta T)}P_iV$. However, the relationship between f and G can be problematic when looking at differences in free energy with respect to temperature, because $G_2-G_1=\beta_2f_2-\beta_1f_1$. [MRS: needs to find notes on how this was dealt with last time

Since with MBAR, one can make the differences as small as one would like (you don't have to actually carry out a simulation at those points), we can use the simplest formulas: 132 central difference for first derivatives:

$$\frac{dA}{dx} \approx \frac{1}{2\Delta x} \left(A(x + \Delta x) - A(x - \Delta x) \right)$$

133 And for 2nd deriatives:

$$\frac{d^2A}{dx^2} \approx \frac{1}{\Delta x^2} \left(A(x + \Delta x) - 2A(x) + A(x - \Delta x) \right)$$

134 Thus, only properties at two additional points need to be evaluated to calculate both first and 2nd derivatives.

Note that if the finite differences are reevaluated using reweighting approaches, it is important that the simulation used generates the correct Boltzmann distribution. If not, reweighted observables will be incorrect, and the results of the finite difference approach will have significant error.

PURE SOLVENT PROPERTIES

Density

Direct calculation

Starting with the equation used to calculate the density

$$\rho = \frac{M}{V} \tag{6}$$

146 We replace the average with the esemble estimate (calculated either directly, or with reweighting) to obtain:

$$\rho = \frac{M}{\langle V \rangle} \tag{7}$$

2. Derivative Estimate

148

From the differential definition of the Gibbs free energy degree of $dG=VdP-SdT+\sum_i\mu_idN_i$ that V can be calculated from the Gibbs free energy as:

$$V = \left(\frac{\partial G}{\partial P}\right)_{T N} \tag{8}$$

152 The density can therefore be estimated from the Gibbs free 153 energy.

$$\rho = \frac{M}{\left(\frac{\partial G}{\partial P}\right)_{T,N}}\tag{9}$$

The derivative can be estimated using a central difference numerical method utilizing Gibbs free energies reweighted to different pressures.

$$\left(\frac{\partial G}{\partial P}\right)_{T,N} \approx \frac{G_{P+\Delta P} - G_{P-\Delta P}}{2\Delta p}$$
 (10)

157 The density can then finally be estimated.

$$\rho \approx \frac{M}{\frac{G_{P+\Delta P} - G_{P-\Delta P}}{2\Delta P}} \tag{11}$$

177

185

This can be calculated from the reduced free energy f if desired by simply substituting:

$$\rho \approx \frac{\beta M}{\frac{f_{P+\Delta P} - f_{P-\Delta P}}{2\Delta P}} \tag{12}$$

Intuitively, one would imagine that equation 12 would be a worse estimate of density given that the calculations involved have more room for error than direct simulations. That being said, this method should prove invaluable when estimating densities of unsampled states using MBAR.

B. Molar Enthalpy

This section is on the relation of enthalpy to Gibbs free energy (should we need it). This is not an experimental quantity, but will be helpful in calculating related properties of interest. The enthalpy, H, can be found from the Gibbs free energy, G, by the Gibbs-Helmholtz relation:

$$H = -T^2 \left(\frac{\partial \left(\frac{G}{T} \right)}{\partial T} \right)_{P,N} \tag{13}$$

Transforming the derivative in the Gibbs-Helmholtz relation to be in terms of β instead of T yields:

$$H = -T^{2} \frac{\beta^{2}}{\beta^{2}} \left(\frac{\partial \left(\frac{G}{T} \right)}{\partial T} \frac{\partial T}{\partial \beta} \frac{\partial \beta}{\partial T} \right)_{P,N} \tag{14}$$

Recall that $\beta=\frac{1}{k_BT}$, therefore $\frac{\partial \beta}{\partial T}=-\frac{1}{k_BT^2}$. Substituting these values into the enthalpy equation gives:

$$H = \frac{1}{k_B^3 T^2 \beta^2} \left(\frac{\partial \left(\frac{G}{T} \right)}{\partial \beta} \right)_{P,N} = \frac{1}{k_B} \left(\frac{\partial \left(\frac{G}{T} \right)}{\beta} \right)_{P,N} = \frac{\partial f}{\partial \beta}_{P,N} \tag{15}$$

C. Heat Capacity

The definition of the isobaric heat capacity is:

$$C_P = \left(\frac{\partial H}{\partial T}\right)_{P,N} \tag{16}$$

$$C_{P} = \frac{\partial \left(\frac{\partial f}{\partial \beta}\right)}{\partial T}_{P,N} \tag{17}$$

$$C_P = k_B \beta^2 \frac{\partial^2 f}{\partial \beta^2} \tag{18}$$

This could be computed by finite differences approach or analytical derivation using MBAR

The enthalpy fluctuation formula can also be used to calculate C_P [?].

$$C_P = \frac{\langle H^2 \rangle - \langle H \rangle^2}{N k_B \langle T \rangle^2} \tag{19}$$

The form is equivalent for isochoric heat capacity, but with derivatives at constant volume rather than pressure.

Horn et al suggest a number of vibrational corrections be applied to the calculation of C_P due to a number of approximations made during the simulation of the liquid [?]. The following terms were added as a correction.

$$\left(\frac{\partial E_{vib,l}}{\partial T}\right)_{P} = \left(\frac{\partial E_{vib,l,intra}^{QM}}{\partial T}\right)_{P} + \left(\frac{\partial E_{vib,l,inter}^{QM}}{\partial T}\right)_{P} - \left(\frac{\partial E_{vib,l,inter}^{CM}}{\partial T}\right)_{P} - \left(\frac{\partial E_{vib,l,inter}}{\partial T}\right$$

Where:

$$\left(\frac{\partial E_{vib}^{CM}}{\partial T}\right)_{P} = k_{B} n_{vib} \tag{21}$$

$$\left(\frac{\partial E_{vib}^{QM}}{\partial T}\right)_{P} = \sum_{i=1}^{n_{vib}} \left(\frac{h^{2}v_{i}^{2}e^{\frac{hv_{i}}{k_{B}T}}}{k_{B}T^{2}\left(e^{\frac{hv_{i}}{k_{B}T}} - 1\right)^{2}}\right)$$
(22)

Above, n_{vib} is the number of vibrational modes, h is Planck's constant and v_i is the vibrational frequency of mode i.

D. Isothermal Compressibility

²⁰³ The definition of isothermal compressibility is:

195 196

197

198

202

204

207

212

213

214

$$\kappa_T = -\frac{1}{V} \left(\frac{\partial V}{\partial P} \right)_T \tag{23}$$

1. First Derivative

 $_{ t 205}$ $\,$ Thus, it can be estimated by the finite difference of $\langle V
angle$

$$\kappa_T = -\frac{1}{2V(T, P)^2} \left(\langle V(P + \Delta P, T) \rangle - \langle V(P - \Delta P, T) \rangle \right) \tag{24}$$

²⁰⁶ Or by the finite differences evaluation of:

$$\kappa_T = -\frac{\left(\frac{\partial^2 G}{\partial P^2}\right)_{T,N}}{\left(\frac{\partial G}{\partial P}\right)_{T,N}} \tag{25}$$

 κ_T can also be estimated from the ensemble average and fluctuation of volume (in the NPT ensemble) or particle number (in the μ VT ensemble)[?]:

$$\kappa_T = \beta \frac{\langle \Delta V^2 \rangle_{NTP}}{\langle V \rangle_{NTP}} = V \beta \frac{\langle \Delta N^2 \rangle_{VT}}{\langle N \rangle_{VT}}$$
 (26)

E. Speed of Sound

The definition of the speed of sound is[?]:

$$c^{2} = \left(\frac{\partial P}{\partial \rho}\right)_{S} = -\frac{V^{2}}{M} \left(\frac{\partial P}{\partial V}\right)_{S} \tag{27}$$

$$c^{2} = \frac{V^{2}}{\beta M} \left[\frac{\left(\frac{\gamma_{V}}{k_{B}}\right)^{2}}{\frac{C_{V}}{k_{B}}} + \frac{\beta}{V \kappa_{T}} \right]$$
 (28)

Where:

217

219

220

227

237

238

$$\gamma_V = \left(\frac{\partial P}{\partial T}\right)_V \tag{29}$$

 γ_V is known as the isochoric pressure coefficient. κ_T is the same isothermal compressibility from section A.1.3

An alternate derivation, applying the triple product rule to $\left(\frac{\partial P}{\partial V}\right)_S$ yields the following.

$$\left(\frac{\partial P}{\partial V}\right)_{S} = \frac{\left(\frac{\partial S}{\partial V}\right)_{P}}{\left(\frac{\partial S}{\partial P}\right)_{V}} \tag{30}$$

Where $\alpha=\frac{1}{V}\left(\frac{\partial V}{\partial T}\right)_P=\left(\frac{\partial \ln V}{\partial T}\right)_P$ is the coefficient of thermal expansion. The second term is our triple product rule $\left(\frac{\partial S}{\partial P}\right)_V$ can be expressed as follows.

$$\left(\frac{\partial S}{\partial P}\right)_{V} = \left(\frac{\partial S}{\partial T}\right)_{V} \left(\frac{\partial T}{\partial P}\right)_{V} = \frac{C_{V}}{T} \left(\frac{\partial T}{\partial P}\right)_{V} = \frac{C_{V}}{T\gamma_{V}} \tag{32}$$

Thus our derivation yields:

$$\left(\frac{\partial P}{\partial V}\right)_{S} = \frac{C_{P}\gamma_{V}}{C_{V}V\alpha} \tag{33}$$

Horn et al set out several ways for calculating α [?]:

1. Analytical derivative of density with respect to temperature

$$\alpha = -\frac{d\ln\langle\rho\rangle}{dT} \tag{34}$$

Numerical derivative of density over range of T of interest

The same finite differnces approach as shown for isother-243 mal compressibility can be applied here, thus:

$$C_{pol} = \frac{1}{2} \frac{1}{\alpha_{p,gas}} \tag{42}$$

$$\alpha = -\frac{d \ln \langle \rho \rangle}{dT} = -\frac{1}{2\rho(T,P)} \left(\ln \langle \rho(P,T+\Delta T) \rangle - \ln \langle V(P,T^{27}\Delta T) \rangle \right)$$

$$(35) \frac{1}{273} \qquad \text{Where } d_i \text{ is the dipole moment of a molecule in phase } i$$
 and $\alpha_{p,gas}$ is the mean polarizability of a molecule in the gas

Using the enthalpy-volume fluctuation formula

$$\alpha = \frac{\langle VH \rangle - \langle V \rangle \langle H \rangle}{k_B \langle T \rangle^2 \langle V \rangle} \tag{36}$$

Finite differences approximations and/or analytical derivation can also be used to calculate γ_V or by note of the 249 relation:

245

250

252

254

258

263

267

268

$$\gamma_V = -\frac{\alpha}{\kappa_T} \tag{37}$$

279

Enthalpy of Vaporization

The definition of the enthalpy of vaporization is[?]:

$$\Delta H_{vap} = H_{gas} - H_{liq} = E_{gas} - E_{liq} + P(V_{gas} - V_{liq})$$
 (38)

If we assume that $V_{qas} >> V_{liq}$ and that the gas is ideal ²⁵⁷ (and therefore kinetic energy terms cancel):

$$\Delta H_{vap} = E_{gas,potential} - E_{liq,potential} + RT$$
 (39)

An alternate, but similar, method is recommended by 261 Horn et al [?].

$$\Delta H_{vap} = -\frac{E_{liq,potential}}{N} + RT - PV_{liq} + C$$
 (40)

In the above equation C is a correction factor for vibra-265 tional energies, polarizability, non-ideality of the gas and ₂₆₆ pressure. It can be calculated as follows.

$$C_{vib} = C_{vib,intra} + C_{vib,inter} = (E_{vib,QM,gas,intra} - E_{vib,QM,gas,intra})$$

The QM and CM subscripts stand for quantum and clas-270 sical mechanics, resectively.

$$C_{pol} = \frac{N}{2} \frac{\left(d_{gas} - d_{liq}\right)^2}{\alpha_{p,gas}} \tag{42}$$

and $lpha_{p,gas}$ is the mean polarizability of a molecule in the gas

$$C_{ni} = P_{vap} \left(B - T \frac{dB}{dT} \right) \tag{43}$$

Where B is the second virial coefficient.

$$C_{x} = \int_{P_{ext}}^{P_{vap}} \left[V\left(P_{ext}\right) \left[1 - \left(P - P_{ext}\right) \kappa_{T} \right] - TV\alpha \right] dP \tag{44}$$

Where P_{ext} in the external pressure and $V\left(P_{ext}\right)$ is the volume at P_{ext} .

This is frequently done as a single simulation calculation by assuming the average intramolecular energies remains constant during the phase change, which is rigorously correct for something like a rigid water molecule (intramolecular energies are zero), but less true for something with structural rearrangement between gas and liquid phases.

As discussed by myself and MRS, we have decided to not initially begin the parametrization process using enthalpy of vaporization data. While force field parametrization is commonly done using said property we have ample reason to 293 not follow classical practice. First of all, the enthalpy data is usually not collected at standard temperature and pres-295 sure, but at the saturation conditions of the liquid being va-296 porized [?]. This would require corrections to be made to get the property at STP (the process will be explained below) using fitted equations for heat capacity. Not only is this inconvenient, but it adds an unknown complexity when adjusting experimental uncertainties due to the added correction. Often times the uncertainties of these "experimental" enthalpies are unrecorded because they are estimated from fitted Antoine equation coefficients [?].

An additional issue is the necessity of having to use gas phase simulation data in order to validate a parametrization process meant for small organic liquids and their mix-307 tures. Following an example of Wang et al. [?] we plan to 308 instead use enthalpy of vaporization calculations as an unbi- $C_{vib} = C_{vib,intra} + C_{vib,inter} = (E_{vib,QM,qas,intra} - E_{vib,QM,qas,ed})$ etrization. If (41) 310 the parametrization procedure is expanded to use enthalpy of vaporization, corrections can be made to the experimental heat of vaporization in order to get a value at STP using

313 the following equation.

315

316

322

323

341

$$\Delta H_{vap}(T) = \Delta H_{vap}^{ref} + \int_{T_{ref}}^{T} \left(C_{P,gas} - C_{P,liq} \right) dT \quad \mbox{(45)} \label{eq:delta_tau}$$

1. Dielectric Constant

This equation was provided by a literature reference authored by CJ Fennell[?] and is the standard for calculating the dielectric constant. Below, $\epsilon(0)$ is the zero frequency dielectric constant, V is the system volume and D is the total system dipole moment.

$$\epsilon(0) = 1 + \frac{4\pi}{3k_B T \langle V \rangle} (\langle D^2 \rangle - \langle D \rangle^2) \tag{46}$$

III. BINARY MIXTURE PROPERTIES

A. Mass Density, Speed of Sound and Dielectric Constant

The methods for these calculations are the same for a multicomponent system.

1. Activity Coefficient

The definition of chemical potential in a pure substance is:

$$\mu(T, P) = \left(\frac{\partial G}{\partial N}\right)_{T, P} \tag{47}$$

which is a function of only temperaure and pressure.

Then the definition of the chemical potential μ_i of compound i in a mixture is:

$$\mu_i(T, P, \vec{N}) = \left(\frac{\partial G}{\partial N_i}\right)_{T, P, N_{i+1}} \tag{48}$$

 333 N_i refers to a molecule of component i and $N_{j \neq i}$ refers to all molecules other than component i, with \vec{N} the vector of all component numbers. Since μ_i is intensive, this is equivalently a function of the vector of mole fractions \vec{x}_i instead of simply of N_i .

For an ideal solution, the chemical potential μ_i can be related to the pure chemical potential by

$$\mu_i(T, P, \vec{x}_i) = \mu(T, P) + k_B T \ln(\gamma_i) \tag{49}$$

By analogy to this form, we can

345

362

381

$$\mu_i(T, P, \vec{x}_i) = \mu(T, P) + k_B T \ln(x_i \gamma_i)$$
 (50)

Where γ_i is the activity coefficient of component i, and is a function of T,P,and \vec{x}_i . Rearrangement of the previous equation yields:

$$\gamma_i = \frac{e^{\left(\frac{\mu_i(T, P, \vec{x}_i) - \mu(T, P)}{k_B T}\right)}}{x_i} \tag{51}$$

Although chemical potentials cannot be directly calculated from simulation, chemical potential differences can. We can calculate the difference $\mu_i(T,P,\vec{x}_i)-\mu(T,P)$ by calculating $\Delta\mu(T,P)_{liquid}-\Delta\mu(T,P)_{gas}$ using a standard alchemical simulation of the pure substance, followed by the calculation of $\mu_i(T,P,\vec{x}_i)_{liquid}-\Delta\mu(T,P,\vec{x}_i)_{gas}$, and assuming that $\Delta\mu(T,P,\vec{x}_i)_{gas}=\Delta\mu(T,P)_{gas}$ (note: there are a few subleties here relating to the $\ln x_i$ factor, but it appears that with alchemical simulations with a only one particle that is allowed to change, this will cancel out (need to follow up).

2. Excess Molar Properties

The general definition of an excess molar property can be stated as follows:

$$y^E = y^M - \sum_i x_i y_i \tag{52}$$

Where y^E is the excess molar quantity, y^M is the mixture quantity, x_i is the mole fraction of component i in the mixture and y_i is the pure solvent quantity. In general, the simplest methods for calculating excess molar properties for binary mixtures will require three simulations. One simulation is run for each pure component and a third will be run for the specific mixture of interest. We note that only one set of pure simulations are needed to calculate excess properties at all compositions.

3. Excess Molar Heat Capacity and Volume

Excess molar heat capacities and volume will be calcu- (49) $_{\rm 378}$ lated using the methods for the pure quantities in section $_{\rm 379}$ A.1 in combination with the general method for excess $_{\rm 380}$ property calculation above.

4. Excess Molar Enthalpy

382

Excess molar enthalpy can be calculated using the general 389 383 relation of molar enthalpy as it relates to Gibbs Free Energy lated using the general method of excess molar properties. $_{\rm 385}$ from section A.1 and the generalized method of ecess molar $^{\rm 391}$ 386 property calculation above or by the following[?]:

Where $\langle\rangle$ denotes an ensemble average and V^E is calcu-

$$H^E = \langle E^M \rangle + PV^E - \sum_i x_i \langle E_i \rangle \tag{53}$$

387